

# CS 423 Operating System Design: OS support for Synchronization

Professor Adam Bates Fall 2018

# Goals for Today



- Learning Objectives:
  - Discuss OS support for Synchronization
- Announcements:
  - MP1 available on Compass2G. Due February 19th!
  - Next week scheduling (skipping chapter 6 for now)





**Reminder**: Please put away devices at the start of class

# Implementing Synchronization



- Take I: using memory load/store
  - See too much milk solution/Peterson's algorithm
- Take 2: (corrected from last class!)

```
Lock::acquire() {
    disableInterrupts();
}
Lock::release() {
    enableInterrupts();
}
```

Above solution "works" on single processor...

### Queueing Lock Implementation (1 Proc)



```
Lock::acquire() {
                                      Lock::release() {
                                          disableInterrupts();
    disableInterrupts();
    if (value == BUSY) {
                                           if (!waiting.Empty()) {
        waiting.add(myTCB);
                                               next = waiting.remove();
                                               next->state = READY;
        myTCB->state = WAITING;
        next = readyList.remove();
                                               readyList.add(next);
        switch(myTCB, next);
                                           } else {
                                           value = FREE;
        myTCB->state = RUNNING;
    } else {
        value = BUSY;
                                           enableInterrupts();
                                       }
    enableInterrupts();
```

# Question



Why won't this work for multiprocessing?

# Multiprocessor Sync Tool!



- Read-modify-write instructions
  - Atomically read a value from memory, operate on it, and then write it back to memory
  - Intervening instructions prevented in hardware
- Examples
  - Test and set
  - Intel: xchgb, lock prefix
  - Compare and swap
- Any of these can be used for implementing locks and condition variables!

# Spinlocks



- A spinlock is a lock where the processor waits in a loop for the lock to become free
  - Assumes lock will be held for a short time
  - Used to protect the CPU scheduler and to implement locks

```
Spinlock::acquire() {
    while (testAndSet(&lockValue) == BUSY)
    ;
}

Spinlock::release() {
    lockValue = FREE;
    memorybarrier();
}
```

# How many spinlocks?



**Neat. So how many spinlocks do we need?** 

# How many spinlocks?



- Many data structures requiring synchronization!
  - Queue of waiting threads on lock X
  - Queue of waiting threads on lock Y
  - List of threads ready to run
- One spinlock per kernel?
  - Spinlock becomes bottleneck!
- Instead:
  - One spinlock per lock
  - One spinlock for the scheduler ready list
    - Per-core ready list: one spinlock per core

# What thread is currently running?



- Thread scheduler needs to find the TCB of the currently running thread
  - To suspend and switch to a new thread
  - To check if the current thread holds a lock before acquiring or releasing it
- On a uniprocessor, easy: just use a global
- On a multiprocessor, various methods:
  - Compiler dedicates a register (e.g., r31 points to TCB running on the this CPU; each CPU has its own r31)
  - If hardware has a special per-processor register, use it
  - Fixed-size stacks: put a pointer to the TCB at the bottom of its stack
  - Find it by masking the current stack pointer

#### Queueing Lock Implementation (Multiproc)



#### Lock implementation —

```
Lock::acquire() {
    disableInterrupts();
    spinLock.acquire();
    if (value == BUSY) {
        waiting.add(myTCB);
        suspend(&spinlock);
    } else {
        value = BUSY;
    }
    spinLock.release();
    enableInterrupts();
}
```

```
Lock::release() {
    disableInterrupts();
    spinLock.acquire();
    if (!waiting.Empty()) {
        next = waiting.remove();
        scheduler->makeReady(next);
    } else {
    value = FREE;
    }
    spinLock.release();
    enableInterrupts();
}
```

#### Queueing Lock Implementation (Multiproc)



#### Scheduler implementation —

```
Sched::suspend(SpinLock *lock) {
                                    Sched::makeReady(TCB *thread) {
    TCB *next;
    disableInterrupts();
                                        disableInterrupts ();
    schedSpinLock.acquire();
                                        schedSpinLock.acquire();
    lock->release();
                                        readyList.add(thread);
   myTCB->state = WAITING;
                                        thread->state = READY;
    next = readyList.remove();
                                        schedSpinLock.release();
    thread switch(myTCB, next);
                                        enableInterrupts();
   myTCB->state = RUNNING;
    schedSpinLock.release();
    enableInterrupts();
```

# Locks for user space??



- Kernel-managed threads
  - Manage data structures in kernel space
  - System calls to communicate w/ scheduler
- User-managed threads
  - Implement functionality in thread library
  - Can't disable interrupts, but can temporarily disable upcalls to avoid preemption in library scheduler, etc.

## Locks in Linux



- Most locks are free most of the time. Linux implementation takes advantage of this fact!
- Fast path:
  - If lock is FREE, and no one is waiting, two instructions to acquire the lock
  - If no one is waiting, two instructions to release the lock
- Slow path
  - If lock is BUSY or someone is waiting, use multiproc impl.
- User-level locks also optimized:
  - Fast path: count is mapped to proc address space, no sys call needed when count is 0.
  - Slow path: system call to kernel, use kernel lock when waiting thread

## Locks in Linux



Lock struct contains 3 (not two) states...

```
struct mutex {
   /* 1: unlocked;
    0: locked;
    negative : locked, possible waiters */
   atomic_t count;
   spinlock_t wait_lock;
   struct list_head wait_list;
};
```

Lock acquire code is a macro (to avoid proc call)...

# Semaphores



- Semaphore has a non-negative integer value
  - P() atomically waits for value to become > 0, then decrements
  - V() atomically increments value (waking up waiter if needed)
- Semaphores are like integers except:
  - Only operations are P and V
  - Operations are atomic
    - If value is I, two P's will result in value 0 and one waiter
- Semaphores are useful for
  - Unlocked wait: interrupt handler, fork/join

## Compare Implementations



#### Lock implementation —

```
Lock::acquire() {
    disableInterrupts();
    spinLock.acquire();
    if (value == BUSY) {
        waiting.add(myTCB);
        suspend(&spinlock);
    } else {
        value = BUSY;
    }
    spinLock.release();
    enableInterrupts();
}
```

```
Lock::release() {
    disableInterrupts();
    spinLock.acquire();
    if (!waiting.Empty()) {
        next = waiting.remove();
        scheduler->makeReady(next);
    } else {
    value = FREE;
    }
    spinLock.release();
    enableInterrupts();
}
```

## Compare Implementations



#### Semaphore implementation —

```
Semaphore::P() {
    disableInterrupts();
    spinLock.acquire();
    if (value == 0) {
        waiting.add(myTCB);
        suspend(&spinlock);
    } else {
        value--;
    }
    spinLock.release();
    enableInterrupts();
}
```

```
Semaphore::V() {
    disableInterrupts();
    spinLock.acquire();
    if (!waiting.Empty()) {
        next = waiting.remove();
        scheduler->makeReady(next);
    } else {
    value++;
    }
    spinLock.release();
    enableInterrupts();
}
```

# Semaphores Harmful?



- Semaphores conflate mutual the roles of locks and condition variables (mutual exclusion, shared data).
  - Simpler code verification: prove every lock is eventually unlocked.
- Semaphores have state!
  - What does value=3 mean? Programmer must carefully map object state to semaphore value.
  - CVs, in contrast, allows us to wait on arbitrary state. A better abstraction.
- However, semaphores have good uses, including...
  - Unlocked waits, e.g., interrupt handler that synchronizes communication between I/O device and waiting threads.

# Semaphore Bounded Buffer



```
get() {
    fullSlots.P();
    mutex.P();
    item = buf[front % MAX];
    front++;
    mutex.V();
    emptySlots.V();
    return item;
}

put(item) {
    emptySlots.P();
    mutex.P();
    mutex.P();
    mutex.P();
    mutex.V();
    fullSlots.V();
}
```

```
Initially: front = last = 0; MAX is buffer capacity mutex = 1; emptySlots = MAX; fullSlots = 0;
```



How can we implement Condition Variables using semaphores?

#### Take 1:

```
wait(lock) {
    lock.release();
    semaphore.P();
    lock.acquire();
}
signal() {
    semaphore.V();
}
```

Problems?



How can we implement Condition Variables using semaphores?

#### Take 2:

```
wait(lock) {
    lock.release();
    semaphore.P();
    lock.acquire();
}
signal() {
    if (semaphore is not empty)
        semaphore.V();
}
```

Problems?



How can we implement Condition Variables using semaphores?

#### Take 2:

```
wait(lock) {
    semaphore = new Semaphore;
    queue.Append(semaphore); // queue of waiting threads
    lock.release();
    semaphore.P();
    lock.acquire();
}
signal() {
    if (!queue.Empty()) {
        semaphore = queue.Remove();
        semaphore.V(); // wake up waiter
    }
}
Problems?
```



Implementation used for Microsoft Windows before native support was offered:

#### Take 4:

```
//Put thread on queue of waiting threads....
void CV::wait(Lock *lock){
   semaphore = new Semaphore(0);
   waitQueue. Append(semaphore)
        lock.release();
   semaphore.P();
   lock.acquire();
}

//Wake up one waiter if any.
void CV::signal() {
   if(!waitQueue.isEmpty()) {
        semaphore = queue.Remove();
        semaphore.V();
   }
}
```