# How To Set Up Password Authentication with Nginx on Ubuntu:-

If you haven't done so already, install Nginx on your machine by typing:

- sudo apt-get update
- sudo apt-get install nginx

#### Create the Password File

To start out, we need to create the file that will hold our username and password combinations. You can do this by using the OpenSSL utilities that may already be available on your server. Alternatively, you can use the purpose-made htpasswd utility included in the apache2-utils package (Nginx password files use the same format as Apache). Choose the method below that you like best.

### Create the Password File Using the OpenSSL Utilities

If you have OpenSSL installed on your server, you can create a password file with no additional packages. We will create a hidden file called .htpasswd in the /etc/nginx configuration directory to store our username and password combinations.

You can add a username to the file using this command. We are using sammy as our username, but you can use whatever name you'd like:

sudo sh -c "echo -n 'sammy:' >> /etc/nginx/.htpasswd"

Next, add an encrypted password entry for the username by typing:

sudo sh -c "openssl passwd -apr1 >> /etc/nginx/.htpasswd"

You can repeat this process for additional usernames. You can see how the usernames and encrypted passwords are stored within the file by typing:

cat /etc/nginx/.htpasswd

Output

sammy:\$apr1\$wl1/T0nB\$jEKuTJHkTOOWkopnXqC1d1

### **Create the Password File Using Apache Utilities**

While OpenSSL can encrypt passwords for Nginx authentication, many users find it easier to use a purpose-built utility. The htpasswd utility, found in the apache2-utils package, serves this function well.

Install the apache2-utils package on your server by typing:

- sudo apt-get update
- sudo apt-get install apache2-utils

Now, you have access to the htpasswd command. We can use this to create a password file that Nginx can use to authenticate users. We will create a hidden file for this purpose called .htpasswd within our /etc/nginx configuration directory.

The first time we use this utility, we need to add the -c option to create the specified file. We specify a username (sammy in this example) at the end of the command to create a new entry within the file:

sudo htpasswd -c /etc/nginx/.htpasswd sammy

You will be asked to supply and confirm a password for the user.

Leave out the -c argument for any additional users you wish to add:

sudo htpasswd /etc/nginx/.htpasswd another\_user

If we view the contents of the file, we can see the username and the encrypted password for each record:

cat /etc/nginx/.htpasswd

Output

## Configure Nginx Password Authentication

Now that we have a file with our users and passwords in a format that Nginx can read, we need to configure Nginx to check this file before serving our protected content.

Begin by opening up the server block configuration file that you wish to add a restriction to. For our example, we'll be using the default server block file installed through Ubuntu's Nginx package:

• sudo nano /etc/nginx/sites-enabled/<config file in which you want to put authentication>

Inside, with the comments stripped, the file should look similar to this:

```
/etc/nginx/sites-enabled/<config file in which you want to put authentication>
server {
    listen 80 default_server;
    listen [::]:80 default_server ipv6only=on;

    root /usr/share/nginx/html;
    index index.html index.htm;

    server_name localhost;

    location / {
        try_files $uri $uri/ =404;
    }
```

To set up authentication, you need to decide on the context to restrict. Among other choices, Nginx allows you to set restrictions on the server level or inside a specific location. In our example, we'll restrict the entire document root with a location block, but you can modify this listing to only target a specific directory within the web space:

Within this location block, use the auth\_basic directive to turn on authentication and to choose a realm name to be displayed to the user when prompting for credentials. We will use the auth\_basic\_user\_file directive to point Nginx to the password file we created:

/etc/nginx/sites-enabled/<config file in which you want to put authentication>

```
server {
    listen 80 default_server;
    listen [::]:80 default_server ipv6only=on;

    root /usr/share/nginx/html;
    index index.html index.htm;

    server_name localhost;

    location / {
        try_files $uri $uri/ =404;
        auth_basic "Restricted Content";
        auth_basic_user_file /etc/nginx/.htpasswd;
    }
}
```

Save and close the file when you are finished. Restart Nginx to implement your password policy:

• sudo service nginx restart

•