

## **Cloud Backup documentation**

Cloud Backup

NetApp July 19, 2022

This PDF was generated from https://docs.netapp.com/us-en/cloud-manager-backup-restore/azure/index.html on July 19, 2022. Always check docs.netapp.com for the latest.

# **Table of Contents**

Cloud Backup documentation	
What's new with Cloud Backup	
13 July 2022	
14 June 2022	
8 June 2022	
2 May 2022	
4 April 2022	4
3 March 2022	4
14 February 2022	5
2 January 2022	5
28 November 2021	5
5 November 2021	6
4 October 2021	6
2 September 2021	
1 August 2021	
7 July 2021	
7 June 2021	8
5 May 2021	8
Get started	
Learn about Cloud Backup	
Set up licensing for Cloud Backup	
Back up and restore ONTAP data	
Protect your ONTAP cluster data using Cloud Backup	
Backing up Cloud Volumes ONTAP data to Azure Blob storage	24
Backing up on-premises ONTAP data to Azure Blob storage	
Backing up on-premises ONTAP data to StorageGRID	
Managing backups for your ONTAP systems	45
Restoring ONTAP data from backup files	59
Back up and restore Kubernetes data	
Protect your Kubernetes cluster data using Cloud Backup	
Backing up Kubernetes persistent volume data to Azure Blob storage	78
Managing backups for your Kubernetes systems	
Restoring Kubernetes data from backup files	95
Back up and restore on-premises applications data	97
Protect your on-premises applications data	97
Back up on-premises applications data to cloud	
Manage protection of applications	101
Restore applications data	104
Back up and restore Virtual Machines data	107
Protect your virtual machines data	
Back up datastores to the cloud	109
Manage protection of virtual machines	
Restore virtual machines from the cloud	112

Cloud Backup APIs	
Getting started	113
Example using the APIs	
API reference	
Reference	119
AWS S3 archival storage classes and restore retrieval times	119
Azure archival tiers and restore retrieval times	120
Cross-account and cross-region configurations.	121
Knowledge and support	137
Register for support	137
Get help	138
Legal notices	140
Copyright	140
Trademarks	140
Patents	140
Privacy policy	140
Open source	140

# **Cloud Backup documentation**

## What's new with Cloud Backup

Learn what's new in Cloud Backup.

## 13 July 2022

## Support has been added to back up SnapLock Enterprise volumes

Now you can use Cloud Backup to back up SnapLock Enterprise volumes to public and private clouds. This feature requires that your ONTAP system is running ONTAP 9.11.1 or later. SnapLock Compliance volumes, however, aren't currently supported.

# Now you can create backup files in the public cloud when using an on-premises Connector

In the past you needed to deploy the Connector in the same cloud provider as where you were creating backup files. Now you can use a Connector deployed in your premises to create backup files from on-prem ONTAP systems to Amazon S3, Azure Blob, and Google Cloud Storage. (An on-prem Connector was always required when creating backup files on StorageGRID systems.)

# Additional features are available when creating backup policies for ONTAP systems

- Backup on a yearly schedule is now available. The default retention value is 1 for yearly backups, but you can change this value if you want to have access to many previous years' backup files.
- You can name your backup policies so you can identify your policies with more descriptive text.

## 14 June 2022

# Support has been added to back up on-premises ONTAP cluster data in sites without internet access

If your on-prem ONTAP cluster resides in a site with no internet access, also known as a dark site or offline site, now you can use Cloud Backup to back up volume data to a NetApp StorageGRID system that resides in the same site. This functionality requires that the Cloud Manager Connector (version 3.9.19 or greater) is also deployed in the offline site.

See how to install the Connector in your offline site.

See how to back up ONTAP data to StorageGRID in your offline site.

## 8 June 2022

## Cloud Backup for Virtual Machines 1.1.0 is now GA

You can protect data on your virtual machines by integrating the SnapCenter Plug-in for VMware vSphere with Cloud Manager. You can back up datastores to the cloud and restore virtual machines back to the on-premises SnapCenter Plug-in for VMware vSphere with ease.

Learn more about protecting virtual machines to cloud.

### Cloud Restore instance is not needed for ONTAP Browse & Restore functionality

A separate Cloud Restore instance/virtual machine used to be required for file-level Browse & Restore operations from S3 and Blob storage. This instance shut down when not in use — but it still added some time and cost when restoring files. This functionality has been replaced with a no-cost container that gets deployed on the Connector when needed. It provides the following advantages:

- · No added cost for file-level restore operations
- Faster file-level restore operations
- Support for Browse & Restore operations for files from the cloud when the Connector is installed on your premises

Note that the Cloud Restore instance/VM will be removed automatically if you were previously using it. A Cloud Backup process will run once a day to delete all old Cloud Restore instances. This change is completely transparent — there is no effect on your data, and you won't notice any changes to your backup or restore jobs.

## Browse & Restore support for files from Google Cloud and StorageGRID storage

With the addition of the container for Browse & Restore operations (as described above), file restore operations now can be performed from backup files stored in Google Cloud and StorageGRID systems. Now Browse & Restore can be used to restore files across all public cloud providers and from StorageGRID. See how to use Browse & Restore to restore volumes and files from your ONTAP backups.

## Drag and drop to enable Cloud Backup to S3 storage

If the Amazon S3 destination for your backups exists as a working environment on the Canvas, you can drag your on-prem ONTAP cluster or Cloud Volumes ONTAP system (installed in AWS) onto the Amazon S3 working environment to initiate the setup wizard.

# Automatically apply a backup policy to newly created volumes in Kubernetes clusters

If you added new persistent volumes to your Kubernetes clusters after Cloud Backup was activated, in the past you needed to remember to configure backups for those volumes. Now you can select a policy that will be applied automatically to newly created volumes from the *Backup Settings* page for clusters that have already activated Cloud Backup.

## Cloud Backup APIs are now available for managing backup and restore operations

The APIs are available at https://docs.netapp.com/us-en/cloud-manager-automation/cbs/overview.html. See this page for an overview of the APIs.

## 2 May 2022

## Search & Restore is now supported with backup files in Google Cloud Storage

The Search & Restore method of restoring volumes and files was introduced in April for users who store their backup files in AWS. Now the capability is available for users who store their backup files in Google Cloud Storage. See how to restore your volumes and files using Search & Restore.

# Configure a backup policy to be applied automatically to newly created volumes in Kubernetes clusters

If you added new persistent volumes to your Kubernetes clusters after Cloud Backup was activated, in the past you needed to remember to configure backups for those volumes. Now you can select a policy that will be applied automatically to newly created volumes. This option is available in the setup wizard when activating Cloud Backup for a new Kubernetes cluster.

# Cloud Backup now requires a license before being activated on a working environment

There are a few changes to how licensing is implemented with Cloud Backup:

- You must sign up for a PAYGO Marketplace subscription from your cloud provider, or purchase a BYOL license from NetApp, before you can activate Cloud Backup.
- The 30-day Free Trial is available only when using a PAYGO subscription from your cloud provider it is not available when using the BYOL license.
- The Free Trial starts the day the Marketplace subscription starts. For example, if you activate the Free Trial after you have been using a Marketplace subscription for 30 days for a Cloud Volumes ONTAP system, the Cloud Backup Trial will not be available.

Learn more about the available licensing models.

## 4 April 2022

## Cloud Backup for Applications 1.1.0 (powered by SnapCenter) is now GA

The new Cloud Backup for Applications capability enables you to offload existing application consistent Snapshots (backups) for Oracle and Microsoft SQL from on-premises primary storage to cloud object storage in Amazon S3 or Azure Blob.

When required, you can restore this data from cloud to on-premises.

Learn more about protecting on-premises applications data to the cloud.

# New Search & Restore feature to search for volumes or files across all ONTAP backup files

Now you can search for a volume or file across **all ONTAP backup files** by partial or full volume name, partial or full file name, size range, and additional search filters. This is a great new way to find the data you want to restore if you are not sure which cluster or volume was the source for the data. Learn how to use Search & Restore.

## 3 March 2022

# Ability to back up persistent volumes from your GKE Kubernetes clusters to Google Cloud storage

If your GKE cluster has NetApp Astra Trident installed, and it's using Cloud Volumes ONTAP for GCP as backend storage for the cluster, then you can back up and restore your persistent volumes to and from Google Cloud storage. Go here for details.

# The Beta capability to use Cloud Data Sense to scan your Cloud Backup files has been discontinued in this release

## **14 February 2022**

## Now you can assign backup policies to individual volumes in a single cluster

In the past you could assign only a single backup policy to all volumes in a cluster. Now you can create multiple backup policies for a single cluster and apply different policies to different volumes. See how to create new backup policies for a cluster and assign them to selected volumes.

# A new option enables you to automatically apply a default backup policy to newly created volumes

In the past, new volumes created in a working environment after Cloud Backup was activated required that you manually apply a backup policy. Now, regardless of if the volume was created in Cloud Manager, System Manager, the CLI, or by using APIs, Cloud Backup will discover the volume and apply the backup policy you have chosen as the default policy.

This option is available when enabling backup in a new working environment, or from the *Manage Volumes* page for existing working environments.

# New Job Monitor is available to see the in-process status of all backup and restore jobs

The Job Monitor can be very helpful when you have initiated an operation against multiple volumes, like changing the backup policy, or deleting backups, so you can see when the operation has completed on all volumes. See how to use the Job Monitor.

## **2 January 2022**

# Ability to back up persistent volumes from your AKS Kubernetes clusters to Azure Blob storage

If your AKS cluster has NetApp Astra Trident installed, and it's using Cloud Volumes ONTAP for Azure as backend storage for the cluster, then you can back up and restore volumes to and from Azure Blob storage. Go here for details.

# Cloud Backup service charges have been changed in this release to align more closely with industry standards

Instead of paying NetApp for capacity based on the size of your backup files, now you pay only for the data that you protect, calculated by the logical used capacity (before ONTAP efficiencies) of the source ONTAP volumes which are being backed up. This capacity is also known as Front-End Terabytes (FETB).

## **28 November 2021**

# Ability to back up persistent volumes from your EKS Kubernetes clusters to Amazon S3

If your EKS cluster has NetApp Astra Trident installed, and it's using Cloud Volumes ONTAP for AWS as backend storage for the cluster, then you can back up and restore volumes to and from Amazon S3. Go here for details.

## **Enhanced functionality to back up DP volumes**

Cloud Backup now supports creating backups of DP volumes that exist on the target ONTAP system in an SVM-DR relationship. There are a few restrictions, so see the limitations for details.

## 5 November 2021

# Ability to select a private endpoint when restoring a volume to an on-premises ONTAP system

When restoring a volume to an on-premises ONTAP system from a backup file that resides on Amazon S3 or Azure Blob, now you can select a private endpoint that connects to your on-prem system privately and securely.

# Now you can tier older backup files to archival storage after a number of days to save costs

If your cluster is running ONTAP 9.10.1 or greater, and you're using AWS or Azure cloud storage, you can enable tiering of backups to archival storage. See more information about AWS S3 archival storage classes and Azure Blob archival access tiers.

# Cloud Backup BYOL licenses have moved to the Data Services Licenses tab in the Digital Wallet

BYOL licensing for Cloud Backup has moved from the Cloud Backup Licenses tab to the Data Services Licenses tab in the Cloud Manager Digital Wallet.

## **4 October 2021**

# Backup file size is now available in the Backup page when performing a volume or file restore

This is useful if you want to delete large backup files that are unnecessary, or so you can compare backup file sizes to identify any abnormal backup files that could be the result of a malicious software attack.

### TCO calculator is available to compare Cloud Backup costs

The Total Cost of Ownership calculator helps you understand the total cost of ownership for Cloud Backup, and to compare these costs to traditional backup solutions and estimate potential savings. Check it out here.

### Ability to unregister Cloud Backup for a working environment

Now you can easily unregister Cloud Backup for a working environment if you no longer want to use backup functionality (or be charged) for that working environment.

## 2 September 2021

### Ability to create an on-demand backup of a volume

Now you can create an on-demand backup at any time to capture the current state of a volume. This is useful if important changes have been made to a volume and you don't want to wait for the next scheduled backup to protect that data.

See how to create an on-demand backup.

### Ability to define a Private Interface connection for secure backups to Amazon S3

When configuring backups to Amazon S3 from an on-premises ONTAP system, now you can define a connection to a Private Interface Endpoint in the activation wizard. This allows you to use a network interface that connects your on-prem system privately and securely to a service powered by AWS PrivateLink. See details about this option.

# Now you can choose your own customer-managed keys for data encryption when backing up data to Amazon S3

For additional security and control, you can choose your own customer-managed keys for data encryption in the activation wizard instead of using the default Amazon S3 encryption keys. This is available when configuring backups from an on-premises ONTAP system or from a Cloud Volumes ONTAP system in AWS.

## Now you can restore files from directories that have more than 30,000 files

## 1 August 2021

## Ability to define a Private Endpoint connection for secure backups to Azure Blob

When configuring backups to Azure Blob from an on-premises ONTAP system, you can define a connection to an Azure Private Endpoint in the activation wizard. This allows you to use a network interface that connects you privately and securely to a service powered by Azure Private Link.

## An Hourly backup policy is now supported

This new policy is in addition to the existing Daily, Weekly, and Monthly policies. The Hourly backup policy provides a minimal Recovery Point Objective (RPO).

## 7 July 2021

## Now you can create backups using different accounts and in different regions

Cloud Backup now allows you to create backups using a different account/subscription than the one you are using for your Cloud Volumes ONTAP system. You can also create backup files in a different region than the one in which your Cloud Volumes ONTAP system is deployed.

This capability is available when using when using AWS or Azure, and only when enabling backup on an existing working environment - it is not available when creating a new Cloud Volumes ONTAP working environment.

# Now you can choose your own customer-managed keys for data encryption when backing up data to Azure Blob

For additional security and control, you can choose your own customer-managed keys for data encryption in the activation wizard instead of using the default Microsoft-managed encryption keys. This is available when configuring backups from an on-premises ONTAP system or from a Cloud Volumes ONTAP system in Azure.

## Now you can restore up to 100 files at a time when using single-file restore

## 7 June 2021

### Limitations lifted for DP volumes when using ONTAP 9.8 or greater

Two known limitations for backing up data protection (DP) volumes have been resolved:

- Before, cascaded backup worked only if the SnapMirror relationship type was Mirror-Vault or Vault. Now
  you can make backups if the relationship type is MirrorAllSnapshots.
- Cloud Backup now can use any label for the backup as long as it is configured in the SnapMirror policy. The restriction of requiring labels with the names daily, weekly, or monthly is gone.

## 5 May 2021

# Back up on-prem cluster data to Google Cloud Storage or NetApp StorageGRID systems

Now you can create backups from your on-premises ONTAP systems to Google Cloud Storage or to your NetApp StorageGRID systems. See Backing up to Google Cloud Storage and Backing up to StorageGRID for details.

## Now you can use System Manager to perform Cloud Backup operations

A new feature in ONTAP 9.9.1 enables you to use System Manager to send backups of your on-premises ONTAP volumes to object storage you've set up through Cloud Backup. See how to use System Manager to back up your volumes to the cloud using Cloud Backup.

## Backup policies have been improved with a few enhancements

- Now you create a custom policy that includes a combination of daily, weekly, and monthly backups.
- When you change a backup policy, the change applies to all new backups **and** to all volumes using the original backup policy. In the past the change only applied to new volume backups.

## Miscellaneous backup and restore improvements

• When configuring the cloud destination for your backup files, now you can select a different region than the region in which the Cloud Volumes ONTAP system resides.

- The number of backup files you can create for a single volume has been increased from 1,019 to 4,000.
- In addition to the earlier ability to delete all backup files for a single volume, now you can delete just a single backup file for a volume, or you can delete all backup files for an entire working environment, if needed.

## **Get started**

## Learn about Cloud Backup

Cloud Backup is a service for Cloud Manager working environments that provides backup and restore capabilities for protection and long-term archive of your data. Backups are automatically generated and stored in an object store in your public or private cloud account.

When necessary, you can restore an entire *volume* from a backup to the same or different working environment. When backing up ONTAP data, you can also choose to restore or one or more *files* from a backup to the same or different working environment.

Learn more about Cloud Backup.

Backup & Restore can be used to:

- Back up and Restore ONTAP volumes from Cloud Volumes ONTAP and on-premises ONTAP systems.
   See detailed features here.
- Back up and Restore Kubernetes persistent volumes. See detailed features here.
- Back up the application consistent Snapshots from on-premises ONTAP to cloud using Cloud Backup for Applications. See detailed features here.
- Back up datastores to the cloud and restore virtual machines back to the on-premises vCenter using Cloud Backup for VMware. See detailed features here.




When the Cloud Manager Connector is deployed in a Government region in the cloud, or in a site without internet access (a dark site), Cloud Backup only supports backup and restore operations from ONTAP systems. When using these alternate deployment methods, Cloud Backup does not support backup and restore operations from Kubernetes clusters, Applications, or Virtual Machines.

## **How Cloud Backup works**

When you enable Cloud Backup on a Cloud Volumes ONTAP or on-premises ONTAP system, the service performs a full backup of your data. Volume snapshots are not included in the backup image. After the initial backup, all additional backups are incremental, which means that only changed blocks and new blocks are backed up. This keeps network traffic to a minimum.

In most cases you'll use the Cloud Manager UI for all backup operations. However, starting with ONTAP 9.9.1 you can initiate volume backup operations of your on-premises ONTAP clusters using ONTAP System Manager. See how to use System Manager to back up your volumes to the cloud using Cloud Backup.

The following image shows the relationship between each component:



#### Where backups reside

Backup copies are stored in an object store that Cloud Manager creates in your cloud account. There's one object store per cluster/working environment, and Cloud Manager names the object store as follows: "netapp-backup-clusteruuid". Be sure not to delete this object store.

- In Azure, Cloud Manager uses a new or existing resource group with a storage account for the Blob container. Cloud Manager blocks public access to your blob data by default.
- In StorageGRID, Cloud Manager uses an existing storage account for the object store bucket.

### Backups are taken at midnight

- Hourly backups start 5 minutes past the hour, every hour.
- · Daily backups start just after midnight each day.
- Weekly backups start just after midnight on Sunday mornings.
- Monthly backups start just after midnight on the first day of each month.
- Yearly backups start just after midnight on the first day of the year.

The start time is based on the time zone set on each source ONTAP system. You can't schedule backup operations at a user-specified time from the UI. For more information, contact your System Engineer.

#### Backup copies are associated with your NetApp account

Backup copies are associated with the NetApp account in which the Connector resides.

If you have multiple Connectors in the same NetApp account, each Connector will display the same list of backups. That includes the backups associated with Cloud Volumes ONTAP and on-premises ONTAP instances from other Connectors.

## **Set up licensing for Cloud Backup**

You can license Cloud Backup by purchasing a pay-as-you-go (PAYGO) marketplace subscription from your cloud provider, or by purchasing a bring-your-own-license (BYOL) from NetApp. A valid license is required to activate Cloud Backup on a working environment, to create backups of your production data, and to restore backup data to a production system.

A few notes before you read any further:

- If you've already subscribed to the Cloud Manager pay-as-you-go (PAYGO) subscription in your cloud provider's marketplace for a Cloud Volumes ONTAP system, then you're automatically subscribed to Cloud Backup as well. You won't need to subscribe again.
- The Cloud Backup bring-your-own-license (BYOL) is a floating license that you can use across all systems
  associated with your Cloud Manager account. So if you have sufficient backup capacity available from an
  existing BYOL license, you won't need to purchase another BYOL license.
- When backing up on-prem ONTAP data to StorageGRID, you need a BYOL license, but there's no cost for cloud provider storage space.

Learn more about the costs related to using Cloud Backup.

## 30-day free trial

A Cloud Backup 30-day free trial is available from the pay-as-you-go subscription in your cloud provider's marketplace. The free trial starts at the time that you subscribe to the marketplace listing. Note that if you pay for the marketplace subscription when deploying a Cloud Volumes ONTAP system, and then start your Cloud Backup free trial 10 days later, you'll have 20 days to use the free trial.

When the free trial ends, you'll be switched over automatically to the PAYGO subscription without interruption. If you decide not to continue using Cloud Backup, just unregister Cloud Backup from the working environment before the trial ends and you won't be charged.

## Use a Cloud Backup PAYGO subscription

For pay-as-you-go, you'll pay your cloud provider for object storage costs and for NetApp backup licensing costs on an hourly basis in a single subscription. You should subscribe even if you have a free trial or if you bring your own license (BYOL):

- Subscribing ensures that there's no disruption of service after your free trial ends. When the trial ends, you'll be charged hourly according to the amount of data that you back up.
- If you back up more data than allowed by your BYOL license, then data backup continues through your pay-as-you-go subscription. For example, if you have a 10 TiB BYOL license, all capacity beyond the 10 TiB is charged through the PAYGO subscription.

You won't be charged from your pay-as-you-go subscription during your free trial or if you haven't exceeded your BYOL license.

There are a few PAYGO plans for Cloud Backup:

- A "Cloud Backup" package that enables you to back up Cloud Volumes ONTAP data and on-premises ONTAP data.
- A "CVO Professional" package that enables you to bundle Cloud Volumes ONTAP and Cloud Backup. This
  includes unlimited backups for Cloud Volumes ONTAP volumes charged against this license (backup
  capacity is not counted against the license). This option doesn't enable you to back up on-premises
  ONTAP data.
- A "CVO Edge Cache" package has the same capabilities as the "CVO Professional" package, but it also
  includes support for Global File Cache. You are entitled to deploy one Global File Cache Edge system for
  each 3 TiB of provisioned capacity on the Cloud Volumes ONTAP system. This option is available only
  through the Azure Marketplace, and it doesn't enable you to back up on-premises ONTAP data.

Learn more about these capacity-based license packages.

Use these links to subscribe to Cloud Backup from your cloud provider marketplace:

· Azure: Go to the Cloud Manager Marketplace offering for pricing details.

#### Use an annual contract

Pay for Cloud Backup annually by purchasing an annual contract.

When using Azure, contact your NetApp sales representative to purchase an annual contract. The contract is available as a private offer in the Azure Marketplace.

After NetApp shares the private offer with you, you can select the annual plan when you subscribe from the Azure Marketplace during Cloud Backup activation.

## Use a Cloud Backup BYOL license

Bring-your-own licenses from NetApp provide 1-, 2-, or 3-year terms. You pay only for the data that you protect, calculated by the logical used capacity (*before* any efficiencies) of the source ONTAP volumes which are being backed up. This capacity is also known as Front-End Terabytes (FETB).

The BYOL Cloud Backup license is a floating license where the total capacity is shared across all systems associated with your Cloud Manager account. For ONTAP systems, you can get a rough estimate of the capacity you'll need by running the CLI command volume show-space -logical-used for the volumes you plan to back up.

If you don't have a Cloud Backup BYOL license, click the chat icon in the lower-right of Cloud Manager to purchase one.

Optionally, if you have an unassigned node-based license for Cloud Volumes ONTAP that you won't be using, you can convert it to a Cloud Backup license with the same dollar-equivalence and the same expiration date. Go here for details.

You use the Digital Wallet page in Cloud Manager to manage BYOL licenses. You can add new licenses, update existing licenses, and view license status from the Digital Wallet.

#### Obtain your Cloud Backup license file

After you've purchased your Cloud Backup license, you activate the license in Cloud Manager either by entering the Cloud Backup serial number and NSS account, or by uploading the NLF license file. The steps below show how to get the NLF license file if you plan to use that method.


If you're running Cloud Backup in an on-premises site that doesn't have internet access, meaning that you've deployed the Cloud Manager Connector on a host in the offline on-premises site, you'll need to obtain the license file from an internet-connected system. Activating the license using the serial number and NSS account is not available for offline (dark site) installations.

#### Steps

- 1. Sign in to the NetApp Support Site and click Systems > Software Licenses.
- 2. Enter your Cloud Backup license serial number.



- 3. In the License Key column, click Get NetApp License File.
- 4. Enter your Cloud Manager Account ID (this is called a Tenant ID on the support site) and click **Submit** to download the license file.



You can find your Cloud Manager Account ID by selecting the **Account** drop-down from the top of Cloud Manager, and then clicking **Manage Account** next to your account. Your Account ID is in the Overview tab.

#### Add Cloud Backup BYOL licenses to your account


After you purchase a Cloud Backup license for your NetApp account, you need to add the license to Cloud Manager.

#### **Steps**

- 1. From the Cloud Manager left navigation menu, click **Digital Wallet** and then select the **Data Services Licenses** tab.
- Click Add License.
- 3. In the Add License dialog, enter the license information and click Add License:
  - If you have the backup license serial number and know your NSS account, select the **Enter Serial Number** option and enter that information.

If your NetApp Support Site account isn't available from the drop-down list, add the NSS account to Cloud Manager.

If you have the backup license file (required when installed in a dark site), select the Upload License
 File option and follow the prompts to attach the file.




#### Result

Cloud Manager adds the license so that Cloud Backup is active.

### **Update a Cloud Backup BYOL license**

If your licensed term is nearing the expiration date, or if your licensed capacity is reaching the limit, you'll be notified in the Backup UI. This status also appears in the Digital Wallet page and in Notifications.



You can update your Cloud Backup license before it expires so that there is no interruption in your ability to back up and restore your data.

#### Steps

- 1. Click the chat icon in the lower-right of Cloud Manager, or contact Support, to request an extension to your term or additional capacity to your Cloud Backup license for the particular serial number.
  - After you pay for the license and it is registered with the NetApp Support Site, Cloud Manager automatically updates the license in the Digital Wallet and the Data Services Licenses page will reflect the change in 5 to 10 minutes.
- 2. If Cloud Manager can't automatically update the license (for example, when installed in a dark site), then you'll need to manually upload the license file.
  - a. You can obtain the license file from the NetApp Support Site.
  - b. On the Digital Wallet page *Data Services Licenses* tab, click ••• for the service serial number you are updating, and click **Update License**.



c. In the *Update License* page, upload the license file and click **Update License**.

#### Result

Cloud Manager updates the license so that Cloud Backup continues to be active.

#### **BYOL license considerations**

When using a Cloud Backup BYOL license, Cloud Manager displays a warning in the user interface when the size of all the data you are backing up is nearing the capacity limit or nearing the license expiration date. You'll receive these warnings:

- When backups have reached 80% of licensed capacity, and again when you have reached the limit
- 30 days before a license is due to expire, and again when the license expires

Use the chat icon in the lower right of the Cloud Manager interface to renew your license when you see these warnings.

Two things can happen when your BYOL license expires:

- If the account you are using has a marketplace account, the backup service continues to run, but you are shifted over to a PAYGO licensing model. You are charged for the capacity that your backups are using.
- If the account you are using doesn't have a marketplace account, the backup service continues to run, but you will continue to see the warnings.

Once you renew your BYOL subscription, Cloud Manager automatically updates the license. If Cloud Manager can't access the license file over the secure internet connection (for example, when installed in a dark site), you can obtain the file yourself and manually upload it to Cloud Manager. For instructions, see how to update a Cloud Backup license.

Systems that were shifted over to a PAYGO license are returned to the BYOL license automatically. And systems that were running without a license will stop seeing the warnings.

## Back up and restore ONTAP data

## Protect your ONTAP cluster data using Cloud Backup

Cloud Backup provides backup and restore capabilities for protection and long-term archive of your ONTAP cluster data. Backups are automatically generated and stored in an object store in your public or private cloud account, independent of volume Snapshot copies used for near-term recovery or cloning.

When necessary, you can restore an entire *volume*, or one or more *files*, from a backup to the same or different working environment.

#### **Features**

#### Backup features:

- Back up independent copies of your data volumes to low-cost object storage.
- Apply a single backup policy to all volumes in a cluster, or assign different backup policies to volumes that have unique recovery point objectives.
- Name your backup policies so it is easy to see what each policy is used for.
- Tier older backup files to archival storage to save costs (supported when using ONTAP 9.10.1+)
- Back up from cloud to cloud, and from on-premises systems to public or private cloud.
- For Cloud Volumes ONTAP systems, your backups can reside on a different subscription/account or different region.
- Backup data is secured with AES-256 bit encryption at-rest and TLS 1.2 HTTPS connections in-flight.
- Use your own customer-managed keys for data encryption instead of using the default encryption keys from your cloud provider.
- Support for up to 4,000 backups of a single volume.

#### Restore features:

- Restore data from a specific point in time.
- Restore a volume, or individual files, to the source system or to a different system.
- Restore data to a working environment using a different subscription/account or that is in a different region.
- Restores data on a block level, placing the data directly in the location you specify, all while preserving the original ACLs.
- Browsable and searchable file catalogs for selecting individual files for single file restore.

## Supported ONTAP working environments and object storage providers

Cloud Backup enables you to back up ONTAP volumes from the following working environments to object storage in the following public and private cloud providers:

Source Working Environment	Backup File Destination
Cloud Volumes ONTAP in Azure	Azure Blob

Source Working Environment	Backup File Destination
On-premises ONTAP system	Azure Blob NetApp StorageGRID

You can restore a volume, or individual files, from an ONTAP backup file to the following working environments:

Backup File	Destination Working Environment		
Location	Volume Restore	File Restore	
Azure Blob	Cloud Volumes ONTAP in Azure On-premises ONTAP system	Cloud Volumes ONTAP in Azure On-premises ONTAP system	
NetApp StorageGRID	On-premises ONTAP system	On-premises ONTAP system	

Note that references to "on-premises ONTAP systems" includes FAS, AFF, and ONTAP Select systems.

#### Support for sites with no internet connectivity

Cloud Backup can be used in a site with no internet connectivity (also known as an "offline" or "dark" site) to back up volume data from local on-premises ONTAP systems to local NetApp StorageGRID systems. Both volume and file restore are also supported in this configuration. In this case, you'll need to deploy the Cloud Manager Connector (minimum version 3.9.20) in the dark site. See Backing up on-premises ONTAP data to StorageGRID for details.

#### Cost

There are two types of costs associated with using Cloud Backup with ONTAP systems: resource charges and service charges.

#### Resource charges

Resource charges are paid to the cloud provider for object storage capacity and for running a virtual machine/instance in the cloud.

- For Backup, you pay your cloud provider for object storage costs.
  - Since Cloud Backup preserves the storage efficiencies of the source volume, you pay the cloud provider object storage costs for the data *after* ONTAP efficiencies (for the smaller amount of data after deduplication and compression have been applied).
- For Volume or File Restore using Search & Restore, certain resources are provisioned by your cloud provider and there is per-TiB cost associated with the amount of data that is scanned by your search requests.
- If you need to restore volume data from a backup file that has been moved to archival storage, then there's an additional per-GiB retrieval fee and per-request fee from the cloud provider.

#### Service charges

Service charges are paid to NetApp and cover both the cost to *create* backups and to *restore* volumes, or files, from those backups. You pay only for the data that you protect, calculated by the source logical used capacity (*before* ONTAP efficiencies) of ONTAP volumes which are backed up to object storage. This capacity is also known as Front-End Terabytes (FETB).

There are three ways to pay for the Backup service. The first option is to subscribe from your cloud provider, which enables you to pay per month. The second option is to get an annual contract. The third option is to purchase licenses directly from NetApp. Read the Licensing section for details.

## Licensing

Cloud Backup is available with the following consumption models:

- BYOL: A license purchased from NetApp that can be used with any cloud provider.
- PAYGO: An hourly subscription from your cloud provider's marketplace.
- Annual: An annual contract from your cloud provider's marketplace.

If you purchase a BYOL license from NetApp, you also need to subscribe to the PAYGO offering from your cloud provider's marketplace. Your license is always charged first, but you'll be charged from the hourly rate in the marketplace in these cases:



- · If you exceed your licensed capacity
- If the term of your license expires

If you have an annual contract from a marketplace, all Cloud Backup consumption is charged against that contract. You can't mix and match an annual marketplace contract with a BYOL.

### Bring your own license

BYOL is term-based (12, 24, or 36 months) *and* capacity-based in 1 TiB increments. You pay NetApp to use the service for a period of time, say 1 year, and for a maximum amount capacity, say 10 TiB.

You'll receive a serial number that you enter in the Cloud Manager Digital Wallet page to enable the service. When either limit is reached, you'll need to renew the license. The Backup BYOL license applies to all source systems associated with your Cloud Manager account.

Learn how to manage your BYOL licenses.

## Pay-as-you-go subscription

Cloud Backup offers consumption-based licensing in a pay-as-you-go model. After subscribing through your cloud provider's marketplace, you pay per GiB for data that's backed up—there's no up-front payment. You are billed by your cloud provider through your monthly bill.

Learn how to set up a pay-as-you-go subscription.

Note that a 30-day free trial is available when you initially sign up with a PAYGO subscription.

#### **Annual contract**

• When using Azure, you can request a private offer from NetApp, and then select the plan when you subscribe from the Azure Marketplace during Cloud Backup activation.

Learn how to set up annual contracts.

## **How Cloud Backup works**


When you enable Cloud Backup on a Cloud Volumes ONTAP or on-premises ONTAP system, the service performs a full backup of your data. Volume snapshots are not included in the backup image. After the initial backup, all additional backups are incremental, which means that only changed blocks and new blocks are backed up. This keeps network traffic to a minimum.

In most cases you'll use the Cloud Manager UI for all backup operations. However, starting with ONTAP 9.9.1 you can initiate volume backup operations of your on-premises ONTAP clusters using ONTAP System Manager. See how to use System Manager to back up your volumes to the cloud using Cloud Backup.



Any actions taken directly from your cloud provider environment to manage or change backup files may corrupt the files and will result in an unsupported configuration.

The following image shows the relationship between each component:



#### Where backups reside

Backup copies are stored in an object store that Cloud Manager creates in your cloud account. There's one object store per cluster/working environment, and Cloud Manager names the object store as follows: "netapp-backup-clusteruuid". Be sure not to delete this object store.

• In Azure, Cloud Manager uses a new or existing resource group with a storage account for the Blob container. Cloud Manager blocks public access to your blob data by default.

• In StorageGRID, Cloud Manager uses an existing storage account for the object store bucket.

If you want to change the destination object store for a cluster in the future, you'll need to unregister Cloud Backup for the working environment, and then enable Cloud Backup using the new cloud provider information.

### Supported storage classes or access tiers

• In Azure, backups are associated with the Cool access tier.

If your cluster is using ONTAP 9.10.1 or greater, you can choose to tier older backups to *Azure Archive* storage after a certain number of days for further cost optimization. Learn more about Azure archival storage.

• In StorageGRID, backups are associated with the *Standard* storage class.

### Customizable backup schedule and retention settings per cluster

When you enable Cloud Backup for a working environment, all the volumes you initially select are backed up using the default backup policy that you define. If you want to assign different backup policies to certain volumes that have different recovery point objectives (RPO), you can create additional policies for that cluster and assign those policies to the other volumes after Backup is activated.

You can choose a combination of hourly, daily, weekly, monthly, and yearly backups of all volumes. You can also select one of the system-defined policies that provide backups and retention for 3 months, 1 year, and 7 years. These policies are:

<b>Backup Policy Name</b>	Backups per interval			Max. Backups
	Daily	Weekly	Monthly	
Netapp3MonthsRetention	30	13	3	46
Netapp1YearRetention	30	13	12	55
Netapp7YearsRetention	30	53	84	167

Backup protection policies that you have created on the cluster using ONTAP System Manager or the ONTAP CLI will also appear as selections.

Once you have reached the maximum number of backups for a category, or interval, older backups are removed so you always have the most current backups (and so obsolete backups don't continue to take up space in the cloud).

Note that you can create an on-demand backup of a volume from the Backup Dashboard at any time, in addition to those backup files created from the scheduled backups.



The retention period for backups of data protection volumes is the same as defined in the source SnapMirror relationship. You can change this if you want by using the API.

## FabricPool tiering policy considerations

There are certain things you need to be aware of when the volume you are backing up resides on a FabricPool aggregate and it has an assigned policy other than none:

• The first backup of a FabricPool-tiered volume requires reading all local and all tiered data (from the object

store). A backup operation does not "reheat" the cold data tiered in object storage.

This operation could cause a one-time increase in cost to read the data from your cloud provider.

- Subsequent backups are incremental and do not have this effect.
- If the tiering policy is assigned to the volume when it is initially created you will not see this issue.
- Consider the impact of backups before assigning the all tiering policy to volumes. Because data is tiered immediately, Cloud Backup will read data from the cloud tier rather than from the local tier. Because concurrent backup operations share the network link to the cloud object store, performance degradation might occur if network resources become saturated. In this case, you may want to proactively configure multiple network interfaces (LIFs) to decrease this type of network saturation.

### Supported volumes

Cloud Backup supports the following types of volumes:

- FlexVol read-write volumes
- SnapMirror data protection (DP) destination volumes
- SnapLock Enterprise volumes (requires ONTAP 9.11.1 or later)

FlexGroup volumes and SnapLock Compliance volumes aren't currently supported.

### Limitations

- The ability to tier older backup files to archival storage requires that the cluster is running ONTAP 9.10.1 or greater. Restoring volumes from backup files that reside in archival storage also requires that the destination cluster is running ONTAP 9.10.1+.
- When creating or editing a backup policy when no volumes are assigned to the policy, the number of
  retained backups can be a maximum of 1018. As a workaround you can reduce the number of backups to
  create the policy. Then you can edit the policy to create up to 4000 backups after you assign volumes to
  the policy.
- When backing up data protection (DP) volumes, relationships with the following SnapMirror labels won't be backed up to cloud:
  - app\_consistent
  - all\_source\_snapshot
- SVM-DR volume backup is supported with the following restrictions:
  - Backups are supported from the ONTAP secondary only.
  - The Snapshot policy applied to the volume must be one of the policies recognized by Cloud Backup, including daily, weekly, monthly, etc. The default "sm\_created" policy (used for Mirror All Snapshots) is not recognized and the DP volume will not be shown in the list of volumes that can be backed up.
- Ad-hoc volume backups using the **Backup Now** button aren't supported on data protection volumes.
- · SM-BC configurations are not supported.
- MetroCluster (MCC) backup is supported from ONTAP secondary only: MCC > SnapMirror > ONTAP > Cloud Backup > object storage.
- ONTAP doesn't support fan-out of SnapMirror relationships from a single volume to multiple object stores; therefore, this configuration is not supported by Cloud Backup.
- WORM/Compliance mode on an object store is not supported.

#### Single File Restore limitations

These limitations apply to both the Search & Restore and the Browse & Restore methods of restoring files; unless called out specifically.

- Browse & Restore can restore up to 100 individual files at a time.
- Search & Restore can restore 1 file at a time.
- There is currently no support for restoring folders/directories.
- The file being restored must be using the same language as the language on the destination volume. You will receive an error message if the languages are not the same.
- File level restore is not supported when using the same account with different Cloud Managers in different subnets.
- You can't restore individual files if the backup file resides in archival storage.
- File level restore using Search & Restore is not supported when the Connector is installed on a site without internet access (dark site).

# Backing up Cloud Volumes ONTAP data to Azure Blob storage

Complete a few steps to get started backing up data from Cloud Volumes ONTAP to Azure Blob storage.

### **Quick start**

Get started quickly by following these steps or scroll down to the remaining sections for full details.



### Verify support for your configuration

- You're running Cloud Volumes ONTAP 9.7P5 or later in Azure.
- · You have a valid cloud provider subscription for the storage space where your backups will be located.
- You have subscribed to the Cloud Manager Marketplace Backup offering, or you have purchased and activated a Cloud Backup BYOL license from NetApp.



### Enable Cloud Backup on your new or existing system

- New systems: Cloud Backup is enabled by default in the working environment wizard. Be sure to keep the option enabled.
- Existing systems: Select the working environment and click **Enable** next to the Backup & Restore service in the right-panel, and then follow the setup wizard.





### Enter the provider details

Select the provider subscription and region, and choose whether you want to create a new resource group or use an already existing resource group. You can also choose your own customer-managed keys for data encryption instead of using the default Microsoft-managed encryption key.






#### Define the default backup policy

The default policy backs up volumes every day and retains the most recent 30 backup copies of each volume. Change to hourly, daily, weekly, monthly, or yearly backups, or select one of the system-defined policies that provide more options. You can also change the number of backup copies you want to retain.

By default, backups are stored in the Cool access tier. If your cluster is using ONTAP 9.10.1 or greater, you can choose to tier backups to Azure Archive storage after a certain number of days for further cost optimization.






### Select the volumes that you want to back up

Identify which volumes you want to back up using the default backup policy in the Select Volumes page. If you want to assign different backup policies to certain volumes, you can create additional policies and apply them to volumes later.

### Requirements

Read the following requirements to make sure that you have a supported configuration before you start backing up volumes to Azure Blob storage.

The following image shows each component and the connections that you need to prepare between them:



#### **Supported ONTAP versions**

Minimum of ONTAP 9.7P5; ONTAP 9.8P11 and later is recommended.

#### License requirements

For Cloud Backup PAYGO licensing, a subscription through the Azure Marketplace is required before you enable Cloud Backup. Billing for Cloud Backup is done through this subscription. You can subscribe from the Details & Credentials page of the working environment wizard.

For Cloud Backup BYOL licensing, you need the serial number from NetApp that enables you to use the service for the duration and capacity of the license. Learn how to manage your BYOL licenses.

And you need to have a Microsoft Azure subscription for the storage space where your backups will be located.

#### **Supported Azure regions**

Cloud Backup is supported in all Azure regions where Cloud Volumes ONTAP is supported; including Azure Government regions.

#### Required setup for creating backups in a different Azure subscription

By default, backups are created using the same subscription as the one used for your Cloud Volumes ONTAP system. If you want to use a different Azure subscription for your backups, you must log in to the Azure portal and link the two subscriptions.

#### Required information for using customer-managed keys for data encryption

You can use your own customer-managed keys for data encryption in the activation wizard instead of using the default Microsoft-managed encryption keys. In this case you will need to have the Azure Subscription, Key Vault name, and the Key. See how to use your own keys.

### **Enabling Cloud Backup on a new system**

Cloud Backup is enabled by default in the working environment wizard. Be sure to keep the option enabled.

See Launching Cloud Volumes ONTAP in Azure for requirements and details for creating your Cloud Volumes ONTAP system.



If you want to pick the name of the resource group, **disable** Cloud Backup when deploying Cloud Volumes ONTAP. Follow the steps for enabling Cloud Backup on an existing system to enable Cloud Backup and choose the resource group.

#### Steps

- 1. Click Create Cloud Volumes ONTAP.
- 2. Select Microsoft Azure as the cloud provider and then choose a single node or HA system.
- 3. In the Define Azure Credentials page, enter the credentials name, client ID, client secret, and directory ID, and click **Continue**.
- 4. Fill out the Details & Credentials page and be sure that an Azure Marketplace subscription is in place, and click **Continue**.
- 5. On the Services page, leave the service enabled and click Continue.



6. Complete the pages in the wizard to deploy the system.

#### Result

Cloud Backup is enabled on the system and backs up volumes every day and retains the most recent 30 backup copies.

#### What's next?

You can start and stop backups for volumes or change the backup schedule.

You can also restore entire volumes or individual files from a backup file to a Cloud Volumes ONTAP system in Azure, or to an on-premises ONTAP system.

### **Enabling Cloud Backup on an existing system**

Enable Cloud Backup at any time directly from the working environment.

#### Steps

Select the working environment and click Enable next to the Backup & Restore service in the right-panel.




- 2. Select the provider details and click Next.
  - a. The Azure subscription used to store the backups. This can be a different subscription than where the Cloud Volumes ONTAP system resides.

If you want to use a different Azure subscription for your backups, you must log in to the Azure portal and link the two subscriptions.


- b. The region where the backups will be stored. This can be a different region than where the Cloud Volumes ONTAP system resides.
- c. The resource group that manages the Blob container you can create a new resource group or select an existing resource group.
- d. Whether you'll use the default Microsoft-managed encryption key or choose your own customer-managed keys to manage encryption of your data. (See how to use your own keys).



- 3. Enter the backup policy details that will be used for your default policy and click **Next**. You can select an existing policy, or you can create a new policy by entering your selections in each section:
  - a. Enter the name for the default policy. You don't need to change the name.
  - b. Define the backup schedule and choose the number of backups to retain. See the list of existing policies you can choose.
  - c. When using ONTAP 9.10.1 and greater, you can choose to tier backups to Azure Archive storage after a certain number of days for further cost optimization. Learn more about using archival tiers.



4. Select the volumes that you want to back up using the default backup policy in the Select Volumes page. If you want to assign different backup policies to certain volumes, you can create additional policies and apply them to those volumes later.



- To back up all volumes, check the box in the title row ( Volume Name ).
- To back up individual volumes, check the box for each volume (
   ✓ volume 1).
- 5. If you want all volumes added in the future to have backup enabled, just leave the checkbox for "Automatically back up future volumes..." checked. If you disable this setting, you'll need to manually enable backups for future volumes.
- 6. Click **Activate Backup** and Cloud Backup starts taking the initial backups of each selected volume.

#### Result

Cloud Backup starts taking the initial backups of each selected volume and the Volume Backup Dashboard is displayed so you can monitor the state of the backups.

#### What's next?

You can start and stop backups for volumes or change the backup schedule.

You can also restore entire volumes or individual files from a backup file to a Cloud Volumes ONTAP system in Azure, or to an on-premises ONTAP system.

## Backing up on-premises ONTAP data to Azure Blob storage

Complete a few steps to get started backing up data from your on-premises ONTAP systems to Azure Blob storage.

Note that "on-premises ONTAP systems" includes FAS, AFF, and ONTAP Select systems.

#### **Quick start**

Get started quickly by following these steps, or scroll down to the remaining sections for full details.



### Verify support for your configuration

- You have discovered the on-premises cluster and added it to a working environment in Cloud Manager.
   See Discovering ONTAP clusters for details.
  - The cluster is running ONTAP 9.7P5 or later.
  - The cluster has a SnapMirror license it is included as part of the Premium Bundle or Data Protection Bundle.
  - The cluster must have the required network connections to Blob storage and to the Connector.
- The Connector must have the required network connections to Blob storage and to the cluster, and the required permissions.
- You have a valid Azure subscription for the object storage space where your backups will be located.



### **Enable Cloud Backup on the system**


Select the working environment and click **Enable > Backup Volumes** next to the Backup & Restore service in the right-panel, and then follow the setup wizard.





#### Select the cloud provider and enter the provider details


Select Microsoft Azure as your provider and then enter the provider details. You'll need to select the Azure Subscription and the region where you want to create the backups. You can also choose your own customermanaged key for data encryption instead of using the default Microsoft-managed encryption key.





### Select the cluster IPspace and optional use of a private VNet endpoint

Select the IPspace in the ONTAP cluster where the volumes reside. You can also choose to use an existing Azure Private Endpoint for a more secure connection to the VNet from your on-prem data center.






### Define the default backup policy

The default policy backs up volumes every day and retains the most recent 30 backup copies of each volume. Change to hourly, daily, weekly, monthly, or yearly backups, or select one of the system-defined policies that provide more options. You can also change the number of backup copies you want to retain.

By default, backups are stored in the Cool access tier. If your cluster is using ONTAP 9.10.1 or greater, you can choose to tier backups to Azure Archive storage after a certain number of days for further cost optimization.





## Select the volumes that you want to back up

Identify which volumes you want to back up using the default backup policy in the Select Volumes page. If you want to assign different backup policies to certain volumes, you can create additional policies and apply them to volumes later.


## Requirements

Read the following requirements to make sure you have a supported configuration before you start backing up on-premises volumes to Azure Blob storage.


There are two connection methods you can use when configuring backups from on-premises ONTAP systems to Azure Blob.

- Public connection Directly connect the ONTAP system to Azure Blob storage using a public Azure endpoint.
- Private connection Use a VPN or ExpressRoute and route traffic through a VNet Private Endpoint that uses a private IP address.

The following diagram shows the **public connection** method and the connections that you need to prepare between the components. You can use a Connector that you've installed on your premises, or a Connector that you've deployed in the Azure VNet.



The following diagram shows the **private connection** method and the connections that you need to prepare between the components. You can use a Connector that you've installed on your premises, or a Connector that you've deployed in the Azure VNet.



### **Preparing your ONTAP clusters**

You need to discover your on-premises ONTAP clusters in Cloud Manager before you can start backing up volume data.

Learn how to discover a cluster.

# **ONTAP** requirements

- Minimum of ONTAP 9.7P5; ONTAP 9.8P11 and later is recommended.
- A SnapMirror license (included as part of the Premium Bundle or Data Protection Bundle).

Note: The "Hybrid Cloud Bundle" is not required when using Cloud Backup.

See how to manage your cluster licenses.

· Time and time zone are set correctly.

See how to configure your cluster time.

# Cluster networking requirements

• The ONTAP cluster initiates an HTTPS connection over port 443 from the intercluster LIF to Azure Blob storage for backup and restore operations.

ONTAP reads and writes data to and from object storage. The object storage never initiates, it just responds.

- ONTAP requires an inbound connection from the Connector to the cluster management LIF. The Connector can reside in an Azure VNet.
- An intercluster LIF is required on each ONTAP node that hosts the volumes you want to back up. The LIF must be associated with the *IPspace* that ONTAP should use to connect to object storage. Learn more about IPspaces.

When you set up Cloud Backup, you are prompted for the IPspace to use. You should choose the IPspace that each LIF is associated with. That might be the "Default" IPspace or a custom IPspace that you created.

- The nodes' and intercluster LIFs are able to access the object store.
- DNS servers have been configured for the storage VM where the volumes are located. See how to configure DNS services for the SVM.
- Note that if you use are using a different IPspace than the Default, then you might need to create a static route to get access to the object storage.
- Update firewall rules, if necessary, to allow Cloud Backup service connections from ONTAP to object storage through port 443 and name resolution traffic from the storage VM to the DNS server over port 53 (TCP/UDP).

### **Creating or switching Connectors**

If you already have a Connector deployed in your Azure VNet or on your premises, then you're all set. If not, then you'll need to create a Connector in either of those locations to back up ONTAP data to Azure Blob storage. You can't use a Connector that's deployed in another cloud provider.

Learn about Connectors

- Getting started with Connectors
- · Installing a Connector in Azure
- · Installing a Connector in your premises

# **Preparing networking for the Connector**

Ensure that the Connector has the required networking connections.

### **Steps**

- 1. Ensure that the network where the Connector is installed enables the following connections:
  - An outbound internet connection to the Cloud Backup service over port 443 (HTTPS)
  - An HTTPS connection over port 443 to your Blob object storage
  - An HTTPS connection over port 443 to your ONTAP cluster management LIF
- 2. Enable a VNet Private Endpoint to Azure storage. This is needed if you have an ExpressRoute or VPN connection from your ONTAP cluster to the VNet and you want communication between the Connector and Blob storage to stay in your virtual private network (a **private** connection).

### Supported regions

You can create backups from on-premises systems to Azure Blob in all regions where Cloud Volumes ONTAP is supported; including Azure Government regions. You specify the region where the backups will be stored when you set up the service.

# Verify license requirements

- Before you can activate Cloud Backup for your cluster, you'll need to either subscribe to a pay-as-you-go
  (PAYGO) Cloud Manager Marketplace offering from Azure, or purchase and activate a Cloud Backup
  BYOL license from NetApp. These licenses are for your account and can be used across multiple systems.
  - For Cloud Backup PAYGO licensing, you'll need a subscription to the Azure Cloud Manager
     Marketplace offering to use Cloud Backup. Billing for Cloud Backup is done through this subscription.
  - For Cloud Backup BYOL licensing, you'll need the serial number from NetApp that enables you to use the service for the duration and capacity of the license. Learn how to manage your BYOL licenses.
- · You need to have an Azure subscription for the object storage space where your backups will be located.

You can create backups from on-premises systems to Azure Blob in all regions where Cloud Volumes ONTAP is supported; including Azure Government regions. You specify the region where backups will be stored when you set up the service.

### **Preparing Azure Blob storage for backups**

- 1. You can use your own custom-managed keys for data encryption in the activation wizard instead of using the default Microsoft-managed encryption keys. In this case you will need to have the Azure Subscription, Key Vault name, and the Key. See how to use your own keys.
- 2. If you want to have a more secure connection over the public internet from your on-prem data center to the VNet, there is an option to configure an Azure Private Endpoint in the activation wizard. In this case you will need to know the VNet and Subnet for this connection. See details about using a Private Endpoint.

# **Enabling Cloud Backup**


Enable Cloud Backup at any time directly from the on-premises working environment.

### Steps


 From the Canvas, select the working environment and click Enable > Backup Volumes next to the Backup & Restore service in the right-panel.




- 2. Select Microsoft Azure as your provider and click Next.
- 3. Enter the provider details and click **Next**.
  - a. The Azure subscription used for backups and the Azure region where the backups will be stored.
  - b. The resource group that manages the Blob container you can create a new resource group or select an existing resource group.
  - c. Whether you will use the default Microsoft-managed encryption key or choose your own customer-managed keys to manage encryption of your data. (See how to use your own keys).



- 4. If you don't have an existing Cloud Backup license for your account, you'll be prompted at this point to select the type of charging method that you want to use. You can subscribe to a pay-as-you-go (PAYGO) Cloud Manager Marketplace offering from Azure (or if you have multiple subscriptions you'll need to select one), or purchase and activate a Cloud Backup BYOL license from NetApp. Learn how to set up Cloud Backup licensing.
- 5. Enter the networking details and click **Next**.
  - a. The IPspace in the ONTAP cluster where the volumes you want to back up reside. The intercluster LIFs for this IPspace must have outbound internet access.
  - b. Optionally, choose whether you will configure an Azure Private Endpoint. See details about using a Private Endpoint.




- 6. Enter the backup policy details that will be used for your default policy and click **Next**. You can select an existing policy, or you can create a new policy by entering your selections in each section:
  - a. Enter the name for the default policy. You don't need to change the name.
  - b. Define the backup schedule and choose the number of backups to retain. See the list of existing policies you can choose.
  - c. When using ONTAP 9.10.1 and greater, you can choose to tier backups to Azure Archive storage after a certain number of days for further cost optimization. Learn more about using archival tiers.



- 7. Select the volumes that you want to back up using the default backup policy in the Select Volumes page. If you want to assign different backup policies to certain volumes, you can create additional policies and apply them to those volumes later.
  - To back up all volumes, check the box in the title row ( Volume Name ).
  - ∘ To back up individual volumes, check the box for each volume (

    volume

    vol



If you want all volumes added in the future to have backup enabled, just leave the checkbox for "Automatically back up future volumes..." checked. If you disable this setting, you'll need to manually enable backups for future volumes.

8. Click Activate Backup and Cloud Backup starts taking the initial backups of your volumes.

#### Result

Cloud Backup starts taking the initial backups of each selected volume and the Volume Backup Dashboard is displayed so you can monitor the state of the backups.

#### What's next?

You can start and stop backups for volumes or change the backup schedule.

You can also restore entire volumes or individual files from a backup file to a Cloud Volumes ONTAP system in Azure, or to an on-premises ONTAP system.

# Backing up on-premises ONTAP data to StorageGRID

Complete a few steps to get started backing up data from your on-premises ONTAP systems to object storage in your NetApp StorageGRID systems.

Note that "on-premises ONTAP systems" includes FAS, AFF, and ONTAP Select systems.

### **Quick start**

Get started quickly by following these steps, or scroll down to the remaining sections for full details.



# Verify support for your configuration

- You have discovered the on-premises cluster and added it to a working environment in Cloud Manager.
   See Discovering ONTAP clusters for details.
  - The cluster is running ONTAP 9.7P5 or later.
  - The cluster has a SnapMirror license it is included as part of the Premium Bundle or Data Protection Bundle.

- The cluster must have the required network connections to StorageGRID and to the Connector.
- You have a Connector installed on your premises.
  - The Connector can be installed in a site with or without internet access.
  - Networking for the Connector enables an outbound HTTPS connection to the ONTAP cluster and to StorageGRID.
- You have purchased and activated a Cloud Backup BYOL license from NetApp.
- Your StorageGRID has version 10.3 or later with access keys that have S3 permissions.



# **Enable Cloud Backup on the system**


Select the working environment and click **Enable > Backup Volumes** next to the Backup & Restore service in the right-panel, and then follow the setup wizard.





# **Enter the StorageGRID details**


Select StorageGRID as the provider, and then enter the StorageGRID server and service account details. You also need to specify the IPspace in the ONTAP cluster where the volumes reside.





### Define the default backup policy

The default policy backs up volumes every day and retains the most recent 30 backup copies of each volume. Change to hourly, daily, weekly, monthly, or yearly backups, or select one of the system-defined policies that provide more options. You can also change the number of backup copies you want to retain.





# Select the volumes that you want to back up


Identify which volumes you want to back up using the default backup policy in the Select Volumes page. If you want to assign different backup policies to certain volumes, you can create additional policies and apply them to volumes later.

An S3 bucket is created automatically in the service account indicated by the S3 access key and secret key you entered, and the backup files are stored there.

# Requirements

Read the following requirements to make sure you have a supported configuration before you start backing up on-premises volumes to StorageGRID.

The following image shows each component when backing up an on-prem ONTAP system to StorageGRID and the connections that you need to prepare between them:



When the Connector and on-premises ONTAP system are installed in an on-prem location without internet access, the StorageGRID system must be located in the same on-prem data center.

### **Preparing your ONTAP clusters**

You need to discover your on-premises ONTAP clusters in Cloud Manager before you can start backing up volume data.

Learn how to discover a cluster.

### **ONTAP** requirements

- Minimum of ONTAP 9.7P5; ONTAP 9.8P11 and later is recommended.
- A SnapMirror license (included as part of the Premium Bundle or Data Protection Bundle).

Note: The "Hybrid Cloud Bundle" is not required when using Cloud Backup.

See how to manage your cluster licenses.

· Time and time zone are set correctly.

See how to configure your cluster time.

# Cluster networking requirements

 The ONTAP cluster initiates an HTTPS connection over a user-specified port from the intercluster LIF to the StorageGRID Gateway Node for backup and restore operations. The port is configurable during backup setup.

ONTAP reads and writes data to and from object storage. The object storage never initiates, it just responds.

- ONTAP requires an inbound connection from the Connector to the cluster management LIF. The Connector must reside on your premises.
- An intercluster LIF is required on each ONTAP node that hosts the volumes you want to back up. The LIF must be associated with the *IPspace* that ONTAP should use to connect to object storage. Learn more about IPspaces.

When you set up Cloud Backup, you are prompted for the IPspace to use. You should choose the IPspace that each LIF is associated with. That might be the "Default" IPspace or a custom IPspace that you created.

- The nodes' intercluster LIFs are able to access the object store (not required when the Connector is installed in a "dark" site).
- DNS servers have been configured for the storage VM where the volumes are located. See how to configure DNS services for the SVM.
- Note that if you use are using a different IPspace than the Default, then you might need to create a static route to get access to the object storage.
- Update firewall rules, if necessary, to allow Cloud Backup service connections from ONTAP to object storage through the port you specified (typically port 443) and name resolution traffic from the storage VM to the DNS server over port 53 (TCP/UDP).

#### Preparing StorageGRID

StorageGRID must meet the following requirements. See the StorageGRID documentation for more information.

### Supported StorageGRID versions

StorageGRID 10.3 and later is supported.

#### S3 credentials

When you set up backup to StorageGRID, the backup wizard prompts you for an S3 access key and secret key for a service account. A service account enables Cloud Backup to authenticate and access the StorageGRID buckets used to store backups. The keys are required so that StorageGRID knows who is making the request.

These access keys must be associated with a user who has the following permissions:

```
"s3:ListAllMyBuckets",
"s3:ListBucket",
"s3:GetObject",
"s3:PutObject",
"s3:DeleteObject",
"s3:CreateBucket"
```

# **Object versioning**

You must not enable StorageGRID object versioning on the object store bucket.

# **Creating or switching Connectors**

When backing up data to StorageGRID, a Connector must be available on your premises. You'll either need to install a new Connector or make sure that the currently selected Connector resides on-prem. The Connector can be installed in a site with or without internet access.

- Learn about Connectors
- Installing the Connector on a Linux host with internet access
- Installing the Connector on a Linux host without internet access
- Switching between Connectors



Cloud Backup functionality is built into the Cloud Manager Connector. When installed in a site with no internet connectivity, you'll need to update the Connector software periodically to get access to new features. Check the Cloud Backup What's New to see the new features in each Cloud Backup release, and then you can follow the steps to upgrade the Connector software when you want to use new features.

### **Preparing networking for the Connector**

Ensure that the Connector has the required networking connections.

### **Steps**

- 1. Ensure that the network where the Connector is installed enables the following connections:
  - An HTTPS connection over port 443 to the StorageGRID Gateway Node
  - An HTTPS connection over port 443 to your ONTAP cluster management LIF
  - An outbound internet connection over port 443 to Cloud Backup (not required when the Connector is installed in a "dark" site)

### License requirements

Before you can activate Cloud Backup for your cluster, you'll need to purchase and activate a Cloud Backup BYOL license from NetApp. This license is for the account and can be used across multiple systems.

You'll need the serial number from NetApp that enables you to use the service for the duration and capacity of the license. Learn how to manage your BYOL licenses.



PAYGO licensing is not supported when backing up files to StorageGRID.

# **Enabling Cloud Backup to StorageGRID**

Enable Cloud Backup at any time directly from the on-premises working environment.


### Steps

1. From the Canvas, select the on-premises working environment and click **Enable > Backup Volumes** next to the Backup & Restore service in the right-panel.




- 2. Select **StorageGRID** as the provider, click **Next**, and then enter the provider details:
  - a. The FQDN of the StorageGRID Gateway Node and the port that ONTAP should use for HTTPS communication with StorageGRID; for example: s3.eng.company.com:8082
  - b. The Access Key and the Secret Key used to access the bucket to store backups.
  - c. The IPspace in the ONTAP cluster where the volumes you want to back up reside. The intercluster LIFs for this IPspace must have outbound internet access (not required when the Connector is installed in a "dark" site).

Selecting the correct IPspace ensures that Cloud Backup can set up a connection from ONTAP to your StorageGRID object storage.




Note that you cannot change this information after the service has started.

- 3. Enter the backup policy details that will be used for your default policy and click **Next**. You can select an existing policy, or you can create a new policy by entering your selections in each section:
  - a. Enter the name for the default policy. You don't need to change the name.
  - b. Define the backup schedule and choose the number of backups to retain. See the list of existing policies you can choose.



- 4. Select the volumes that you want to back up using the default backup policy in the Select Volumes page. If you want to assign different backup policies to certain volumes, you can create additional policies and apply them to those volumes later.
  - To back up all volumes, check the box in the title row ( Volume Name ).
  - To back up individual volumes, check the box for each volume (
     ✓ volume 1).



If you want all volumes added in the future to this cluster to have backup enabled, just leave the checkbox for "Automatically back up future volumes..." checked. If you disable this setting, you'll need to manually enable backups for future volumes.

5. Click **Activate Backup** and Cloud Backup starts taking the initial backups of each selected volume.

#### Result

An S3 bucket is created automatically in the service account indicated by the S3 access key and secret key you entered, and the backup files are stored there. The Volume Backup Dashboard is displayed so you can monitor the state of the backups.

#### What's next?

You can start and stop backups for volumes or change the backup schedule.

You can also restore entire volumes or individual files from a backup file to an on-premises ONTAP system.

# Managing backups for your ONTAP systems

You can manage backups for your Cloud Volumes ONTAP and on-premises ONTAP systems by changing the backup schedule, enabling/disabling volume backups, deleting backups, and more.




Do not manage or change backup files directly from your cloud provider environment. This may corrupt the files and will result in an unsupported configuration.

# Viewing the volumes that are being backed up

You can view a list of all the volumes that are currently being backed up in the Backup Dashboard.

### **Steps**

- 1. From the Cloud Manager left navigation menu, click **Backup & Restore**.
- Click the Volumes tab to view the list of volumes for Cloud Volumes ONTAP and on-premises ONTAP systems.



If you are looking for specific volumes in certain working environments, you can refine the list by working environment and volume, or you can use the search filter.

# **Enabling and disabling backups of volumes**

You can stop backing up a volume if you do not need backup copies of that volume and you do not want to pay for the cost to store the backups. You can also add a new volume to the backup list if it is not currently being backed up.

### **Steps**


1. From the Volumes tab, select Backup Settings.



2. From the Backup Settings page, click ••• for the working environment and select Manage Volumes.



3. Select the checkbox for a volume, or volumes, that you want to change, and then click **Activate** or **Deactivate** depending on whether you want to start or stop backups for the volume.



4. Click **Save** to commit your changes.

**Note:** When stopping a volume from being backed up you'll continue to be charged by your cloud provider for object storage costs for the capacity that the backups use unless you delete the backups.

# Editing an existing backup policy


You can change the attributes for a backup policy that is currently applied to volumes in a working environment. Changing the backup policy affects all existing volumes that are using the policy.

### **Steps**

1. From the Volumes tab, select Backup Settings.




2. From the *Backup Settings* page, click ••• for the working environment where you want to change the settings, and select **Manage Policies**.



3. From the *Manage Policies* page, click **Edit Policy** for the backup policy you want to change in that working environment.



4. From the Edit Policy page, change the schedule and backup retention and click Save.



If your cluster is running ONTAP 9.10.1 or greater, you also have the option to enable or disable tiering of backups to archival storage after a certain number of days.

Learn more about using Azure archival storage.

Note that any backup files that have been tiered to archival storage are left in that tier if you stop tiering backups to archive - they are not automatically moved back to the standard tier.

# Adding a new backup policy

When you enable Cloud Backup for a working environment, all the volumes you initially select are backed up using the default backup policy that you defined. If you want to assign different backup policies to certain volumes that have different recovery point objectives (RPO), you can create additional policies for that cluster and assign those policies to other volumes.


If you want to apply a new backup policy to certain volumes in a working environment, you first need to add the backup policy to the working environment. Then you can apply the policy to volumes in that working environment.

### Steps

1. From the Volumes tab, select Backup Settings.




2. From the *Backup Settings* page, click ••• for the working environment where you want to add the new policy, and select **Manage Policies**.



3. From the Manage Policies page, click Add New Policy.




4. From the Add New Policy page, define the schedule and backup retention and click Save.



If your cluster is running ONTAP 9.10.1 or greater, you also have the option to enable or disable tiering of backups to archival storage after a certain number of days.

Learn more about using Azure archival storage.




# Changing the policy assigned to existing volumes

You can change the backup policy assigned to your existing volumes if you want to change the frequency of taking backups, or if you want to change the retention value.


Note that the policy that you want to apply to the volumes must already exist. See how to add a new backup policy for a working environment.

### **Steps**


1. From the Volumes tab, select Backup Settings.




2. From the *Backup Settings page*, click ••• for the working environment where the volumes exist, and select **Manage Volumes**.



3. Select the checkbox for a volume, or volumes, that you want to change the policy for, and then click **Change Policy**.



4. In the *Change Policy* page, select the policy that you want to apply to the volumes, and click **Change Policy**.



Click Save to commit your changes.

# Setting a backup policy to be assigned to new volumes

If you did not select the option to automatically assign a backup policy to newly created volumes when you first activated Cloud Backup on your ONTAP cluster, you can choose this option in the *Backup Settings* page later. Having a backup policy assigned to newly created volumes ensures that all your data is protected.

Note that the policy that you want to apply to the volumes must already exist. See how to add a new backup policy for a working environment.


You can also disable this setting so that newly created volumes do not get backed up automatically. In that case you'll need to manually enable backups for any specific volumes that you do want to back up in the future.

#### **Steps**


1. From the Volumes tab, select Backup Settings.



2. From the *Backup Settings page*, click ••• for the working environment where the volumes exist, and select **Auto Backup New Volumes**.



3. Select the checkbox "Automatically back up new volumes...", choose the backup policy that you want to apply to new volumes, and click **Save**.



### Result

Now this backup policy will be applied to any new volume created in this working environment using Cloud Manager, System Manager, or the ONTAP CLI.

# Creating a manual volume backup at any time

You can create an on-demand backup at any time to capture the current state of the volume. This can be useful if very important changes have been made to a volume and you don't want to wait for the next scheduled backup to protect that data, or if the volume is not currently being backed up and you want to capture its current state.

The backup name includes the timestamp so you can identify your on-demand backup from other scheduled backups.


Note that when creating an ad-hoc backup, a Snapshot is created on the source volume. Since this Snapshot is not part of a normal Snapshot schedule, it will not rotate off. You may want to manually delete this Snapshot from the source volume once the backup is complete. This will allow blocks related to this Snapshot to be freed up. The name of the Snapshot will begin with cbs-snapshot-adhoc-. See how to delete a Snapshot using the ONTAP CLI.



On-demand volume backup isn't supported on data protection volumes.

#### **Steps**

1. From the **Volumes** tab, click ••• for the volume and select **Backup Now**.



The Backup Status column for that volume displays "In Progress" until the backup is created.

# Viewing the list of backups for each volume

You can view the list of all backup files that exist for each volume. This page displays details about the source volume, destination location, and backup details such as last backup taken, the current backup policy, backup file size, and more.

This page also enables you perform the following tasks:


- · Delete all backup files for the volume
- · Delete individual backup files for the volume
- · Download a backup report for the volume

#### **Steps**

1. From the Volumes tab, click ••• for the source volume and select Details & Backup List.



The list of all backup files is displayed along with details about the source volume, destination location, and backup details.



# **Deleting backups**

Cloud Backup enables you to delete a single backup file, delete all backups for a volume, or delete all backups of all volumes in a working environment. You might want to delete all backups if you no longer need the backups or if you deleted the source volume and want to remove all backups.



If you plan to delete a working environment or cluster that has backups, you must delete the backups **before** deleting the system. Cloud Backup doesn't automatically delete backups when you delete a system, and there is no current support in the UI to delete the backups after the system has been deleted. You'll continue to be charged for object storage costs for any remaining backups.

### Deleting all backup files for a working environment

Deleting all backups for a working environment does not disable future backups of volumes in this working environment. If you want to stop creating backups of all volumes in a working environment, you can deactivate backups as described here.

# **Steps**

1. From the Volumes tab, select Backup Settings.



2. Click ••• for the working environment where you want to delete all backups and select **Delete All Backups**.



3. In the confirmation dialog box, enter the name of the working environment and click **Delete**.

# Deleting all backup files for a volume

Deleting all backups for a volume also disables future backups for that volume.


You can restart making backups for the volume at any time from the Manage Backups page.

### **Steps**


1. From the Volumes tab, click ••• for the source volume and select Details & Backup List.



The list of all backup files is displayed.



2. Click Actions > Delete all Backups.




3. In the confirmation dialog box, enter the volume name and click **Delete**.

# Deleting a single backup file for a volume

You can delete a single backup file. This feature is available only if the volume backup was created from a system with ONTAP 9.8 or greater.

### Steps


1. From the **Volumes** tab, click ••• for the source volume and select **Details & Backup List**.



The list of all backup files is displayed.



2. Click ••• for the volume backup file you want to delete and click **Delete**.



3. In the confirmation dialog box, click **Delete**.


# Disabling Cloud Backup for a working environment

Disabling Cloud Backup for a working environment disables backups of each volume on the system, and it also disables the ability to restore a volume. Any existing backups will not be deleted. This does not unregister the backup service from this working environment - it basically allows you to pause all backup and restore activity for a period of time.

Note that you'll continue to be charged by your cloud provider for object storage costs for the capacity that your backups use unless you delete the backups.

### **Steps**

1. From the Volumes tab, select Backup Settings.



2. From the *Backup Settings page*, click ••• for the working environment where you want to disable backups and select **Deactivate Backup**.



3. In the confirmation dialog box, click **Deactivate**.



An **Activate Backup** button appears for that working environment while backup is disabled. You can click this button when you want to re-enable backup functionality for that working environment.

# Unregistering Cloud Backup for a working environment

You can unregister Cloud Backup for a working environment if you no longer want to use backup functionality and you want to stop being charged for backups in that working environment. Typically this feature is used when you're planning to delete a working environment, and you want to cancel the backup service.

You can also use this feature if you want to change the destination object store where your cluster backups are being stored. After you unregister Cloud Backup for the working environment, then you can enable Cloud Backup for that cluster using the new cloud provider information.

Before you can unregister Cloud Backup, you must perform the following steps, in this order:

- Deactivate Cloud Backup for the working environment
- Delete all backups for that working environment

The unregister option is not available until these two actions are complete.

# **Steps**

1. From the Volumes tab, select Backup Settings.



2. From the *Backup Settings page*, click ••• for the working environment where you want to unregister the backup service and select **Unregister**.



In the confirmation dialog box, click Unregister.

# Restoring ONTAP data from backup files

Backups are stored in an object store in your cloud account so that you can restore data from a specific point in time. You can restore an entire ONTAP volume from a backup file,

or if you only need to restore a few files, you can restore individual files from a backup file.

You can restore a **volume** (as a new volume) to the original working environment, to a different working environment that's using the same cloud account, or to an on-premises ONTAP system.

You can restore **files** to a volume in the original working environment, to a volume in a different working environment that's using the same cloud account, or to a volume on an on-premises ONTAP system.

A valid Cloud Backup license is required to restore data from backup files to a production system.


### The Restore Dashboard

You use the Restore Dashboard to perform volume and file restore operations. You access the Restore Dashboard by clicking **Backup & Restore** from the Cloud Manager left navigation menu, and then clicking the

**Restore** tab. You can also click **> View Restore Dashboard** from the Backup & Restore service from the Services panel.



Cloud Backup must already be activated for at least one working environment and initial backup files must exist.



As you can see, the Restore Dashboard provides 2 different ways to restore data from backup files: **Browse & Restore** and **Search & Restore**.

# Comparing Browse & Restore and Search & Restore

In broad terms, *Browse & Restore* is typically better when you need to restore a specific volume or file from the last week or month — and you know the name and location of the file, and the date when it was last in good shape. *Search & Restore* is typically better when you need to restore a volume or file, but you don't remember the exact name, or the volume in which it resides, or the date when it was last in good shape.

This table provides a comparison of the 2 methods.

Browse & Restore	Search & Restore
Browse through a folder-style structure to find the volume or file within a single backup file	Search for a volume or file across <b>all backup files</b> by partial or full volume name, partial or full file name, size range, and additional search filters
Volume and file restore works with backup files stored in Amazon S3, Azure Blob, Google Cloud, and NetApp StorageGRID.	Volume and file restore works with backup files stored in Amazon S3 and Google Cloud
Restore volumes and files from StorageGRID in sites with no internet access	Not supported in dark sites
Does not handle files that have been renamed or deleted	Handles newly created/deleted/renamed directories and newly created/deleted/renamed files
Browse for results across public and private clouds	Browse for results across public clouds and local Snapshots copies
No additional cloud provider resources required	Additional bucket and public cloud provider resources required per account
No additional cloud provider costs required	Cost associated with public cloud provider resources when scanning your backups and volumes for search results

Before you can use either restore method, make sure you have configured your environment for the unique resource requirements. Those requirements are described in the sections below.

See the requirements and restore steps for the type of restore operation you want to use:

- Restore volumes using Browse & Restore
- Restore files using Browse & Restore
- Restore volumes and files using Search & Restore

# Restoring ONTAP data using Browse & Restore

Before you start restoring a volume or file, you should know the name of the volume or file you want to restore, the name of the working environment where the volume resides, and the approximate date of the backup file that you want to restore from.

**Note:** If the backup file for the volume that you want to restore resides in archival storage (starting with ONTAP 9.10.1), the restore operation will take a longer amount of time and will incur a cost. Additionally, the destination cluster must also be running ONTAP 9.10.1 or greater.

Learn more about restoring from Azure archival storage.

### Browse & Restore supported working environments and object storage providers

You can restore a volume, or individual files, from an ONTAP backup file to the following working environments:

Backup File Location	Destination Working Environment	
	Volume Restore	File Restore

Backup File Location	Destination Working Environment		
Azure Blob	Cloud Volumes ONTAP in Azure On-premises ONTAP system	Cloud Volumes ONTAP in Azure On-premises ONTAP system	
NetApp StorageGRID	On-premises ONTAP system	On-premises ONTAP system	

(1) The Connector must be deployed in your Google Cloud Platform VPC for this support.


Note that references to "on-premises ONTAP systems" includes FAS, AFF, and ONTAP Select systems.



If the backup file resides in archival storage, only volume restore is supported. File restore is not currently supported from archival storage when using Browse & Restore.

# Restoring volumes using Browse & Restore

When you restore a volume from a backup file, Cloud Backup creates a *new* volume using the data from the backup. You can restore the data to a volume in the original working environment or to a different working environment that's located in the same cloud account as the source working environment. You can also restore volumes to an on-premises ONTAP system.



As you can see, you need to know the working environment name, volume name, and backup file date to perform a volume restore.

The following video shows a quick walkthrough of restoring a volume:




### **Steps**


- 1. Select the **Backup & Restore** service.
- 2. Click the **Restore** tab and the Restore Dashboard is displayed.
- 3. From the *Browse & Restore* section, click **Restore Volume**.




4. In the *Select Source* page, navigate to the backup file for the volume you want to restore. Select the **Working Environment**, the **Volume**, and the **Backup** file that has the date/time stamp from which you want to restore.



- 5. Click Continue.
- 6. In the Select Destination page, select the Working Environment where you want to restore the volume.



- 7. If you select an on-premises ONTAP system and you haven't already configured the cluster connection to the object storage, you are prompted for additional information:
  - When restoring from Azure Blob, select the IPspace in the ONTAP cluster where the destination volume will reside, select the Azure Subscription to access the object storage, and optionally choose a private endpoint for secure data transfer by selecting the VNet and Subnet.
  - When restoring from StorageGRID, enter the FQDN of the StorageGRID server and the port that ONTAP should use for HTTPS communication with StorageGRID, select the Access Key and Secret Key needed to access the object storage, and the IPspace in the ONTAP cluster where the destination volume will reside.
- 8. Enter the name you want to use for the restored volume, and select the Storage VM where the volume will reside. By default, <source\_volume\_name>\_restore is used as the volume name.



You can select the Aggregate that the volume will use for its' capacity only when restoring a volume to an on-premises ONTAP system.

And if you are restoring the volume from a backup file that resides in an archival storage tier (available starting with ONTAP 9.10.1), then you can select the Restore Priority.

Learn more about restoring from Azure archival storage.

Click **Restore** and you are returned to the Restore Dashboard so you can review the progress of the restore operation.

#### Result

Cloud Backup creates a new volume based on the backup you selected. You can manage the backup settings for this new volume as required.

Note that restoring a volume from a backup file that resides in archival storage can take many minutes or hours depending on the archive tier and the restore priority. You can click the **Job Monitor** tab to see the restore progress.

#### Restoring ONTAP files using Browse & Restore

If you only need to restore a few files from an ONTAP volume backup, you can choose to restore individual files instead of restoring the entire volume. You can restore files to an existing volume in the original working environment, or to a different working environment that's using the same cloud account. You can also restore files to a volume on an on-premises ONTAP system.

If you select multiple files, all the files are restored to the same destination volume that you choose. So if you want to restore files to different volumes, you'll need to run the restore process multiple times.



You can't restore individual files if the backup file resides in archival storage. In this case, you can restore files from a newer backup file that has not been archived, or you can restore the entire volume from the archived backup and then access the files you need, or you can restore files using Search & Restore.


#### **Prerequisites**

• The ONTAP version must be 9.6 or greater in your Cloud Volumes ONTAP or on-premises ONTAP systems to perform file restore operations.

### File Restore process

The process goes like this:

- 1. When you want to restore one or more files from a volume backup, click the **Restore** tab, click **Restore**Files under *Browse & Restore*, and select the backup file in which the file (or files) reside.
- 2. Cloud Backup displays the folders and files that exist within the selected backup file.
- 3. Choose the file (or files) that you want to restore from that backup.
- 4. Select the location where you want the file(s) to be restored (the working environment, volume, and folder), and click **Restore**.
- 5. The file(s) are restored.



As you can see, you need to know the working environment name, volume name, backup file date, and file name to perform a file restore.

#### Restoring files using Browse & Restore

Follow these steps to restore files to a volume from an ONTAP volume backup. You should know the name of the volume and the date of the backup file that you want to use to restore the file, or files. This functionality uses Live Browsing so that you can view the list of directories and files within each backup file.

The following video shows a quick walkthrough of restoring a single file:




### **Steps**


- 1. Select the Backup & Restore service.
- 2. Click the **Restore** tab and the Restore Dashboard is displayed.
- 3. From the Browse & Restore section, click Restore Files.



4. In the *Select Source* page, navigate to the backup file for the volume that contains the files you want to restore. Select the **Working Environment**, the **Volume**, and the **Backup** that has the date/time stamp from which you want to restore files.




5. Click **Continue** and the list of folders and files from the volume backup are displayed.



- 6. In the Select Files page, select the file or files that you want to restore and click **Continue**. To assist you in finding the file:
  - You can click the file name if you see it.
  - You can click the search icon and enter the name of the file to navigate directly to the file.
  - You can navigate down levels in folders using the > button at the end of the row to find the file.


As you select files they are added to the left side of the page so you can see the files that you have already chosen. You can remove a file from this list if needed by clicking the  $\mathbf{x}$  next to the file name.

7. In the Select Destination page, select the Working Environment where you want to restore the files.



If you select an on-premises cluster and you haven't already configured the cluster connection to the object storage, you are prompted for additional information:

- When restoring from Azure Blob, enter the IPspace in the ONTAP cluster where the destination volume resides.
- When restoring from StorageGRID, enter the FQDN of the StorageGRID server and the port that ONTAP should use for HTTPS communication with StorageGRID, enter the Access Key and Secret Key needed to access the object storage, and the IPspace in the ONTAP cluster where the destination volume resides.
- 8. Then select the **Volume** and the **Folder** where you want to restore the files.



You have a few options for the location when restoring files.

- When you have chosen **Select Target Folder**, as shown above:
  - You can select any folder.
  - You can hover over a folder and click > at the end of the row to drill down into subfolders, and then select a folder.
- If you have selected the same destination Working Environment and Volume as where the source file
  was located, you can select Maintain Source Folder Path to restore the file, or all files, to the same
  folder where they existed in the source structure. All the same folders and sub-folders must already
  exist; folders are not created.
- 9. Click **Restore** and you are returned to the Restore Dashboard so you can review the progress of the restore operation. You can also click the **Job Monitor** tab to see the restore progress.

# Restoring ONTAP data using Search & Restore

You can restore a volume or individual files from an ONTAP backup file using Search & Restore. Search & Restore enables you to search for a specific volume or file from all backups stored on cloud storage for a particular provider, and then perform a restore. You don't need to know the exact working environment name or volume name - the search looks through all volume backup files.

The search operation also looks across all local Snapshot copies that exist for your ONTAP volumes too. Since restoring data from a local Snapshot copy can be faster and less costly than restoring from a backup file, you may want to restore data from the Snapshot. You can restore the Snapshot as a new volume from the Volume Details page on the Canvas.

When you restore a volume from a backup file, Cloud Backup creates a *new* volume using the data from the backup. You can restore the data as a volume in the original working environment, or to a different working environment that's located in the same cloud account as the source working environment. You can also restore volumes to an on-premises ONTAP system.

You can restore files to the original volume location, to a different volume in the same working environment, or to a different working environment that's using the same cloud account. You can also restore files to a volume on an on-premises ONTAP system.

If the backup file for the volume that you want to restore resides in archival storage (available starting with ONTAP 9.10.1), the restore operation will take a longer amount of time and will incur additional cost. Note that the destination cluster must also be running ONTAP 9.10.1 or greater, and that file restore from archival storage is not currently supported.

Before you start, you should have some idea of the name or location of the volume or file you want to restore.

The following video shows a quick walkthrough of restoring a single file:



#### Search & Restore supported working environments and object storage providers

You can restore a volume, or individual files, from an ONTAP backup file to the following working environments:

Backup File Location	Destination Working Environment	
	Volume Restore	File Restore
Azure Blob	Not currently supported	
NetApp StorageGRID	Not currently supported	



The Connector must be deployed in your cloud provider platform for this support. Search & Restore is not supported when the Connector is installed on your premises.

Note that references to "on-premises ONTAP systems" includes FAS, AFF, and ONTAP Select systems.

#### **Prerequisites**

- · Cluster requirements:
  - The ONTAP version must be 9.8 or greater.
  - The storage VM (SVM) on which the volume resides must have a configured data LIF.
  - NFS must be enabled on the volume.
  - The SnapDiff RPC Server must be activated on the SVM. Cloud Manager does this automatically when you enable Indexing on the working environment.


#### Search & Restore process

The process goes like this:

- 1. Before you can use Search & Restore, you need to enable "Indexing" on each source working environment from which you'll want to restore volumes or files. This allows the Indexed Catalog to track the backup files for every volume.
- 2. When you want to restore a volume or files from a volume backup, under *Search & Restore*, click **Search & Restore**.
- 3. Enter the search criteria for a volume or file by partial or full volume name, partial or full file name, size range, creation date range, other search filters, and click **Search**.

The Search Results page displays all the locations that have a file or volume that matches your search criteria.

- 4. Click **View All Backups** for the location you want to use to restore the volume or file, and then click **Restore** on the actual backup file you want to use.
- 5. Select the location where you want the volume or file(s) to be restored and click **Restore**.
- The volume or file(s) are restored.



As you can see, you really only need to know a partial volume or file name and Cloud Backup searches through all backup files that match your search.

#### **Enabling the Indexed Catalog for each working environment**

Before you can use Search & Restore, you need to enable "Indexing" on each source working environment from which you're planning to restore volumes or files. This allows the Indexed Catalog to track every volume and every backup file - making your searches very quick and efficient.


When you enable this functionality, Cloud Backup enables SnapDiff v3 on the SVM for your volumes, and it performs the following actions:

If Indexing has already been enabled for your working environment, go to the next section to restore your data.

To enable Indexing for a working environment:

- If no working environments have been indexed, on the Restore Dashboard under *Search & Restore*, click **Enable Indexing for Working Environments**, and click **Enable Indexing** for the working environment.
- If at least one working environment has already been indexed, on the Restore Dashboard under *Search & Restore*, click **Indexing Settings**, and click **Enable Indexing** for the working environment.

After all the services are provisioned and the Indexed Catalog has been activated, the working environment is shown as "Active".



Depending on the size of the volumes in the working environment, and the number of backup files in the cloud, the initial indexing process could take up to an hour. After that it is transparently updated hourly with incremental changes to stay current.

#### Restoring volumes and files using Search & Restore


After you have enabled Indexing for your working environment, you can restore volumes or files using Search & Restore. This allows you to use a broad range of filters to find the exact file or volume that you want to restore from all backup files.

#### **Steps**


- 1. Select the Backup & Restore service.
- 2. Click the **Restore** tab and the Restore Dashboard is displayed.
- 3. From the Search & Restore section, click Search & Restore.



- 4. From the Search & Restore page:
  - a. In the Search bar, enter a full or partial volume name or file name.
  - b. In the Filter area, select the filter criteria. For example, you can select the working environment where the data resides and the file type, for example a .doc file.
- 5. Click **Search** and the Search Results area displays all the locations that have a file or volume that matches your search.



6. Click **View All Backups** for the location that has the data you want to restore to display all the backup files that contain the volume or file.



7. Click **Restore** for the backup file you want to use to restore the volume or file from the cloud.

Note that the results also identify local volume Snapshot copies that contain the file in your search. The **Restore** button is not functional for Snapshots at this time, but if you want to restore the data from the Snapshot copy instead of from the Backup file, write down the name and location of the volume, open the Volume Details page on the Canvas, and use the **Restore from Snapshot copy** option.

- 8. Select the location where you want the volume or file(s) to be restored and click **Restore**.
  - For files, you can restore to the original location or you can select an alternate location
  - For volumes you can select the location.

#### Results

The volume or file(s) are restored and you are returned to the Restore Dashboard so you can review the progress of the restore operation. You can also click the **Job Monitor** tab to see the restore progress.

For restored volumes, you can manage the backup settings for this new volume as required.

# Back up and restore Kubernetes data

# Protect your Kubernetes cluster data using Cloud Backup

Cloud Backup provides backup and restore capabilities for protection and long-term archive of your Kubernetes cluster data. Backups are automatically generated and stored in an object store in your public or private cloud account.

When necessary, you can restore an entire *volume* from a backup to the same or different working environment.

#### **Features**

#### Backup features:

- · Back up independent copies of your persistent volumes to low-cost object storage.
- Apply a single backup policy to all volumes in a cluster, or assign different backup policies to volumes that have unique recovery point objectives.
- Backup data is secured with AES-256 bit encryption at-rest and TLS 1.2 HTTPS connections in-flight.
- Support for up to 4,000 backups of a single volume.

#### Restore features:

- · Restore data from a specific point in time.
- Restore a volume to the source system or to a different system.
- Restores data on a block level, placing the data directly in the location you specify, all while preserving the original ACLs.

## Supported Kubernetes working environments and object storage providers

Cloud Backup enables you to back up Kubernetes volumes from the following working environments to object storage in the following public and private cloud providers:

Source Working Environment	Backup File Destination
Kubernetes cluster in Azure	Azure Blob

You can restore a volume from a Kubernetes backup file to the following working environments:

Backup File Location	Destination Working Environment
Azure Blob	Kubernetes cluster in Azure

#### Cost

There are two types of costs associated with using Cloud Backup: resource charges and service charges.

#### Resource charges

Resource charges are paid to the cloud provider for object storage capacity in the cloud. Since Cloud Backup

preserves the storage efficiencies of the source volume, you pay the cloud provider object storage costs for the data *after* ONTAP efficiencies (for the smaller amount of data after deduplication and compression have been applied).

#### Service charges

Service charges are paid to NetApp and cover both the cost to *create* backups and to *restore* volumes, from those backups. You pay only for the data that you protect, calculated by the source logical used capacity (*before* ONTAP efficiencies) of volumes which are backed up to object storage. This capacity is also known as Front-End Terabytes (FETB).

There are two ways to pay for the Backup service. The first option is to subscribe from your cloud provider, which enables you to pay per month. The second option is to purchase licenses directly from NetApp. Read the Licensing section for details.

## Licensing

Cloud Backup is available in two licensing options: Pay As You Go (PAYGO), and Bring Your Own License (BYOL). A 30-day free trial is available if you don't have a license.

#### Free trial

When using the 30-day free trial, you are notified about the number of free trial days that remain. At the end of your free trial, backups stop being created. You must subscribe to the service or purchase a license to continue using the service.

Backup files are not deleted when the service is disabled. You'll continue to be charged by your cloud provider for object storage costs for the capacity that your backups use unless you delete the backups.

#### Pay-as-you-go subscription

Cloud Backup offers consumption-based licensing in a pay-as-you-go model. After subscribing through your cloud provider's marketplace, you pay per GB for data that's backed up—there's no up-front payment. You are billed by your cloud provider through your monthly bill.

You should subscribe even if you have a free trial or if you bring your own license (BYOL):

- Subscribing ensures that there's no disruption of service after your free trial ends.
  - When the trial ends, you'll be charged hourly according to the amount of data that you back up.
- If you back up more data than allowed by your BYOL license, then data backup continues through your pay-as-you-go subscription.

For example, if you have a 10 TB BYOL license, all capacity beyond the 10 TB is charged through the PAYGO subscription.

You won't be charged from your pay-as-you-go subscription during your free trial or if you haven't exceeded your BYOL license.

Learn how to set up a pay-as-you-go subscription.

#### Bring your own license

BYOL is term-based (12, 24, or 36 months) *and* capacity-based in 1 TB increments. You pay NetApp to use the service for a period of time, say 1 year, and for a maximum amount capacity, say 10 TB.

You'll receive a serial number that you enter in the Cloud Manager Digital Wallet page to enable the service. When either limit is reached, you'll need to renew the license. The Backup BYOL license applies to all source systems associated with your Cloud Manager account.

Learn how to manage your BYOL licenses.

## **How Cloud Backup works**

When you enable Cloud Backup on a Kubernetes system, the service performs a full backup of your data. After the initial backup, all additional backups are incremental, which means that only changed blocks and new blocks are backed up. This keeps network traffic to a minimum.



Any actions taken directly from your cloud provider environment to manage or change backup files may corrupt the files and will result in an unsupported configuration.

The following image shows the relationship between each component:



#### Supported storage classes or access tiers

• In Azure, backups are associated with the Cool access tier.

## Customizable backup schedule and retention settings per cluster

When you enable Cloud Backup for a working environment, all the volumes you initially select are backed up using the default backup policy that you define. If you want to assign different backup policies to certain volumes that have different recovery point objectives (RPO), you can create additional policies for that cluster and assign those policies to other volumes.

You can choose a combination of hourly, daily, weekly, and monthly backups of all volumes.

Once you have reached the maximum number of backups for a category, or interval, older backups are removed so you always have the most current backups.

## Supported volumes

Cloud Backup supports Persistent volumes (PVs).

#### Limitations

- When creating or editing a backup policy when no volumes are assigned to the policy, the number of
  retained backups can be a maximum of 1018. As a workaround you can reduce the number of backups to
  create the policy. Then you can edit the policy to create up to 4000 backups after you assign volumes to
  the policy.
- Ad-hoc volume backups using the **Backup Now** button aren't supported on Kubernetes volumes.

# Backing up Kubernetes persistent volume data to Azure Blob storage

Complete a few steps to get started backing up data from your persistent volumes on AKS Kubernetes clusters to Azure Blob storage.

#### **Quick start**

Get started quickly by following these steps or scroll down to the remaining sections for full details.



#### Review prerequisites

- You have discovered the Kubernetes cluster as a Cloud Manager working environment.
  - Trident must be installed on the cluster, and the Trident version must be 21.1 or greater.
  - All PVCs that will be used to create persistent volumes that you want to back up must have "snapshotPolicy" set to "default".
  - The cluster must be using Cloud Volumes ONTAP on Azure for its' backend storage.
  - The Cloud Volumes ONTAP system must be running ONTAP 9.7P5 or later.
- You have a valid cloud provider subscription for the storage space where your backups will be located.
- You have subscribed to the Cloud Manager Marketplace Backup offering, or you have purchased and activated a Cloud Backup BYOL license from NetApp.



#### **Enable Cloud Backup on your existing Kubernetes cluster**

Select the working environment and click **Enable** next to the Backup & Restore service in the right-panel, and then follow the setup wizard.





#### Define the backup policy

The default policy backs up volumes every day and retains the most recent 30 backup copies of each volume. Change to hourly, daily, weekly, or monthly backups, or select one of the system-defined policies that provide more options. You can also change the number of backup copies you want to retain.






#### Select the volumes that you want to back up

Identify which volumes you want to back up in the Select Volumes page. The backup files are stored in a Blob container using the same Azure subscription and Region as the Cloud Volumes ONTAP system.

## Requirements

Read the following requirements to make sure that you have a supported configuration before you start backing up Kubernetes persistent volumes to Blob storage.

The following image shows each component and the connections that you need to prepare between them:



Note that the Private Endpoint is optional.

#### **Kubernetes cluster requirements**

- You have discovered the Kubernetes cluster as a Cloud Manager working environment. See how to discover the Kubernetes cluster.
- Trident must be installed on the cluster, and the Trident version must be a minimum of 21.1. See how to install Trident or how to upgrade the Trident version.
- The cluster must be using Cloud Volumes ONTAP on Azure for its' backend storage.
- The Cloud Volumes ONTAP system must be in the same Azure region as the Kubernetes cluster, and it must be running ONTAP 9.7P5 or later (ONTAP 9.8P11 and later is recommended).

Note that Kubernetes clusters in on-premises locations are not supported. Only Kubernetes clusters in cloud deployments that are using Cloud Volumes ONTAP systems are supported.

• All Persistent Volume Claim objects that will be used to create the persistent volumes that you want to back up must have "snapshotPolicy" set to "default".

You can do this for individual PVCs by adding snapshotPolicy under annotations:

```
kind: PersistentVolumeClaim
apiVersion: v1
metadata:
   name: full
   annotations:
        trident.netapp.io/snapshotPolicy: "default"
spec:
   accessModes:
        - ReadWriteMany
resources:
    requests:
        storage: 1000Mi
storageClassName: silver
```

You can do this for all PVCs associated with a particular backend storage by adding the snapshotPolicy field under defaults in the backend.json file:

```
apiVersion: trident.netapp.io/v1
kind: TridentBackendConfig
metadata:
 name: backend-tbc-ontap-nas-advanced
spec:
 version: 1
 storageDriverName: ontap-nas
 managementLIF: 10.0.0.1
 dataLIF: 10.0.0.2
 backendName: tbc-ontap-nas-advanced
 svm: trident svm
 credentials:
    name: backend-tbc-ontap-nas-advanced-secret
 limitAggregateUsage: 80%
 limitVolumeSize: 50Gi
  nfsMountOptions: nfsvers=4
 defaults:
    spaceReserve: volume
    exportPolicy: myk8scluster
    snapshotPolicy: default
    snapshotReserve: '10'
  deletionPolicy: retain
```

#### License requirements

For Cloud Backup PAYGO licensing, a subscription through the Azure Marketplace is required before you enable Cloud Backup. Billing for Cloud Backup is done through this subscription. You can subscribe from the Details & Credentials page of the working environment wizard.

For Cloud Backup BYOL licensing, you need the serial number from NetApp that enables you to use the service for the duration and capacity of the license. Learn how to manage your BYOL licenses.

And you need to have a Microsoft Azure subscription for the storage space where your backups will be located.

#### **Supported Azure regions**

Cloud Backup is supported in all Azure regions where Cloud Volumes ONTAP is supported.

## **Enabling Cloud Backup**

Enable Cloud Backup at any time directly from the Kubernetes working environment.


#### Steps

1. Select the working environment and click **Enable** next to the Backup & Restore service in the right-panel.




2. Enter the backup policy details and click Next.

You can define the backup schedule and choose the number of backups to retain.



- 3. Select the persistent volumes that you want to back up.
  - To back up all volumes, check the box in the title row ( Volume Name )
  - To back up individual volumes, check the box for each volume (
     ✓ volume 1).



- 4. If you want all current and future volumes to have backup enabled, just leave the checkbox for "Automatically back up future volumes..." checked. If you disable this setting, you'll need to manually enable backups for future volumes.
- 5. Click Activate Backup and Cloud Backup starts taking the initial backups of each selected volume.

#### Result

The backup files are stored in a Blob container using the same Azure subscription and Region as the Cloud Volumes ONTAP system.

The Kubernetes Dashboard is displayed so you can monitor the state of the backups.

#### What's next?

You can start and stop backups for volumes or change the backup schedule.

You can also restore entire volumes from a backup file as a new volume on the same or different Kubernetes cluster in Azure (in the same region).

# Managing backups for your Kubernetes systems

You can manage backups for your Kubernetes systems by changing the backup schedule, enabling/disabling volume backups, deleting backups, and more.



Do not manage or change backup files directly from your cloud provider environment. This may corrupt the files and will result in an unsupported configuration.

## Viewing the volumes that are being backed up

You can view a list of all the volumes that are currently being backed up by Cloud Backup.

#### **Steps**

- 1. From the Cloud Manager left navigation menu, click Backup & Restore.
- 2. Click the **Kubernetes** tab to view the list of persistent volumes for Kubernetes systems.



If you are looking for specific volumes in certain clusters, you can refine the list by cluster and volume, or you can use the search filter.

## **Enabling and disabling backups of volumes**


You can stop backing up a volume if you do not need backup copies of that volume and you do not want to pay for the cost to store the backups. You can also add a new volume to the backup list if it is not currently being backed up.

#### **Steps**


1. From the **Kubernetes** tab, select **Backup Settings**.



2. From the *Backup Settings page*, click ••• for the Kubernetes cluster and select **Manage Persistent Volumes**.



3. Select the checkbox for a volume, or volumes, that you want to change, and then click **Activate** or **Deactivate** depending on whether you want to start or stop backups for the volume.



4. Click **Save** to commit your changes.


**Note:** When stopping a volume from being backed up you'll continue to be charged by your cloud provider for object storage costs for the capacity that the backups use unless you delete the backups.

## Editing an existing backup policy

You can change the attributes for a backup policy that is currently applied to volumes in a working environment. Changing the backup policy affects all existing volumes that are using the policy.

#### **Steps**

1. From the **Kubernetes** tab, select **Backup Settings**.




2. From the *Backup Settings* page, click ••• for the working environment where you want to change the settings, and select **Manage Policies**.



3. From the *Manage Policies* page, click **Edit Policy** for the backup policy you want to change in that working environment.



4. From the Edit Policy page, change the schedule and backup retention and click Save.



## Setting a backup policy to be assigned to new volumes


If you did not select the option to automatically assign a backup policy to newly created volumes when you first activated Cloud Backup on your Kubernetes cluster, you can choose this option in the *Backup Settings* page later. Having a backup policy assigned to newly created volumes ensures that all your data is protected.

Note that the policy that you want to apply to the volumes must already exist. See how to add a new backup policy for a working environment.

You can also disable this setting so that newly created volumes do not get backed up automatically. In that case you'll need to manually enable backups for any specific volumes that you do want to back up in the future.

#### **Steps**

1. From the **Kubernetes** tab, select **Backup Settings**.



2. From the *Backup Settings page*, click ••• for the Kubernetes cluster where the volumes exist, and select **Auto Backup New Volumes**.



3. Select the checkbox "Automatically back up future persistent volumes...", choose the backup policy that you want to apply to new volumes, and click **Save**.



#### Result

Now this backup policy will be applied to any new volumes created in this Kubernetes cluster.

## Viewing the list of backups for each volume

You can view the list of all backup files that exist for each volume. This page displays details about the source volume, destination location, and backup details such as last backup taken, the current backup policy, backup file size, and more.

This page also enables you perform the following tasks:

- · Delete all backup files for the volume
- · Delete individual backup files for the volume
- · Download a backup report for the volume

#### **Steps**

1. From the Kubernetes tab, click ••• for the source volume and select Details & Backup List.



The list of all backup files is displayed along with details about the source volume, destination location, and backup details.



## **Deleting backups**

Cloud Backup enables you to delete a single backup file, delete all backups for a volume, or delete all backups of all volumes in a Kubernetes cluster. You might want to delete all backups if you no longer need the backups or if you deleted the source volume and want to remove all backups.



If you plan to delete a working environment or cluster that has backups, you must delete the backups **before** deleting the system. Cloud Backup doesn't automatically delete backups when you delete a system, and there is no current support in the UI to delete the backups after the system has been deleted. You'll continue to be charged for object storage costs for any remaining backups.

#### Deleting all backup files for a working environment

Deleting all backups for a working environment does not disable future backups of volumes in this working environment. If you want to stop creating backups of all volumes in a working environment, you can deactivate backups as described here.

#### **Steps**

1. From the Kubernetes tab, select Backup Settings.



2. Click ••• for the Kubernetes cluster where you want to delete all backups and select **Delete All Backups**.



3. In the confirmation dialog box, enter the name of the working environment and click **Delete**.


#### Deleting all backup files for a volume

Deleting all backups for a volume also disables future backups for that volume.

You can restart making backups for the volume at any time from the Manage Backups page.

#### **Steps**

1. From the Kubernetes tab, click ••• for the source volume and select Details & Backup List.



The list of all backup files is displayed.



2. Click Actions > Delete all Backups.



3. In the confirmation dialog box, enter the volume name and click **Delete**.

#### Deleting a single backup file for a volume

You can delete a single backup file. This feature is available only if the volume backup was created from a system with ONTAP 9.8 or greater.

#### **Steps**


1. From the **Kubernetes** tab, click ••• for the source volume and select **Details & Backup List**.



The list of all backup files is displayed.



2. Click ••• for the volume backup file you want to delete and click **Delete**.



3. In the confirmation dialog box, click **Delete**.

## Disabling Cloud Backup for a working environment

Disabling Cloud Backup for a working environment disables backups of each volume on the system, and it also disables the ability to restore a volume. Any existing backups will not be deleted. This does not unregister the backup service from this working environment - it basically allows you to pause all backup and restore activity for a period of time.

Note that you'll continue to be charged by your cloud provider for object storage costs for the capacity that your backups use unless you delete the backups.

#### **Steps**

1. From the **Kubernetes** tab, select **Backup Settings**.



2. From the *Backup Settings page*, click ••• for the working environment, or the Kubernetes cluster, where you want to disable backups and select **Deactivate Backup**.



3. In the confirmation dialog box, click **Deactivate**.



An **Activate Backup** button appears for that working environment while backup is disabled. You can click this button when you want to re-enable backup functionality for that working environment.

## Unregistering Cloud Backup for a working environment

You can unregister Cloud Backup for a working environment if you no longer want to use backup functionality and you want to stop being charged for backups in that working environment. Typically this feature is used when you're planning to delete a Kubernetes cluster, and you want to cancel the backup service.

You can also use this feature if you want to change the destination object store where your cluster backups are being stored. After you unregister Cloud Backup for the working environment, then you can enable Cloud Backup for that cluster using the new cloud provider information.


Before you can unregister Cloud Backup, you must perform the following steps, in this order:

- Deactivate Cloud Backup for the working environment
- · Delete all backups for that working environment

The unregister option is not available until these two actions are complete.

#### Steps

1. From the Kubernetes tab, select Backup Settings.



2. From the *Backup Settings page*, click ••• for the Kubernetes cluster where you want to unregister the backup service and select **Unregister**.



3. In the confirmation dialog box, click Unregister.

## Restoring Kubernetes data from backup files

Backups are stored in an object store in your cloud account so that you can restore data from a specific point in time. You can restore an entire Kubernetes persistent volume from a saved backup file.

You can restore a persistent volume (as a new volume) to the same working environment or to a different working environment that's using the same cloud account.

## Supported working environments and object storage providers

You can restore a volume from a Kubernetes backup file to the following working environments:

Backup File Location	Destination Working Environment
Azure Blob	Kubernetes cluster in Azure

## Restoring volumes from a Kubernetes backup file

When you restore a persistent volume from a backup file, Cloud Manager creates a *new* volume using the data from the backup. You can restore the data to a volume in the same Kubernetes cluster or to a different Kubernetes cluster that's located in the same cloud account as the source Kubernetes cluster.

Before you start, you should know the name of the volume you want to restore and the date of the backup file you want to use to create the newly restored volume.


#### **Steps**

- 1. Select the Backup & Restore service.
- 2. Click the Kubernetes tab and the Kubernetes Dashboard is displayed.



3. Locate the volume you want to restore, click ..., and then click Details & Backup List.

The list of all backup files for that volume is displayed along with details about the source volume, destination location, and backup details.



- 4. Locate the specific backup file that you want to restore based on the date/time stamp, click •••, and then **Restore**.
- 5. In the Select Destination page, select the Kubernetes cluster where you want to restore the volume, the Namespace, the Storage Class, and the new Persistent volume name.



6. Click **Restore** and you are returned to the Kubernetes Dashboard so you can review the progress of the restore operation.

#### Result

Cloud Manager creates a new volume in the Kubernetes cluster based on the backup you selected. You can manage the backup settings for this new volume as required.

# Back up and restore on-premises applications data

# Protect your on-premises applications data

You can integrate Cloud Backup for Applications with Cloud Manager and on-premises SnapCenter to back up the application consistent Snapshots from on-premises ONTAP to cloud. When required you can restore from cloud to on-premises SnapCenter Server.

You can back up Oracle and Microsoft SQL applications data from on-premises ONTAP systems to the following cloud providers:

- · Amazon Web Services
- · Microsoft Azure



You should be using SnapCenter Software 4.6.

For more information about Cloud Backup for Applications, refer to:

- Application aware backup with Cloud Backup and SnapCenter
- · Cloud backup for applications

## Requirements

Read the following requirements to make sure that you have a supported configuration before you start backing up application data to cloud services.

- ONTAP 9.8 or later
- · Cloud Manager 3.9
- SnapCenter Server 4.6
- At least one backup per application should be available in SnapCenter Server
- At least one daily, weekly, or monthly policy in SnapCenter with no label or same label as that of the Cloud Backup for Applications policy in Cloud Manager.

The following image shows each component and the connections that you need to prepare between them:



### **Protection Policies**

You should use the one of the policies defined in Cloud Backup for Applications to back up the application data to cloud.



Custom policies are not supported.

Policy Name	Label	Retention Value
1 Year Daily LTR	Daily	366
5 Years Daily LTR	Daily	1830
7 Year Weekly LTR	Weekly	370
10 Year Monthly LTR	Monthly	120

The labels and retention value of these policies can be modified using the REST API until the policy is associated with an application. Only one policy can be associated with an application and once associated, you cannot dissociate.

In addition to the Cloud Backup for Applications policies, you would also need at least one SnapCenter policy to back up the application data to cloud.

# Back up on-premises applications data to cloud

You can back up the applications data from ONTAP to cloud by integrating Cloud Backup for Applications with Cloud Manager and on-premises SnapCenter.

## Register SnapCenter Server

Only a user with SnapCenterAdmin role can register the host on which SnapCenter Server 4.6 is running. You can register multiple SnapCenter Server hosts but once registered, you cannot remove the SnapCenter Server host.

#### **Steps**

- 1. In Cloud Manager UI, click **Backup & Restore > Applications**.
- 2. From the Settings drop-down, click SnapCenter Servers.
- 3. Click Register SnapCenter Server.
- 4. Specify the following details:
  - a. In the SnapCenter Server field, specify the FQDN or IP address of the SnapCenter Server host.
  - b. In the Port field, specify the port number on which the SnapCenter Server is running.

You should ensure that the port is open for the communication to happen between SnapCenter Server and the Cloud Backup for Applications.

c. In the Tags field, specify a site name, city name, or any custom name with which you want to tag the SnapCenter Server.

The tags are comma separated.

- d. In the Username and Password field, specify the credentials of the user with SnapCenterAdmin role.
- 5. Click Register.

#### After you finish

Click **Backup & Restore > Applications** to view all the applications that are protected using the registered SnapCenter Server host.



For SQL Server databases, the Application Name column displays the name in application\_name (host name) format. When you search by providing the name in application name (host name) format, the SQL Server database details are not displayed.

The supported applications and their configurations are:

- Oracle database: Full backups (data + log) created with at least one daily, weekly, or monthly schedules.
- · Microsoft SQL Server database:
  - Standalone, failover cluster instances, and availability groups
  - Full backups created with at least one daily, weekly, or monthly schedules

The following Oracle and SQL Server databases will not be displayed:

- · Databases that have no backups
- Databases that have only on-demand or hourly policy
- · Databases residing on RDM or VMDK

## Back up applications data

You can protect one or more applications simultaneously to the cloud using a single policy. Only the default pre-canned policies can be assigned to protect the application.



You can protect only one application at a time if you are using the Cloud Manager GUI. However, if you are using REST APIs, you can protect multiple applications simultaneously.

If you are protecting an SQL Server instance, then cloud protection will be configured for all the volumes of the eligible databases in that instance.

If you are protecting an SQL Server availability group, then cloud protection will be configured for all the volumes of the databases in that availability group. However, based on the backup preference, the Snapshot will be copied form the respective volumes.

#### **Steps**

- 1. In Cloud Manager UI, click Backup & Restore > Applications.
- 2. Click ••• corresponding to the application and click Activate Backup.
- 3. Add the working environment.

Configure the ONTAP cluster that hosts the SVM on which the application is running. After adding the working environment for one of the applications, it can be reused for all the other applications residing on the same ONTAP cluster.

- a. Select the SVM and click Add Working Environment.
- b. In the Add Working Environment wizard:
  - i. Specify the IP address of the ONTAP cluster.
  - ii. Specify the admin credentials.

Cloud Backup for Applications supports only cluster admin.

c. Click Add Working Environment.



You should not proceed until the working environment details are updated. It might take up to 30 minutes for the working environment details to be updated. After 30 minutes, you should close the wizard and retry from step 1 to view the working environment details

After retrying if the working environment details are not updated, ensure that you have added the right working environment.

4. Select and configure the cloud provider.

#### **Configure Amazon Web Services**

- a. Specify the AWS account.
- b. In the AWS Access Key field, specify the key.
- c. In the AWS Secret Key field, specify the password.
- d. Select the region where you want to create the backups.
- e. Specify the IP addresses of the ONTAP clusters that were added as the working environments.

#### **Configure Microsoft Azure**

- a. Specify the Azure subscription ID.
- b. Select the region where you want to create the backups.
- c. Either create a new resource group or use an existing resource group.
- d. Specify the IP addresses of the ONTAP clusters that were added as the working environments.
- 5. In the Assign Policy page, select the policy and click Next.
- Review the details and click Activate Backup.

The following video shows a quick walkthrough of protecting a database:



# Manage protection of applications

You can view the policies and backups. Depending upon the change in database, policies, or resource groups, you can refresh the updates from the Cloud Manager UI.

## View policies

You can view all the default pre-canned policies. For each of these policies, when you view the details all the associated Cloud Backup for Applications policies and all the associated applications are listed.

- 1. Click Backup & Restore > Applications.
- 2. From the **Settings** drop-down, click **Policies**.
- 3. Click View Details corresponding to policy whose details you want to view.

The associated Cloud Backup for Applications policies and all the applications are listed.



You should not delete the Cloud Backup for Applications policies.

You can also view cloud extended SnapCenter policies, by running the Get-SmResources SnapCenter cmdlet.

The information regarding the parameters that can be used with the cmdlet and their descriptions can be obtained by running Get-Help command\_name. Alternatively, you can also refer the SnapCenter Software Cmdlet Reference Guide.

## View backups on cloud

You can view the backups on cloud in the Cloud Manager UI.

- 1. Click Backup & Restore > Applications.
- 2. Click ••• corresponding to the application and click View Details.



The time taken for the backups to be listed depends on ONTAP's default replication schedule (maximum of 1 hour) and Cloud Manager (maximum of 6 hours).

- For Oracle databases, both data and log backups, SCN number for each backup, end date for each backup are listed. You can select only the data backup and restore the database to on-premises SnapCenter Server.
- For Microsoft SQL Server databases, only the full backups and the end date for each backup are listed. You can select the backup and restore the database to on-premises SnapCenter Server.
- For Microsoft SQL Server instance, backups are not listed instead only the databases under that instance is listed.



The backups created before enabling cloud protection are not listed for restore.

You can also view these backups by running the <code>Get-SmBackup</code> SnapCenter cmdlet. The information regarding the parameters that can be used with the cmdlet and their descriptions can be obtained by running <code>Get-Help</code> command\_name. Alternatively, you can also refer the <code>SnapCenter</code> Software Cmdlet Reference Guide.

## **Database layout change**

When volumes are added to the database, SnapCenter Server will label the snapshots on the new volumes automatically as per the policy and the schedule. These new volumes will not have the object store endpoint and you should refresh by executing the following steps:

- 1. Click Backup & Restore > Applications.
- 2. From the Settings drop-down, click SnapCenter Servers.
- 3. Click ••• corresponding to the SnapCenter Server hosting the application and click Refresh.

The new volumes are discovered.

4. Click ••• corresponding to the application and click **Refresh Protection** to enable cloud protection for the new volume.

If a storage volume is removed from the application after configuring the cloud service, for new backups SnapCenter Server will only label the snapshots on which the application is residing. If the removed volume is not used by any other applications, then you should manually delete the object store relationship. If you update the application inventory, it will contain the current storage layout of the application.

## Policy or resource group change

If there is a change to the SnapCenter policy or resource group, you should refresh the protection.

- 1. Click Backup & Restore > Applications.
- 2. Click ••• corresponding to the application and click Refresh Protection.

#### **Monitor Jobs**

Jobs are created for all the Cloud Backup operations. You can monitor all the jobs and all the sub tasks that are performed as part of each task.

1. Click Backup & Restore > Job Monitoring.

When you initiate an operation, a window appears stating that the job is initiated. You can click the link to monitor the job.

Click the primary task to view the sub tasks and status of each of these sub tasks.

## **Configure CA Certificates**

If you have CA certificates, you should manually copy the root CA certificates to the connector machine.

However, if you do not have CA certificates, you can proceed without configuring CA certificates.

#### Steps

- 1. Copy the certificate to the volume that can be accessed from the docker agent.
  - cd /var/lib/docker/volumes/cloudmanager\_snapcenter\_volume/\_data/mkdir sc\_certs
  - ° chmod 777 sc certs
- 2. Copy the RootCA certificate files to the above folder on the connector machine.

```
cp <path on connector>/<filename>
/var/lib/docker/volumes/cloudmanager_snapcenter_volume/_data/sc_certs
```

Copy the CRL file to the volume which can be accessed from the docker agent.

- ° cd /var/lib/docker/volumes/cloudmanager\_snapcenter\_volume/\_data/mkdir sc\_crl
- ° chmod 777 sc\_crl
- 4. Copy the CRL files to the above folder on the connector machine.

```
cp <path on connector>/<filename>
/var/lib/docker/volumes/cloudmanager_snapcenter_volume/_data/sc_crl
```

- After copying the certificates and CRL files, restart the Cloud Backup for Apps service.
  - sudo docker exec cloudmanager\_snapcenter sed -i 's/skipSCCertValidation: true/skipSCCertValidation: false/g' /opt/netapp/cloudmanager-snapcenteragent/config/config.yml
  - ° sudo docker restart cloudmanager snapcenter

# Restore applications data

#### **Restore Oracle database**

You can only restore the Oracle database to the same SnapCenter Server host, same SVM, or to the same database host. For a RAC database, the data will be restored to the on-premises node where the backup was created.

Only full database with control file restore is supported. If the archive logs are not present in the AFS, you should specify the location that contains the archive logs required for recovery.

#### Steps

- 1. In Cloud Manager UI, click **Backup & Restore > Applications**.
- 2. In the Filter By field, select the filter Type and from the drop-down select Oracle.
- 3. Click View Details corresponding to the database that you want to restore and click Restore.
- 4. On the Restore Type page, perform the following actions:
  - a. Select Control files if you want to restore control file along with full database.
  - b. Select **Change database state if needed for restore and recovery** to change the state of the database to the state required to perform restore and recovery operations.

The various states of a database from higher to lower are open, mounted, started, and shutdown. You must select this check box if the database is in a higher state but the state must be changed to a lower state to perform a restore operation. If the database is in a lower state but the state must be changed to a higher state to perform the restore operation, the database state is changed automatically even if you do not select the check box.

If a database is in the open state, and for restore the database needs to be in the mounted state, then the database state is changed only if you select this check box.

- 5. On the Recovery Scope page, perform the following actions:
  - a. Specify the recovery scope.

If you	Do this
Want to recover to the last transaction	Select All Logs.
Want to recover to a specific System Change Number (SCN)	Select Until SCN (System Change Number).
Want to recover to a specific data and time	Select <b>Date and Time</b> .  You must specify the date and time of the database host's time zone.
Do not want to recover	Select No recovery.
Want to specify any external archive log locations	If the archive logs are not present in the AFS, you should specify the location that contains the archive logs required for recovery.

b. Select the check box if you want to open the database after recovery.

In a RAC setup, only the RAC instance that is used for recovery is opened after recovery.

6. Review the details and click **Restore**.

#### Restore SQL Server database

You can restore SQL Server database either to the same host or to the alternate host. Recovery of log backups and reseed of availability groups are not supported.

#### Steps

- 1. In Cloud Manager UI, click Backup & Restore > Applications.
- 2. In the Filter By field, select the filter Type and from the drop-down select SQL.
- 3. Click View Details to view all the available backups.
- 4. Select the backup and click **Restore**.
- 5. Select the location where you want to restore the database files.

Option	Description
Restore the database to the same host where the backup was created	Select this option if you want to restore the database to the same SQL server where the backups are taken.

Option	Description		
Restore the database to an alternate host	Select this option if you want the database to be restored to a different SQL server in the same or different host where backups are taken.		
	Select a host name, provide a database name (optional), select an instance, and specify the restore paths.		
	i	The file extension provided in the alternate path must be same as the file extension of the original database file.	
	If the <b>Restore the database to an alternate host</b> option is not displayed in the Restore Scope page, clear the browser cache.		

- 6. On the **Pre Restore Options** page, select one of the following options:
  - Select Overwrite the database with same name during restore to restore the database with the same name.
  - Select Retain SQL database replication settings to restore the database and retain the existing replication settings.
- 7. On the **Post Restore Options** page, to specify the database state for restoring additional transactional logs, select one of the following options:
  - Select **Operational, but unavailable** if you are restoring all of the necessary backups now.

This is the default behavior, which leaves the database ready for use by rolling back the uncommitted transactions. You cannot restore additional transaction logs until you create a backup.

 Select Non-operational, but available to leave the database non-operational without rolling back the uncommitted transactions.

Additional transaction logs can be restored. You cannot use the database until it is recovered.

• Select **Read-only mode**, and available to leave the database in read-only mode.

This option undoes uncommitted transactions, but saves the undone actions in a standby file so that recovery effects can be reverted.

If the Undo directory option is enabled, more transaction logs are restored. If the restore operation for the transaction log is unsuccessful, the changes can be rolled back. The SQL Server documentation contains more information.

8. Review the details and click **Restore**.

# **Back up and restore Virtual Machines data**

## Protect your virtual machines data

You can protect data on your virtual machines by integrating the SnapCenter Plug-in for VMware vSphere with Cloud Manager. You can back up datastores to the cloud and restore virtual machines back to the on-premises SnapCenter Plug-in for VMware vSphere with ease.


You can back up datastores to Amazon Web Services S3 or Microsoft Azure Blob.

### Requirements

Read the following requirements to make sure that you have a supported configuration before you start backing up datastores and virtual machines to cloud services.

- SnapCenter Plug-in for VMware vSphere 4.6P1 or later
- ONTAP 9.8 or later
- · Cloud Manager 3.9 or later
- At least one backup should have been taken in SnapCenter Plug-in for VMware vSphere 4.6P1.
- At least one daily, weekly, or monthly policy in SnapCenter Plug-in for VMware vSphere with no label or same label as that of the Cloud Backup for Virtual Machines policy in Cloud Manager.
- For a pre-canned policy, the schedule tier should be the same for the datastore in SnapCenter Plug-in for VMware vSphere and in the cloud.
- Ensure that there are no FlexGroup volumes in the datastore because backing up and restoring FlexGroup volumes are not supported.
- Ensure that none of the volumes are encrypted because restoring encrypted volumes are not supported.
- Disable "\_recent" on the required resource groups. If you have "\_recent" enabled for the resource group, then the backups of those resource groups cannot be used for data protection to cloud and subsequently cannot be used for the restore operation.
- Ensure that the destination datastore where the virtual machine will be restored has enough space to accommodate a copy of all virtual machine files such as VMDK, VMX, VMSD, and so on.
- Ensure that the destination datastore does not have stale virtual machine files in the format of restore\_xxx\_xxxxxx\_filename from the previous restore operation failures. You should delete the stale files before triggering a restore operation.

The following image shows each component and the connections that you need to prepare between them:



### **Protection Policies**

You should use the one of the policies defined in the Cloud Backup for virtual machines to back up datastores to cloud.



Custom polices are not supported.

You can view the default policies by clicking **Backup & Restore** > **Virtual Machines** > **Policies** in Cloud Manager.

Policy Name	Label	Retention Value
1 Year Daily LTR	Daily	366
5 Years Daily LTR	Daily	1830
7 Year Weekly LTR	Weekly	370
10 Year Monthly LTR	Monthly	120

## Back up datastores to the cloud

You can back up datastores to the cloud by integrating the SnapCenter Plug-in for VMware vSphere with Cloud Manager. This will help the VM administrators to easily and quickly back up and archive data for storage efficiency and accelerate cloud transition.



Ensure that you have met all the requirements before backing up datastores to the cloud.

### Register SnapCenter Plug-in for VMware vSphere

You should register the SnapCenter Plug-in for VMware vSphere in Cloud Manager for the datastores and virtual machines to be displayed in Cloud Manager. Only a user with administrative access can register the SnapCenter Plug-in for VMware vSphere.



You can register multiple SnapCenter Plug-in for VMware vSphere. However, once registered, you cannot remove the SnapCenter Plug-in for VMware vSphere.

### **Steps**

- 1. In Cloud Manager UI, click Backup & Restore > Virtual Machines.
- 2. From the Settings drop-down, click SnapCenter Plug-in for VMware vSphere.
- 3. Click Register SnapCenter Plug-in for VMware vSphere.
- 4. Specify the following details:
  - a. In the SnapCenter Plug-in for VMware vSphere field, specify the FQDN or IP address of the SnapCenter Plug-in for VMware vSphere.
  - b. In the Port field, specify the port number on which the SnapCenter Plug-in for VMware vSphere is running.

You should ensure that the port is open for communication to happen between SnapCenter Plug-in for VMware vSphere and Cloud Backup for Applications.

- c. In the Username and Password field, specify the credentials of the user with the administrator role.
- 5. Click Register.

#### After you finish

Click **Backup & Restore > Virtual Machines** to view all the datastores and virtual machines that are eligible for protection using the registered SnapCenter Plug-in for VMware vSphere.

### **Back up datastores**

You can back up one or more datastores simultaneously to the cloud using a single policy. Only the default policies can be assigned to the datastore.

#### **Steps**

- 1. In Cloud Manager UI, click Backup & Restore > Virtual Machines.
- 2. Click ••• corresponding to the datastore that you want to back up and click **Activate Backup**.
- 3. Add the working environment.

Configure the ONTAP clusters that you want Cloud Manager to discover to back up your datastores. After adding the working environment for one of the datastores, it can be reused for all the other datastores residing on the same ONTAP cluster.

- a. Click Add Working Environment corresponding to the SVM.
- b. In the Add Working Environment wizard:
  - i. Specify the IP address of the ONTAP cluster.
  - ii. Specify the credentials of the ONTAP cluster user.
- c. Click Add Working Environment.
- 4. Select and configure the cloud provider.

### **Configure Amazon Web Services**

- a. Specify the AWS account.
- b. In the AWS Access Key field, specify the key for data encryption.
- c. In the AWS Secret Key field, specify the password for data encryption.
- d. Select the region where you want to create the backups.
- e. Specify the IP addresses of the ONTAP clusters that were added as the working environments.

#### **Configure Microsoft Azure**

- a. Specify the Azure subscription ID.
- b. Select the region where you want to create the backups.
- c. Create a new resource group or use an existing resource group.
- d. Specify the IP addresses of the ONTAP clusters that were added as the working environments.
- 5. In the Assign Policy page, select the policy and click **Next**.
- 6. Review the details and click **Activate Backup**.

## Manage protection of virtual machines

You can view policies, datastores, and virtual machines before you back up and restore data. Depending upon the change in database, policies, or resource groups, you can refresh the updates from the Cloud Manager UI.

### View policies

You can view all the default pre-canned policies. For each of these policies, when you view the details, all the associated Cloud Backup for Virtual Machines policies and all the associated virtual machines are listed.

- Click Backup & Restore > Virtual Machines.
- 2. From the **Settings** drop-down, click **Policies**.
- Click View Details corresponding to policy whose details you want to view.

The associated Cloud Backup for Virtual Machines policies and all the virtual machines are listed.

### View the datastores and virtual machines

The datastores and virtual machines that are protected using the registered SnapCenter Plug-in for VMware vSphere are displayed.

#### About this task

- · Only NFS datastores are displayed.
- Only datastores for which at least one successful backup has been taken in SnapCenter Plug-in for VMware vSphere are displayed.

### **Steps**

- 1. In Cloud Manager UI, click Backup & Restore > Virtual Machines > Settings > SnapCenter Plug-in for VMware vSphere.
- 2. Click the SnapCenter Plug-in for VMware vSphere for which you want to see the datastores and virtual machines.

### Edit the SnapCenter Plug-in for VMware vSphere Instance

You can edit the details of the SnapCenter Plug-in for VMware vSphere in Cloud Manager

#### Steps

- 1. In Cloud Manager UI, click Backup & Restore > Virtual Machines > Settings > SnapCenter Plug-in for VMware vSphere.
- 2. Click and select Edit
- 3. Modify the details as required
- 4. Click Save.

#### Refresh Protection Status

When new volumes are added to the database, or if there is a change to the policy or resource group, you should refresh the protection.

- 1. Click Backup & Restore > Virtual Machines.
- From the Settings drop-down, click SnapCenter Plug-in for VMware vSphere.
- 3. Click ••• corresponding to the SnapCenter Plug-in for VMware vSphere hosting the virtual machine and click **Refresh**.

The new changes are discovered.

4. Click ••• corresponding to the datastore and click **Refresh Protection** to enable cloud protection for the changes.

### **Monitor Jobs**

Jobs are created for all the Cloud Backup operations. You can monitor all the jobs and all the sub tasks that are performed as part of each task.

1. Click Backup & Restore > Job Monitoring.

When you initiate an operation, a window appears stating that the job is initiated. You can click the link to

monitor the job.

2. Click the primary task to view the sub tasks and status of each of these sub tasks.

### Restore virtual machines from the cloud

You can restore virtual machines from the cloud back to the on-premises vCenter. The backup will be restored to the exact same location from where the backup was taken. You cannot restore the backup to any other alternate location. You can restore virtual machines from the datastore or from the VMs view.



You cannot restore virtual machines that are spanned across datastores.

#### What you'll need

Ensure that you have met all the requirements before restoring virtual machines from the cloud.

#### **Steps**

 In Cloud Manager, click Backup & Restore > Virtual Machines > SnapCenter Plug-in for VMware vSphere and select the SnapCenter Plug-in for VMware vSphere whose virtual machine you want to restore.



If the source virtual machine is moved to another location (vMotion), and if the user triggers a restore of that virtual machine from Cloud Manager, then the virtual machine will get restored to the original source location from where the backup was taken.

- 2. To restore from Datastore:
  - a. Click ••• corresponding to the datastore that you want to restore and click View Details.
  - b. Click **Restore** corresponding to the backup you want to restore.
  - c. Select the virtual machine that you want to restore from the backup and click Next.
  - d. Review the details and click **Restore**.
- 3. To restore from Virtual Machines:
  - a. Click ••• corresponding to the virtual machine that you want to restore and click **Restore**.
  - b. Select the backup through which you want to restore the virtual machine and click Next.
  - c. Review the details and click Restore.

The VM is restored to the same location from where the backup was taken.

# **Cloud Backup APIs**

The Cloud Backup capabilities that are available through the web UI are also available through the RESTful API.

There are eight categories of endpoints defined within the Cloud Backup service:

- backup
- catalog
- cloud
- job
- license
- restore
- · single file-level restore (SFR)
- · working environment

## **Getting started**

To get started with the Cloud Backup APIs, you'll need to obtain a user token, your Cloud Central account ID, and the Cloud Connector ID.

When making API calls, you'll add the user token in the Authorization header, and the Cloud Connector ID in the x-agent-id header. You should use the Cloud Central account ID in the APIs.

#### **Steps**

1. Obtain a user token from NetApp Cloud Central.

Make sure to generate the refresh token from the following xref:./ https://services.cloud.netapp.com/refresh-token/. The refresh token is an alpha-numeric string that you'll use to generate a user token.

```
curl --location --request POST 'https://netapp-cloud-
account.auth0.com/oauth/token?=' \
    --header 'Content-Type: application/json' \
    -d '{
        "grant_type": "refresh_token",
        "refresh_token": "JxaVHn9cGkX92aPVCkhat3zxxxxxwsC9qMl_pLHkZtsVA",
        "client_id": "Mu0VlywgYteI6w1MbD15fKfVIUrNXGWC"
}'
```

Obtain your NetApp Cloud Central account ID.

```
GET 'https://cloudmanager.cloud.netapp.com/tenancy/account' -H
'authority: cloudmanager.cloud.netapp.com'
Header:
-H 'accept: application/json'
-H 'accept-language: en-GB,en;q=0.9'
-H 'authorization: Bearer eyJhbGciOiJSUzI1NiIsInR........
```

This API will return a response like the following. You can retrieve account ID by parsing the output from **[0].[ accountPublicId]**.

```
[{"accountPublicId":"account-
i6vJXvZW", "accountName": "rashidn", "isSaas": true, "isGov": false, "isPrivate
PreviewEnabled": false, "is3rdPartyServicesEnabled": false, "accountSerial":
"96064469711530003565", "userRole": "Role-1"}........
```

3. Obtain the x-agent-id which contains the Cloud Manager Connector ID.

This API will return a response like the following. You can retrieve the agent id by parsing the output from occm.[0].[agent].[agentId].

```
{"occms":[{"account":"account-OOnAR4ZS", "accountName":"cbs", "occm":"imEdsEW4HyYTFbt8ZcNKTKDF05jMIe6Z", "agentId":"imEdsEW4HyYTFbt8ZcNKTKDF05jMIe6Z", "status":"ready", "occmName":"cbsgcpdevcntsg-asia", "primaryCallbackUri":"http://34.93.197.21", "manualOverrideUris":[], "automaticCallbackUris":["http://34.93.197.21", "http://34.93.197.21/occmui", "https://34.93.197.21", "https://34.93.197.21/occmui", "http://10.138.0.16/occmui", "https://10.138.0.16", "http://10.138.0.16/occmui", "http://localhost/occmui", "http://localhost:1337", "http://localhost:1337/occmui", "https://localhost/occmui", "https://localhost:1337/occmui", "https://localhost:1337/occmu
```

## **Example using the APIs**

The following example shows an API call to activate backup on Working Environment with a new policy that has daily, hourly, and weekly labels set and archive after days set as 180 days, in East-US-2 region in Azure cloud. Please note this enables backup only on Working Environment but no volumes are backed up. If you choose ""auto-backup-enabled": true then any volumes already existing in the system would be backed up, plus future volumes added.

#### **API Request**

You'll see that we use the Cloud Central account ID "account-DpTFcxN3", Cloud Manager Connector ID "iZwFFeVCZjWnzGlw8RgD0QQNANZvpP7Iclients", and user token "Bearer eyJhbGciOiJSUzI1NilsInR5cCl6IkpXVCIsImtpZCl6Ik5rSXIPVFUzUWpZek1E...y6nyhBjwkeMwHc4ValobjUmju 2x0xUH48g" in this command.

```
curl --location --request POST
'https://cloudmanager.cloud.netapp.com/account/account-
DpTFcxN3/providers/cloudmanager cbs/api/v3/backup/working-
environment/VsaWorkingEnvironment-99hPYEgk' \
--header 'x-agent-id: iZwFFeVCZjWnzGlw8RgD0QQNANZvpP7Iclients' \
--header 'Accept: application/json' \
--header 'Content-Type: application/json' \
--header 'Authorization: Bearer
eyJhbGciOiJSUzI1NiIsInR5cCI6IkpXVCIsImtpZCI6Ik5rSXlPVFUzUWpZek1E...y6nyhBjwk
eMwHc4ValobjUmju2x0xUH48g' \
--data-raw '{
    "provider": "AZURE",
    "backup-policy": {
      "archive-after-days": 180,
      "rule": [
          "label": "hourly",
          "retention": "2"
        },
          "label": "daily",
          "retention": "30"
        },
          "label": "weekly",
          "retention": "52"
     ]
    "ip-space": "Default",
    "region": "eastus2",
    "azure": {
      "resource-group": "rn-test-backup-rg",
      "subscription": "3beb4dd0-25d4-464f-9bb0-303d7cf5c0c2"
```

### Response is a job ID that you can then monitor.

```
{
    "job-id": "1b34b6f6-8f43-40fb-9a52-485b0dfe893a"
}
```

#### Monitor the response.

```
curl --location --request GET
'https://cloudmanager.cloud.netapp.com/account/account-
DpTFcxN3/providers/cloudmanager_cbs/api/v1/job/1b34b6f6-8f43-40fb-9a52-
485b0dfe893a' \
    --header 'x-agent-id: iZwFFeVCZjWnzGlw8RgD0QQNANZvpP7Iclients' \
    --header 'Accept: application/json' \
    --header 'Accept: application/json' \
    --header 'Content-Type: application/json' \
    --header 'Authorization: Bearer
eyJhbGciOiJSUzI1NiIsInR5cCI6IkpXVCIsImtpZCI6Ik5rSXlPVFUzUWpZek1E...hE9ss2Nub
K6wZRHUdSaORI7JvcOorUhJ8srqdiUiW6MvuGIFAQIh668of2M3dLbhVDBe8BBMtsa939UGnJx
7Qz6Eg'
```

### Response.

#### Monitor until "status" is "COMPLETED".

### What should I do when the token expires?

The user token from NetApp Cloud Central has an expiration date. To refresh the token, you need to call the API from step 1 again.

The API response includes an "expires\_in" field that states when the token expires.

## **API** reference

Documentation for each Cloud Backup API is available from https://docs.netapp.com/us-en/cloud-manager-automation/cbs/overview.html.

## Reference

## AWS S3 archival storage classes and restore retrieval times

Cloud Backup supports two S3 archival storage classes and most regions.

### Supported S3 archival storage classes for Cloud Backup

When backup files are initially created they're stored in S3 *Standard* storage. This tier is optimized for storing data that's infrequently accessed; but that also allows you to access it immediately. After 30 days the backups transition to the S3 *Standard-Infrequent Access* storage class to save on costs.

If your source clusters are running ONTAP 9.10.1 or greater, you can choose to tier backups to either *S3 Glacier* or *S3 Glacier Deep Archive* storage after a certain number of days (typically more than 30 days) for further cost optimization. Data in these tiers can't be accessed immediately when needed, and will require a higher retrieval cost, so you need to consider how often you may need to restore data from these archived backup files. See the section about restoring data from archival storage.

Note that when you configure Cloud Backup with this type of lifecycle rule, you must not configure any lifecycle rules when setting up the bucket in your AWS account.

Learn about S3 storage classes.

### Restoring data from archival storage

While storing older backup files in archival storage is much less expensive than Standard or Standard-IA storage, accessing data from a backup file in archive storage for restore operations will take a longer amount of time and will cost more money.

#### How much does it cost to restore data from Amazon S3 Glacier and Amazon S3 Glacier Deep Archive?

There are 3 restore priorities you can choose when retrieving data from Amazon S3 Glacier, and 2 restore priorities when retrieving data from Amazon S3 Glacier Deep Archive. S3 Glacier Deep Archive costs less than S3 Glacier:

Archive Tier	Restore Priority & Cost		
	High	Standard	Low
S3 Glacier	Fastest retrieval, highest cost	Slower retrieval, lower cost	Slowest retrieval, lowest cost
S3 Glacier Deep Archive		Faster retrieval, higher cost	Slower retrieval, lowest cost

Each method has a different per-GB retrieval fee and per-request fee. For detailed S3 Glacier pricing by AWS Region, visit the Amazon S3 pricing page.

### How long will it take to restore my objects archived in Amazon S3 Glacier?

There are 2 parts that make up the total restore time:

• **Retrieval time**: The time to retrieve the backup file from archive and place it in Standard storage. This is sometimes called the "rehydration" time. The retrieval time is different depending on the restore priority you choose.

Archive Tier	Restore Priority & Retrieval Time			
	High	Standard	Low	
S3 Glacier	3-5 minutes	3-5 hours	5-12 hours	
S3 Glacier Deep Archive		12 hours	48 hours	

• **Restore time**: The time to restore the data from the backup file in Standard storage. This time is no different than the typical restore operation directly from Standard storage - when not using an archival tier.

For more information about Amazon S3 Glacier and S3 Glacier Deep Archive retrieval options, refer to the Amazon FAQ about these storage classes.

### Azure archival tiers and restore retrieval times

Cloud Backup supports one Azure archival access tier and most regions.

### Supported Azure Blob access tiers for Cloud Backup

When backup files are initially created they're stored in the *Cool* access tier. This tier is optimized for storing data that's infrequently accessed; but when needed, can be accessed immediately.

If your source clusters are running ONTAP 9.10.1 or greater, you can choose to tier backups from *Cool* to *Azure Archive* storage after a certain number of days (typically more than 30 days) for further cost optimization. Data in this tier can't be accessed immediately when needed, and will require a higher retrieval cost, so you need to consider how often you may need to restore data from these archived backup files. See the next section about restoring data from archival storage.

Note that when you configure Cloud Backup with this type of lifecycle rule, you must not configure any lifecycle rules when setting up the container in your Azure account.

Learn about Azure Blob access tiers.

### Restoring data from archival storage

While storing older backup files in archival storage is much less expensive than Cool storage, accessing data from a backup file in Azure Archive for restore operations will take a longer amount of time and will cost more money.

#### How much does it cost to restore data from Azure Archive?

There are two restore priorities you can choose when retrieving data from Azure Archive:

- · High: Fastest retrieval, higher cost
- · Standard: Slower retrieval, lower cost

Each method has a different per-GB retrieval fee and per-request fee. For detailed Azure Archive pricing by Azure Region, visit the Azure pricing page.

### How long will it take to restore my data archived in Azure Archive?

There are 2 parts that make up the restore time:

- Retrieval time: The time to retrieve the archived backup file from Azure Archive and place it in Cool storage. This is sometimes called the "rehydration" time. The retrieval time is different depending on the restore priority you choose:
  - **High**: < 1 hour
  - Standard: < 15 hours
- **Restore time**: The time to restore the data from the backup file in Cool storage. This time is no different than the typical restore operation directly from Cool storage when not using an archival tier.

For more information about Azure Archive retrieval options, refer to this Azure FAQ.

## Cross-account and cross-region configurations

These topics describe how to configure Cloud Backup for cross account configurations when using different cloud providers.

• Configure Cloud Backup for multi-account access in Azure

### Configure backup for multi-account access in AWS

Cloud Backup enables you to create backup files in an AWS account that is different than where your source Cloud Volumes ONTAP volumes reside. And both of those accounts can be different than the account where the Cloud Manager Connector resides.

These steps are required only when you are backing up Cloud Volumes ONTAP data to Amazon S3.

Follow the steps below to set up your configuration in this manner.

### Set up VPC peering between accounts

- 1. Log in to second account and Create Peering Connection:
  - a. Select a local VPC: Select the VPC of the second account.
  - b. Select another VPC: Enter the account ID of the first account.
  - c. Select the Region where the Cloud Manager Connector is running. In this test setup both accounts are running in same region.
  - d. VPC ID: Log into first account and enter the acceptor VPC ID. This is the VPC ID of the Cloud Manager Connector.



A Success dialog displays.



The status of the peering connection shows as Pending Acceptance.



2. Log into the first account and accept the peering request:






a. Click Yes.



The connection now shows as Active. We have also added a Name tag to identify the peering connection called cbs-multi-account.




b. Refresh the peering connection in the second account and notice that the status changes to Active.




#### Add a route to the route tables in both accounts

1. Go to VPC > Subnet > Route table.



2. Click on the Routes tab.



3. Click Edit routes.



- 4. Click **Add route**, and from the Target drop-down list select **Peering Connection**, and then select the peering connection that you created.
  - a. In the Destination, enter the other account's subnet CIDR.



b. Click Save routes and a Success dialog displays.




### Add the second AWS account credentials in Cloud Manager


1. Add the second AWS account, for example, Saran-XCP-Dev.



2. In the Discover Cloud Volumes ONTAP page, select the newly added credentials.



3. Select the Cloud Volumes ONTAP system you want to discover from second account. You can also deploy a new Cloud Volumes ONTAP system in the second account.



The Cloud Volumes ONTAP system from the second account is now added to Cloud Manager which is running in a different account.



### Enable backup in the other AWS account

1. In Cloud Manager, enable backup for the Cloud Volumes ONTAP system running in the first account, but select the second account as the location for creating the backup files.



2. Then select a backup policy and the volumes you want to back up, and Cloud Backup attempts to create a new bucket in the selected account.


However, adding the bucket to the Cloud Volumes ONTAP system will fail because Cloud Backup uses the instance profile to add the bucket and the Cloud Manager instance profile doesn't have access to the resources in the second account.

3. Get the working environment ID for the Cloud Volumes ONTAP system.



Cloud Backup creates every bucket with the prefix Netapp-backup- and will include the working environment ID; for example: 87ULeA10

4. In the EC2 portal, go to S3 and search for the bucket with name ending with 87uLeA10 and you'll see the bucket name displayed as Netapp-backup-vsa87uLeA10.



5. Click on the bucket, then click the Permissions tab, and then click **Edit** in the Bucket policy section.



6. Add a bucket policy for the newly created bucket to provide access to the Cloud Manager's AWS account, and then Save the changes.

```
"Version": "2012-10-17",
  "Statement": [
      "Sid": "PublicRead",
      "Effect": "Allow",
      "Principal": {
        "AWS": "arn:aws:iam::464262061435:root"
      },
      "Action": [
        "s3:ListBucket",
        "s3:GetBucketLocation",
        "s3:GetObject",
        "s3:PutObject",
        "s3:DeleteObject"
      1,
      "Resource": [
        "arn:aws:s3:::netapp-backup-vsa87uleai0",
        "arn:aws:s3:::netapp-backup-vsa87uleai0/*"
  1
}
```

Note that "AWS": "arn:aws:iam::464262061435:root" gives complete access this bucket for all resources in account 464262061435. If you want to reduce it to specific role, level, you can update the policy with specific role(s). If you are adding individual roles, ensure that occm role also added, otherwise backups will not get updated in the Cloud Backup UI.

For example: "AWS": "arn:aws:iam::464262061435:role/cvo-instance-profile-version10-d8e-lamInstanceRole-IKJPJ1HC2E7R"

7. Retry enabling Cloud Backup on the Cloud Volumes ONTAP system and this time it should be successful.

### Configure backup for multi-account access in Azure

Cloud Backup enables you to create backup files in an Azure account that is different than where your source Cloud Volumes ONTAP volumes reside. And both of those accounts can be different than the account where the Cloud Manager Connector resides.

These steps are required only when you are backing up Cloud Volumes ONTAP data to Azure Blob storage.


Just follow the steps below to set up your configuration in this manner.

#### Set up VNet peering between accounts

Note that if you want Cloud Manager to manage your Cloud Volumes ONTAP system in a different account/region, then you need to setup VNet peering. VNet peering is not required for storage account

#### connectivity.

- 1. Log in to the Azure portal and from home, select Virtual Networks.
- 2. Select the subscription you are using as subscription 1 and click on the VNet where you want to set up peering.




3. Select cbsnetwork and from the left panel, click on Peerings, and then click Add.



- 4. Enter the following information on the Peering page and then click **Add**.
  - Peering link name for this network: you can give any name to identify the peering connection.
  - Remote virtual network peering link name: enter a name to identify the remote VNet.

- Keep all the selections as default values.
- Under subscription, select the subscription 2.
- Virtual network, select the virtual network in subscription 2 to which you want to set up the peering.



5. Perform the same steps in subscription 2 VNet and specify the subscription and remote VNet details of subscription 1.



The peering settings are added.



### Create a private endpoint for the storage account

Now you need to create a private endpoint for the storage account. In this example, the storage account is created in subscription 1 and the Cloud Volumes ONTAP system is running in subscription 2.



You need network contributor permission to perform the following action.

```
"id": "/subscriptions/d333af45-0d07-4154-
943dc25fbbce1b18/providers/Microsoft.Authorization/roleDefinitions/4d97b98
b-1d4f-4787-a291-c67834d212e7",
  "properties": {
    "roleName": "Network Contributor",
    "description": "Lets you manage networks, but not access to them.",
    "assignableScopes": [
      11 / 11
    ],
    "permissions": [
      {
        "actions": [
          "Microsoft.Authorization/*/read",
          "Microsoft.Insights/alertRules/*",
          "Microsoft.Network/*",
          "Microsoft.ResourceHealth/availabilityStatuses/read",
          "Microsoft.Resources/deployments/*",
          "Microsoft.Resources/subscriptions/resourceGroups/read",
          "Microsoft.Support/*"
        ],
        "notActions": [],
        "dataActions": [],
        "notDataActions": []
    1
  }
}
```

1. Go to the storage account > Networking > Private endpoint connections and click + Private endpoint.



### 2. In the Private Endpoint *Basics* page:


- Select subscription 2 (where the Cloud Manager Connector and Cloud Volumes ONTAP system are deployed) and the resource group.
- · Enter an endpoint name.
- Select the region.



3. In the Resource page, select Target sub-resource as blob.



- 4. In the Configuration page:
  - Select the virtual network and subnet.
  - Click the Yes radio button to "Integrate with private DNS zone".



5. In the Private DNS zone list, ensure that the Private Zone is selected from the correct Region, and click **Review + Create**.



Now the storage account (in subscription 1) has access to the Cloud Volumes ONTAP system which is running in subscription 2.

6. Retry enabling Cloud Backup on the Cloud Volumes ONTAP system and this time it should be successful.

# **Knowledge and support**

## Register for support

Before you can open a support case with NetApp technical support, you need to add a NetApp Support Site account to Cloud Manager and then register for support.

### Add an NSS account

The Support Dashboard enables you to add and manage all of your NetApp Support Site accounts from a single location.

### **Steps**

- 1. If you don't have a NetApp Support Site account yet, register for one.
- 2. In the upper right of the Cloud Manager console, click the Help icon, and select Support.



- 3. Click NSS Management > Add NSS Account.
- 4. When you're prompted, click **Continue** to be redirected to a Microsoft login page.

NetApp uses Microsoft Azure Active Directory as the identity provider for authentication services specific to support and licensing.

5. At the login page, provide your NetApp Support Site registered email address and password to perform the authentication process.

This action enables Cloud Manager to use your NSS account.

Note the account must be a customer-level account (not a guest or temp account).

### Register your account for support

Support registration is available from Cloud Manager in the Support Dashboard.

### **Steps**

In the upper right of the Cloud Manager console, click the Help icon, and select Support.



- 2. In the Resources tab, click Register for Support.
- 3. Select the NSS credentials that you want to register and then click **Register**.

## Get help

NetApp provides support for Cloud Manager and its cloud services in a variety of ways. Extensive free self-support options are available 24x7, such as knowledgebase (KB) articles and a community forum. Your support registration includes remote technical support via web ticketing.

### Self support

These options are available for free, 24 hours a day, 7 days a week:

· Knowledge base

Search through the Cloud Manager knowledge base to find helpful articles to troubleshoot issues.

Communities

Join the Cloud Manager community to follow ongoing discussions or create new ones.

Documentation

The Cloud Manager documentation that you're currently viewing.

Feedback email

We value your input. Submit feedback to help us improve Cloud Manager.

### **NetApp support**

In addition to the self-support options above, you can work with a NetApp Support Engineer to resolve any issues after you activate support.

### Steps

- 1. In Cloud Manager, click **Help > Support**.
- 2. Choose one of the available options under Technical Support:
  - a. Click Call Us to find phone numbers for NetApp technical support.
  - b. Click **Open an Issue**, select one the options, and then click **Send**.

A NetApp representative will review your case and get back to you soon.

# Legal notices

Legal notices provide access to copyright statements, trademarks, patents, and more.

# Copyright

http://www.netapp.com/us/legal/copyright.aspx

### **Trademarks**

NETAPP, the NETAPP logo, and the marks listed on the NetApp Trademarks page are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.

http://www.netapp.com/us/legal/netapptmlist.aspx

### **Patents**

A current list of NetApp owned patents can be found at:

https://www.netapp.com/us/media/patents-page.pdf

# **Privacy policy**

https://www.netapp.com/us/legal/privacypolicy/index.aspx

## Open source

Notice files provide information about third-party copyright and licenses used in NetApp software.

- Notice for Cloud Manager 3.9
- Notice for the Cloud Backup
- Notice for Single File Restore

### **Copyright Information**

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

#### **Trademark Information**

NETAPP, the NETAPP logo, and the marks listed at <a href="http://www.netapp.com/TM">http://www.netapp.com/TM</a> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.