# **■** NetApp

### 9.3 Release Notes

**Cloud Volumes ONTAP** 

NetApp July 19, 2021

This PDF was generated from https://docs.netapp.com/us-en/cloud-volumes-ontap/reference\_new\_93.html on July 19, 2021. Always check docs.netapp.com for the latest.

## **Table of Contents**

| 9. | .3 Release Notes                              | 1 |
|----|-----------------------------------------------|---|
|    | What's new in ONTAP Cloud 9.3                 | 1 |
|    | Supported configurations for ONTAP Cloud 9.3. | 2 |
|    | Storage limits for ONTAP Cloud 9.3            | 3 |
|    | Known issues for ONTAP Cloud 9.3              | 6 |
|    | Known limitations for ONTAP Cloud 9.3.        | 6 |

### 9.3 Release Notes

### What's new in ONTAP Cloud 9.3

ONTAP Cloud 9.3 includes several new features and enhancements.

#### ONTAP Cloud HA enhancements in AWS

The 9.3 release addresses the resiliency of ONTAP Cloud HA pairs to tolerate network glitches or transient higher latencies within the AWS ecosystem, and to ensure the availability of customer data during such events.

### Support for the EU (Paris) region in AWS

ONTAP Cloud is now supported in the EU (Paris) region in AWS. Based on the supported instance types in this region, the following ONTAP Cloud configurations are available in the EU (Paris) region:

- ONTAP Cloud Standard (r4.xlarge)
- ONTAP Cloud Premium (r4.2xlarge)
- ONTAP Cloud BYOL (r4.xlarge and r4.2xlarge)

### **Enhanced write performance with Azure Premium disks**

Write performance for ONTAP Cloud has been improved in Azure when using Premium Storage disks. The enhancement is supported with ONTAP Cloud Standard, Premium, and BYOL.



Write performance enhancements are not supported when using the DS3\_v2 virtual machine type.

### Increased capacity limit for ONTAP Cloud Premium and BYOL in Azure

The capacity limit for ONTAP Cloud Premium and ONTAP Cloud BYOL has doubled to 252 TB when using the DS5\_v2 or DS14\_v2 virtual machine types.



This change is possible due to an increase in the number of disks available per Azure virtual machine. It does not change the maximum capacity per aggregate.

### **Support for Azure US Gov regions**

You can now deploy Cloud Manager and ONTAP Cloud BYOL in the following Azure regions:

- US Gov Arizona
- US Gov Texas
- US Gov Virginia

To deploy Cloud Manager in these regions, you must create a CentOS 7.3 virtual machine from the Azure Marketplace, download the Cloud Manager installer from the NetApp Support Site, and then install the software. After Cloud Manager is running, you can deploy ONTAP Cloud BYOL systems in the these regions just like any other region.

### Support for SVM disaster recovery

ONTAP Cloud supports one data-serving SVM and one destination SVM used for disaster recovery. You can activate the destination SVM for data access if there's an outage on the source SVM.

SVM disaster recovery is the asynchronous mirroring of SVM data and configuration from a source SVM to a destination SVM. You can quickly activate a destination SVM for data access if the source SVM is no longer available.



Cloud Manager does not provide any setup or orchestration support for SVM disaster recovery. It also does not support storage-related tasks on any additional SVMs. You must use System Manager or the CLI for SVM disaster recovery.

SVM Disaster Recovery Preparation Express Guide

SVM Disaster Recovery Express Guide

### **Upgrade notes**

- Upgrades must be completed from Cloud Manager. You should not upgrade ONTAP Cloud by using System Manager or the CLI. Doing so can impact system stability.
- You can upgrade to ONTAP Cloud 9.3 from ONTAP Cloud 9.2.
- The upgrade of a single node system takes the system offline for up to 25 minutes, during which I/O is interrupted.
- Upgrading an HA pair is nondisruptive and I/O is uninterrupted. During this nondisruptive upgrade process, each node is upgraded in tandem to continue serving I/O to clients.

### Supported configurations for ONTAP Cloud 9.3

ONTAP Cloud is available in AWS and Azure in two pricing options: pay-as-you-go and Bring Your Own License (BYOL). For pay-as-you-go, you can choose from three configurations: Explore, Standard, or Premium.

#### **ONTAP Cloud for AWS**

In AWS, you can deploy ONTAP Cloud as a single system or an HA pair.

|                    | Explore   | Standard     | Premium      | BYOL         |
|--------------------|-----------|--------------|--------------|--------------|
| EC2 instance types | m4.xlarge | • m4.2xlarge | • c4.4xlarge | • c4.4xlarge |
|                    |           | • r4.xlarge  | • c4.8xlarge | • c4.8xlarge |
|                    |           |              | • m4.4xlarge | • m4.xlarge  |
|                    |           |              | • r4.2xlarge | • m4.2xlarge |
|                    |           |              |              | • m4.4xlarge |
|                    |           |              |              | • r4.xlarge  |
|                    |           |              |              | • r4.2xlarge |
|                    |           |              |              |              |

|                        | Explore                                                                                                     | Standard | Premium | BYOL               |  |
|------------------------|-------------------------------------------------------------------------------------------------------------|----------|---------|--------------------|--|
| Underlying storage     | General Purpose SSDs, Provisioned IOPS SSDs, Throughput Optimized HDDs, and Cold HDDs, up to 16 TB per disk |          |         |                    |  |
| License capacity limit | 2 TB                                                                                                        | 10 TB    | 368 TB  | 368 TB per license |  |

#### Notes:

- 1. Pay-as-you-go configurations are not supported in GovCloud (US).
- 2. When you choose an EC2 instance type, you can specify whether it is a shared instance or a dedicated instance.
- 3. Enhanced write performance is supported when using EBS SSDs with ONTAP Cloud Standard, Premium, and BYOL.
- 4. Data tiering is supported with ONTAP Cloud Standard, Premium, and BYOL.
- 5. If you enable data tiering, a system's capacity limit stays the same. The capacity limit includes both disks and object storage.
- 6. For AWS region support, see Cloud Volumes Global Regions.

### **ONTAP Cloud for Azure**

In Azure, you can deploy ONTAP Cloud as a single node system.

|                                                                                                                                      | Explore | Standard  | Premium        | BYOL               |
|--------------------------------------------------------------------------------------------------------------------------------------|---------|-----------|----------------|--------------------|
| Virtual machine                                                                                                                      | DS3_v2  | • DS4_v2  | • DS5_v2       | • DS3_v2           |
| types                                                                                                                                |         | • DS13_v2 | • DS14_v2      | • DS4_v2           |
|                                                                                                                                      |         |           |                | • DS5_v2           |
|                                                                                                                                      |         |           |                | • DS13_v2          |
|                                                                                                                                      |         |           |                | • DS14_v2          |
|                                                                                                                                      |         |           |                |                    |
| <b>Underlying storage</b> Standard HDD Managed Disks, Standard SSD Managed Disks, and Premium SS Managed Disks, up to 32 TB per disk |         |           | nd Premium SSD |                    |
| License capacity limit                                                                                                               | 2 TB    | 10 TB     | 368 TB         | 368 TB per license |

#### Notes:

- 1. Enhanced write performance is supported when using Azure Premium Storage disks with ONTAP Cloud Standard, Premium, and BYOL, but not when using the DS3 v2 virtual machine type.
- 2. For Azure region support, see Cloud Volumes Global Regions.

### **Storage limits for ONTAP Cloud 9.3**

ONTAP Cloud has storage configuration limits to provide reliable operations. For best performance, do not configure your system at the maximum values.

The following sections list limits for aggregates, volumes, LUNs, and related storage objects. Note that the maximum capacity for an ONTAP Cloud system is model specific. ONTAP Cloud configurations that support a lower raw capacity limit cannot reach some of the size and disk limits.

### Physical storage limits for ONTAP Cloud in AWS

| Physical storage     | Parameter                                                       | Limit                                                                                |
|----------------------|-----------------------------------------------------------------|--------------------------------------------------------------------------------------|
| Aggregates and disks | Maximum number of aggregates                                    | 34 for single-node configurations<br>18 per node in an HA configuration <sup>1</sup> |
|                      | Maximum aggregate size                                          | 96 TB of raw capacity                                                                |
|                      | Disks per aggregate                                             | 1-6 <sup>2</sup>                                                                     |
|                      | Maximum disk size                                               | 16 TB                                                                                |
|                      | Maximum number of data disks across all aggregates <sup>3</sup> | 34 for single-node configurations 31 per node in an HA configuration                 |
| RAID groups          | Maximum per aggregate                                           | 1                                                                                    |

#### Notes:

- 1. It is not possible to create 18 aggregates on both nodes in an HA pair because doing so would exceed the data disk limit.
- 2. All disks in an aggregate must be the same size.
- 3. The data disk limit is specific to disks that contain user data. The boot disk and root disk for each node are not included in this limit.

### Physical storage limits for ONTAP Cloud in Azure

| Physical storage     | Parameter                                                       | Limit                                                                                                            |
|----------------------|-----------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------|
| Aggregates and disks | Maximum number of aggregates                                    | 63                                                                                                               |
|                      | Maximum aggregate size                                          | 200 TB of raw capacity                                                                                           |
|                      | Disks per aggregate                                             | 1-12 1                                                                                                           |
|                      | Maximum disk size                                               | 32 TB                                                                                                            |
|                      | Maximum number of data disks across all aggregates <sup>2</sup> | <ul> <li>DS3_v2: 15</li> <li>DS4_v2: 31</li> <li>DS5_v2: 63</li> <li>DS13_v2: 31</li> <li>DS14_v2: 63</li> </ul> |
| RAID groups          | Maximum per aggregate                                           | 1                                                                                                                |

Notes:

- 1. All disks in an aggregate must be the same size.
- 2. The data disk limit is specific to disks that contain user data. The boot disk and root disk for each node are not included in this limit.

### Logical storage limits

| Logical storage                 | Parameter                                                        | Limit                                                                                                                                                                                                                                                          |
|---------------------------------|------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Storage virtual machines (SVMs) | Maximum number for<br>ONTAP Cloud<br>(HA pair or single<br>node) | One data-serving SVM and one destination SVM used for disaster recovery. You can activate the destination SVM for data access if there's an outage on the source SVM.   The one data-serving SVM spans the entire ONTAP Cloud system (HA pair or single node). |
| Files                           | Maximum size                                                     | 16 TB                                                                                                                                                                                                                                                          |
|                                 | Maximum per volume                                               | Volume size dependent, up to 2 billion                                                                                                                                                                                                                         |
| FlexClone volumes               | Hierarchical clone depth <sup>2</sup>                            | 499                                                                                                                                                                                                                                                            |
| FlexVol volumes                 | Maximum per node                                                 | 500                                                                                                                                                                                                                                                            |
|                                 | Minimum size                                                     | 20 MB                                                                                                                                                                                                                                                          |
|                                 | Maximum size                                                     | AWS: Dependent on the size of the aggregate <sup>3</sup> Azure: 100 TB                                                                                                                                                                                         |
| Qtrees                          | Maximum per FlexVol volume                                       | 4,995                                                                                                                                                                                                                                                          |
| Snapshot copies                 | Maximum per FlexVol volume                                       | 255                                                                                                                                                                                                                                                            |

### Notes:

- Cloud Manager does not provide any setup or orchestration support for SVM disaster recovery. It also does
  not support storage-related tasks on an additional SVM. You must use System Manager or the CLI for SVM
  disaster recovery.
  - SVM Disaster Recovery Preparation Express Guide
  - SVM Disaster Recovery Express Guide
- 2. Hierarchical clone depth is the maximum depth of a nested hierarchy of FlexClone volumes that can be created from a single FlexVol volume.
- 3. Less than 100 TB is supported because aggregates for this configuration are limited to 96 TB of *raw* capacity.

### iSCSI storage limits

| iSCSI storage  | Parameter                  | Limit |
|----------------|----------------------------|-------|
| LUNs           | Maximum per node           | 1,024 |
|                | Maximum number of LUN maps | 1,024 |
|                | Maximum size               | 16 TB |
|                | Maximum per volume         | 512   |
| igroups        | Maximum per node           | 256   |
| Initiators     | Maximum per node           | 512   |
|                | Maximum per igroup         | 128   |
| iSCSI sessions | Maximum per node           | 1,024 |
| LIFs           | Maximum per port           | 32    |
|                | Maximum per portset        | 32    |
| Portsets       | Maximum per node           | 256   |

### **Known issues for ONTAP Cloud 9.3**

Known issues identify problems that might prevent you from using this release of the product successfully.

There are no known issues in this release specific to ONTAP Cloud.

You can find known issues for ONTAP software in the ONTAP Release Notes.

### **Known limitations for ONTAP Cloud 9.3**

Known limitations identify platforms, devices, or functions that are not supported by this release of the product, or that do not interoperate correctly with it. Review these limitations carefully.

### **General limitations**

The following limitations apply to ONTAP Cloud in AWS and in Azure.

### Software updates must be completed by Cloud Manager

Upgrades of Cloud Volumes ONTAP must be completed from Cloud Manager. You should not upgrade Cloud Volumes ONTAP by using System Manager or the CLI. Doing so can impact system stability.

#### Encryption is not supported on boot and root disks

If you enabled an option from your cloud provider that automatically encrypts all new volumes or disks, then you must temporarily disable that option when deploying ONTAP Cloud. If you don't, then deployment of ONTAP Cloud will fail. Encryption is not supported on the boot and root disks for the ONTAP Cloud system.

### ONTAP Cloud deployment must not be modified from your cloud provider's console

Changes to an ONTAP Cloud configuration from your cloud provider's console results in an unsupported configuration. Any changes to the ONTAP Cloud resources that Cloud Manager creates and manages can impact system stability and Cloud Manager's ability to manage the system.

### Disks and aggregates must be managed from Cloud Manager

All disks and aggregates must be created and deleted directly from Cloud Manager. You should not perform these actions from another management tool. Doing so can impact system stability, hamper the ability to add disks in the future, and potentially generate redundant cloud provider fees.

### **SnapManager licensing limitation**

SnapManager per-server licenses are supported with ONTAP Cloud. Per-storage system (SnapManager suite) licenses are not supported.

### **Unsupported ONTAP features**

The following features are not supported with ONTAP Cloud:

- · Aggregate-level inline deduplication
- · Aggregate-level background deduplication
- · Disk maintenance center
- · Disk sanitization
- Fibre Channel (FC)
- Flash Pools
- FlexCache
- FlexGroup volumes
- · Infinite Volumes
- · Interface groups
- Intranode LIF failover
- MetroCluster
- Multi-tenancy (only one data-serving SVM is supported)
- NetApp Volume Encryption
- RAID4, RAID-DP, RAID-TEC (RAID0 is supported)
- Service Processor
- SnapLock
- SnapMirror Synchronous
- VLANs

### **Known limitations for ONTAP Cloud in AWS**

The following known limitations affect ONTAP Cloud in AWS.

#### False alarms reported by Amazon CloudWatch

ONTAP Cloud does not release CPUs when idle, so Amazon CloudWatch can report a high CPU warning for the EC2 instance because it sees 100% usage. You can ignore this alarm. The ONTAP statistics command displays the true usage of the CPUs.

#### ONTAP Cloud HA pairs do not support immediate storage giveback

After a node reboots, the partner must sync data before it can return the storage. The time that it takes to resync data depends on the amount of data written by clients while the node was down and the data write speed during the time of giveback.

### Limitations with the AWS GovCloud (US) region

- Cloud Manager must be deployed in an AWS GovCloud (US) region if you want to launch Cloud Volumes ONTAP instances in any AWS GovCloud (US) region.
- The ONTAP Cloud pay-as-you-go AMI is not supported in the AWS GovCloud (US) region.
- When deployed in the AWS GovCloud (US) region, Cloud Manager cannot discover ONTAP clusters in a NetApp Private Storage for Microsoft Azure configuration or a NetApp Private Storage for SoftLayer configuration.

#### Detaching and reattaching EBS volumes is not supported

Detaching an EBS volume from an ONTAP Cloud instance and then reattaching it to another ONTAP Cloud instance is not supported. You should use Cloud Manager to replicate data between instances.

### **Encryption limitations**

- LUN move is not supported on systems that have ONTAP Cloud encryption enabled.
- ONTAP Cloud sends encryption keys to key managers even for aggregates that it failed to create.

You must manually delete the keys from key managers.

#### **Known limitations for ONTAP Cloud in Azure**

The following known limitations affect ONTAP Cloud in Azure.

#### ONTAP Cloud pay-as-you-go not available for CSP partners

If you are a Microsoft Cloud Solution Provider (CSP) partner, you cannot deploy ONTAP Cloud Explore, Standard, or Premium because pay-as-you-go subscriptions are not available for CSP partners. You must purchase a license and deploy ONTAP Cloud BYOL.

#### **Copyright Information**

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

#### **Trademark Information**

NETAPP, the NETAPP logo, and the marks listed at <a href="http://www.netapp.com/TM">http://www.netapp.com/TM</a> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.