Security group rules for Azure

Cloud Manager 3.5

Ben Cammett 11/01/2018

This PDF was generated from https://docs.netapp.com/us-en/occm35/reference_security_groups_azure.html on 04/17/2020. Always check docs.netapp.com for the latest.



Table of Contents

| Security group rules for Azure | |
|--------------------------------|--|
| Rules for Cloud Manager | |
| Rules for Cloud Volumes ONTAP | |

Security group rules for Azure

Cloud Manager creates Azure security groups that include the inbound and outbound rules that Cloud Manager and Cloud Volumes ONTAP need to operate successfully. You might want to refer to the ports for testing purposes or if you prefer your to use own security groups.

Rules for Cloud Manager

The security group for Cloud Manager requires both inbound and outbound rules.

Inbound rules for Cloud Manager

The source for inbound rules in the predefined security group is 0.0.0.0/0.

| Protocol | Port | Purpose |
|----------|------|---|
| SSH | 22 | Provides SSH access to the Cloud Manager host |
| HTTP | 80 | Provides HTTP access from client web browsers to the Cloud Manager web console |
| HTTPS | 443 | Provides HTTPS access from client web browsers to the Cloud Manager web console |

Outbound rules for Cloud Manager

The predefined security group for Cloud Manager opens all outbound traffic. If that is acceptable, follow the basic outbound rules. If you need more rigid rules, use the advanced outbound rules.

Basic outbound rules

The predefined security group for Cloud Manager includes the following outbound rules.

| Protocol | Port | Purpose |
|----------|------|----------------------|
| All TCP | All | All outbound traffic |
| All UDP | All | All outbound traffic |

Advanced outbound rules

If you need rigid rules for outbound traffic, you can use the following information to open only those ports that are required for outbound communication by Cloud Manager.



The source IP address is the Cloud Manager host.

| Service | Prot ocol | Po rt | Destination | Purpose |
|------------------------------|--|----------|--|--|
| Active | TCP | 88 | Active Directory forest | Kerberos V authentication |
| Directory | TCP | 139 | Active Directory forest | NetBIOS service session |
| | TCP | 389 | Active Directory forest | LDAP |
| | TCP | 445 | Active Directory forest | Microsoft SMB/CIFS over TCP with NetBIOS framing |
| | TCP | 464 | Active Directory forest | Kerberos V change & set password (SET_CHANGE) |
| | TCP | 749 | Active Directory forest | Active Directory Kerberos V change & set password (RPCSEC_GSS) |
| | UDP | 137 | Active Directory forest | NetBIOS name service |
| | UDP | 138 | Active Directory forest | NetBIOS datagram service |
| | UDP | 464 | Active Directory forest | Kerberos key administration |
| API calls and AutoSupport | HTTP S | 443 | Outbound internet and ONTAP cluster management LIF | API calls to AWS and ONTAP, and sending AutoSupport messages to NetApp |
| API calls | TCP 300 ONTAP cluster management 0 LIF | | _ | API calls to ONTAP |
| DNS | UDP | 53 | DNS | Used for DNS resolve by Cloud Manager |

Rules for Cloud Volumes ONTAP

The security group for Cloud Volumes ONTAP requires both inbound and outbound rules.

Inbound rules for Cloud Volumes ONTAP

The source for inbound rules in the predefined security group is 0.0.0.0/0.

| Protocol | Port | Purpose |
|----------|------|---|
| All ICMP | All | Pinging the instance |
| HTTP | 80 | HTTP access to the System Manager web console using the IP address of the cluster management LIF |
| HTTPS | 443 | HTTPS access to the System Manager web console using the IP address of the cluster management LIF |
| SSH | 22 | SSH access to the IP address of the cluster management LIF or a node management LIF |
| TCP | 111 | Remote procedure call for NFS |

| Protocol | Port | Purpose |
|----------|---------|--|
| TCP | 139 | NetBIOS service session for CIFS |
| TCP | 161-162 | Simple network management protocol |
| TCP | 445 | Microsoft SMB/CIFS over TCP with NetBIOS framing |
| TCP | 635 | NFS mount |
| TCP | 749 | Kerberos |
| TCP | 2049 | NFS server daemon |
| TCP | 3260 | iSCSI access through the iSCSI data LIF |
| TCP | 4045 | NFS lock daemon |
| TCP | 4046 | Network status monitor for NFS |
| TCP | 10000 | Backup using NDMP |
| TCP | 11104 | Management of intercluster communication sessions for SnapMirror |
| TCP | 11105 | SnapMirror data transfer using intercluster LIFs |
| UDP | 111 | Remote procedure call for NFS |
| UDP | 161-162 | Simple network management protocol |
| UDP | 635 | NFS mount |
| UDP | 2049 | NFS server daemon |
| UDP | 4045 | NFS lock daemon |
| UDP | 4046 | Network status monitor for NFS |
| UDP | 4049 | NFS rquotad protocol |

Outbound rules for Cloud Volumes ONTAP

The predefined security group for Cloud Volumes ONTAP opens all outbound traffic. If that is acceptable, follow the basic outbound rules. If you need more rigid rules, use the advanced outbound rules.

Basic outbound rules

The predefined security group for Cloud Volumes ONTAP includes the following outbound rules.

| Protocol | Port | Purpose |
|----------|------|----------------------|
| All ICMP | All | All outbound traffic |
| All TCP | All | All outbound traffic |
| All UDP | All | All outbound traffic |

Advanced outbound rules

If you need rigid rules for outbound traffic, you can use the following information to open only those ports that are required for outbound communication by Cloud Volumes ONTAP.



The source is the interface (IP address) on the Cloud Volumes ONTAP system.

| Service | Protoco | Port | Source | Destination | Purpose |
|---------|---------|------|--------|-------------|---------|
| | 1 | | | | |

Active Director

у

| | TCP | 464 | Data LIF (NFS, CIFS) | Active Directory forest | Kerberos V change & set password (SET_CHANGE) |
|----------------|--------------|-----------------|---|---------------------------------|--|
| Service | Protoco 1 | P64 t | Sater Lef (NFS, CIFS) | Destin Diron tory forest | Kuripase s key administration |
| | TCP | 749 | Data LIF (NFS, CIFS) | Active Directory forest | Kerberos V change & set password (RPCSEC_GSS) |
| DHCP | UDP | 68 | Node management LIF | DHCP | DHCP client for first-time setup |
| DHCPS | UDP | 67 | Node management LIF | DHCP | DHCP server |
| DNS | UDP | 53 | Node management LIF and data LIF (NFS, CIFS) | DNS | DNS |
| NDMP | TCP | 18600–1 8699 | Node management LIF | Destination servers | NDMP copy |
| SMTP | ТСР | 25 | Node management LIF | Mail server | SMTP alerts, can be used for AutoSupport |
| SNMP | ТСР | 161 | Node management LIF | Monitor server | Monitoring by SNMP traps |
| | UDP | 161 | Node management LIF | Monitor server | Monitoring by SNMP traps |
| | TCP | 162 | Node management LIF | Monitor server | Monitoring by SNMP traps |
| | UDP | 162 | Node management LIF | Monitor server | Monitoring by SNMP traps |
| SnapMi rror | ТСР | 11104 | Intercluster LIF | ONTAP intercluster LIFs | Management of intercluster communication sessions for SnapMirror |
| | TCP | 11105 | Intercluster LIF | ONTAP intercluster LIFs | SnapMirror data transfer |
| Syslog | UDP | 514 | Node management LIF | Syslog server | Syslog forward messages |

Copyright Information

Copyright © 2019–2020 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval systemwithout prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.