# **■** NetApp

# **View IPsec security associations**

ONTAP 9.12.1 REST API reference

NetApp February 13, 2024

# **Table of Contents**

V	iew IPsec security associations	. 1	ı
	Security IPsec security-associations endpoint overview	. 1	I
	Retrieve IPsec and IKE security associations	. 1	l
	Retrieve an IPsec or IKE security association	10	)

# **View IPsec security associations**

# Security IPsec security-associations endpoint overview

### Overview

- · Collection Get: GET security/ipsec/security-associations
- Instance Get: GET security/ipsec/security-associations/uuid

# Retrieve IPsec and IKE security associations

GET /security/ipsec/security-associations

Introduced In: 9.8

Retrieves the IPsec and IKE (Internet Key Exchange) security associations.

#### **Related ONTAP commands**

- security ipsec show-ipsecsa
- security ipsec show-ikesa

### **Parameters**

Name	Туре	In	Required	Description
uuid	string	query	False	Filter by uuid
cipher_suite	string	query	False	Filter by cipher_suite
node.uuid	string	query	False	Filter by node.uuid
node.name	string	query	False	Filter by node.name
scope	string	query	False	Filter by scope
remote_address	string	query	False	Filter by remote_address
lifetime	integer	query	False	Filter by lifetime
svm.uuid	string	query	False	Filter by svm.uuid
svm.name	string	query	False	Filter by svm.name

Name	Туре	In	Required	Description
policy_name	string	query	False	Filter by policy_name
type	string	query	False	Filter by type
ike.state	string	query	False	Filter by ike.state
ike.is_initiator	boolean	query	False	Filter by ike.is_initiator
ike.version	integer	query	False	Filter by ike.version
ike.authentication	string	query	False	Filter by ike.authentication
ike.initiator_security_ parameter_index	string	query	False	Filter by ike.initiator_security _parameter_index
ike.responder_securi ty_parameter_index	string	query	False	Filter by ike.responder_secur ity_parameter_index
local_address	string	query	False	Filter by local_address
ipsec.action	string	query	False	Filter by ipsec.action
ipsec.inbound.bytes	integer	query	False	Filter by ipsec.inbound.bytes
ipsec.inbound.securi ty_parameter_index	string	query	False	Filter by ipsec.inbound.securi ty_parameter_index
ipsec.inbound.packe ts	integer	query	False	Filter by ipsec.inbound.packe ts
ipsec.state	string	query	False	Filter by ipsec.state
ipsec.outbound.byte s	integer	query	False	Filter by ipsec.outbound.byte s

Name	Туре	In	Required	Description
ipsec.outbound.pack ets	integer	query	False	Filter by ipsec.outbound.pack ets
ipsec.outbound.secu rity_parameter_inde x	string	query	False	Filter by ipsec.outbound.secu rity_parameter_inde x
fields	array[string]	query	False	Specify the fields to return.
max_records	integer	query	False	Limit the number of records returned.
return_records	boolean	query	False	The default is true for GET calls. When set to false, only the number of records is returned.  • Default value: 1
return_timeout	integer	query	False	The number of seconds to allow the call to execute before returning. When iterating over a collection, the default is 15 seconds. ONTAP returns earlier if either max records or the end of the collection is reached.  • Default value: 1  • Max value: 120  • Min value: 0
order_by	array[string]	query	False	Order results by specified fields and optional [asc

# Response

Status: 200, Ok

Name	Туре	Description
_links	_links	
error	error	
num_records	integer	Number of records
records	array[records]	

```
" links": {
  "next": {
   "href": "/api/resourcelink"
 },
 "self": {
   "href": "/api/resourcelink"
 }
},
"error": {
 "arguments": {
   "code": "string",
   "message": "string"
  },
  "code": "4",
 "message": "entry doesn't exist",
 "target": "uuid"
},
"num records": 1,
"records": {
  "cipher suite": "suite aescbc",
 "ike": {
   "authentication": "none",
   "state": "none"
  },
  "ipsec": {
   "action": "bypass"
  },
  "node": {
   " links": {
     "self": {
       "href": "/api/resourcelink"
     }
    },
   "name": "node1",
   "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
  },
  "scope": "svm",
  "svm": {
   " links": {
     "self": {
       "href": "/api/resourcelink"
     }
```

```
"name": "svm1",
        "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
     },
        "type": "ipsec"
     }
}
```

### **Error**

```
Status: Default, Error
```

Name	Туре	Description
error	error	

### **Example error**

```
{
   "error": {
        "arguments": {
            "code": "string",
            "message": "string"
        },
        "code": "4",
        "message": "entry doesn't exist",
        "target": "uuid"
     }
}
```

### **Definitions**

# **See Definitions**

href

Name	Туре	Description
href	string	

\_links

Name	Туре	Description
next	href	
self	href	

# error\_arguments

Name	Туре	Description
code	string	Argument code
message	string	Message argument

### error

Name	Туре	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

# ike

Objects containing parameters specific to IKE (Internet Key Exchange) security association.

Name	Туре	Description
authentication	string	Authentication method for internet key exchange protocol.
initiator_security_parameter_inde x	string	Initiator's security parameter index for the IKE security association.

Name	Туре	Description
is_initiator	boolean	Indicates whether or not IKE has been initiated by this node.
responder_security_parameter_in dex	string	Responder's security parameter index for the IKE security association.
state	string	State of the IKE connection.
version	integer	Internet key exchange protocol version.

#### inbound

Status for inbound parameters for the IPsec security association.

Name	Туре	Description
bytes	integer	Number of inbound bytes for the IPsec security association.
packets	integer	Number of inbound packets for the IPsec security association.
security_parameter_index	string	Inbound security parameter index for the IPSec security association.

### outbound

Status for outbound parameters for the IPsec security association.

Name	Туре	Description
bytes	integer	Number of outbound bytes for the IPsec security association.
packets	integer	Number of outbound packets for the IPsec security association.
security_parameter_index	string	Outbound security parameter index for the IPSec security association.

### ipsec

Objects containing parameters specific to IPsec security association.

Name	Туре	Description
action	string	Action for the IPsec security association.
inbound	inbound	Status for inbound parameters for the IPsec security association.
outbound	outbound	Status for outbound parameters for the IPsec security association.
state	string	State of the IPsec security association.

# \_links

Name	Туре	Description
self	href	

# node

Node with the security association.

Name	Туре	Description
_links	_links	
name	string	
uuid	string	

### svm

Name	Туре	Description
_links	_links	
name	string	The name of the SVM.
uuid	string	The unique identifier of the SVM.

### records

Security association object for IPsec security association and IKE (Internet Key Exchange) security association.

Name	Туре	Description
cipher_suite	string	Cipher suite for the security association.

Name	Туре	Description
ike	ike	Objects containing parameters specific to IKE (Internet Key Exchange) security association.
ipsec	ipsec	Objects containing parameters specific to IPsec security association.
lifetime	integer	Lifetime for the security association in seconds.
local_address	string	Local address of the security association.
node	node	Node with the security association.
policy_name	string	Policy name for the security association.
remote_address	string	Remote address of the security association.
scope	string	Set to "svm" for interfaces owned by an SVM. Otherwise, set to "cluster".
svm	svm	
type	string	Type of security association, it can be IPsec or IKE (Internet Key Exchange).
uuid	string	Unique identifier of the security association.

# Retrieve an IPsec or IKE security association

GET /security/ipsec/security-associations/{uuid}

Introduced In: 9.8

Retrieves a specific IPsec or IKE (Internet Key Exchange) security association.

# **Related ONTAP commands**

- security ipsec show-ipsecsa
- security ipsec show-ikesa

# **Parameters**

Name	Туре	In	Required	Description
uuid	string	path	True	UUID of IPsec or IKE security association.
fields	array[string]	query	False	Specify the fields to return.

# Response

Status: 200, Ok

Name	Туре	Description
cipher_suite	string	Cipher suite for the security association.
ike	ike	Objects containing parameters specific to IKE (Internet Key Exchange) security association.
ipsec	ipsec	Objects containing parameters specific to IPsec security association.
lifetime	integer	Lifetime for the security association in seconds.
local_address	string	Local address of the security association.
node	node	Node with the security association.
policy_name	string	Policy name for the security association.
remote_address	string	Remote address of the security association.

Name	Туре	Description
scope	string	Set to "svm" for interfaces owned by an SVM. Otherwise, set to "cluster".
svm	svm	
type	string	Type of security association, it can be IPsec or IKE (Internet Key Exchange).
uuid	string	Unique identifier of the security association.

#### **Example response**

```
"cipher_suite": "suite_aescbc",
"ike": {
 "authentication": "none",
  "state": "none"
},
"ipsec": {
 "action": "bypass"
"node": {
  " links": {
    "self": {
     "href": "/api/resourcelink"
   }
  },
  "name": "node1",
 "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
},
"scope": "svm",
"svm": {
  " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  },
  "name": "svm1",
 "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
} ,
"type": "ipsec"
```

### **Error**

```
Status: Default
```

#### **ONTAP Error Response Codes**

Error Code	Description
66257118	IPsec SA with the specified UUID was not found.
66257119	IPsec SA with the specified UUID was not found.

Name	Туре	Description
error	error	

# Example error

```
{
   "error": {
        "arguments": {
            "code": "string",
            "message": "string"
        },
        "code": "4",
        "message": "entry doesn't exist",
        "target": "uuid"
      }
}
```

# **Definitions**

### See Definitions

ike

Objects containing parameters specific to IKE (Internet Key Exchange) security association.

Name	Туре	Description
authentication	string	Authentication method for internet key exchange protocol.
initiator_security_parameter_inde x	string	Initiator's security parameter index for the IKE security association.
is_initiator	boolean	Indicates whether or not IKE has been initiated by this node.
responder_security_parameter_in dex	string	Responder's security parameter index for the IKE security association.
state	string	State of the IKE connection.
version	integer	Internet key exchange protocol version.

# inbound

Status for inbound parameters for the IPsec security association.

Name	Туре	Description
bytes	integer	Number of inbound bytes for the IPsec security association.
packets	integer	Number of inbound packets for the IPsec security association.
security_parameter_index	string	Inbound security parameter index for the IPSec security association.

### outbound

Status for outbound parameters for the IPsec security association.

Name	Туре	Description
bytes	integer	Number of outbound bytes for the IPsec security association.
packets	integer	Number of outbound packets for the IPsec security association.
security_parameter_index	string	Outbound security parameter index for the IPSec security association.

# ipsec

Objects containing parameters specific to IPsec security association.

Name	Туре	Description
action	string	Action for the IPsec security association.
inbound	inbound	Status for inbound parameters for the IPsec security association.
outbound	outbound	Status for outbound parameters for the IPsec security association.
state	string	State of the IPsec security association.

# href

Name	Туре	Description
href	string	

# \_links

Name	Туре	Description
self	href	

### node

Node with the security association.

Name	Туре	Description
_links	_links	
name	string	

Name	Туре	Description
uuid	string	

#### svm

Name	Туре	Description
_links	_links	
name	string	The name of the SVM.
uuid	string	The unique identifier of the SVM.

# error\_arguments

Name	Туре	Description
code	string	Argument code
message	string	Message argument

#### error

Name	Туре	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

#### Copyright information

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

#### **Trademark information**

NETAPP, the NETAPP logo, and the marks listed at <a href="http://www.netapp.com/TM">http://www.netapp.com/TM</a> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.