

# Manage configuration backups

ONTAP 9.12.1 REST API reference

NetApp February 13, 2024

This PDF was generated from https://docs.netapp.com/us-en/ontap-restapi-9121/ontap/support\_configuration-backup\_backups\_endpoint\_overview.html on February 13, 2024. Always check docs.netapp.com for the latest.

# **Table of Contents**

| V | lanage configuration backups                           | . 1 |
|---|--------------------------------------------------------|-----|
|   | Support configuration-backup backups endpoint overview | . 1 |
|   | Retrieve configuration backup files                    | . 5 |
|   | Create a configuration backup                          | 10  |
|   | Delete a configuration backup                          | 17  |
|   | Retrieve configuration backup file details.            | 19  |

# Manage configuration backups

## Support configuration-backup backups endpoint overview

#### Overview

This API supports creating, deleting and retrieving configuration backup files. Configuration backups can be 'cluster' or 'node' type. A 'cluster' backup contains cluster-wide configuration in addition to the configuration of each node in the cluster. A 'node' backup contains only node-specific configuration such as configuration files on the root volume and the boot variables. For creating a cluster backup, a cluster-wide job is queued. For creating a node backup, a private job local to the node is queued. In addition to the backups created using this API, ONTAP creates configuration backups automatically based on job schedules. This API supports creating configuration backups on demand only. It supports deleting and retrieving configuration backups that are created automatically or on demand. For information on configuration backup settings for automatically created backups, see DOC /support/configuration-backup

#### **Examples**

Retrieving a list of configuration backup files

```
# The API:
/api/support/configuration-backup/backups
# The call:
curl -X GET "https://<mgmt-ip>/api/support/configuration-backup/backups"
-H "accept: application/hal+json"
# The response:
{
"records": [
    "node": {
      "uuid": "5cafe0f6-499f-11e9-b644-005056bbcf93",
      "name": "node1",
      " links": {
        "self": {
          "href": "/api/cluster/nodes/5cafe0f6-499f-11e9-b644-
005056bbcf93"
     }
    "name": "backup1.7z",
    " links": {
      "self": {
        "href": "/api/support/configuration-backup/backups/5cafe0f6-499f-
11e9-b644-005056bbcf93/backup1.7z"
 }
],
"num records": 1,
" links": {
 "self": {
    "href": "/api/support/configuration-backup/backups"
}
}
```

#### Retrieving details of the specified configuration backup file

```
# The API:
/api/support/configuration-backup/backups/{node.uuid}/{name}
# The call:
curl -X GET "https://<mgmt-ip>/api/support/configuration-
backup/backups/bc2f15d0-8b93-11e9-90e9-005056bb6a30/backup1.7z" -H
"accept: application/hal+json"
# The response:
"node": {
 "uuid": "bc2f15d0-8b93-11e9-90e9-005056bb6a30",
  "name": "node1",
  " links": {
    "self": {
      "href": "/api/cluster/nodes/bc2f15d0-8b93-11e9-90e9-005056bb6a30"
   }
  }
},
"name": "backup1.7z",
"type": "cluster",
"time": "2019-06-10T13:35:06-04:00",
"size": 6058408,
"backup nodes": [
    "name": "node1"
 },
    "name": "node2"
 }
],
"version": "9.7.0",
"auto": false,
"download link": "https://10.224.66.113/backups/backup1.7z",
" links": {
  "self": {
    "href": "/api/support/configuration-backup/backups/bc2f15d0-8b93-11e9-
90e9-005056bb6a30/backup1.7z"
 }
}
}
```

```
# The API:
/api/support/configuration-backup/backups
# The call:
curl -X POST "https://<mgmt-ip>/api/support/configuration-backup/backups"
-H "accept: application/hal+json" -d "@create backup.txt"
create backup.txt:
{
"node":
    "uuid": "ac13c636-4fc9-11e9-94c2-005056bb2516",
    "name": "node1"
 },
"name": "backup3.7z"
}
# The response header:
HTTP/1.1 202 Accepted
Date: Tue, 26 Mar 2019 14:26:24 GMT
Server: libzapid-httpd
X-Content-Type-Options: nosniff
Cache-Control: no-cache, no-store, must-revalidate
Location: /api/support/configuration-backup/backups/ac13c636-4fc9-11e9-
94c2-005056bb2516/backup3.7z
Content-Length: 189
Content-Type: application/hal+json
"job": {
  "uuid": "22acfb68-4fd3-11e9-94c2-005056bb2516",
  " links": {
    "self": {
      "href": "/api/cluster/jobs/22acfb68-4fd3-11e9-94c2-005056bb2516"
  }
}
}
```

#### Deleting a configuration backup file

# The API:

/api/support/configuration-backup/backups/{node.uuid}/{name}

# The call:

curl -X DELETE "https://<mgmt-ip>/api/support/configuration-

backup/backups/5cafe0f6-499f-11e9-b644-005056bbcf93/backup1.7z" -H

"content-type: application/json"

# The response header:

HTTP/1.1 200 OK

Date: Tue, 26 Mar 2019 14:32:23 GMT

Server: libzapid-httpd

X-Content-Type-Options: nosniff

Cache-Control: no-cache, no-store, must-revalidate

Content-Length: 3

Content-Type: application/hal+json

## Retrieve configuration backup files

GET /support/configuration-backup/backups

Introduced In: 9.7

Retrieves a list of configuration backup files.

#### **Related ONTAP commands**

system configuration backup show

#### **Parameters**

| Name      | Туре    | In    | Required | Description         |
|-----------|---------|-------|----------|---------------------|
| auto      | boolean | query | False    | Filter by auto      |
| type      | string  | query | False    | Filter by type      |
| size      | integer | query | False    | Filter by size      |
| node.uuid | string  | query | False    | Filter by node.uuid |
| node.name | string  | query | False    | Filter by node.name |
| name      | string  | query | False    | Filter by name      |

| Name                                                       | Туре          | In            | Required | Description                                                                                                                                                                                                                                                                  |
|------------------------------------------------------------|---------------|---------------|----------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| backup_nodes.name                                          | string        | query         | False    | Filter by backup_nodes.nam e                                                                                                                                                                                                                                                 |
| version                                                    | string        | query         | False    | Filter by version                                                                                                                                                                                                                                                            |
| download_link                                              | string        | query         | False    | Filter by download_link                                                                                                                                                                                                                                                      |
| time                                                       | string        | query         | False    | Filter by time                                                                                                                                                                                                                                                               |
| max_records                                                | integer       | query         | False    | Limit the number of records returned.                                                                                                                                                                                                                                        |
| return_records                                             | boolean       | query         | False    | The default is true for GET calls. When set to false, only the number of records is returned.  • Default value: 1                                                                                                                                                            |
| return_timeout                                             | integer       | query         | False    | The number of seconds to allow the call to execute before returning. When iterating over a collection, the default is 15 seconds. ONTAP returns earlier if either max records or the end of the collection is reached.  • Default value: 1  • Max value: 120  • Min value: 0 |
| order_by                                                   | array[string] | query         | False    | Order results by specified fields and optional [asc                                                                                                                                                                                                                          |
| desc] direction. Default direction is 'asc' for ascending. | fields        | array[string] | query    | False                                                                                                                                                                                                                                                                        |

### Response

```
Status: 200, Ok
```

| Name        | Туре                             | Description       |
|-------------|----------------------------------|-------------------|
| _links      | _links                           |                   |
| num_records | integer                          | Number of records |
| records     | array[configuration_backup_file] |                   |

#### **Example response**

```
" links": {
  "next": {
   "href": "/api/resourcelink"
 },
 "self": {
  "href": "/api/resourcelink"
 }
},
"num records": 1,
"records": {
  "backup_nodes": {
  },
  "download link": "https://10.224.65.198/backups/backup file.7z",
  "name": "backup file.7z",
  "node": {
   " links": {
     "self": {
       "href": "/api/resourcelink"
     }
   "name": "node1",
   "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
  },
  "size": 4787563,
  "time": "2019-02-04T13:33:48-05:00",
 "type": "node",
  "version": "9.7.0"
}
```

## **Error**

```
Status: Default, Error
```

| Name  | Туре  | Description |
|-------|-------|-------------|
| error | error |             |

## **Example error**

```
{
   "error": {
        "arguments": {
            "code": "string",
            "message": "string"
        },
        "code": "4",
        "message": "entry doesn't exist",
        "target": "uuid"
      }
}
```

## **Definitions**

#### **See Definitions**

href

| Name | Туре   | Description |
|------|--------|-------------|
| href | string |             |

\_links

| Name | Туре | Description |
|------|------|-------------|
| next | href |             |
| self | href |             |

backup\_node

The node name in the backup.

| Name | Туре   | Description |
|------|--------|-------------|
| name | string |             |

\_links

| Name | Туре | Description |
|------|------|-------------|
| self | href |             |

node

The node that owns the configuration backup.

| Name   | Туре   | Description |
|--------|--------|-------------|
| _links | _links |             |
| name   | string |             |
| uuid   | string |             |

configuration\_backup\_file

The configuration backup file.

| Name         | Туре               | Description                                        |
|--------------|--------------------|----------------------------------------------------|
| auto         | boolean            | Indicates if the backup was created automatically. |
| backup_nodes | array[backup_node] | The list of nodes included in the backup.          |

| Name          | Туре    | Description                                  |
|---------------|---------|----------------------------------------------|
| download_link | string  | The link to download the backup file.        |
| name          | string  | The backup name.                             |
| node          | node    | The node that owns the configuration backup. |
| size          | integer | The size of the backup in bytes.             |
| time          | string  | The backup creation time.                    |
| type          | string  | The backup type.                             |
| version       | string  | The software version.                        |

#### error\_arguments

| Name    | Туре   | Description      |
|---------|--------|------------------|
| code    | string | Argument code    |
| message | string | Message argument |

#### error

| Name      | Туре                   | Description                                 |
|-----------|------------------------|---------------------------------------------|
| arguments | array[error_arguments] | Message arguments                           |
| code      | string                 | Error code                                  |
| message   | string                 | Error message                               |
| target    | string                 | The target parameter that caused the error. |

# Create a configuration backup

POST /support/configuration-backup/backups

Introduced In: 9.7

Creates a configuration backup. The required backup file name must end with .7z extension.

## **Required properties**

- node.uuid or node.name The node UUID or node name on which the configuration backup will be created.
- name The backup file name

## **Related ONTAP commands**

• system configuration backup create

## **Parameters**

| Name           | Туре    | In    | Required | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|----------------|---------|-------|----------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| return_timeout | integer | query | False    | The number of seconds to allow the call to execute before returning. When doing a POST, PATCH, or DELETE operation on a single record, the default is 0 seconds. This means that if an asynchronous operation is started, the server immediately returns HTTP code 202 (Accepted) along with a link to the job. If a non-zero value is specified for POST, PATCH, or DELETE operations, ONTAP waits that length of time to see if the job completes so it can return something other than 202.  • Default value: 1 • Max value: 120 • Min value: 0 |

| Name           | Туре    | In    | Required | Description                                                                       |
|----------------|---------|-------|----------|-----------------------------------------------------------------------------------|
| return_records | boolean | query | False    | The default is false. If set to true, the records are returned.  • Default value: |

## Request Body

| Name          | Туре               | Description                                        |
|---------------|--------------------|----------------------------------------------------|
| auto          | boolean            | Indicates if the backup was created automatically. |
| backup_nodes  | array[backup_node] | The list of nodes included in the backup.          |
| download_link | string             | The link to download the backup file.              |
| name          | string             | The backup name.                                   |
| node          | node               | The node that owns the configuration backup.       |
| size          | integer            | The size of the backup in bytes.                   |
| time          | string             | The backup creation time.                          |
| type          | string             | The backup type.                                   |
| version       | string             | The software version.                              |

#### **Example request**

```
"backup_nodes": {
 } ,
 "download link": "https://10.224.65.198/backups/backup file.7z",
 "name": "backup file.7z",
 "node": {
   " links": {
     "self": {
       "href": "/api/resourcelink"
     }
   },
   "name": "node1",
   "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
 },
 "size": 4787563,
 "time": "2019-02-04T13:33:48-05:00",
 "type": "node",
 "version": "9.7.0"
}
```

## Response

```
Status: 202, Accepted
```

| Name | Туре     | Description |
|------|----------|-------------|
| job  | job_link |             |

## **Example response**

#### Headers

| Name     | Description                               | Туре   |
|----------|-------------------------------------------|--------|
| Location | Useful for tracking the resource location | string |

## **Error**

```
Status: Default
```

## **ONTAP Error Response Codes**

| Error Code | Description                                  |
|------------|----------------------------------------------|
| 5963818    | Failed to queue private job.                 |
| 5963819    | Failed to queue cluster job.                 |
| 5963871    | Requested backup name is missing .7z suffix. |

| Name  | Туре  | Description |
|-------|-------|-------------|
| error | error |             |

#### Example error

```
{
   "error": {
        "arguments": {
            "code": "string",
            "message": "string"
        },
        "code": "4",
        "message": "entry doesn't exist",
        "target": "uuid"
      }
}
```

## **Definitions**

#### **See Definitions**

backup\_node

The node name in the backup.

| Name | Туре   | Description |
|------|--------|-------------|
| name | string |             |

#### href

| Name | Туре   | Description |
|------|--------|-------------|
| href | string |             |

## \_links

| Name | Туре | Description |
|------|------|-------------|
| self | href |             |

#### node

The node that owns the configuration backup.

| Name   | Туре   | Description |
|--------|--------|-------------|
| _links | _links |             |
| name   | string |             |
| uuid   | string |             |

configuration\_backup\_file

The configuration backup file.

| Name          | Туре               | Description                                        |
|---------------|--------------------|----------------------------------------------------|
| auto          | boolean            | Indicates if the backup was created automatically. |
| backup_nodes  | array[backup_node] | The list of nodes included in the backup.          |
| download_link | string             | The link to download the backup file.              |
| name          | string             | The backup name.                                   |
| node          | node               | The node that owns the configuration backup.       |

| Name    | Туре    | Description                      |
|---------|---------|----------------------------------|
| size    | integer | The size of the backup in bytes. |
| time    | string  | The backup creation time.        |
| type    | string  | The backup type.                 |
| version | string  | The software version.            |

## job\_link

| Name   | Туре   | Description                                                                               |
|--------|--------|-------------------------------------------------------------------------------------------|
| _links | _links |                                                                                           |
| uuid   | string | The UUID of the asynchronous job that is triggered by a POST, PATCH, or DELETE operation. |

## error\_arguments

| Name    | Туре   | Description      |
|---------|--------|------------------|
| code    | string | Argument code    |
| message | string | Message argument |

#### error

| Name      | Туре                   | Description                                 |
|-----------|------------------------|---------------------------------------------|
| arguments | array[error_arguments] | Message arguments                           |
| code      | string                 | Error code                                  |
| message   | string                 | Error message                               |
| target    | string                 | The target parameter that caused the error. |

# Delete a configuration backup

DELETE /support/configuration-backup/backups/{node.uuid}/{name}

Introduced In: 9.7

Deletes a configuration backup.

## **Related ONTAP commands**

• system configuration backup delete

#### **Parameters**

| Name      | Туре   | In   | Required | Description                                          |
|-----------|--------|------|----------|------------------------------------------------------|
| node.uuid | string | path | True     | UUID of the node that owns the configuration backup. |
| name      | string | path | True     | Name of the configuration backup to be deleted.      |

## Response

Status: 200, Ok

## **Error**

Status: Default

## ONTAP Error Response Codes

| Error Code | Description                   |
|------------|-------------------------------|
| 5963826    | Failed to delete backup file. |

| Name  | Туре  | Description |
|-------|-------|-------------|
| error | error |             |

#### **Example error**

```
{
   "error": {
        "arguments": {
            "code": "string",
            "message": "string"
        },
        "code": "4",
        "message": "entry doesn't exist",
        "target": "uuid"
      }
}
```

#### **Definitions**

#### **See Definitions**

error arguments

| Name    | Туре   | Description      |
|---------|--------|------------------|
| code    | string | Argument code    |
| message | string | Message argument |

error

| Name      | Туре                   | Description                                 |
|-----------|------------------------|---------------------------------------------|
| arguments | array[error_arguments] | Message arguments                           |
| code      | string                 | Error code                                  |
| message   | string                 | Error message                               |
| target    | string                 | The target parameter that caused the error. |

# Retrieve configuration backup file details

GET /support/configuration-backup/backups/{node.uuid}/{name}

Introduced In: 9.7

Retrieves details of the specified configuration backup file.

## **Related ONTAP commands**

• system configuration backup show

## **Parameters**

| Name      | Туре          | In    | Required | Description                                          |
|-----------|---------------|-------|----------|------------------------------------------------------|
| node.uuid | string        | path  | True     | UUID of the node that owns the configuration backup. |
| name      | string        | path  | True     | Name of the configuration backup.                    |
| fields    | array[string] | query | False    | Specify the fields to return.                        |

## Response

Status: 200, Ok

| Name          | Туре               | Description                                        |
|---------------|--------------------|----------------------------------------------------|
| auto          | boolean            | Indicates if the backup was created automatically. |
| backup_nodes  | array[backup_node] | The list of nodes included in the backup.          |
| download_link | string             | The link to download the backup file.              |
| name          | string             | The backup name.                                   |
| node          | node               | The node that owns the configuration backup.       |
| size          | integer            | The size of the backup in bytes.                   |
| time          | string             | The backup creation time.                          |

| Name    | Туре   | Description           |
|---------|--------|-----------------------|
| type    | string | The backup type.      |
| version | string | The software version. |

#### **Example response**

```
"backup nodes": {
 "download_link": "https://10.224.65.198/backups/backup_file.7z",
 "name": "backup_file.7z",
 "node": {
   " links": {
     "self": {
       "href": "/api/resourcelink"
     }
   },
    "name": "node1",
   "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
 "size": 4787563,
 "time": "2019-02-04T13:33:48-05:00",
 "type": "node",
 "version": "9.7.0"
}
```

#### **Error**

```
Status: Default
```

#### **ONTAP Error Response Codes**

| Error Code | Description                               |
|------------|-------------------------------------------|
| 5963777    | Configuration backup file does not exist. |

| Name  | Туре  | Description |
|-------|-------|-------------|
| error | error |             |

#### Example error

```
{
  "error": {
    "arguments": {
        "code": "string",
        "message": "string"
    },
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
    }
}
```

## **Definitions**

## See Definitions

backup\_node

The node name in the backup.

| Name | Туре   | Description |
|------|--------|-------------|
| name | string |             |

#### href

| Name | Туре   | Description |
|------|--------|-------------|
| href | string |             |

## \_links

| Name | Туре | Description |
|------|------|-------------|
| self | href |             |

## node

The node that owns the configuration backup.

| Name   | Туре   | Description |
|--------|--------|-------------|
| _links | _links |             |
| name   | string |             |
| uuid   | string |             |

#### error\_arguments

| Na | ame    | Туре   | Description      |
|----|--------|--------|------------------|
| CO | ode    | string | Argument code    |
| m  | essage | string | Message argument |

#### error

| Name      | Туре                   | Description       |
|-----------|------------------------|-------------------|
| arguments | array[error_arguments] | Message arguments |
| code      | string                 | Error code        |
| message   | string                 | Error message     |

| Name   | Туре   | Description                                 |
|--------|--------|---------------------------------------------|
| target | string | The target parameter that caused the error. |

#### Copyright information

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

#### **Trademark information**

NETAPP, the NETAPP logo, and the marks listed at <a href="http://www.netapp.com/TM">http://www.netapp.com/TM</a> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.