■ NetApp

View CIFS active file sessions

ONTAP 9.12.1 REST API reference

NetApp February 13, 2024

Table of Contents

View CIFS active file sessions		 	 	 	 	1
Protocols CIFS session files endpoint over	view	 	 	 	 	1
Retrieve CIFS open files		 	 	 	 	2
Close open files identified by SVM		 	 	 	 	. 11
Retrieve a CIFS open file		 	 	 	 	. 13

View CIFS active file sessions

Protocols CIFS session files endpoint overview

Overview

ONTAP ${\tt cifs}$ sessions file show functionality is used to provide a list of currently opened files.

```
<mark># Information on the open files * Lists all files opened in current session.
</mark> Example <mark># Retrieving established open file information To retrieve
the list of open files, use the following API. Note that
<em>return records=true</em>. "' <code>` # The API: GET
/protocols/cifs/session/files # The call: curl -X GET "https://<cluster-mgmt-
ip>/api/protocols/cifs/session/files?return_timeout=15&return_records=true"
-H "accept: application/json" # The response: { "records": [ { "node": { "uuid":
"9ea96c65-4411-11ec-b358-005056bbdd2c", "name": "node1" }, "svm": { "uuid": "62234287-4412-11ec-b358-005056bbdd2c", "name": "svm1" }, "file": { "identifier":
24, "type": "regular" }, "connection": { "identifier": 127465, "count": 1 },
"session_id": 1827054073828868097, "open_mode": "w", "volume": { "name":
"vol1", "uuid": "7a5ef257-52de-11e8-95f4-005056952000" }, "share": { "name":
"root", "mode": "rwd" }, "path": "a\\b\\c\\f1", "continuously_available": "no",
"reconnected": "No", "range_lock_count": 0 }, { "node": { "uuid": "9ea96c65-4411-
11ec-b358-005056bbdd2c", "name": "node2" }, "svm": { "uuid": "62234287-4412-11ec-b358-005056bbdd2c", "name": "svm2" }, "file": { "identifier": 14, "type":
"regular" }, "connection": { "identifier": 127465, "count": 1 }, "session id":
1827054073828868097, "open_mode": "r", "volume": { "name": "vol2", "uuid": "7a5ef257-52de-11e8-95f4-005056952000" }, "share": { "name": "root", "mode":
"rwd" }, "path": "a\\b\\c\\f2", "continuously_available": "no", "reconnected": "No",
"range_lock_count": 0 } ], "num_records": 2 } </code>` "' </mark># Retrieving
specific open file Information " <code>` # The API: GET
/protocols/cifs/session/files/{node.uuid}/{svm.uuid}/{file.identifier}/{connection.ide
ntifier}/{session id} # The call: curl -X GET "https://<cluster-mgmt-
ip>/api/protocols/cifs/session/files/8d7ef257-52de-11e8-95f4-
005056952ecd/b009a9e7-4081-b576-7575-
ada21efcaf16/14/82792/4466726405421400095" # The response: { "node": { "uuid":
"9ea96c65-4411-11ec-b358-005056bbdd2c", "name": "node1" }, "svm": { "uuid":
"62234287-4412-11ec-b358-005056bbdd2c", "name": "svm1" }, "file": { "identifier":
24, "type": "regular" }, "connection": { "identifier": 127465, "count": 1 },
"session_id": 1827054073828868097, "open_mode": "r", "volume": { "name":
"vol1", "uuid": "7a5ef257-52de-11e8-95f4-005056952000" }, "share": { "name":
"root", "mode": "rwd" }, "path": "a\\b\\c\\f1", "continuously_available": "no",
"reconnected": "No", "range_lock_count": 0 } </code>` "' <mark>#</mark> Closing
a specific file based on <code>file.identifier</code>.
<code>connection.identifier</code> and <code>session id</code> The file being
closed is identified by the UUID of its SVM, the corresponding file.identifier.
connection.identifier and session id. " <code>` # The API: DELETE
/protocols/cifs/session/files/{node.uuid}/{svm.uuid}/{file.identifier}/{connection.ide
ntifier}/{session id} # The call: curl -X DELETE "https://<mgmt-
ip>/api/protocols/cifs/session/files/8d7ef257-52de-11e8-95f4-
005056952ecd/b009a9e7-4081-b576-7575-
ada21efcaf16/14/82792/4466726405421400095" -H "accept: application/json"
</code>` "'</mgmt-ip></cluster-mgmt-ip></cluster-mgmt-ip>
```

Retrieve CIFS open files

GET /protocols/cifs/session/files

Introduced In: 9.11

Parameters

Name	Туре	In	Required	Description
volume.uuid	string	query	False	Filter by volume.uuid
volume.name	string	query	False	Filter by volume.name
session.identifier	integer	query	False	Filter by session.identifier
path	string	query	False	Filter by path
range_locks_count	integer	query	False	Filter by range_locks_count
continuously_availab le	string	query	False	Filter by continuously_availa ble
share.name	string	query	False	Filter by share.name
share.mode	string	query	False	Filter by share.mode
open_mode	string	query	False	Filter by open_mode
type	string	query	False	Filter by type
connection.count	integer	query	False	Filter by connection.count
connection.identifier	integer	query	False	Filter by connection.identifier
identifier	integer	query	False	Filter by identifier
svm.uuid	string	query	False	Filter by svm.uuid
svm.name	string	query	False	Filter by svm.name
node.uuid	string	query	False	Filter by node.uuid
node.name	string	query	False	Filter by node.name

Name	Туре	In	Required	Description
fields	array[string]	query	False	Specify the fields to return.
max_records	integer	query	False	Limit the number of records returned.
return_records	boolean	query	False	The default is true for GET calls. When set to false, only the number of records is returned. • Default value: 1
return_timeout	integer	query	False	The number of seconds to allow the call to execute before returning. When iterating over a collection, the default is 15 seconds. ONTAP returns earlier if either max records or the end of the collection is reached. • Default value: 1 • Max value: 120 • Min value: 0
order_by	array[string]	query	False	Order results by specified fields and optional [asc

Response

Status: 200, Ok

Name	Туре	Description
_links	collection_links	
num_records	integer	Number of records
records	array[cifs_open_file]	

```
" links": {
  "next": {
   "href": "/api/resourcelink"
 },
 "self": {
   "href": "/api/resourcelink"
 }
},
"num records": 1,
"records": {
  " links": {
   "self": {
     "href": "/api/resourcelink"
  },
  "connection": {
  "count": 3,
   "identifier": 356756
  "continuously available": "no",
  "identifier": 17,
  "node": {
   " links": {
     "self": {
       "href": "/api/resourcelink"
     }
    },
    "name": "node1",
    "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
  } ,
  "open mode": "r",
  "path": "sub1\\sub2\\f4",
  "range locks count": 4,
  "session": {
   "identifier": 8966666858094657537
  },
  "share": {
   "mode": "r",
   "name": "share1"
  },
  "svm": {
   " links": {
      "self": {
```

```
"href": "/api/resourcelink"
     }
    },
    "name": "svm1",
    "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
  },
  "type": "regular",
  "volume": {
    " links": {
     "self": {
       "href": "/api/resourcelink"
     }
    },
    "name": "volume1",
    "uuid": "028baa66-41bd-11e9-81d5-00a0986138f7"
}
```

Error

```
Status: Default, Error
```

Name	Туре	Description
error	error	

Example error

```
{
   "error": {
        "arguments": {
            "code": "string",
            "message": "string"
        },
        "code": "4",
        "message": "entry doesn't exist",
        "target": "uuid"
     }
}
```

Definitions

See Definitions

href	
------	--

Name	Туре	Description
href	string	

collection_links

Name	Туре	Description
next	href	
self	href	

self_link

Name	Туре	Description
self	href	

connection

Name	Туре	Description
count	integer	The number of CIFS connections associated with the CIFS session.
identifier	integer	The connection that is used to open the file.

_links

Name	Туре	Description
self	href	

node

Name	Туре	Description
_links	_links	
name	string	
uuid	string	

session

Name	Туре	Description
identifier	integer	Session under which file is opened.

share

Name	Туре	Description
mode	string	The share mode used to open the file. The share mode can be a combination of: • r: read mode • w: write mode • d: delete
name	string	CIFS share name where the file resides.

svm

Name	Туре	Description
_links	_links	
name	string	The name of the SVM.
uuid	string	The unique identifier of the SVM.

volume

Name	Туре	Description
_links	_links	
name	string	The name of the volume.
uuid	string	Unique identifier for the volume. This corresponds to the instance- uuid that is exposed in the CLI and ONTAPI. It does not change due to a volume move.
		 example: 028baa66-41bd- 11e9-81d5-00a0986138f7
		• Introduced in: 9.6

cifs_open_file

Manage opened files over CIFS.

Name	Туре	Description
_links	self_link	
connection	connection	
continuously_available	string	The type of continuous availability protection provided to the file. Opened files are continuously available if there are opened through a SMB3 client through a share with "continuously_available" set to yes. These open files are capable of non-disruptively recovering from take over and giveback as well as general aggregate relocation. • no: the open file is not continuously available. • yes: the open file is continuously available.
identifier	integer	The unique identifier for the opened file.
node	node	
open_mode	string	Open mode corresponding to the opened file • r: Opened for read • w: Opened for write • d: Opened for Delete
path	string	Path from CIFS share.
range_locks_count	integer	The number of range locks granted on the file.
session	session	
share	share	
svm	svm	

Name	Туре	Description
type	string	The type of opened file. The file can be a regular file, directory, a symbolic link to an existing file/directory, or an alternate data stream.
volume	volume	

error_arguments

Name	Туре	Description
code	string	Argument code
message	string	Message argument

error

Name	Туре	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Close open files identified by SVM

DELETE

/protocols/cifs/session/files/{node.uuid}/{svm.uuid}/{identifier}/{connection.ide
ntifier}/{session.identifier}

Introduced In: 9.11

Closes open files identified by svm.uuid, file.identifier, connection.identifier and session id.

Learn more

DOC /protocols/cifs/session/files

Parameters

Name	Туре	In	Required	Description
node.uuid	string	path	True	Node UUID.
identifier	integer	path	True	File ID • format: int64
connection.identifier	integer	path	True	Connection ID
session.identifier	integer	path	True	Session ID • format: int64
svm.uuid	string	path	True	UUID of the SVM to which this object belongs. • Introduced in: 9.13
fields	array[string]	query	False	Specify the fields to return.

Response

Status: 200, Ok

Error

Status: Default, Error

Name	Туре	Description
error	error	

Example error

```
{
   "error": {
        "arguments": {
            "code": "string",
            "message": "string"
        },
        "code": "4",
        "message": "entry doesn't exist",
        "target": "uuid"
      }
}
```

Definitions

See Definitions

error arguments

Name	Туре	Description
code	string	Argument code
message	string	Message argument

error

Name	Туре	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Retrieve a CIFS open file

GET

/protocols/cifs/session/files/{node.uuid}/{svm.uuid}/{identifier}/{connection.ide
ntifier}/{session.identifier}

Introduced In: 9.11

Retrieves specific CIFS Open File

Parameters

Name	Туре	In	Required	Description
node.uuid	string	path	True	Node UUID.
identifier	integer	path	True	File ID • format: int64
connection.identifier	integer	path	True	Connection ID
session.identifier	integer	path	True	Session ID • format: int64
svm.uuid	string	path	True	UUID of the SVM to which this object belongs. • Introduced in: 9.13
fields	array[string]	query	False	Specify the fields to return.

Response

Status: 200, Ok

Name	Туре	Description
_links	self_link	
connection	connection	

Name	Туре	Description
continuously_available	string	The type of continuous availability protection provided to the file. Opened files are continuously available if there are opened through a SMB3 client through a share with "continuously_available" set to yes. These open files are capable of non-disruptively recovering from take over and giveback as well as general aggregate relocation. • no: the open file is not continuously available. • yes: the open file is continuously available.
identifier	integer	The unique identifier for the opened file.
node	node	
open_mode	string	Open mode corresponding to the opened file • r: Opened for read • w: Opened for write • d: Opened for Delete
path	string	Path from CIFS share.
range_locks_count	integer	The number of range locks granted on the file.
session	session	
share	share	
svm	svm	
type	string	The type of opened file. The file can be a regular file, directory, a symbolic link to an existing file/directory, or an alternate data stream.
volume	volume	

```
" links": {
 "self": {
   "href": "/api/resourcelink"
 }
} ,
"connection": {
 "count": 3,
 "identifier": 356756
},
"continuously available": "no",
"identifier": 17,
"node": {
  " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  },
  "name": "node1",
 "uuid": "1cd8a442-86d1-11e0-ae1c-123478563412"
},
"open mode": "r",
"path": "sub1\\sub2\\f4",
"range locks count": 4,
"session": {
 "identifier": 8966666858094657537
},
"share": {
 "mode": "r",
 "name": "share1"
},
"svm": {
 " links": {
   "self": {
     "href": "/api/resourcelink"
   }
  "name": "svm1",
  "uuid": "02c9e252-41be-11e9-81d5-00a0986138f7"
},
"type": "regular",
"volume": {
 " links": {
    "self": {
```

Error

```
Status: Default, Error
```

Name	Туре	Description
error	error	

Example error

```
{
  "error": {
    "arguments": {
        "code": "string",
        "message": "string"
    },
    "code": "4",
    "message": "entry doesn't exist",
    "target": "uuid"
    }
}
```

Definitions

See Definitions

			•
n	r	Δ	т
		v	

Name	Туре	Description
href	string	

self_link

Name	Туре	Description
self	href	

connection

Name	Туре	Description
count	integer	The number of CIFS connections associated with the CIFS session.
identifier	integer	The connection that is used to open the file.

_links

Name	Туре	Description
self	href	

node

Name	Туре	Description
_links	_links	
name	string	
uuid	string	

session

Name	Туре	Description
identifier	integer	Session under which file is opened.

share

Name	Туре	Description
mode	string	The share mode used to open the file. The share mode can be a combination of: • r: read mode • w: write mode • d: delete
name	string	CIFS share name where the file resides.

svm

Name	Туре	Description
_links	_links	
name	string	The name of the SVM.
uuid	string	The unique identifier of the SVM.

volume

Name	Туре	Description
_links	_links	
name	string	The name of the volume.
uuid	string	Unique identifier for the volume. This corresponds to the instance- uid that is exposed in the CLI and ONTAPI. It does not change due to a volume move. • example: 028baa66-41bd- 11e9-81d5-00a0986138f7 • Introduced in: 9.6

error_arguments

Name	Туре	Description
code	string	Argument code
message	string	Message argument

error

Name	Туре	Description
arguments	array[error_arguments]	Message arguments
code	string	Error code
message	string	Error message
target	string	The target parameter that caused the error.

Copyright information

Copyright © 2024 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.