NetSim Multi-Parameter Sweeper Python Script

Software: NetSim v13.2 (64 bit), DOT NET CORE SDK 3.1, Python 3.7.4

Project Download Link:

https://github.com/NetSim-TETCOS/Multi-Parameter_Sweeper_v13.2/archive/refs/heads/main.zip

Introduction

When users want to sweep one or more parameters, they change their values between simulation runs, and compare and analyse the performance metrics from each run. NetSim multi-parameter

sweeper enables users to automate the sweep process.

Consider an example, where a user wishes to create and simulate a network scenario for all possible

values of one or more parameters in combination and analyse a set of performance metrics across

the simulation runs. This is extremely time consuming to do manually using the NetSim GUI.

The multi-parameter sweep program enables users to automate the sweep process across multiple

input parameters, simulate each run, save each result, and compare specific output metrics via a

spreadsheet software like MS Excel.

The sweep program runs NetSim via its CLI interface.

File Organization

The project directory consists of several binaries which are responsible for different tasks during a

multi-parameter sweep:




Figure 1: project directory consists of several binaries

1. **input.xml**: This file contains the base NetSim network configuration that is to be simulated. This file is created by copy pasting the Configuration.netsim file that can be obtained by saving a network configuration in NetSim and renaming it to input.xml.




Figure 2: NetSim input Configuration.netsim file

- The values of parameters which are to be varied during each simulation run needs to be specified as {0}, {1}, {2}, etc. respectively.
- For Example, if the X and Y coordinates of a device is to be varied the values can be modified in the input.xml file as shown below:

```
Project Debug XML Test Analyze Tools Extensions Window
   | 🏗 - 📤 🖺 🚜 | り - 0
                                            ▶ Attach... - | 👼 | 🚳 _
      <?xml version="1.0" encoding="UTF-8" standalone="no"?>
    □<TETCOS_NETSIM xmlns:ns0="http://www.w3.org/2001/XMLSchema-instance" ns0:noNamespaceSchem
    <GUI_INFORMATION>...
        <NETWORK CONFIGURATION>
          <DEVICE CONFIGURATION DEVICE COUNT="4">
            CDEVICE DEFAULT_DEVICE_NAME="gnB" DEVICE_ID="1" DEVICE_IMAGE=

KDEVICE_DEFAULT_DEVICE_NAME="EPC" DEVICE_ID="2" DEVICE_IMAGE=
             <DEVICE DEFAULT DEVICE NAME="UE" DEVICE ID="4" DEVICE IMAGE="UserEquipment.png" DEVI</pre>
              <POS_3D X_OR_LON="{0}" Y_OR_LAT="{1}" Z="0">
<MOBILITY MODEL="NO_MOBILITY"/>
169
               <INTERFACE ID="1" INTERFACE_TYPE="LTE_NR">
                <LAYER TYPE="NETWORK_LAYER">
                  <NETWORK_PROTOCOL NAME="IPV4" SETPROPERTY="TRUE">
                     <PROTOCOL_PROPERTY DEFAULT_GATEWAY="11.2.1.1" IP_ADDRESS="11.2.1.2" SUBNET_N</pre>
               ← → TVDE-"DATALTMY LAVED"
```

Figure 3: Modify X and Y coordinates in input input.xml file

2. **Script.txt:** This file should be updated with the parameter from the output metrics of NetSim that is to be logged at the end of each simulation run for the purpose of analysis.

At the end of every simulation, NetSim generates a Metrics.xml file which contain the performance metrics written in a specific format based on which it is loaded in the results dashboard.

Each Metric is part of a results table which can be accessed using a menu in the results dashboard. A NetSim Metrics.xml file is shown below:

```
▶ File Edit Yiew Project Debug XML Test A<u>n</u>alyze Tools Extensions <u>W</u>indow <u>H</u>elp Search (Ctrl+Q)
 O - O | M - 🚈 🖺 🚜 | り - 🤇
                                                                    ▶ Attach... - 🎜 🙆 _
                                                                                                                                                | Live Share
             <MENU Name="Application_Metrics">
              <TABLE name="Application_Metrics">
               <TH name="Application Id" isShow="true"/>
                <TH name="Throughput Plot" isShow="true",
<TH name="Application Name" isShow="true"</pre>
                <TH name="Destination Id" isShow="false"/>
<TH name="Packet generated" isShow="true"/</pre>
                <TH name="Payload generated (bytes)" isShow="false"/>
                 <TH name="Payload received (bytes)" isShow="false"/>
                <TH name="Throughput (Mbps)" isShow="true"/>
<TH name="Delay(microsec)" isShow="true"/>
                 <TH name="Jitter(microsec)" isShow="true"/>
                  <TC Value="1"/>
                 <TC Value="App1_CBR"/>
                 <TC Value="3"/
<TC Value="4"/
                  <TC Value="17946"/>
<TC Value="36500000"/>
                  <TC Value="26201160"/>
                 <TC Value="4192.185600"/>
<TC Value="7188.952970"/>
                                                                                                                                           Ln: 458 Ch: 1 SPC
```

Figure 4: NetSim output Metrics.xml file

For Example, if the application throughput is to be logged for each simulation run then the script file can be updated as shown below:




Figure 5: The application throughput is to be logged for each simulation modified in Script.txt

- 3. ConfigWriter.exe: This executable takes one or more command line arguments as input and generated Configuration.netsim file by replacing the arguments in place of the variable parameters specified in the input.xml file.
 - If there are two variable parameters specified in the input.xml file ({0} and {1}) then two arguments need to be passed while calling ConfigWriter.exe.
- 4. **MetricsCSV.exe:** This executable is used to convert the Metrics.xml file present in the output folder into a comma separated file, MetricsPrint.csv.

5. MetricsReader.exe: This executable is responsible for reading the output parameter from the Metrics.xml file generated after each simulation and logging it to the results file.
It uses the Script.txt file to determine which parameter to read from the Metrics file.

If multiple parameters are to be read and logged, then the MetricsReader.exe can be called multiple times with Script.txt file having information about the parameter to be read each time.

- 6. Supporting DLL's: Some the supporting files such as ConfigWriter.dll, MetricsReader.dll, NetSimMetricsReader.dll, NetSimXmlReader.dll, etc. which are present in the project folder are used by other executable such as ConfigWriter.exe and MetricsReader.exe for various purposes during a multi-parameter sweep.
- 7. **MultiParameterSweeper.py** uses python programming language which is less complex and offers more flexibility as the number of input and output parameters increases.
 - Users can also write the script to run the multi-parameter sweep process in a preferred programming language as per the convenience.
 - The script can be configured to run multiple simulation iterations based on the number of parameters to be varied and the range of values of each parameter.
 - NETSIM_PATH variable can be set to the path of NetSim 64-bit binaries (bin_x64) in the install directory or workspace which is to be used to run Simulations.
 - LICENSE_ARG variable can be set to License server port and IP details in case of floating on premise licenses or the path of license file in case of node locked or cloud licenses.

```
tile Edit View Git Project Debug Test Analyze Tools Extensions Window Help Search (Ctrl+Q)
                                                                                                                                                                                  Solution1
                                                                                                                                                                                                                                                  Sign in 🖔
(6 • 9 | 10 • ≤ 8 9 | 19 • € • |
                                                                                             ▼ ► Attach... ▼ ▷ │ 👨 │ 👼 및 Python 3.9 (64-bit)
                                                                                                                                                                                 🖻 Live Share 🛮 👨
        lultiParameterSweeper.py 😕 🗙
               import subproce
import shlex
import random
import shutil
import math
import sys
import datetime
               # Set the path of 64 bit NetSim Binaries to be used for simulation.

NETSIM_PATH = "C:\\Users\\HP\\OneDrive\\Documents\\WetSim\\Workspaces\\Default_Workspace_v13_2_34\\bin_x64"

# Floating on-premise License

LICENSE_ARG = "50538192.168.0.9"

# Node Locked/ Cloud License

# LICENSE_ARG="\"C:\\Program Files\\NetSim\\Pro_v13_1\\bin\"";
               # Set NETSIM_AUTO environment variable to avoid keyboard interrupt at the end of each simulation os.environ["NETSIM_AUTO"] = "1"
                # Create IOPath directory to store the input Configuration.netsim file and the simulation output files during each iteration
              if not os.path.exists("IOPath"):
os.makedirs("IOPath")
              # Create Data directory to store the Configuration.netsim and the Metrics.xml files associated with each iteration
Dif not os.path.exists("Data"):
Os.makedirs("Data"):
              # Clear the IOPath folder if it has any files created during previous multi-parameter sweep runs
For root, dirs, files in os.walk("IOPath"):
| or file in files:
| os.remove(os.path.join(root, file))
                # Delete result.csv file if it already exists
iif os.nath.isfile("result.csv"):
pissues found
```

Figure 6: User need to set NetSim Path based on 64-bit

For example,

NETSIM_PATH=

"C:\\Users\\HP\\OneDrive\\Documents\\NetSim\\Workspaces\\Default_Workspace_v13_2_34\\bin_x 64"

Floating on-premise license (<port no>@<server ip address>):

LICENSE_ARG = "5053@192.168.0.9"

Node Locked or Cloud licenses (path of license file):

LICENSE_ARG="\"C:\\Program Files\\NetSim\\Pro_v13_1\\bin\\""

• The MetricsCSV.exe will convert the Metrics.xml file inside the output folder into a csv file.

```
Solution1
tile Edit View Git Project Debug Test Analyze Tools Extensions Window Help Search (Ctrl+Q)
                                                                                                                                                                                                                                                      Sign in 🕏
● • ● | * • ≠ ■ ■ | > • ○ • | 「
                                                                                                                                                                                    - 曲 | 田 📲 🖢 偱 | 🥫 🔲 🖫 🖫 🖫 🖫
                                                                                             → Attach... → ▷ | 👼 | 👼 - Python 3.9 (64-bit)
                                                                                                                                                                                                                                                                         🖒 Live Share 🛮 👨
      MultiParameterSweeper.py 💠 🗙
                      # print(cmd)
                       # Create a copy of the output Metrics.xml file for writing the result log
if os.path.isfile("IOPath\Metrics.xml"):
                          shutil.copy("IOPath\Metrics.xml", "Metrics.xml")
os.system("MetricsCsv.exe IOPath")
                      # Number of Script files i.e Number of Output parameters to be read from Metrics.xml
# If only one output parameter is to be read only one Script text file with name Script.txt to be provided
# If more than one output parameter is to be read, multiple Script text file with name Script1.txt, Script2.txt,...
# ..., Scriptn.txt to be provided
OUTPUT_PARAM_COUNT = 1
                             # Write the value of the variable parameters in the current iteration to the result log
                            csvfile = open("result.csv", "a")
csvfile.write("\n" + str(i) + ",")
csvfile.close()
                            if OUTPUT_PARAM_COUNT == 1:
                                   # Call the MetricsReader.exe passing the name of the output log file for updating the log based on script.txt
os.system("MetricsReader.exe result.csv")
                                  os.rename("Script." + str(n) + ".txt", "Script.txt")
os.system("MetricsReader.exe result.csv")
csvfile = open("result.csv", "a")
csvfile.write(",")
csvfile.tolse()
os.rename("Script.txt", "Script" + str(n) + ".txt")
              # Update the output Metric as crash if Metrics.xml file is missing
```

Figure 7: MetricsPrint.csv file will be created in the IOPath and then copied into the respective output folder

8. Multi-Parameter Sweeping process is started by opening command prompt in the directory of the Multi-Parameter-Sweeping project and starting the python script as shown below:

```
C:\Windows\System32\cmd.exe — X

Microsoft Windows [Version 10.0.22621.674]
(c) Microsoft Corporation. All rights reserved.

C:\Users\HP\OneDrive\Desktop\ToDo\Multi-Parameter_Sweeper_v13.2\Multi-Parameter-Sweeper>python MultiParameterSweeper.py
```

Figure 8: Running python script using cmd prompt

- This starts the Multi-Parameter-Sweeping process which runs NetSim simulations iteratively for different values of Y parameter of UE.
- 10. At the end of the process the Multi-Parameter-Sweeping folder will have the following file and folders created:




Figure 9: After Simulation Multi-Parameter-Sweeping folder contains output files like result.scv, Data etc

Data: Contains multiple folders created based on date and time of simulation inside which
multiple output folders corresponding to each simulation run, with its name including the value
of the parameters in that iteration gets created.




Figure 10: Based on values in the iteration, Output folder gets created in the Data directory inside a folder named as per date and time of simulation along with a copy of result.csv file.

Each folder contains the all the output files associated with the simulation run.




Figure 11: Each folder contains all the output files and the Metrics.xml file converted to MetricsPrint.csv file

Note: User should keep a back-up of the data folder to avoid data loss.

- **IO Path**: Used for storing the Configuration.netsim file and the simulation files generated during each simulation run.
- Result.csv: This is the output log which contains the parameter varied during each simulation
 run and the output parameter associated with each run. The result.csv file will also be copied
 into the output folder after each simulation.




Figure 12: Iterated value and Throughput obtained listed in result.csv

Example 1: Modifying a single input parameter and logging a single output parameter

Consider the following network 5G network scenario in NetSim, comprising of a Wired Node, Router, gNB and a UE.




Figure 13: Network Topology

The network configuration has the initial distance between the gNB and UE as 50 meters with the gNB located at (500,0) and UE located at (500,500).

Multi-Parameter Sweeper is configured to run simulations for different distance between the gNB and UE by varying the UE Y coordinate value from 500 to 2000 in steps of 500 meters.

The network scenario is saved and the content of the Configuration.netsim file is copied to the Multi-Parameter-Sweeper directory and renamed as input.xml.

Refer to the Example 1 directory which is part of the project folder (Multi-Parameter-Sweeper_v13.1\Examples\Multi-Parameter-Sweeper-Example-1)




Figure 14: Renamed Configuration.netsim to input.xml and pasted in Multi-Parameter-Sweeper directory

1. The value of the Y coordinate of UE that is to be modified during each simulation run is updated ("{0}") in the configuration file as shown below:




Figure 15: Modified Y coordinate of UE in input.xml

2. The Script.txt file is updated with the details of the output parameter to be read from the Metrics.xml file and added to the result csv log file. In this case the Application throughput is to be logged for each simulation run.




Figure 16: The application throughput is to be logged for each simulation modified in Script.txt

3. MultiParameterSweeper.py is updated to pass the Y coordinate value during each iteration to generate Configuration file run simulation and update the result csv log.

The MultiParameterSweeper.bat batch script modified for running simulations for different values of Y coordinates starting from 500 up to 2000 in steps of 500 is shown below:

- A result.csv file is created and added with headings Y and Throughput (Mbps).
- A MetricsPrint.csv is created inside every output folder.
- For loop is set to iteratively run simulations for values starting from 500 to 2000 in steps of 500.
- The value of the parameter Y in the current iteration is written to the result log file for analysis.
- The value of the parameter Y in the current iteration is passed as input to ConfigWriter executable to generate Configuration.netsim file for each simulation.
- NetSim simulation is run via CLI mode by passing the apppath, iopath and license server information
- Configuration file and Metrics file are copied and renamed appending the value of the parameter in the current iteration.

The MultiParameterSweeper.py python script modified for running simulations for different values of Y coordinates starting from 500 up to 2000 in steps of 500 is shown below:




Figure 17: To Create result.csv file, added with headings Y and Throughput (Mbps) and NetSim installation Path and License information

- NETSIM_PATH variable is set to the path of NetSim 64-bit binaries in the install directory or workspace in the system.
- LICENSE_ARG variable is set to the license server details
- A result.csv file is created and added with headings Y and Throughput (Mbps).




Figure 18: Varying Distance and set license server information

- For loop is set to iteratively run simulations for values starting from 500 to 2000 in steps of 500.
- The value of the parameter Y in the current iteration is passed as input to ConfigWriter executable to generate Configuration.netsim file for each simulation.

```
od Eile Edit View Git Project Debug Test Analyze Tools Extensions Window Help Search (Ctrl+Q)
                                                                                                                                                                                                                                   Sign in 🙎 — 🗇
▼ ► Attach... ▼ ▷ | 📭 | ¬ Python 3.9 (64-bit)
                                                                                                                                                                     🖻 Live Share 👂
      AultiParameterSweeper.py 💠 🗙
                       Number of Script files i.e Number of Output parameters to be read from Metrics.xml
                    # If only one output parameter is to be read only one Script text file with name Script.txt to be provided
# If more than one output parameter is to be read, multiple Script text file with name Script1.txt, Script2.txt,...
                             Scriptn.txt to be provided
                    OUTPUT_PARAM_COUNT = 1
                    if os.path.isfile("Metrics.xml"):
    # Write the value of the variable parameters in the current iteration to the result log
    csvfile = open("result.csv", "a")
    [csvfile.write("\n" + str(i) + ",")
    csvfile.close()
                         if OUTPUT_PARAM_COUNT == 1:
                                # Call the MetricsReader.exe passing the name of the output log file for updating the log based on script.txt
                                os.system("MetricsReader.exe result.csv")
                               os.rename("Script" + str(n) + ".txt", "Script.txt")
os.srename("Script" + str(n) + ".txt", "Script.txt")
os.system("MetricsReader.exe result.csv")
csvfile = open("result.csv", "a")
csvfile.unite(",")
csvfile.close()
os.rename("Script.txt", "Script" + str(n) + ".txt")
                          # Update the output Metric as crash if Metrics.xml file is missing
                        csvfile = open("result.csv", "a")
csvfile.write("\n" + str(i) + "," + "crash" + ",")
csvfile.close()
                   # Name of the Output folder to which the results will be saved
OUTPUT_PATH = "Data\\" + str(foldername) + "\\Output_" + str(i)
                    if not os.path.exists(OUTPUT_PATH):
    os.makedirs(OUTPUT_PATH)
                                                                                                                                                                                                                                            Ln: 4 Ch: 14 SPC
                                                                                                                                                                                                                                            Select Repository -
```

Figure 19: Modify parameters in MultiParameterSweeper.py

- The value of the parameter Y in the current iteration is written to the result log file for analysis.
- Configuration file and Metrics file are copied and renamed appending the value of the parameter in the current iteration.
- 4. Multi-Parameter Sweeping process is started by opening command prompt in the directory of the Multi-Parameter-Sweeping project and starting the python script as shown below:

```
C:\Users\HP\OneDrive\Desktop\ToDo\Multi-Parameter_Sweeper_v13.2\Examples\Multi-Parameter-Sweeper-Example-1>python MultiP arameterSweeper.py_
```

Figure 20: Running python script using cmd prompt

This starts the Multi-Parameter-Sweeping process which runs NetSim simulations iteratively for different values of Y parameter of UE.

At the end of the process the Multi-Parameter-Sweeping folder will have the following file and folders created:




Figure 21: After Simulation Multi-Parameter-Sweeping folder contains output files like result.csv, Data etc

Data: Contains multiple folders corresponding to each simulation run, with its name including
the value of the parameters in that iteration. The output folders will be created inside folder
with name in the format Year-Month-Day-Hours-Minutes-Seconds.




Figure 22: Based on distance Configuration.netsim files created in output folder

• Each folder contains the all the output files associated with the simulation run.




Figure 23: Each folder contains the all the output files

- **IOPath**: Used for storing the Configuration.netsim file and the simulation files generated during each simulation run.
- **Result.csv**: This is the output log which contains the parameter varied during each simulation run and the output parameter associated with each run.




Figure 24: Distance Vs. Throughput obtained in result.csv

Varying multiple network parameters

In order to vary multiple network parameters during the multi-parameter sweep process each parameter in the input.xml file can be modified as {0},{1},{2},{3},...{n} respectively.

Logging multiple output parameters

Each output parameter that is to be logged should be part of the Script.txt file. However, the Script.txt file should contain only the details of one output parameter during the call to MetricsReader.exe.

To log multiple parameters, multiple script files can be used. If n output parameters are to be logged, then there can be script1.txt, script2.txt, script.txt in the sweeper folder. For Example, there can be two Script files as shown below:




Figure 25: Multiple output parameters

Example 2: Modifying multiple input parameters and logging multiple output parameter

 Consider the following network 5G network scenario in NetSim, comprising of a Wired Node, Router, gNB and a UE.




Figure 26: Network Scenario

2. Properties configured in the LTE_NR interface of the gNB is shown in the table below:

Tx_Power(dBM)	40
Tx_Antenna_Count	8
Rx_Antenna_Count	4
CA_Type	Single Band
CA_Configuration	n78
CA_Count	1
Numerology	0
Channel Bandwidth (MHz)	10
PRB Count	52
MCS Table	QAM64
CQI Table	Table 1
X_Overhead	XOH0
DL UL Ratio	4:1
Outdoor Scenario	Rural Macro
	Standard
LOS Mode	Standard
LOS Mode Wireless Link Properties	Standard
	No_Pathloss
Wireless Link Properties	
Wireless Link Properties Channel Characteristics	
Wireless Link Properties Channel Characteristics Wired Link Properties	No_Pathloss
Wireless Link Properties Channel Characteristics Wired Link Properties Link Speed (Mbps)	No_Pathloss
Wireless Link Properties Channel Characteristics Wired Link Properties Link Speed (Mbps) BER	No_Pathloss 10000 0
Wireless Link Properties Channel Characteristics Wired Link Properties Link Speed (Mbps) BER Propagation Delay (µs)	No_Pathloss 10000 0
Wireless Link Properties Channel Characteristics Wired Link Properties Link Speed (Mbps) BER Propagation Delay (µs) Application Properties	No_Pathloss 10000 0 0
Wireless Link Properties Channel Characteristics Wired Link Properties Link Speed (Mbps) BER Propagation Delay (µs) Application Properties Packet Size (Byte)	No_Pathloss 10000 0 0 1460
Wireless Link Properties Channel Characteristics Wired Link Properties Link Speed (Mbps) BER Propagation Delay (µs) Application Properties Packet Size (Byte) Inter Arrival Time (µs)	No_Pathloss 10000 0 0 1460 166
Wireless Link Properties Channel Characteristics Wired Link Properties Link Speed (Mbps) BER Propagation Delay (µs) Application Properties Packet Size (Byte) Inter Arrival Time (µs) Generation Rate (Mbps)	No_Pathloss 10000 0 0 1460 166 100
Wireless Link Properties Channel Characteristics Wired Link Properties Link Speed (Mbps) BER Propagation Delay (µs) Application Properties Packet Size (Byte) Inter Arrival Time (µs) Generation Rate (Mbps) Transport Control	No_Pathloss 10000 0 0 1460 166 100 UDP
Wireless Link Properties Channel Characteristics Wired Link Properties Link Speed (Mbps) BER Propagation Delay (µs) Application Properties Packet Size (Byte) Inter Arrival Time (µs) Generation Rate (Mbps) Transport Control Start Time (s)	No_Pathloss 10000 0 0 1460 166 100 UDP 1

Table 1: gNB Properties

- 3. Traffic is generated at a rate of 70 Mbps and upon running simulation, the throughput achieved is 59.95 Mbps.
- 4. We now find the max throughput for each possible bandwidth; Tx Antenna count and Rx Antenna count combination varying the generation rate based accordingly.
- 5. Two more parameters to be taken care include, the PRB Count and Guard Band (KHz) which vary with respect to the bandwidth.

Input Variables	Value Range
Channel Bandwidth (MHz)	10,15,20,25,30,40,50
Tx_Antenna_Count	1,2,4,8,16,32,64,128
Rx_Antenna_Count	1,2,4,8,16
PRB Count	52,79,106,133,160,216,270
Guard Band (KHz)	312.5,382.5,452.5,522.5,592.5,552.5,692.5
Reference Inter Arrival Time (Microseconds)	166
Reference Bandwidth	10
Reference DL MIMO Layer Count	2

Table 2: Input variable values

Inter Arrival Time for each case is calculated based on the Reference IAT Bandwidth and DL MIMO Layer Count as shown below:

$$Inter\ Arrival\ Time\ (Micro\ Seconds) = \frac{Ref\ IAT}{\left(\frac{Curr\ BW}{Ref\ BW}\right)*\left(\frac{Curr\ DL\ MIMO\ Count}{Ref\ DL\ MIMO\ Count}\right)}$$

For E.g. In case of Bandwidth of 20 MHz and DL MIMO Count of 4 inter arrival time is

Inter Arrival Time (Micro Seconds) =
$$\frac{166}{\left(\frac{20}{10}\right)*\left(\frac{4}{2}\right)}$$
 = 41.5 Mbps

- 7. The network scenario is saved and the content of the Configuration.netsim file is copied to the Multi-Parameter-Sweeper directory and renamed as input.xml.
- 8. Refer to the Example 2 directory which is part of the project folder (Multi-Parameter-Sweeper_v13.1\Examples\Multi-Parameter-Sweeper-Example-2).




Figure 27: Renamed Configuration.netsim to input.xml and pasted in Multi-Parameter-Sweeper directory

9. In the Input.xml file the value of the input variables are modified as shown in the table below:

Input Variables	
Channel Bandwidth (MHz)	{0}
Tx Antenna Count	{1}
Rx Antenna Count	{2}
Inter Arrival Time (Microseconds)	{3}
PRB Count	{4}
Guard Band (KHz)	{5}

Table 3: Variables are modified to the input.xml file

Figure 28: The above table 3 Variables are modified in input.xml file

10. The python script MultiParameterSweeper.py is modified to run simulation for all possible combinations of Bandwidth and Tx Antenna Count and Rx Antenna Count with the respective values of Guard Band, PRB Count and the IAT that is calculated.





Figure 29: Modified MultiParameterSweeper.py based on input parameter

11. Multiple parameters are read from the Metrics.xml file and logged in the results.csv file along with the input parameters such as CHANNELBANDWIDTH_MHz, TX_ANTENNA_COUNT, RX_ANTENNA_COUNT, INTER_ARRIVAL_TIME (micro sec).



Data Packets transmitted

Table 4: User need to modify these two parameters in Script files

12. Two script text files namely Script1.txt and Script2.txt are created with information to read each of the parameters from the Metrics.xml file. The variable OUTPUT_PARAM_COUNT is set to 2 as per the number of Script files.

Script1.txt

```
Script1.txt - Notepad - X

File Edit Format View Help

MENU NAME="Application_Metrics"

TABLE NAME="Application_Metrics"

SET A="Throughput (Mbps)" WHERE "Application Id"="1"
```

Figure 30: The application throughput is to be logged for each simulation modified in Script1.txt

Scritp2.txt

```
Script2.txt - Notepad - X

File Edit Format View Help

MENU NAME="Link_Metrics"

TABLE NAME="Link_Metrics"

SET A="Packets transmitted\Data" WHERE "Link_id"="All"
```

Figure 31: The Data Packets transmitted is to be logged for each simulation modified in Script2.txt

13. In the python script MultiParameterSweeper.py, MetricsReader is called to log each parameter specified in the script text files separating the entries with a comma (","). If simulation crashes, without generating the output Metrics.xml, then "crash" message is written to the log for each output parameter. The input parameters that were varied during each simulation run are also logged in the results.csv file.

```
od File Edit <u>V</u>iew <u>G</u>it <u>Project D</u>ebug Test A<u>n</u>alyze <u>T</u>ools E<u>x</u>tensions <u>W</u>indow <u>H</u>elp <u>Search (Ctrl+Q)</u>
                                                                                                                                                        ₽ Solution1
                                                                                                                                                                                                               Sign in 🕏
                                                                            → Attach... → ▷ | 👼 | Fython 3.9 (64-bit)
MultiParameterSweeper.py → ×
                        if OUTPUT_PARAM_COUNT == 1:
                                  # Call the MetricsReader.exe passing the name of the output log file for updating the log based on script.txt
os.system("MetricsReader.exe result.csv")
                                e:

for n in range(1, OUTPUT_PARAM_COUNT + 1, 1):

os.rename("Script" + str(n) + ".txt", "Script.txt")

os.system("MetricsReade.vex result.csv")

csvfile = open("result.csv", "a")

csvfile.surite(",")

csvfile.close()

os.rename("Script.txt", "Script" + str(n) + ".txt")
                             # Update the output Metric as crash if Metrics.xml file is missing csvfile = open("result.csv", "a")

csvfile.arite(
"\n"
                                 + str(i)
                                  str(j)
                                  + str(z)
                                 + ","
+ str(iat)
+ ","
+ "crash"
+ ","
```

Figure 32: Modify python script MultiParameterSweeper.py file

14. The simulation Configuration file and all the output files associated with each simulation run is saved to folders with name including the bandwidth and DL MIMO count values that were used during each simulation run.




Figure 33: Modify python script MultiParameterSweeper.py file

15. Multi-Parameter Sweeping process is started by opening command prompt in the directory of the Multi-Parameter-Sweeping project and starting the python script as shown below:

Python Script:



Figure 34: Running Python Script using cmd Prompt

This starts the Multi-Parameter-Sweeping process which runs NetSim simulations iteratively for different combinations of input parameters.

At the end of the process the Multi-Parameter-Sweeping folder will have the following file and folders created:




Figure 35: After Simulation Multi-Parameter-Sweeping folder contains output files like result.csv, Data etc

16. **Data**: The Data directory contains multiple output folders with the output files associated with each simulation run.




Figure 36: Based on input parameter Configuration.netsim and other files created in output folder

- 17. **IOPath**: Used for storing the Configuration.netsim file and the simulation files generated during each simulation run.
- 18. **Result.csv**: This is the output log which contains the parameter varied during each simulation run and the output parameter associated with each run.




Figure 37: Based on script result stored in result.csv file