## **PyMOTW**

Home

Blog

The Book

A bout

Site Index

If you find this information useful, consider picking up a copy of my book, *The Python Standard Library By Example*.

# TCP/IP Client and Server

Sockets can be configured to act as a server and listen for incoming messages, or connect to other applications as a client. After both ends of a TCP/IP socket are connected, communication is bi-directional.

#### **Echo Server**

This sample program, based on the one in the standard library documentation, receives incoming messages and echos them back to the sender. It starts by creating a TCP/IP socket.

```
import socket
import sys

# Create a TCP/IP socket
sock = socket.socket(socket.AF_I
```

Then bind() is used to associate the socket with the server address. In this case, the address is localhost, referring to the current server, and the port number is 10000.

```
# Bind the socket to the port
server_address = ('localhost', 1
print >>sys.stderr, 'starting up
sock.bind(server_address)
```

Calling listen() puts the socket into server mode, and accept() waits for an incoming connection.

```
# Listen for incoming connection
sock.listen(1)

while True:
    # Wait for a connection
    print >>sys.stderr, 'waiting
    connection, client_address =
```

accept() returns an open connection between the server and client, along with

#### **Page Contents**

- TCP/IP Client and Server
  - o Echo Server
  - Echo Client
  - Client and Server Together
  - Easy Client Connections
  - Choosing an Address for Listening

#### Navigation

#### **Table of Contents**

**Previous:** Addressing, Protocol Families and Socket Types **Next:** User Datagram Client and Server

#### **This Page**

Show Source

#### **Examples**

The output from all the example programs from PyMOTW has been generated with Python 2.7.8, unless otherwise noted. Some of the features described here may not be available in earlier versions of Python.

the address of the client. The connection is actually a different socket on another port (assigned by the kernel). Data is read from the connection with recv() and transmitted with sendall().

```
try:
    print >>sys.stderr, 'con

# Receive the data in sn
while True:
    data = connection.re
    print >>sys.stderr,
    if data:
        print >>sys.stde
        connection.senda
else:
        print >>sys.stde
        break

finally:
    # Clean up the connectic
    connection.close()
```

When communication with a client is finished, the connection needs to be cleaned up using close(). This example uses a try:finally block to ensure that close() is always called, even in the event of an error.

#### **Echo Client**

The client program sets up its socket differently from the way a server does. Instead of binding to a port and listening, it uses connect() to attach the socket directly to the remote address.

```
import socket
import sys

# Create a TCP/IP socket
sock = socket.socket(socket.AF_I

# Connect the socket to the port
server_address = ('localhost', 1
print >>sys.stderr, 'connecting
sock.connect(server_address)
```

After the connection is established, data can be sent through the **socket** with **sendall()** and received with **recv()**, just as in the server.

```
try:
```

```
# Send data
message = 'This is the messa
print >>sys.stderr, 'sending
sock.sendall(message)

# Look for the response
amount_received = 0
amount_expected = len(messag)

while amount_received < amound data = sock.recv(16)
amount_received += len(continue)
print >>sys.stderr, 'received'

finally:
    print >>sys.stderr, 'closing sock.close()
```

When the entire message is sent and a copy received, the socket is closed to free up the port.

#### **Client and Server Together**

The client and server should be run in separate terminal windows, so they can communicate with each other. The server output is:

```
$ python ./socket_echo_server.py
starting up on localhost port 10
waiting for a connection
connection from ('127.0.0.1', 52
received "This is the mess"
sending data back to the client
received "age. It will be"
sending data back to the client
received " repeated."
sending data back to the client
received ""
no more data from ('127.0.0.1',
waiting for a connection
```

#### The client output is:

```
$ python socket_echo_client.py

connecting to localhost port 100
sending "This is the message. I
received "This is the mess"
received "age. It will be"
received " repeated."
closing socket
$
```

### **Easy Client Connections**

TCP/IP clients can save a few steps by using the convenience function create\_connection() to connect to a server. The function takes one argument, a two-value tuple containing the address of the server, and derives the best address to use for the connection.

```
import socket
import sys
def get constants(prefix):
    """Create a dictionary mappi
    return dict ( (getattr (socket
                 for n in dir(sc
                 if n.startswith
families = get_constants('AF_')
types = get_constants('SOCK ')
protocols = get constants('IPPRC
# Create a TCP/IP socket
sock = socket.create connection(
print >>sys.stderr, 'Family :',
print >>sys.stderr, 'Type :',
print >>sys.stderr, 'Protocol:',
print >>sys.stderr
try:
    # Send data
    message = 'This is the messa
    print >>sys.stderr, 'sending
    sock.sendall(message)
    amount received = 0
    amount expected = len (messag
    while amount received < amou</pre>
       data = sock.recv(16)
        amount received += len(d
        print >>sys.stderr, 'rec
finally:
    print >>sys.stderr, 'closing
    sock.close()
```

create\_connection() USES getaddrinfo()
to find candidate connection parameters,
and returns a socket opened with the first
configuration that creates a successful
connection. The family, type, and proto
attributes can be examined to determine
the type of socket being returned.

```
$ python socket_echo_client_easy
Family : AF_INET
```

```
Type : SOCK_STREAM
Protocol: IPPROTO_TCP

sending "This is the message. I received "This is the mess" received "age. It will be" received " repeated." closing socket
```

# **Choosing an Address for Listening**

It is important to bind a server to the correct address, so that clients can communicate with it. The previous examples all used 'localhost' as the IP address, which limits connections to clients running on the same server. Use a public address of the server, such as the value returned by gethostname(), to allow other hosts to connect. This example modifies the echo server to listen on an address specified via a command line argument.

```
import socket
import sys
# Create a TCP/IP socket
sock = socket.socket(socket.AF I
# Bind the socket to the address
server name = sys.argv[1]
server address = (server name, 1
print >>sys.stderr, 'starting up
sock.bind(server address)
sock.listen(1)
while True:
    print >>sys.stderr, 'waiting
    connection, client address =
    try:
        print >>sys.stderr, 'cli
        while True:
            data = connection.re
            print >>sys.stderr,
            if data:
                connection.senda
            else:
                break
    finally:
        connection.close()
```

A similar modification to the client program is needed before the server can be tested.

```
import socket
```

```
import sys
# Create a TCP/IP socket
sock = socket.socket(socket.AF I
# Connect the socket to the port
server address = (sys.argv[1], 1
print >>sys.stderr, 'connecting
sock.connect(server address)
try:
   message = 'This is the messa
   print >>sys.stderr, 'sending
   sock.sendall(message)
    amount received = 0
    amount expected = len (messag
    while amount received < amou</pre>
        data = sock.recv(16)
       amount received += len(c
        print >>sys.stderr, 'rec
finally:
    sock.close()
```

After starting the server with the argument farnsworth.hellfly.net, the **netstat** command shows it listening on the address for the named host.

Running the the client on another host, passing farnsworth.hellfly.net as the host where the server is running, produces:

```
$ hostname
homer

$ python socket_echo_client_expl
connecting to farnsworth.hellfly
sending "This is the message. I
received "This is the mess"
received "age. It will be"
received " repeated."
```


And the server output is:

```
$ python ./socket_echo_server_ex
starting up on farnsworth.hellfl
waiting for a connection
client connected: ('192.168.1.8'
received "This is the mess"
received "age. It will be"
received " repeated."
received ""
waiting for a connection
```

Many servers have more than one network interface, and therefore more than one IP address. Rather than running separate copies of a service bound to each IP address, use the special address INADDR\_ANY to listen on all addresses at the same time. Although socket defines a constant for INADDR\_ANY, it is an integer value and must be converted to a dotted-notation string address before it can be passed to bind(). As a shortcut, use the empty string '' instead of doing the conversion.

```
import socket
import sys
# Create a TCP/IP socket
sock = socket.socket(socket.AF I
# Bind the socket to the address
server address = ('', 10000)
sock.bind(server address)
print >>sys.stderr, 'starting up
sock.listen(1)
while True:
   print >>sys.stderr, 'waiting
    connection, client address =
    try:
        print >>sys.stderr, 'cli
        while True:
           data = connection.re
            print >>sys.stderr,
            if data:
                connection.senda
            else:
                break
    finally:
        connection.close()
```

To see the actual address being used by a socket, call its <code>getsockname()</code> method. After starting the service, running <code>netstat</code> again shows it listening for incoming connections on any address.



Be the first to comment.

© Copyright Doug Hellmann. | (CC) BY-NC-SA | Last updated on Nov 29, 2015. | Created using Sphinx. | Design based on "Leaves" by SmallPark | GREEN HOSTING