



CS2200 Systems and Networks Spring 2024

Lecture 3: Processors (cont'ed)

Alexandros (Alex) Daglis
School of Computer Science
Georgia Institute of Technology

adaglis@gatech.edu

Announcements

- First lab tomorrow
 - Examples on endianness, operand packing, addressing modes
 - Intro to CircuitSim
 - Please attend your official lab section!
- Project I released on Friday
 - Duration: 3 weeks
- PS participation counts, starting this week

Building an ISA — so far

Software	Hardware
Expressions & assignments	ALU instructions
Variable reuse	register addressing mode Id/st instructions
Data abstraction • struct • array	base + offset addr mode base + index addr mode
Granularity of operands	Idb/Idh/Idw instructions addressability (byte, word)
Packing operands	Memory alignment (space/time tradeoff)
Endianness 0x11223344	Little (first byte is 0x44) / Big (first byte is 0x11)

^{*} LC-2200 is Little Endian (like x86)

What do we need for...


- Conditional statements
- Switch statements
- Loops
- Procedure calls
- Other considerations for ISA

Compiling Conditional Statements

- In what order are program statements normally executed?
- How do we know what instruction to execute next?
- How can we handle this high-level language construct:

$$if(x == y) z = 7;$$


What Do We Need to Do?



- Evaluate predicate
- Break the sequential flow of instructions
- Rejoin control path

Implementing a Conditional

- Evaluate predicate
 - ALU Op
- Break sequential flow
 - Need to know where we are
 - **→** PC
 - Need a new instruction
 - → BEQ rl, r2, offset
 - → if rI == r2 then PC = PC + offset else do nothing
 - → PC relative addressing mode!
- Rejoin control flow
 - → need an unconditional jump



An Example

```
if (a == b)
   c = d + e;
else
   c = f + g;
```

```
Assembly
```

```
beq r1, r2, then
add r3, r6, r7
beq r1, r1, skip*
then add r3, r4, r5
skip ...
```

Assuming rI = a r2 = b r3 = c r4 = d r5 = e r6 = f r7 = g

* Effectively an unconditional branch

Outcome of Supporting Conditional Statements

- Introduction of PC
- One new instruction BEQ r_1 , r_2 , offset
- One new addressing mode: PC-relative
- (optional) an Unconditional Jump $J r_n ; PC \leftarrow r_n$
- Do we really need an unconditional jump??

Compiling Switch Statements

```
if (n==0)
    x=a;
else if (n==1)
    x=b;
else if (n==2)
    x=c;
else
    x=d;
```

Do these produce essentially equivalent assembly code?


They can, but they don't have to!

```
switch (n) {
     case 0:
          x=a;
          break;
     case 1:
          x=b;
          break;
     case 2:
          X=C;
          break;
     default:
          x=d;
```

Switch Can Use a Jump Table

- Think of a C array of pointers to the individual cases
- To do this we need an indirect addressing mode

 \rightarrow PC \leftarrow Mem[r₁]



Jump table

Loops

- Do we need anything new in the ISA?
- Not really.

Compiling Loops

```
while(j ! = 0)
{
    /* loop body */
    t = t + a[j--];
}
```

Assembly

```
loop beq r1,r0,done
   ; loop body
   ...
   beq r0, r0, loop
done ...
```

Summary

Software	Hardware
Expressions & assignments	ALU instructions, LD/ST instructions
Data abstraction • struct • array	register addr mode base + offset addr mode base + index addr mode
Conditionals & Loops	PC-relative addr mode branch/jump instruction (register or PC-relative) Indirect addr mode (optional)

How Do We Compile Function Calls?

```
State of Caller
    Pass parameters
                                                       Allocate space for local vars
    Remember return addr
    Jump to function
int main()
                                                int foo(formal-parameters)
                                                   <decl local-variables>
  <decl local-variables>
 return-value = foo(actual-parms);
                                                   /* code for function foo */
  /* continue upon
                                                   return(<value>);
   * returning from foo
                                                      Pass result to caller
         Save the result
                                                      Return to caller
         Continue the program
```

Caller

Callee

Remembering the Return Address

Have we needed to do this before?

- Add a Jump & Link instruction
 - JALR r_{target} , r_{link} ; r_{link} <= PC, PC <= r_{target}
- Recall $\int r_{target} ; PC \le r_{target}$
- Do we need this instruction anymore?


Control Flow

```
JALR r_{target}, r_{link} foo() {
main() {
                                   Call
       foo();
                                  Return
```


Control Flow

```
foo() {
main()
                 Save state
                                     Call
                                             Pass in
                  (before)
                                             parameters
        foo();
                                             ← Return
                                              result
                  Restore state
                                    Return
                     (after)
```

Another Way to Save State



Shadow Register Sets



- foo() calls bar() who calls baz(), etc.
- The Big Deal: No memory accesses!
 (but we need lots of extra registers)
- Another form of this is called register renaming

Saving State

- If we don't have shadow registers, where are we going to save all that state?
- A stack

Where are we going to put the stack?

- In memory
- But in small cases, could we hold the state in a few extra registers?
 (another space/time tradeoff)

Use a Stack to Communicate

```
main() {
                                           foo() {
      foo();
                                               - Save/restore state
                                               - Pass parameters
                                               - Return results
                                               - What else is needed in ISA?
```

- Nothing new..

Saving Registers During a Procedure

- We can have the caller save all the registers
 -or-
 - We can have the callee save all the registers
- What's wrong with those choices?
 - Not all registers need to be saved every time...

Saving Registers During a Procedure

- If we split the assignment of the registers, then most of the time, the caller and callee can each save fewer registers based on what they actually need to use
- In the LC-2200 case, we'll functionally divide the working register set
 - s0-s2 registers which the callee must preserve if it wants to use them
 - t0-t2 registers which the caller must preserve if it wants their values to persist over a function call
- This division of responsibility saves memory accesses.

Saving/restoring state over a procedure call

Who does it?

→ Split between Caller and Callee

Returning results

Do we really need to put them on the stack?

→ Use registers (We'll call this register v0)

Parameter Passing

Do we really need to put them on the stack?

→ Use registers (We'll call these registers a0-a2)

- Will we need the stack at all for parameters and results?
- What if we run out of registers?
- We use the stack if we run out
- Here we're trading time for complexity

Moral of the Story

- Use the stack sparingly
 - LD/ST instructions are expensive (i.e., memory access is slow)
- Software calling convention
 - Used by the compiler to keep track of the use of the stack and registers
 - Better have one!

Software Convention for LC-2200

Use: Program Data

Use: Bookkeeping

- Registers s0-s2 are the caller's saved registers
- Registers t0-t2 are the temporary registers
- Registers a0-a2 are the parameter passing registers
- Register v0 is used for return value
- Register ra is used for return address (r_{link})
- Register at is used for target address (r_{target})
- Register sp is used as a stack pointer
- (Not seen yet: Register fp used as a frame pointer)



Review Question I

Saving and restoring of registers on a procedure call...

- A. Is always done by the caller.
- B. Is always done by the callee.
- C. Is never done explicitly since hardware magically takes care of it.
- D. Is done on a need basis partly by the caller and partly by the callee.
- E. What is a caller/callee?





Review Question 2

On the LC-2200, how are actual parameters passed to a function?

- A. On the stack.
- B. On the heap.
- C. Up to 3 in registers, the rest on the stack.
- D. Up to 6 in registers, the rest on the stack.
- E. None of the above.





Review Question 3

We store some values in registers during a procedure call...

- A. Because we like to mix things up variety is good!
- B. Because it reduces memory references.
- C. It makes the stack shorter so it reduces the danger of overflow.
- D. It results in prettier code.




Stack Management

Activation Record


- Also known as a Stack Frame
- It's the space used by the caller and callee during the execution of a procedure call
- Used to store...
 - Caller saved registers
 - Additional parameters
 - Additional return values
 - Return address
 - Callee saved registers
 - Local variables


Stack Conventions





- Stack grows toward lower memory addresses
- Decrement, then push
- Pop, then increment
- Top of Stack points to last item placed in it


Stack is initially empty

















Stack Local variables Pointer Saved s Registers Prev Return address Additional return values Additional parameters Saved t Registers


Step 7.


Callee allocates space for any local variables on the stack

















Local variables in a procedure...

- A. Are usually allocated on the stack.
- B. Are usually kept in processor registers.
- C. Are usually kept in special hardware.
- D. Are usually allocated in the heap space of the program.
- E. None of the above



A Stack of Activation Records (or Stack of Frames)



Recursion

Does recursion require any additional instruction set architecture items?

One More Thing: Frame Pointer

- During execution of given module it is possible for the stack pointer to move.
- Since the location of all items in a stack frame is based on the stack pointer it is useful to define a fixed point in each stack frame and maintain the address of this fixed point in a register called the <u>frame pointer</u>
- This necessitates storing the old frame pointer in each stack frame (i.e., caller's frame pointer)

Why Do We Need a Frame Pointer?


This code will cause us a problem:

```
foo(int p) {
    int a = 1, b = 3;
    if (a != p) {
        int c[p];
        c[p - 1] = b + a;
        longer at the same
        offset from SP

}
b++; a++;
; ...
}
```

Let's look at the stack in detail

Let's Start at Step 7 To See What Our Function Does



Local variables

Saved s Registers

Prev Return address

Additional return values


Additional parameters

Saved t Registers

```
int a = 1, b = 3;
if (a != p) {
    int c[p];
    c[p-1] = b + a;
    ...
}
b++; a++;
```


Slide The Stack Diagram Down





```
int a = 1, b = 3;
if (a != p) {
    int c[p];
    c[p-1] = b + a;
    ...
}
b++; a++;
```

When Our Function Runs



Let's Revise foo()'s Stack Frame

Stack
Pointer

Saved s
Registers


Prev Frame
Pointer


Prev Return
address

We're going to add one more item to the stack: Prev Frame Pointer because we'll need to save/restore our Frame Pointer register.


And that's where we'll point our Frame Pointer register.


Addressing Local Variables with FP







^{*}Stack pointer may change during procedure execution













Step 11 (revised). Callee executes jump to ra No change to stack. Prev Return Stack address Pointer Note that Frame Pointer is now pointing to caller's Additional return values activation record. Additional We proceed as we did before parameters introducing the frame pointer Saved t Registers









Effect of Stack Evolution

- The offset with respect to the stack pointer for referencing variables on the stack changes as the stack grows and shrinks
 - → A pain for the compiler writer
 - → Burdens the code with complicated local variable address calculations
- How to reduce this pain?
 - → Have a fixed harness on the stack for referencing local variables
 - → Frame Pointer (FP)



We keep track of a frame pointer because...

- A. It's faster to access a variable through the frame pointer than it is to access through the stack pointer.
- B. I can't explain why we waste one of our valuable registers doing this.
- C. We have to do it for legacy reasons.
 - D. It gives us a single, consistent, constant offset to reference the local variables in a stack frame.

