4/28/2020 Simulation Viewer

Lab Report

Your Performance

Your Score: 3 of 3 (100%) Pass Status: Pass Elapsed Time: 7 minutes 14 seconds Required Score: 100%

Task Summary

Actions you were required to perform:

- On Support, configure an ip address and broadcast address appropriate for this network
- On Office2, configure the gateway address appropriate for this network
- On ITAdmin, configure a subnet mask appropriate for this network

Explanation

In this lab, your task is to complete the following:

- Use troubleshooting tools such as ping, ip addr show, or traceroute to diagnose the problems in the network.
- Fix the problem at each workstation.
- Use the troubleshooting tools to confirm the problem's resolution.

Location	Name	IP Address
Networking Closet	CorpServer	192.168.0.10/24
Office 1	Office1	192.168.0.30/24
Office 2	Office2	192.168.0.31/24
Support Office	Support	192.168.0.32/24
IT Administration	ITAdmin	192.168.0.33/24
Executive Office	Exec	192.168.0.34/24
Lobby	Gst-Lap	192.168.0.35/24
ISP	External DNS Server	163.128.78.93/24
Router	Internal Router	198.28.56.1/24

Complete this lab as follows:

- 1. In the Support Office, begin troubleshooting the problem by verifying the scope of the connectivity problem as follows:
 - a. Under Support Office, select **Support**.
 - b. At the prompt, type **ping 192.168.0.5** and press **Enter** to ping the gateway.
 - c. Press **Ctrl** + **C**. The ping fails.
 - d. Type **ping 192.168.0.30** and press **Enter** to ping the computer in Office 1.
 - e. Press **Ctrl** + **C**. The ping fails.
 - f. Type **ifconfig** and press **Enter** to examine the network configuration. The IP configuration for the network interface is on a different network.
- 2. Correct the problem on Support by configuring the network properties for the interface as follows:
 - a. Type nano /etc/sysconfig/network-scripts/ifcfg-enp2s1 and press Enter to edit the /etc/sysconfig/network-scripts/ifcfg-enp2s1 file to configure the interface.
 - b. On the IPADDR line, type **192.168.0.32**.
 - c. On the BROADCAST line, type 192.168.0.255.
 - d. Press Ctrl + O.
 - e. Press Enter to save the file.
 - f. Press **Ctrl** + **X** to exit the editor.

4/28/2020 Simulation Viewer

- g. Type **ip link set enp2s1 down** or **ifdown enp2s1** and press **Enter** to bring the interface down.
- h. Type ip link set enp2s1 up or ifup enp2s1 and press Enter to bring the interface back up with the new configuration.
- i. Type **ip addr show** or **ifconfig** and press **Enter** to verify the correct IP address on the interface.
- j. Type **ping 192.168.0.5** and press **Enter** to verify connectivity to the gateway.
- k. Press **Ctrl** + **C**. The ping now succeeds.
- 3. On Office2, begin troubleshooting the problem by verifying the scope of the connectivity problem as follows:
 - a. From the top navigation tabs, select **Floor 1 Overview**.
 - b. Under Office 2, select Office2.
 - c. At the prompt, type **ping 192.168.0.5** and press **Enter** to ping the gateway. The ping succeeds.
 - d. Press Ctrl + C.
 - e. Type **ping 192.168.0.30** and press **Enter** to ping the computer in Office 1. The ping succeeds.
 - f. Press Ctrl + C.
 - g. Type **ping 198.28.56.1** and press **Enter** to ping the internal router interface.
 - h. Press Ctrl + C. The ping fails. Since you have connectivity to the local network, but not beyond the gateway, this indicates a possible problem with the configured gateway address.
 - i. Type **route** and press **Enter** to examine the configured gateway. The gateway is configured incorrectly for this network.
- 4. Correct the problem on Office2 by configuring the network properties for the interface as follows:
 - a. Type nano /etc/sysconfig/network-scripts/ifcfg-enp2s0 and press Enter to edit the /etc/sysconfig/network-scripts/ifcfg-enp2s0 file to configure the interface.
 - b. On the GATEWAY line, type **192.168.0.5**.
 - c. Press Ctrl + O.
 - d. Press Enter to save the file.
 - e. Press **Ctrl** + **X** to exit the editor.
 - f. Type ip link set enp2s0 down or ifdown enp2s0 and press Enter to bring the interface down.
 - g. Type ip link set enp2s0 up or ifup enp2s0 and press Enter to bring the interface back up with the new configuration.
 - h. Type **ping 198.28.56.1** and press **Enter** to verify connectivity to the internal router interface. The ping now succeeds.
 - i. Press Ctrl + C.
- 5. On ITAdmin, begin troubleshooting the problem by verifying the scope of the connectivity problem as follows:
 - a. From the top navigation tabs, select **Floor 1 Overview**.
 - b. Under IT Administration, select **ITAdmin**.
 - c. At the prompt, type **ping 192.168.0.5** and press **Enter** to ping the gateway.
 - d. Press **Ctrl** + **C**. The ping fails.
 - e. Type **ping 192.168.0.30** and press **Enter** to ping the computer in Office 1.
 - f. Press **Ctrl** + **C**. The ping fails.
 - g. Type **ping 192.168.0.34** and press **Enter** to ping the computer in Executive Office. The ping succeeds.
 - h. Press Ctrl + C.
 - i. Type **ifconfig** and press **Enter** to examine the configured subnet mask. The subnet mask is configured incorrectly. Only this workstation and the Exec workstation are on the same network.
- 6. Correct the problem on ITAdmin by configuring the network properties for the interface as follows:
 - a. At the prompt, type nano /etc/sysconfig/network-scripts/ifcfg-enp2s0 and press Enter to edit the /etc/sysconfig/network-scripts/ifcfg-enp2s0 file to configure the interface.
 - b. On the NETMASK line, type **255.255.255.0**.
 - c. Press Ctrl + O.
 - d. Press **Enter** to save the file.
 - e. Press **Ctrl** + **X** to exit the editor.
 - f. Type ip link set enp2s0 down or ifdown enp2s0 and press Enter to bring the interface down.
 - g. Type ip link set enp2s0 up or ifup enp2s0 and press Enter to bring the interface back up with the new configuration.
 - h. Type **ping 192.168.0.5** and press **Enter** to verify connectivity to the gateway. The ping now succeeds.