# Introduction to NorESM2

19 - 20 Nov. 2024

Alok K. Gupta, Yanchun He, Ada Gjermundsen, Tomas Torsvik, Steve Goldhaber, Mariana Vertenstein, Matvey Debolskiy





## **Overview of presentations**


For this workshop we will demonstrate how to set up, build and run the NorESM2 model.

- 1. Downloading the NorESM source code
- 2. Basic steps to run NorESM
- 3. NorESM log files
- 4. First look at model output
- 5. Overview of model structure
- 6. Specify the compset
- 7. Specify model resolution
- 8. Understanding your case
- 9. Check your case
- 10. Reproducible development with scripts

Downloading the NorESM source code

 A recipe for downloading the CMIP6 version of NorESM

#### NorESM model structure



Separate repositories in NorESMhub

#### Downloading the NorESM code

#### Recipe:

- 1. Log on to betzy
- 2. Make a directory which will contain the NorESM code and the experiments
- 3. Enter the folder
- 4. Make a directory called cases. Here you will store all your NorESM experiments.
- 5. Get the NorESM code from GitHub
- 6. Enter the noresm repository
- 7. Checkout the CMIP6 version of NorESM
- 8. Get the corresponding code for the model component and cime

- 1. \$ ssh username@betzy.sigma2.no
- 2. \$ mkdir NorESMworkshop2024
- 3. \$ cd NorESMworkshop2024
- 4. \$ mkdir cases
- 5. \$ git clone https://github.com/NorESMhub/NorESM.git

Optional directory

structure, used for

examples to follow

- 6. \$ cd NorESM
- 7. \$ git checkout release-noresm2.0.9
- 8. \$./manage\_externals/checkout\_externals

**Documentation:** <a href="https://noresm-docs.readthedocs.io/en/noresm2/access/download\_code.html">https://noresm-docs.readthedocs.io/en/noresm2/access/download\_code.html</a>

#### All the steps needed for downloading the CMIP6 version of NorESM2 from github

```
$ mkdir NorESMworkshop2024
$ cd NorESMworkshop2024/
tomast@login-3.betzy:~/NorESMworkshop2024
$ git clone https://github.com/NorESMhub/NorESM.git
Cloning into 'NorESM'...
remote: Enumerating objects: 10909, done.
remote: Counting objects: 100% (1930/1930), done.
remote: Compressing objects: 100% (329/329), done.
remote: Total 10909 (delta 1664), reused 1717 (delta 1589), pack-reused 8979 (from 1)
Receiving objects: 100% (10909/10909), 41.62 MiB | 20.73 MiB/s, done.
Resolving deltas: 100% (7128/7128), done.
tomast@login-3.betzy:~/NorESMworkshop2024
$ cd NorESM/
tomast@login-3.betzy:~/NorESMworkshop2024/NorESM : (master)
$ git checkout release-noresm2.0.9
Note: switching to 'release-noresm2.0.9'.
You are in 'detached HEAD' state. You can look around, make experimental
changes and commit them, and you can discard any commits you make in this
state without impacting any branches by switching back to a branch.
If you want to create a new branch to retain commits you create, you may
do so (now or later) by using -c with the switch command. Example:
 git switch -c <new-branch-name>
Or undo this operation with:
 qit switch -
Turn off this advice by setting config variable advice.detachedHead to false
HEAD is now at 867f735 Update tag for cime to cime5.6.10_NorESM2_3_r5 (#569)
tomast@login-3.betzy:~/NorESMworkshop2024/NorESM : ((HEAD detached at release-noresm2.0.9))
$ ./manage_externals/checkout_externals
Processing externals description file : Externals.cfg
Checking status of externals: cam, cice, cime, cism, clm, mosart, pop, blom, rtm, ww3,
Checking out externals: cam, cice, cime,
```

## Fetching the source: checkout\_externals script

```
./manage_externals/checkout_externals : Fetch model components defined in the Externals.cfg file
./checkout_externals -e [EXTERNALS] : Fetch model components defined in [EXTERNALS] file
./checkout_externals -S : Check status of downloaded model components
./checkout_externals -h : See all options for checkout_externals
```

#### Entries from Externals.cfg file:

```
[cam]
tag = cam_cesm2_1_rel_05-Nor_v1.0.5
protocol = git
repo_url = https://github.com/NorESMhub/CAM
local_path = components/cam
required = True
```

```
[clm]
tag = release-clm5.0.14-Nor_v1.0.4
protocol = git
repo_url = https://github.com/NorESMhub/ctsm
local_path = components/clm
externals = Externals_CLM.cfg
required = True
```

# Basic steps to run NorESM

The Newbies Guide

(see NorESM2 documentation for further details)

#### How set up and run a standard NorESM case by executing 4 steps:

- 1. create a new case (the **create\_newcase** script)
- 2. configure case (the case.setup script)
- 3. build case (the case.build script)
- 4. submit case (the case.submit script)

It is recommended to encapsulate this procedure, and any configuration modifications, in a run shell script. We will look at examples of this later.

# **Basic** steps to run NorESM: Create case

The **create\_newcase** script is an executable python script located in cime/scripts

Mariana will give a detailed description in the next session

./create\_newcase --case \$PATH\_TO\_cases/\$CASENAME --mach \$MACHINE --res \$RESOLUTION

--compset \$COMPSET --project \$PROJECT --pecount={size of processor count}

--case : path and name of the NorESM experiment you are creating

--mach : name of the HPC you are using e.g. betzy, fram, nebula

--res : grid resolution, e.g. 1 degree (f09\_tn14) or 2 degree (f19\_tn14) atmosphere/land resolution

--compset : compset name, e.g. piControl (N1850frc2), historical, ssp585, abrupt-4xCO2 --project : which project provides the cpu hours you are using (e.g. nn9039k = EPOCASA)

\$ cd ~/NorESMworkshop2024/NorESM/cime/scripts/

\$ ./create\_newcase --case ~/NorESMworkshop2024/cases/N1850frc2\_f19\_tn14\_test01\_20241119 --mach betzy --res f19\_tn14 --compset N1850frc2 --project nn9039k --pecount=S

./create\_newcase --help will provide you all input options including a description

#### **Basic** steps to run NorESM: Create case

```
tomast@login-2.betzy:~/NorESMworkshop2024/NorESM : ((HEAD detached at release-noresm2.0.9))
$ cd cime/scripts/
tomast@login-2.betzy:~/.../NorESM/cime/scripts : ((HEAD detached at cime5.6.10 NorESM2 3 r5))
$ ./create_newcase --case ~/cases/N1850frc2_f19_tn14_test01_20241119 --mach betzy --res f19_tn14 --compset N1850frc2 --project nn9039k --pecount=S
Compset longname is 1850_CAM60%NORESM%FRC2_CLM50%BGC-CROP_CICE%NORESM-CMIP6_BLOM%ECO_MOSART_SGLC_SWAV_BGC%BDRDDMS
Compset specification file is /cluster/home/tomast/NorESMworkshop2024/NorESM/cime/../cime config/config compsets.xml
Compset forcing is 1850
ATM component is CAM cam6 physics:
LND component is clm5.0:BGC (vert. resol. CN and methane) with prognostic crop:
ICE component is Sea ICE (cice) model version 5 :with NORESM modifications appropriate for CMIP6 experiments
OCN component is BLOM default:BLOM/Ecosystem:
ROF component is MOSART: MOdel for Scale Adaptive River Transport
GLC component is Stub glacier (land ice) component
WAV component is Stub wave component
ESP component is
       specification file is /cluster/home/tomast/NorESMworkshop2024/NorESM/cime/../cime config/config pes.xml
Compset specific settings: name is RUN_STARTDATE and value is 0001-01-01
Could not find machine match for 'login-2.betzy' or 'login-2'
Machine is betzy
Pes setting: grid match is a%1.9x2.5.+l%1.9x2.5.+oi%tnx1v4
Pes setting: machine match is betzy
Pes setting: pesize match is S
                          is a%1.9x2.5 1%1.9x2.5 oi%tnx1v4 r%r05 g%null w%null m%tnx1v4
Pes setting: grid
                          <u>is 1850 CAM60%NORESM%FR</u>C2_CLM50%BGC-CROP_CICE%NORESM-CMIP6_BLOM%ECO_MOSART_SGLC_SWAV_BGC%BDRDDMS
Pes setting: compset
                         is {'NTASKS_ATM': 384, 'NTASKS_LND': 136, 'NTASKS_ROF': 128, 'NTASKS_ICE': 236, 'NTASKS_OCN': 123, 'NTASKS_GLC': 128, 'NTASKS_WAV': 12, 'NTASKS_CPL': 384}
Pes setting: tasks
Pes setting: threads
                        is {'NTHRDS ATM': 1, 'NTHRDS LND': 1, 'NTHRDS ROF': 1, 'NTHRDS ICE': 1, 'NTHRDS OCN': 1, 'NTHRDS GLC': 1, 'NTHRDS WAV': 1, 'NTHRDS CPL': 1}
                         is {'ROOTPE_ATM': 0, 'ROOTPE_LND': 0, 'ROOTPE_ROF': 0, 'ROOTPE_ICE': 136, 'ROOTPE_OCN': 384, 'ROOTPE_GLC': 0, 'ROOTPE_WAV': 372, 'ROOTPE_CPL': 0}
Pes setting: rootpe
Pes setting: pstrid
                         is {}
Pes other settings: {}
Pes comments: none
Compset is: 1850_CAM60%NORESM%FRC2_CLM50%BGC-CROP_CICE%NORESM-CMIP6_BLOM%ECO_MOSART_SGLC_SWAV_BGC%BDRDDMS
Grid is: a%1.9x2.5 l%1.9x2.5 oi%tnx1v4 r%r05 g%null w%null m%tnx1v4
 Components in compset are: ['cam', 'clm', 'cice', 'blom', 'mosart', 'sqlc', 'sway', 'sesp', 'drv', 'dart']
This is a CESM or NorESM scientifically supported compset at this resolution.
No charge_account info available, using value from PROJECT
No project info available
cesm model version found: release-noresm2.0.9
Batch system type is slurm nor
job is case.run USER_REQUESTED_WALLTIME None USER_REQUESTED_QUEUE None
job is case.st_archive USER_REQUESTED_WALLTIME None USER_REQUESTED_QUEUE None
Creating Case directory /cluster/home/tomast/cases/N1850frc2 f19 tn14 test01 20241119
This component includes user_mods /cluster/home/tomast/NorESMworkshop2024/NorESM/components/cice/cime_confiq/usermods_dirs/noresm-cmip6
Adding user mods directory /cluster/home/tomast/NorESMworkshop2024/NorESM/components/cice/cime config/usermods dirs/noresm-cmip6
tomast@login-2.betzy:~/.../NorESM/cime/scripts : ((HEAD detached at cime5.6.10_NorESM2_3_r5))
```



#### \$ cd ~/NorESMworkshop2024/cases/N1850frc2\_f19\_tn14\_test01\_20241119/

\$ less README.case

```
14:19:02: Compset longname is 1850_CAM60%NORESM%FRC2_CLM50%BGC-CROP_CICE%NORESM-CMIP6_BLOM%ECO_MOSART_SGLC_SWAV_BGC%BDRDDMS
          14:19:02: Compset specification file is /cluster/home/tomast/NorESMworkshop2024/NorESM/cime_confiq_compsets.xml
                            specification file is /cluster/home/tomast/NorESMworkshop2024/NorESM/cime_config/config_pes.xml
2024-11-15 14:19:02: Component ATM is CAM cam6 physics
2024-11-15 14:19:02: Component LND is clm5.0:BGC (vert. resol. CN and methane) with prognostic crop:
2024-11-15 14:19:02: LND GRID is 1.9x2.5
2024-11-15 14:19:02: Component ICE is Sea ICE (cice) model version 5 :with NORESM modifications appropriate for CMIP6 experiments
2024-11-15 14:19:02: This component includes user_mods /cluster/home/tomast/NorESMworkshop2024/NorESM/components/cice/cime_config/usermods_dirs/noresm-cmip6
2024-11-15 14:19:02: Component ROF is MOSART: MOdel for Scale Adaptive River Transport
2024-11-15 14:19:02: ROF GRID is r05
2024-11-15 14:19:02: GLC GRID is null
2024-11-15 14:19:02: Component WAV is Stub wave component
2024-11-15 14:19:02: WAV GRID is null
2024-11-15 14:19:02: INFORMATION ABOUT YOUR GIT VERSION CONTROL SYSTEM
README.case
```

You will find the information about your case in README.case

Including compset long name, grid files, components, git branch, git commit etc.

README.case can be very useful if you want to reproduce a case (either your own or somebody else's case)

## Basic steps to run NorESM: Set up the case

#### Enter the case folder:

```
$ cd ~/NorESMworkshop2024/cases/N1850frc2_f19_tn14_test01_2024119/
```

\$./case.setup

```
tomast@login-3.betzy:-/cases/N1850frc2_f19_tn14_test01_20241119
$ ./case.setup
Setting resource.RLIMIT_STACK to -1 from (8388608, -1)
/cluster/home/tomast/cases/N1850frc2_f19_tn14_test01_20241119/env_mach_specific.xml already exists, delete to replace
job is case.run USER_REQUESTED_WALLTIME None USER_REQUESTED_QUEUE None
Creating batch scripts
Writing case.run script from input template /cluster/home/tomast/NorESMworkshop2024/NorESM/cime/config/cesm/machines/template.case.run
Creating file .case.run
Writing case.st_archive script from input template /cluster/home/tomast/NorESMworkshop2024/NorESM/cime/config/cesm/machines/template.st_archive
Creating file case.st_archive
Creating ifile case.st_archive
Creating user_nl_xxx files for components and cpl
If an old case build already exists, might want to run 'case.build --clean' before building
You can now run './preview_run' to get more info on how your case will be run
tomast@login-3.betzy:-/cases/N1850frc2_f19_tn14_test01_20241119
$ □
```

# Basic steps to run NorESM: Build the case

After running ./case.setup you should see your case in the noresm run directory

\$ Is \$USERWORK/noresm/N1850frc2\_f19\_tn14\_test01\_20241119/

**bld** : build directory run : run directory

\$USERWORK: alias for /cluster/work/users/\$USER/

**bld:** the build folder. Here you find compiled source code for the model **run:** the run folder. Here you find logs, output data, restart files etc. More on that later ...

\$./case.build

Creating an executable cesm.exe; found in \$USERWORK/noresm/\$CASENAME/bld

## Basic steps to run NorESM: Building the case

```
omast@login-3.betzy:~/cases/N1850frc2_f19_tn14_test01_20241119
$ ./case.build
Building case in directory /cluster/home/tomast/cases/N1850frc2_f19_tn14_test01_20241119
sharedlib only is False
model only is False
Setting resource.RLIMIT_STACK to -1 from (8388608, -1)
Generating component namelists as part of build
Creating component namelists
  Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/components/cam//cime_config/buildnml
     ...calling cam buildcpp to set build time options
CAM namelist copy: file1 /cluster/home/tomast/cases/N1850frc2_f19_tn14_test01_20241119/Buildconf/camconf/atm_in file2 /cluster/wc
atm in
  Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/components/clm//cime_config/buildnml
  Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/components/cice//cime config/buildnml
     ...calling cice buildcpp to set build time options
  Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/components/blom//cime_config/buildnml
cluster/home/tomast/NorESMworkshop2024/NorESM/components/blom/cime_config/namelist_definition_blom.xml validates/
  Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/components/mosart//cime_config/buildnml
  Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/cime/src/components/stub comps/sqlc/cime config/buildnml
  Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/cime/src/components/stub_comps/swav/cime_config/buildnml
  Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/cime/src/components/stub_comps/sesp/cime_config/buildnml
  Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/cime/src/drivers/mct/cime_config/buildnml
Finished creating component namelists
Component 1nd build complete with 8 warnings
clm built in 101.328100 seconds
Building atm with output to /cluster/work/users/tomast/noresm/N1850frc2 f19 tn14 test01 20241119/bld/atm.bldløg.241117-071343
Building ice with output to /cluster/work/users/tomast/noresm/N1850frc2_f19_tn14_test01_20241119/bld/ice.bidlog.241117-071343
Building ocn with output to /cluster/work/users/tomast/noresm/N1850frc2_f19_tn14_test01_20241119/bld/ocn.bldlog.241117-071343
Building rof with output to /cluster/work/users/tomast/noresm/N1850frc2_f19_tn14_test01_20241119/bld/rof.bldlog.241117-071343
Building glc with output to /cluster/work/users/tomast/noresm/N1850frc2 f19 tn14 test01 20241119/bld/glc.bldlog.241117-071343
Building wav with output to /cluster/work/users/tomast/noresm/N1850frc2_f19_tn14_test01_202411<u>19</u>/bld/wav.bldlog.241117-071343
Building esp with output to /cluster/work/users/tomast/noresm/N1850frc2_f19_tn14_test01_20242119/bld/esp.bldlog.241117-071343
sglc built in 9.136641 seconds
sesp built in 9.370716 seconds
sway built in 9.494167 seconds
mosart built in 25.373657 seconds
Component atm build complete with 17 warnings
cam built in 117.011821 seconds
Component ice build complete with 1 warnings
cice built in 123.531599 seconds
blom built in 168.510808 seconds
Building cesm with output to /cluster/work/users/tomast/noresm/N1850frc2_f19_tn14_test01_20241119/bld/cesm.bldlog.241117-071343
Component cesm exe build complete with 2 warnings
Time spent not building: 6.836869 sec
Time spent building: 387.080195 sec
MODEL BUILD HAS FINISHED SUCCESSFULLY
```

#### case.build

- Create component namelist files
- Build components
- Build cesm executable

If everything builds correctly: MODEL BUILD HAS FINISHED SUCCESSFULLY

## **Basic** steps to run NorESM: Submitting the case

#### \$./case.submit

```
comast@login-3.betzy:~/cases/N1850frc2_f19_tn14_test01_20241119
$ ./case.submit
Setting resource.RLIMIT STACK to -1 from (-1, -1)
Creating component namelists
  Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/components/cam//cime_config/buildnml
CAM namelist copy: file1 /cluster/home/tomast/cases/N1850frc2_f19_tn14_test01_20241119/Buildconf/<u>camconf/atm in file2 /cluster/w</u>c
atm in
   Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/components/clm//cime config/buildnml
  Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/components/cice//cime_config/buildnml
   Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/components/blom//cime_config/buildnml
cluster/home/tomast/NorESMworkshop2024/NorESM/components/blom/cime config/namelist definition blom.xml validates/
   Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/components/mosart//cime_config/buildnml
   Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/cime/src/components/stub_comps/sglc/cime_config/buildnml
   Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/cime/src/components/stub_comps/swav/cime_config/buildnml
   Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/cime/src/components/stub_comps/sesp/cime_confiq/buildnml
   Calling /cluster/home/tomast/NorESMworkshop2024/NorESM/cime/src/drivers/mct/cime config/buildnml
Finished creating component namelists
Checking that inputdata is available as part of case submission
Setting resource.RLIMIT_STACK to -1 from (-1, -1)
Loading input file list: 'Buildconf/cam.input_data_list'
Loading input file list: 'Buildconf/cpl.input data list'
Loading input file list: 'Buildconf/blom.input data list'
Loading input file list: 'Buildconf/cice.input_data_list'
Loading input file list: 'Buildconf/mosart.input data list'
Loading input file list: 'Buildconf/clm.input_data_list'
Check case OK
submit_jobs case.run
Submit job case.run
Submitting job script sbatch --time 00:59:00 --account nn9039k .case.run --resubmit
Submitted job id is 1032716
Submit job case.st_archive
Submitting job script sbatch --time 0:59:00 --account nn9039k --dependency=afterok:1032716 case.st_archive --resubmit
Submitted job id is 1032717
Submitted job case.run with id 1032716
Submitted job case.st archive with id 1032717
```

case.submit submits two jobs to the queue:

- Run job
- Archive job

#### Monitoring your jobs: some useful commands

squeue: overview of job(s) running and the job id(s)

scontrol: see more details about the job running

scancel: stop job from running

```
$ squeue -u $USER
$ squeue -p $PROJECT
```

\$ scontrol show job \$JOBID

\$ scancel \$JOBID

Note! squeue -u \$USER: If you don't see your job, it has either finished or crashed!

```
tomast@login-3.betzy:~/cases/N1850frc2_f19_tn14_test01_20241119
 squeue -u tomast
            JOBID PARTITION
                                 NAME
                                          USER ST
                                                        TIME
                                                               NODES NODELIST(REASON)
                     normal N1850frc
                                                                   4 b[4340-4343]
          1032716
                                        tomast R
                                                        1:30
                                                                   1 (Dependency)
          1032717
                     preproc N1850frc
                                        tomast PD
                                                        0:00
```

Monitoring jobs: <a href="https://documentation.sigma2.no/jobs/monitoring.html">https://documentation.sigma2.no/jobs/monitoring.html</a>

# Log files

# Log files produced by NorESM

NorESM produce log output for case creation, build process, run process and archiving process.

#### Log files in the case directory:

CaseStatus: Summary of all processes (case setup, build, job submission and job completion).

Good place to start looking at the logs!

README.case: Log for case creation

software\_environment.txt: System environments (modules) used during model build

logs/run\_environment.txt.<id>.<time> : System environment (modules) loaded during model run.

<casename>: Log for job execution, CPU, memory and disk usage.

Documentation: <a href="https://noresm-docs.readthedocs.io/en/noresm2/output/noresm-logs.html">https://noresm-docs.readthedocs.io/en/noresm2/output/noresm-logs.html</a>

# Log files produced by NorESM

<u>Build logs</u>: <workdir>/noresm/<casename>/bld/ (<workdir> = /cluster/work/users/<username>)

cesm.bldlog.<timestamp>.gz : Build the coupled model executable cesm.exe.

<component>.bldlog.<timestamp>.gz : Build log for individual model components.

Run logs: <workdir>/archive/<casename>/logs/ (assuming run and archive processes finished)

cesm.log.<jobid>.<timestamp>.gz : Run log for coupled model system.

<component>.log.<jobid>.<timestamp>.gz : Run log for individual model components.

If NorESM fails during run, you may find these log files in <workdir>/noresm/<casename>/run/.

Archiving logs: <workdir>/archive/<casename>/

archive.log.<timestamp> : Log for short term archiving of model output.

case.log : Log for archiving of case directory.

NOTE: Archived \*.gz files can be read directly using the "less" command, but can otherwise be expanded before reading: gunzip <filename>.gz

# **Experiment status and timing statistics**

In your case directory: the file CaseStatus logs all information on what you have done and if it worked or not:

```
2<mark>0</mark>21-11-10 14:45:01: case.setup starting
2021-11-10 14:45:02: case.setup success
2021-11-10 14:45:07: case.build starting
2021-11-10 14:51:31: case.build success
2021-11-10 14:52:04: case.submit starting
2021-11-10 14:52:12: case.submit error
ERROR: Command: 'sbatch --time 00:59:00 -a devel --account nn9560k .case.run --resubmit' failed with error 'sbatch: error: OOSGrpNodeLimit
sbatch: error: Batch job submission failed: Job violates accounting/QOS policy (job submit limit, user's size and/or time limits)' from dir '/cluster/home/adagj/NorESM/cases/N1850frc2_f19_tn14_test02_2021
2021-11-10 14:52:52: case.submit starting
2021-11-10 14:52:59: case.submit error
ERROR: Command: 'sbatch --time 00:29:00 -q devel --account nn9560k .case.run --resubmit' failed with error 'sbatch: error: QOSGrpNodeLimit
sbatch: error: Batch job submission failed: Job violates accounting/QOS policy (job submit limit, user's size and/or time limits)' from dir '/cluster/home/adagj/NorESM/cases/N1850frc2 f19 tn14 test02 2021
1115'
2021-11-10 14:53:32: case.submit starting
2021-11-10 14:53:39: case.submit error
ERROR: Command: 'sbatch --time 00:29:00 -q devel --account nn9560k .case.run --resubmit' failed with error 'sbatch: error: QOSGrpNodeLimit
sbatch: error: Batch job submission failed: Job violates accounting/QOS policy (job submit limit, user's size and/or time limits)' from dir '/cluster/home/adagj/NorESM/cases/N1850frc2_f19_tn14_test02_2021
1115
2021-11-10 14:57:08: case.setup starting
2021-11-10 14:57:09: build.clean starting
2021-11-10 14:57:27: build.clean success
2021-11-10 14:57:28: case.setup success
2021-11-10 14:57:52: case.build starting
2021-11-10 14:59:37: case.build success
2021-11-10 15:00:26: case.submit starting
2021-11-10 15:00:34: case.submit success case.run:253485, case.st archive:253486
2021-11-10 15:05:37: case.run starting
2021-11-10 15:15:35: model execution success
2021-11-10 15:15:35: case.run success
2021-11-10 15:15:56: st archive starting
2021-11-10 15:16:29: st_archive success
```

## **Experiment status and timing statistics**

In your case directory: in the timing sub-directory; the file cesm\_timing.\$CASE provides information on grid type, run length, compset, processors configuration and many others.

Most important are timing statics: Model throughput, Model cost and run time

```
Overall Metrics:
   Model Cost:
                           985.36
                                    pe-hrs/simulated year
                                    simulated years/day
   Model Throughput:
                             3.12
   Init Time :
                     201.411 seconds
                     379.632 seconds
   Run Time
                                           75.926 seconds/day
   Final Time :
                       0.183 seconds
   Actual Ocn Init Wait Time
                                         5.450 seconds
   Estimated Ocn Init Run Time :
                                         2.344 seconds
   Estimated Run Time Correction :
                                         0.000 seconds
      (This correction has been applied to the ocean and total run times)
Runs Time in total seconds, seconds/model-day, and model-years/wall-day
CPL Run Time represents time in CPL pes alone, not including time associated with data e<u>xchange with other components</u>
   TOT Run Time:
                     379.632 seconds
                                           75.926 seconds/mday
                                                                       3.12 myears/wday
   CPL Run Time:
                                            1.692 seconds/mday
                                                                     139.93 myears/wday
                       8.458 seconds
   ATM Run Time:
                     233.509 seconds
                                           46.702 seconds/mday
                                                                       5.07 myears/wday
   LND Run Time:
                     106.004 seconds
                                           21.201 seconds/mday
                                                                      11.17 myears/wday
   ICE Run Time:
                                            7.345 seconds/mday
                                                                      32.23 myears/wday
                    36.725 seconds
   OCN Run Time:
                     281.239 seconds
                                           56.248 seconds/mday
                                                                       4.21 myears/wday
   ROF Run Time:
                                            3.622 seconds/mday
                                                                      65.35 myears/wday
                   18.111 seconds
   GLC Run Time:
                    0.000 seconds
                                            0.000 seconds/mday
                                                                       0.00 myears/wday
   WAV Run Time:
                       0.000 seconds
                                            0.000 seconds/mday
                                                                       0.00 myears/wday
                                            0.000 seconds/mday
                                                                       0.00 myears/wday
   ESP Run Time:
                       0.000 seconds
   CPL COMM Time:
                     127.679 seconds
                                           25.536 seconds/mday
                                                                       9.27 myears/wday
```

## **Experiment status and timing statistics**

In your RUN directory: /cluster/work/users/\$USER/noresm/\$CASE/run/ You will find all the namelists; component\_in files, the timing folder, restart files and rpointer.\* and if your model simulation for some reason crashes; the log files.

- the cesm.log.\$JOBID file can provide some hints of which component caused the crash
- the component.log.\$JOBID file can provide information about which subroutine caused the crashed
- Log timestamps can be a useful way to keep track of run evolution after several model runs

If your model simulation is successful, the log files are archived in: /cluster/work/users/\$USER/archive/\$CASE/logs/

For a successful simulation the cpl.log.\$JOBID.<timestamp>.gz file will end with:

```
(seq mct drv): =========
                                     SUCCESSFUL TERMINATION OF CPL7-cesm =======
(seg mct drv): ========
                                   at YMD, TOD =
                                                00010106
(seq mct drv): =========
                             # simulated days (this run) =
                                                               5.000
(seg mct drv): =========
                             compute time (hrs)
                                                               0.105
(seq mct drv): =========
                             # simulated years / cmp-day =
                                                               3.118
                             pes min memory highwater (MB)
(seq mct drv): =========
                                                              -0.001
(seq mct drv): =========
                             pes max memory highwater
                                                     (MB)
                                                              -0.001
(seq mct drv): =========
                             pes min memory last usage (MB)
                                                              521.612
(seq mct drv): ========
                             pes max memory last usage (MB)
                                                             1174.614
```

# Looking at model output with neview


# Looking at model output with neview

ncview provides simple visualization of output netCDF files. Useful to check if output is produced and shows some sensible pattern. Other diagnostic tools should be used for in-depth analysis.

Log in with X-forwarding:
 linux/mac: \$ssh -Y <u>username@betzy.sigma2.no</u>


- Load module for ncview:
   \$module load ncview/2.1.8-gompi-2022a
- Navigate to archive directory, ocean output, and launch noview:
   \$cd \$USERWORK/archive/N1850frc2\_f19\_tn14\_test01\_20241119/ocn/hist
   \$noview N1850frc2\_f19\_tn14\_test01\_20241119.blom.hd.0001-01.nc

# Looking at model output with neview



# Overview of NorESM model system


#### NorESM communication framework



NorESM2 is based on the second version of the Community Earth System Model, CESM2, and share most of the CESM2 structure, but modifies model component.

Component communicate with each other through the COUPLER, named CPL7 for the NorESM2 model version.

# cime\_config directory



#### Files in cime\_config/:

**config\_compsets.xml**: compset configuration file


**config\_pes.xml**: processor config for particular compsets

#### Additional component scripts


**buildnml**: build component namelist

**buildlib**: build component library

#### cime



# Example: fully coupled model on multiple processors



Standard setup:

Ocean component usually runs separately from other components.

Atmosphere runs on 30 min physics time steps, and couples to other components except ocean each interval.

Atmosphere - Ocean coupling at 60 min physics time steps.

**Processors** 

# **Questions?**

Extra slides: HPC resources provided by Sigma2

# **Sigma2 HPC machines**

See Sigma2 documentation for more HPC info: <a href="https://documentation.sigma2.no/hpc machines/hardware\_overview.html">https://documentation.sigma2.no/hpc machines/hardware\_overview.html</a>

Sigma2 provides 3 HPC systems:

Betzy for large parallel jobs

(Normal queue: 4-512 nodes, (Normal queue: 1-32 nodes,

4 days max walltime)

Fram for intermediate parallel jobsSaga for serial or single node jobs

(Not configured for NorESM)

7 days max walltime)

HPC job types: https://documentation.sigma2.no/jobs/choosing\_job\_types.html

	Fram	Betzy
System	Lenovo NeXtScale nx360	BullSequana XH2000
CPU type	Intel E5-2683v4 ; 2.1 GHz	AMD Epyc 7742 ; 2.25GHz
Nodes / Cores	1006 / 32256	1344 / 172032
(core / mem) per node	32 / 64 GB	128 / 256 GB
	largemem: 8x 512GB, 2x 6TB	16 Nvidia A100 GPUs

## Fram and Betzy storage areas

Directory	Alias	Purpose
/cluster/home/\$USER	\$HOME	User data
/custer/work/users/\$USER	\$USERWORK	Staging and job data
/custer/work/jobs/\$SLURM_JOB_ID	\$SCRATCH	Per-job data
/cluster/projects/ <project_name></project_name>		Project data
/cluster/shared/ <folder_name></folder_name>		Shared data


NorESM copies build and run files to subdirectories in \$USERWORK. These files are not backed up, and are subject to automatic deletion after 42 days (21 days or 17 days if storage reduced to 30% or 10%, respectively). Therefore, make sure you copy output files you want to keep to a permanent storage area.

Documentation: <a href="https://documentation.sigma2.no/files-storage/clusters.html">https://documentation.sigma2.no/files-storage/clusters.html</a>

# NorESM shared resources on Fram and Betzy

Shared resources for NorESM are available on both Fram and Betzy under directory:

/cluster/shared/noresm/



# Resources for NorESM workshop

## **Betzy for NorESM user workshop**

During the user workshop we have access to Betzy.

Most user will have access to project nn9039k until 1st Dec.

ReservationName = noresm Accounts = nn9039k PartitionName = normal

We are going to use mostly *normal* queue for simulation and it could have a long waiting time and you have access for around 12 days.

# Needed for exercises?

#### Setting the length of the simulation:

- STOP\_OPTION: nseconds,nsecond,nminutes,nhours,nhour,ndays,nmonths, nyears
- STOP\_N: numerical value

./xmlchange STOP\_OPTION=nmonths,STOP\_N=6

#### Writing restart files in middle of simulation:

Restart files are written end of the simulation by default; But, if you are having a long simulation of 100 years; for safety reason you want to write restart files at some frequency you can set below option

- REST\_OPTION: nseconds,nsecond,nminutes,nminute,nhours,nhour,nmonths, nyears
- REST\_N: numerical value
- DOUT\_S\_SAVE\_INTERIM\_RESTART\_FILES: TRUE or FALSE. Set to TRUE if you want to archive all restart files and FALSE if you only want to archive restart files from the end of the simulation

- <a href="https://noresm-docs.readthedocs.io/en/noresm2/configurations/experiment environment.html">https://noresm-docs.readthedocs.io/en/noresm2/configurations/experiment environment.html</a>
- <a href="https://noresm-docs.readthedocs.io/en/noresm2/configurations/experiment\_environment.html#som\_e-common-configuration-settings">https://noresm-docs.readthedocs.io/en/noresm2/configurations/experiment\_environment.html#som\_e-common-configuration-settings</a>

**Continue a simulation**: when you are having WALLCLOCK time limitation on system. For example, you want to have 200 years simulation and WALLCLOCK time limitation is 5 days; you are able to simulate 10 model years/day; to complete 200 model years simulation set RESUBMIT=3, STOP\_N to 50 and STOP\_OPTION to nyears

- CONTINUE\_RUN in env\_run.xml; TRUE or FALSE.
  - You need all restart files and rpointer.\* files in run folder.
  - Please note that CONTINUE\_RUN needs to be FALSE first time you submit an experiment.
  - Will automatically be set to TRUE if the job is automatically resubmitted,
     i.e. if RESUBMIT > 0
- **RESUBMIT** in env\_run.xml; an integer value.
  - will auto resubmit till specified value; you will have total simulation period STOP\_N\*(RESUBMIT+1)

- <a href="https://noresm-docs.readthedocs.io/en/noresm2/configurations/experiment environment.html">https://noresm-docs.readthedocs.io/en/noresm2/configurations/experiment environment.html</a>
- <a href="https://noresm-docs.readthedocs.io/en/noresm2/configurations/experiment\_environment.html#som\_e-common-configuration-settings">https://noresm-docs.readthedocs.io/en/noresm2/configurations/experiment\_environment.html#som\_e-common-configuration-settings</a>

#### **Branch run**

In a branch run, all components are initialized using a consistent set of restart files from a previous run. Mostly used for tuning experiments and investigating parameter space

- RUN\_TYPE to "branch"
- RUN\_REFDIR directory containing reference data
- RUN REFCASE name of reference case
- RUN\_REFDATE Reference date branch run
- GET\_REFCASE TRUE else you have to copy data to run folder

#### Hybrid run

Not as strict as a branch run, all components are initialized but can have reference files from several experiments. Used e.g. for a historical experiment starting from piControl

- RUN\_TYPE to "hybrid"
- RUN\_REFDIR directory containing reference data
- RUN\_REFCASE name of reference case
- RUN\_REFDATE Reference date branch run
- GET\_REFCASE TRUE else you have to copy data to run folder
- RUN\_STARTDATE set the date for the beginning of the simulation

- <a href="https://noresm-docs.readthedocs.io/en/noresm2/configurations/experiment environment.html">https://noresm-docs.readthedocs.io/en/noresm2/configurations/experiment environment.html</a>
- https://noresm-docs.readthedocs.io/en/noresm2/configurations/experiment\_environment.html#some-common-configuration-settings

Two scripts which you will find helpful (located in the case folder):

- 1. xmlquery: provides the information and its value which are set in the \*.xml files, e.g. env\_run.xml
- 2. xmlchange: used to change values/parameters set in the \*.xml files, e.g. in env\_run.xml

```
$ ./xmlquery --value STOP_OPTION,STOP_N
ndays,5
$ ./xmlchange STOP_OPTION=nyears,STOP_N=1
$ ./xmlquery --value STOP_OPTION
nyears,1
```

If you want to look at the env\_run.xml file:

```
$ vi env_run.xml
```

- https://noresm-docs.readthedocs.io/en/noresm2/configurations/experiment\_environment.html
- <a href="https://noresm-docs.readthedocs.io/en/noresm2/configurations/experiment\_environment.html#som\_e-common-configuration-settings">https://noresm-docs.readthedocs.io/en/noresm2/configurations/experiment\_environment.html#som\_e-common-configuration-settings</a>

# Configure run setting: env\_batch.xml

#### You also need to modify **env\_batch.xml**:

- XML block for case.run
- env\_batch.xml sets the arguments for the batch job commands
- Neet to set JOB\_WALLCLOCK\_TIME
- XML block for case.st\_archive
- case.st\_archive is a pending job which moves files from the run directory to the archive directory after a successful simulation.
- also here you need to set JOB\_WALLCLOCK\_TIME
- you can also modify project for CPU hours if required
   (usually it is set during experiment creation, but you may need to change it)

./xmlchange --subgroup case.st\_archive JOB\_WALLCLOCK\_TIME=00:25:00

After setting the walltime for the two jobs, you can submit your case:

\$./case.submit

#### **Documentation:**

https://noresm-docs.readthedocs.io/en/noresm2/configurations/experiment\_environment.html#batch-job-environment