
CS100 Introduction to Programming

Lecture 22. Rvalue references and their use

Today's learning objectives

Introduce Lectures from

- Leading Example: Smart pointers
- Move semantics
- Lvalues and Rvalues
- Rvalue references
- Move construction and move assignment
- std::move
- Efficiency considerations



Today's learning objectives

- Leading Example: Smart pointers
- Move semantics
- Lvalues and Rvalues
- Rvalue references
- Move construction and move assignment
- std::move
- Efficiency considerations

Smart pointers: motivation

Consider the following function:

```
void someFunction()
{
    Resource *ptr = new Resource; // Resource is a struct or class
    // do stuff with ptr here
    delete ptr;
}
```

- Problems:
 - Easy to forget deallocating ptr
 - Even if we don't, early exit could lead to leak

Smart pointers: motivation

Example:

```
#include <iostream>
void someFunction()
{
    Resource *ptr = new Resource;
    int x;
    std::cout << "Enter an integer: ";</pre>
    std::cin >> x;
    if (x == 0)
        return; // function returns early, ptr won't be deleted!
    // do stuff with ptr here
    delete ptr;
```

What are the good things of classes?

- Contain destructors
 - Get executed when object goes out of scope
 - Can deallocate memory that is owned by the class
 - Guarantees memory is free'ed up
 - RAII idiom:
 - Resource Acquisition Is Initialization
 - Resources are allocated upon object construction
 - Resources are de-allocated upon object destruction

Smart Pointer

- A class
- Manages and cleans up pointers
 - It "holds" the pointer
 - It lets us use the pointer
 - It automatically cleans up frees the allocated memory upon destruction

Smart pointer

• Example: #include <iostream>

```
template<class T>
class Auto ptr1 {
T* m ptr;
public:
 // Pass in a pointer to "own" via the constructor
 Auto ptr1(T* ptr=nullptr) : m ptr(ptr) {}
 // The destructor will make sure it gets deallocated
  ~Auto ptr1() {
    delete m ptr;
 // Overload dereference and operator->
  // lets us use Auto ptr1 like m ptr.
 T& operator*() const { return *m ptr; }
 T* operator->() const { return m ptr; }
};
```

Smart pointer

Usage: // A sample class to prove the above works class Resource { public: Resource() { std::cout << "Resource acquired\n"; }</pre> ~Resource() { std::cout << "Resource destroyed\n"; } }; Passed to res, res owns new Resource (composition) **Dynamic allocation** int main() { Output: // Allocation of memory here: Resource acquired Auto ptr1<Resource> res(new Resource); Resource destroyed // ... but no explicit delete needed // Note: Resource in angled braces doesn't need // a * symbol, it is supplied by the template res goes out of scope and return 0; is destroyed // res goes out of scope here, and destroys Destructor of Auto ptr

// allocated Resource for us

will delete Resource

Similarly:

Smart pointer No Memery Leak Basially clean.

```
void someFunction()
    Auto ptr1<Resource> ptr(new Resource); // ptr now owns the Resource
    int x;
    std::cout << "Enter an integer: ";</pre>
    std::cin >> x;
    if (x == 0)
        return; // the function returns early
    // do stuff with ptr here

    If x is not 0, output will be:

    ptr->sayHi();
}
                                            Resource acquired
                                            Hil
int main()
                                            Resource destroyed

    If x is 0, output will be:

    someFunction();
                                            Resource acquired
                                            Resource destroyed
    return 0;
```

Consider the following code

```
int main() {
                                             Double free situation.
 Auto ptr1<Resource> res1(new Resource);
 Auto ptr1<Resource> res2(res1);
                                  Hits
  return 0;
                                       Resource acquired
                                       Resource destroyed
                                       Segmentation fault
int main() {
 Auto ptr1<Resource> res1(new Resource);
 Auto ptr1<Resource> res2;
               Copy one by one and have the same problem.
  return 0;
```

- C++ automatically provides
 - copy-constructor
 - assignment operator
 - Are simply copying over the pointer inside Autopointer
 - → shallow copy

Consider the following code

```
int main() {
  Auto ptr1<Resource> res1(new Resource);
                                                 Both res1 and res2 are now
  Auto ptr1<Resource> res2(res1); ___
                                                 pointing at the same resource
  return 0;
                                   res1 and res2 go out of scope
                                   the first one deletes Resource already
                                   the second one aims at doing so too \rightarrow
int main() {
  Auto ptr1<Resource> res1(new Resource);
  Auto ptr1<Resource> res2;
  res2 = res1;
  return 0;
```

Similar problem is caused by this:

```
void passByValue(Auto_ptr1<Resource> res) {}
int main() {
  Auto_ptr1<Resource> res1(new Resource);
  passByValue(res1) // Not By Reference.
  return 0;
}
```

- Call to passByValue will make a (shallow) copy of res1
- passByValue will use this copy
- passByValue will destroy this copy upon completion of the function body
- this will destroy the resource!

Solution 1

 Prevent the copy constructor and the assignment operator to be "available", thereby preventing copying and assignment alltogether

- Solution 1, method 1 (the old way):
 - Explicitly declare them and make them private!

Solution 1, method 1

```
template<class T>
class Auto ptr1 {
T* m ptr;
public:
  // Pass in a pointer to "own" via the constructor
  Auto ptr1(T* ptr=nullptr) : m ptr(ptr) {}
  // The destructor will make sure it gets deallocated
  ~Auto ptr1() {
    delete m ptr;
  // ...
 private:
                                                    Explicit, private declaration
 Auto ptr1 (const Auto ptr1 & );
 Auto_ptr1& operator= ( const Auto_ptr1 & );
};
```

Solution 1, method 1

- What are the problems with this approach?
 - Automatic generation of default constructor does not happen (not a problem here)
 - The explicitly defined default constructor is less efficient than the automatically provided default constructor
 - Member functions and friends can still call the privately defined copy-constructor etc.
 - > Linking error if declared but not defined
 - Unclear

Solution 1

 Prevent the copy constructor and the assignment operator to be "available", thereby preventing copying and assignment altogether

Solution 1, method 2 (the C++11 way):

time error!

Bringing back default constructor

Calling them would lead to a compile

Solution 1, method2

```
template<class T>
class Auto ptr1 {
T* m ptr;
public:
 // Pass in a pointer to "own" via the constructor
 Auto ptr1(T* ptr=nullptr) : m ptr(ptr) {}
 // The destructor will make sure it gets deallocated
 ~Auto ptr1() {
   delete m ptr;
 Auto ptr1 (const Auto ptr1 & ) = delete;
 Auto ptr1& operator= ( const Auto ptr1 & ) = delete;
```

Auto-pointer

- Consequence:
 - Pass by value is no longer possible
 - → Not a big problem, just pass by reference
 - However, how to do this?

```
??? generateResource() {
   Resource *r = new Resource;
   return Auto_ptr1(r);
}
```

- Can't return by reference! → Object will be destroyed at the end of generateResource
- Can't return by value → copy-constructor is no longer available
- Can't just return pointer r, because that would defy the entire purpose of using the smart pointers

Auto-pointer

- What about just doing deep copies?
 - Not desirable
 - We just want to return a pointer from a function

Today's learning objectives

- Leading Example: Smart pointers
- Move semantics
- Lvalues and Rvalues
- Rvalue references
- Move construction and move assignment
- std::move
- Efficiency considerations

What are move-semantics?

- Do not copy values!
- Simply move ownership!

```
#include <iostream>
template<class T>
class Auto ptr2 {
T* m ptr;
public:
 Auto_ptr2(T* ptr=nullptr) : m_ptr(ptr) {}
  ~Auto ptr2() {
   delete m ptr;
  T& operator*() const { return *m ptr; }
  T* operator->() const { return m ptr; }
 bool isNull() const { return m ptr == nullptr; }
```

•••

```
// Copy constructor with move semantics
Auto ptr2 (Auto ptr2 &a) { // note: not const anymore!
 a.m ptr = nullptr;  // remove ownership from source
// Assignment operator with move semantics
Auto ptr2&
operator=(Auto_ptr2& a) { // note: not const anymore!
 if (&a == this)
   return *this;
 delete m ptr;  // deallocate ptr "this" already holds
 m ptr = a.m ptr; // transfer dumb pointer
 a.m ptr = nullptr; // remove ownership from source
 return *this;
```

Usage

```
class Resource {
  public:
    Resource() { std::cout << "Resource acquired\n"; }
    ~Resource() { std::cout << "Resource destroyed\n"; }
};</pre>
```

Usage

```
Ownership transferred
int main() {
                                                          res1 is null
 Auto ptr2<Resource> res1(new Resource);
                                                          res2 is not null
                                                          Resource destroyed
 Auto ptr2<Resource> res2; // Start as nullptr
  std::cout << "res1 is " << (res1.isNull() ? "null\n" : "not null\n");</pre>
  std::cout << "res2 is " << (res2.isNull() ? "null\n" : "not null\n");</pre>
  res2 = res1; // res2 assumes ownership, res1 is set to null
  std::cout << "Ownership transferred\n";</pre>
  std::cout << "res1 is " << (res1.isNull() ? "null\n" : "not null\n");</pre>
  std::cout << "res2 is " << (res2.isNull() ? "null\n" : "not null\n");</pre>
  return 0;
```

Output:

Resource acquired

res1 is not null

res2 is null


Auto-pointer 2

- Remaining problems:
 - std::auto_ptr is implemented exactly like this in the original C++98 standard
 - Problems occur if passed by value
 - Deprecated and to be fully removed since C++17
- General problems with move-semantics pre C++11:
 - Copy semantics and move semantics can't be differentiated
 - Overwriting copy-constructor leads to weird behavior
 - res1= res2 is unclear

Today's learning objectives

- Leading Example: Smart pointers
- Move semantics
- Lvalues and Rvalues
- Rvalue references
- Move construction and move assignment
- std::move
- Efficiency considerations

- Every expression has two properties
 - A type
 - A "value" property
 - Checks for example whether an expression can be assigned to
- Do not denote properties of values per se, but properties of expressions



- Historically:
 - Lvalues suitable for <u>left</u> side of assignment expression
 - Rvalues suitable for <u>right</u> side of assignment expression

Distinguish Lvalues and Rvalues

- Every expression either an Ivalue or an rvalue
 - Terms historical, now essentially arbitrary
- Lvalues:
 - Refer to objects accessible at more than one point in source code
 - Named objects + objects accessible via pointers/references (locator values)
 - General rule: If you can take its address, it's an Ivalue
 - Conceptual motivation: Lvalues may not be moved from
- Rvalues:
 - Everything that is not an Ivalue
 - Refer to objects accessible at exactly one point in source code
 - Conceptually: temporary objects, e.g., by-value function returns
 - Unnamed + pointers/references to them not possible
 - Conceptual motivation: Rvalues may be moved from

```
int x;
x = 10;
```

- **x** is Ivalue:
 - Named object, address can be taken
 - Could be referred to multiple times
- 10 is rvalue:
 - Can't take its address
 - All build-in numeric literals are rvalues

- sizeDiff,c1,c2 are lvalues:
 - Named objects, addresses can be taken
 - Could be referred to multiple times
- Return value is rvalue
 - Address can't be taken.
 - No way to get pointer/reference to it

```
int *px;
std::vector<int> v;
std::unordered_set<int> s;
...
*px = sizeDiff(v,s);
```


- *px is an Ivalue:
 - Address can be taken
 - Pointed-to object could be referred to multiple times
- sizeDiff(v,s) value is rvalue
 - Address can't be taken
 - No way to get pointer/reference to it


```
std::ifstream myinput( std::string("/some/path.txt") );
```

Anonymous objects are rvalues

Lvalues and Rvalues

- A way to think about it:
 - Expressions are boxes with a certain content
 - Content has a type and a (real) value
 - Content may be a literal, an object, the result of another expression
 - In order to refer to a box (e.g. to modify it), the box needs to have a name
 - Lvalues: boxes with names
 - Rvalues: boxes without names





Rvalues

- Have expression scope
 - They die at the end of an expression
- They are typically evaluated for their values
- Cannot be assigned to
 - Reason:
 - They are part of an expression
 - Assigning to them could change them before they have been used

Lvalues and Rvalues

Consider the following function

```
An Ivalue (object with name and address)
void printSomething( const std::string & str ) {
   std::cout << str << std::endl;
}</pre>
Special case: local const
```

and the following call

Special case: local const reference can be used to prolong the lifetime of temporary value and refers to it until the end of the containing scope (does not incur the cost of a copy-construction!)

```
printSomething( std::string("Hello") );
An rvalue!!
```

Today's learning objectives

- Leading Example: Smart pointers
- Move semantics
- Lvalues and Rvalues
- Rvalue references
- Move construction and move assignment
- std::move
- Efficiency considerations

C++11: Ivalue and rvalue references

- Lvalue references are just "normal" reference as known pre-C++11
- 2 types:

L-value reference	Can be initialized with	Can modify
Modifiable Lvalues	Yes	Yes
Non-modifiable Lvalues	No	No
R-values	No	No

C++11: Ivalue and rvalue references

- Lvalue references are just "normal" reference as known pre-C++11
- 2 types:

L-value reference to const	Can be initialized with	Can modify
Modifiable Lvalues	Yes	No
Non-modifiable Lvalues	Yes	No
R-values	Yes	No

C++11: Ivalue and rvalue references

- What is an rvalue reference?
 - As the name says: a reference to an r-value

- Initialization:
 - Use double ampersand

Again, 2 types

R-value reference	Can be initialized with	Can modify
Modifiable Lvalues	No	No
Non-modifiable Lvalues	No	No
R-values	Yes	Yes

Again, 2 types

R-value reference to const	Can be initialized with	Can modify
Modifiable Lvalues	No	No
Non-modifiable Lvalues	No	No
R-values	Yes	No

- Allow us to:
 - Extend the lifespan of the (rvalue) object they are initialized with by the lifespan of the Rvalue reference
 - Modify the Rvalue!

Example:

```
#include <iostream>
class Fraction {
private:
  int m numerator;
  int m denominator;
public:
  Fraction(int numerator = 0, int denominator = 1) :
    m numerator(numerator), m denominator(denominator) {}
  friend std::ostream& operator<<( std::ostream& out,
                                    const Fraction &f1 ) {
    out << f1.m numerator << "/" << f1.m denominator;</pre>
    return out;
};
```

Usage:

Output: 3/5

May hide creation of temporaries!

```
#include <iostream>
int main() {
  int &&rref = 5; // because we're initializing an
                   // r-value reference with a literal,
                   // a temporary with value 5 is
                   // created here
  rref = 10;
  std::cout << rref;</pre>
  return 0;
                                   Output: 10
```

Typically used as function parameters:

```
void fun(const int &lref) { // l-value args select this function
  std::cout << "l-value reference to const\n";</pre>
void fun(int &&rref) { // r-value arguments will select this function
  std::cout << "r-value reference\n";</pre>
int main() {
  int x = 5;
  fun(x); // 1-value argument calls 1-value version of function
  fun(5); // r-value argument calls r-value version of function
                                  I-value reference to const
  return 0;
                                  r-value reference
                                                                  50
```

- temporaries can be passed as a const Ivalue reference
- However: rvalue reference is considered a better match!
- Tricky:

```
int &&ref = 5;
fun(ref);
• Has type rvalue reference
• Is an Ivalue itself (it has a name)
```

Calls the Ivalue version!

Today's learning objectives

- Leading Example: Smart pointers
- Move semantics
- Lvalues and Rvalues
- Rvalue references
- Move construction and move assignment
- std::move
- Efficiency considerations

Back to our pointer example

- Auto_ptr2:
 - Overriding the default (shallow) copy constructor/ assignment operator to implement move semantics
 - Unsafe
 - Example: pass by value to another function
- Let's make Auto_ptr3:
 - Simply does deep copy everytime
 - Guaranteed safe

```
template<class T>
class Auto_ptr3 {
  T* m ptr;
 public:
 Auto ptr3(T* ptr = nullptr) : m ptr(ptr) {}
  ~Auto ptr3() { delete m ptr; }
  // Copy constructor: Do deep copy of a.m ptr to m ptr
 Auto ptr3(const Auto ptr3& a) {
    m ptr = new T;
    *m ptr = *a.m ptr;
```

Auto_ptr3 (continued)

```
// Copy assignment: Do deep copy of a.m ptr to m ptr
Auto ptr3& operator=(const Auto ptr3& a) {
  // Self-assignment detection
  if (&a == this)
    return *this;
  // Release any resource we're holding
  delete m ptr;
  // Copy the resource
  m ptr = new T;
  *m ptr = *a.m ptr;
  return *this;
T& operator*() const { return *m ptr; }
T* operator->() const { return m_ptr; }
bool isNull() const { return m ptr == nullptr; }
```

Using Auto_ptr3

```
Resource acquired
class Resource {
                                                          Resource destroyed
 public:
                                                          Resource destroyed
  Resource() { std::cout << "Resource acquired\n"; }</pre>
  ~Resource() { std::cout << "Resource destroyed\n"; }
};
Auto ptr3<Resource> generateResource() {
  Auto ptr3<Resource> res(new Resource);
  return res; // return value invokes copy constructor
int main() {
  Auto ptr3<Resource> mainres;
  mainres = generateResource(); // assign invokes copy assignment
  return 0;
                               Very inefficient!
                                  3 Resource allocations just to create an object
```

But at least it is safe!

Output:

Resource acquired Resource acquired Resource destroyed

Move construction/assignment

- Role
 - Move ownership from one object to another
 - Use instead of copying to gain efficiency

- How to define?
 - Somewhat similar to regular copy constructor/ assignment operator
 - **But:** Take non-const r-value reference instead of const l-value reference!

Beginning stays unchanged

```
#include <iostream>
template<class T>
class Auto ptr4 {
 T* m ptr;
public:
 Auto ptr4(T* ptr = nullptr) : m ptr(ptr) {}
  ~Auto ptr4() {
    delete m ptr;
```

Move constructor:

```
// Copy constructor: Do deep copy of a.m ptr to m ptr
Auto ptr4 (const Auto ptr4& a) {
  m ptr = new T;
                              Important:
  *m ptr = *a.m ptr;
                               Remove ownership

    Prevent a from destroying resource

    Prevent a from causing dangling pointers

   Move constructor: Transfer ownership of a.m_ptr to m_ptr
Auto ptr4(Auto ptr4&& a) : m ptr(a.m ptr) {
  a.m ptr = nullptr;
// Copy assignment: Do deep copy of a.m ptr to m ptr
Auto ptr4& operator=(const Auto ptr4& a) {
```

Move assignment operator

```
// Move assignment: Transfer ownership of a.m ptr to m ptr
Auto ptr4& operator=(Auto ptr4&& a) {
  // Self-assignment detection
  if (&a == this)
    return *this;
  // Release any resource we're holding
  delete m ptr;
  // Transfer ownership of a.m_ptr to m_ptr
  m ptr = a.m ptr;
                              Important:
  a.m ptr = nullptr;
                                 Remove ownership
                                 Prevent a from destroying resource
  return *this;
                                 Prevent a from causing dangling pointers
                                                              60
```

Auto_ptr4: Usage

Output: Resource acquired Resource destroyed

Move construction/assignment

- When?
 - When defined and argument is an r-value (literal, temporary)
 - Exception: Automatic I-values returned by value!
 - Special C++ specification
 - Makes sense: automatic l-values will be destroyed at end of function call anyway → just make r-values out of them!

- In most cases, they are not provided by default
 - > If you want them, you need to implement them

Move construction/assignment

- Key insights:
 - If an I-value is used:
 - Copying is the only reasonable alternative
 - Example: a = b; should make a (deep) copy, and not alter b

- If an r-value is used:
 - R-value is just a temporary about to be destroyed
 - It is reasonable to steal ownership and avoid copying! (which is more efficient)
 - Example: a = b + c;

Disable copy constructor/assignment

- In some cases they are undesirable
 - Example:
 - Auto_ptr4
 - Is move assigned/constructed if returned by another function
 - No need to copy, can be passed by value

```
// Copy constructor -- no copying allowed!
Auto_ptr4(const Auto_ptr4& a) = delete;

// Copy assignment -- no copying allowed!
Auto_ptr4& operator=(const Auto_ptr4& a) = delete;
...
```

Today's learning objectives

- Leading Example: Smart pointers
- Move semantics
- Lvalues and Rvalues
- Rvalue references
- Move construction and move assignment
- std::move
- Efficiency considerations

- Extension of move semantics to I-values!
- Example:

```
int main() {
 std::string x{ "abc" };
  std::string y{ "de" };
 std::cout << "x: " << x << '\n';
  std::cout << "y: " << y << '\n';
 swap(x, y);
  std::cout << "x: " << x << '\n';
  std::cout << "y: " << y << '\n';
 return 0;
```

```
Output:
x: abc
y: de
x: de
y: abc
y: abc
```

- Extension of move semantics to I-values!
- Example:

Involves 3 copies!

- Doing 3 copies is unnecessary
- Could be done with 3 moves instead!
- Solution: Cast the I-values to r-values
 - Done using std::move

```
#include <iostream>
#include <string>

template <class T>

void swap(T& a, T& b) {
   T tmp { std::move(a) }; // invokes move constructor
   a = std::move(b); // invokes move assignment
   b = std::move(tmp); // invokes move assignment
}
```

- However:
 - What happens to the original I-value!?
 - Let's do another Example/test

```
#include <iostream>
#include <string>
                                         Output:
#include <utility>
                                         Copying str
                                         str: Knock
#include <vector>
                                         vector: Knock
int main() {
                                         Moving str
  std::vector<std::string> v;
                                         str:
  std::string str = "Knock";
                                         vector: Knock Knock
  std::cout << "Copying str\n";</pre>
  v.push back(str); // calls 1-value version of push back
                     // which copies str to array
  std::cout << "str: " << str << '\n';
  std::cout << "vector: " << v[0] << '\n';
  std::cout << "\nMoving str\n";</pre>
  v.push back(std::move(str)); // calls r-value version
                                 // moving str into array
  std::cout << "str: " << str << '\n';
  std::cout << "vector:" << v[0] << ' ' << v[1] << '\n';
  return 0;
```

- What has happened to original I-value?
- It has changed!
 - Reset to null string
- This is good:
 - Objects that are being stolen from need to be left in a defined "null state"
 - They are not a temporary after all, and may be used again later!

Today's learning objectives

- Leading Example: Smart pointers
- Move semantics
- Lvalues and Rvalues
- Rvalue references
- Move construction and move assignment
- std::move
- Efficiency considerations

Consider the following example:

```
class MyInteger {
 public:
 MyInteger( int value ) : _value(value) {};
 virtual ~MyInteger() {};
 MyInteger operator+( const MyInteger & op ) const {
   return MyInteger( value + op. value );
private:
 int value;
};
int main() {
 MyInteger val1(2);
 MyInteger val2(3);
                                         How many copies are
 MyInteger sum = val1 + val2;
                                         being made?
  return 0;
```

Consider the following example:

```
class MyInteger {
     public:
      MyInteger((int value)): value(value) {};
      virtual ~MyInteger() {};
Return by value: 1 copy
   MyInteger operator+( const MyInteger & op ) const {
        return MyInteger( _value + op._value );
                          Pass by value: 2 copies
     private:
      int value;
    };
    int main() {
      MyInteger val1(2);
      MyInteger val2(3);
                                              How many copies are
      MyInteger sum = val1 + val2;
                                              made in worst case?
      return 0;
                     Copy-construction: 1 copy
```

- Why is this just a "worst-case"?
 - In reality, there is hardly any copy being done here!

- What is copy elision?
 - Copy elision happens if the compiler applies some optimization technique to bypass a copying process!

- Copy elision can and most likely will be applied in in several occasions in our example:
 - If passing a temporary by value (an rvalue), why copy it and not immediately use that temporary inside the function? It is up for destruction after the function call anyway!
 - If returning a temporary or even a locally initialized Ivalue from a function, why make a copy? Why not prevent destruction and immediately use that as the rvalue returned by the function?
 - This is called RVO (Return value optimization)
 - Compiler reserves space for that rvalue before function call

- Copy elision can and most likely will be applied in in several occasions in our example:
 - If initializing an object using the copy constructor and from a temporary that is up for destruction, the compiler may choose automatically to install move semantics

Why bother about move constructors etc.?

- RVO and copy elision will be done by the compiler automatically and only when it is sure to not alter the behavior of the code.
- With move constructors and move assignment operators, this behavior can be explicitly controlled.