

By OCamlPro

August 2, 2021

# Contents

1	Intr	roduction	3			
2	2 Overview					
3	Ger	neral Remarks	)			
	3.1	Readability	)			
		3.1.1 Typography	)			
		3.1.2 Naming of Errors	)			
	3.2	Security	L			
4	Con	ntract DEXClient 12	2			
	4.1	Contract Inheritance	2			
	4.2	Type Definitions	2			
		4.2.1 Struct Connector	2			
		4.2.2 Struct Callback	3			
		4.2.3 Struct Pair	3			
	4.3	Constant Definitions	1			
	4.4	Static Variable Definitions	1			
	4.5	Variable Definitions	5			
	4.6	Modifier Definitions	7			
		4.6.1 Modifier alwaysAccept	7			
		4.6.2 Modifier checkOwnerAndAccept	7			
	4.7	Constructor Definitions	7			
		4.7.1 Constructor	7			
	4.8	Public Method Definitions	3			
		4.8.1 Receive function	3			
		4.8.2 Function connectCallback	3			
		4.8.3 Function connectPair	)			
		4.8.4 Function connectRoot	)			
		4.8.5 Function createNewPair	)			
		4.8.6 Function getAllDataPreparation	L			
		4.8.7 Function getBalance	L			
		4.8.8 Function getCallback	2			
		4.8.9 Function getConnectorAddress	3			

		4.8.10 Function getPairData	3
		4.8.11 Function processLiquidity	4
		4.8.12 Function processSwapA	ŏ
		4.8.13 Function processSwapB	ŏ
		4.8.14 Function returnLiquidity	ô
		4.8.15 Function sendTokens	7
		4.8.16 Function setPair	7
		4.8.17 Function tokensReceivedCallback	3
	4.9	Internal Method Definitions	9
		4.9.1 Function computeConnectorAddress	9
		4.9.2 Function getFirstCallback	9
		4.9.3 Function getQuotient	0
		4.9.4 Function getRemainder	0
		4.9.5 Function is Ready	1
		4.9.6 Function isReadyToProvide	1
		4.9.7 Function this Balance	1
5		stract DEXConnector 33	
	5.1	Contract Inheritance	
	5.2	Constant Definitions	
	5.3	Static Variable Definitions	
	5.4	Variable Definitions	
	5.5	Modifier Definitions	
		5.5.1 Modifier alwaysAccept	
		5.5.2 Modifier checkOwnerAndAccept	
	5.6	Constructor Definitions	
		5.6.1 Constructor	
	5.7	Public Method Definitions	
		5.7.1 Receive function	
		5.7.2 Function burn	
		5.7.3 Function deployEmptyWallet	
		5.7.4 Function expectedWalletAddressCallback	
		5.7.5 Function getBalance	
		5.7.6 Function setBouncedCallback	
		5.7.7 Function setTransferCallback	9
		5.7.8 Function transfer	9
	5.8	Internal Method Definitions	
		5.8.1 Function getQuotient	0
		5.8.2 Function getRemainder	)
0	~	, DDVD	
6		stract DEXPair 41	
	6.1	Contract Inheritance	
	6.2	Type Definitions	
		6.2.1 Struct Connector	
	0.0	6.2.2 Struct Callback	
	6.3	Constant Definitions	2

6.4	Static Variable Definitions
6.5	Variable Definitions
6.6	Modifier Definitions
	6.6.1 Modifier alwaysAccept
	6.6.2 Modifier checkOwnerAndAccept 47
	6.6.3 Modifier checkPubKeyAndAccept 47
6.7	Constructor Definitions
	6.7.1 Constructor
6.8	Public Method Definitions
	6.8.1 Receive function
	6.8.2 Function burnCallback
	6.8.3 Function connect
	6.8.4 Function connectCallback
	6.8.5 Function getBalance
	6.8.6 Function getCallback
	6.8.7 Function getConnectorAddress 53
	6.8.8 Function tokensReceivedCallback 53
6.9	Internal Method Definitions
	6.9.1 Function acceptForProvide 59
	6.9.2 Function cleanProcessing 60
	6.9.3 Function computeConnectorAddress 60
	6.9.4 Function connectRoot 61
	6.9.5 Function getAmountOut 62
	6.9.6 Function getFirstCallback 62
	6.9.7 Function getQuotient
	6.9.8 Function getRemainder 63
	6.9.9 Function liquidity A
	6.9.10 Function liquidityB
	6.9.11 Function qtyAforB
	6.9.12 Function qtyBforA
	6.9.13 Function thisBalance
Cor	ntract DEXroot 66
7.1	Contract Inheritance
7.2	Type Definitions
	7.2.1 Struct Pair
7.3	Constant Definitions
7.4	
7.5	Variable Definitions
7.6	Modifier Definitions
	7.6.1 Modifier alwaysAccept 69
	7.6.2 Modifier checkOwnerAndAccept 69
	7.6.3 Modifier checkCreatorAndAccept 69
7.7	Constructor Definitions
	7.7.1 Constructor
7 2	Public Method Definitions 70

		7.8.1	Receive function	70
		7.8.2	Function checkPubKey	71
		7.8.3	Function createDEXclient	71
		7.8.4	Function createDEXpair	72
		7.8.5	Function getBalanceTONgrams	74
		7.8.6	Function getClientAddress	74
		7.8.7	Function getConnectorAddress	75
		7.8.8	Function getPairAddress	75
		7.8.9	Function getPairByRoots01	76
		7.8.10	Function getPairByRoots10	76
			Function getRootTokenAddress	77
		7.8.12	Function getRootsByPair	77
		7.8.13	Function sendTransfer	78
			Function setCreator	78
		7.8.15	Function setDEXclientCode	78
		7.8.16	Function setDEXconnectorCode	79
		7.8.17	Function setDEXpairCode	79
			Function setRootTokenCode	79
			Function setTONTokenWalletCode	80
	7.9	Interna	al Method Definitions	80
		7.9.1	Function computeClientAddress	80
		7.9.2	Function computeConnectorAddress	81
		7.9.3	Function computePairAddress	81
		7.9.4	$Function\ compute Root Token Address\ .\ .\ .\ .\ .\ .\ .$	82
8	Cor	ntract l	RootTokenContract	84
	8.1	Contra	act Inheritance	84
	8.2	Static	Variable Definitions	84
	8.3	Variab	ble Definitions	85
	8.4	Modifi	er Definitions	87
		8.4.1	Modifier onlyOwner	87
		8.4.2	Modifier onlyInternalOwner	87
	8.5	Consti	ructor Definitions	87
		8.5.1	Constructor	87
	8.6	Public	Method Definitions	88
		8.6.1	Fallback function	88
		8.6.2	OnBounce function	88
		8.6.3	Function deployEmptyWallet	89
		8.6.4	Function deployWallet	90
		8.6.5	Function getDetails	91
		8.6.6	Function getTotalSupply	92
		8.6.7	Function getVersion	92
		8.6.8	Function getWalletAddress	92
		8.6.9	Function getWalletCode	93
		8.6.10	Function mint	93
		0611	Function proxyBurn	94

		8.6.12 Function sendExpectedWalletAddress 95
		8.6.13 Function sendPausedCallbackTo 95
		8.6.14 Function sendSurplusGas
		8.6.15 Function setPaused
		8.6.16 Function tokensBurned
		8.6.17 Function transferOwner
	8.7	Internal Method Definitions
		8.7.1 Function getExpectedWalletAddress
		8.7.2 Function isExternalOwner
		8.7.3 Function isInternalOwner
		8.7.4 Function isOwner
9	Coı	ntract TONTokenWallet 101
	9.1	Contract Inheritance
	9.2	Static Variable Definitions
	9.3	Variable Definitions
	9.4	Modifier Definitions
		9.4.1 Modifier onlyRoot
		9.4.2 Modifier onlyOwner
		9.4.3 Modifier onlyInternalOwner
	9.5	Constructor Definitions
		9.5.1 Constructor
	9.6	Public Method Definitions
		9.6.1 Fallback function
		9.6.2 OnBounce function
		9.6.3 Function accept
		9.6.4 Function allowance
		9.6.5 Function approve
		9.6.6 Function balance
		9.6.7 Function burnByOwner
		9.6.8 Function burnByRoot
		9.6.9 Function destroy
		9.6.10 Function disapprove
		9.6.11 Function getDetails
		9.6.12 Function getVersion
		9.6.13 Function getWalletCode
		9.6.14 Function internalTransfer
		9.6.15 Function internalTransferFrom
		9.6.16 Function setBouncedCallback
		9.6.17 Function setReceiveCallback
		9.6.18 Function transfer
		9.6.19 Function transferFrom
	0.7	9.6.20 Function transferToRecipient
	9.7	Internal Method Definitions
		9.7.1 Function getExpectedAddress

# Table of Issues

Minor issue: Typography of static variables	.0
Minor issue: Typography of global variables	0
Minor issue: Typography of internal function	0
Minor issue: Naming of Errors	0
Critical issue: No Accept All Methods	.1
Critical issue: No Require after Accept	.1

# To edit this document

In the report.tex file, choose:

- \soldraftfalse to remove draft mode (watermarks, advises)
- \solmodulestrue to display modules by chapter instead of contracts
- $\bullet$  \soltable strue to display tables for parameters and returns
- \solissuesfalse to remove the table of issues

Issues can be entered with:

- $\bullet \ \backslash issueCritical\{title\}\{text\}$
- $\sin {title}{text}$
- $\insue Minor{title}{text}$

## Introduction

The present document is an official submission to the  $13^{th}$  contest of the ForMet sub-governance: 13 Radiance-DEX Phase 0 Formal Verification https://formet.gov.freeton.org/proposal?isGlobal=false&proposalAddress=0%3A07783c48e8789fa1163699e9e3071a4

The specification was: The contestants shall provide the informal audit of the central Radiance-DEX smart contracts (DEXClient, DEXConnector, DEXPair, DEXRoot RootTokenContract, TONTokenWallet), hereinafter referred to as "smart contracts". where the detailed description of the "informal audit" is described below. All debot contracts are excluded from the present contest.

and All the source codes must be provided by the authors via https://t.
me/joinchat/-3zDgM62gQ020GUy Telegram group. The code to be audited has
a hash 7d65f0d3b85e504ac33f01395b6ba0ffef9d5fe5 (branch main, link - https:
//github.com/radianceteam/dex2/commit/7d65f0d3b85e504ac33f01395b6ba0ffef9d5fe5)

and finally Contestants shall submit a document in PDF format that covers:

- All the errors found
- All the warnings found
- All the "bad code" (long functions, violation of abstraction levels, poor readability etc.)

Errors and warnings should be submitted to the developers as early as possible, during the contest, so that the code can be fixed immediately.

# Overview

The infrastructure is composed of a set of DEX specific contracts, associated with tokens contracts (developed by Broxus, to the best of our knownledge).

The DEX contracts are:

**DEXRoot:** The "root" contract, used to perform global operations, such as creating "client" contracts;

**DEXClient:** The contract with which a user may interact with the system.

**DEXPair:** The contract associated with a given pair of tokens (root token contracts)

**DEXConnector:** A simplified interface to interact with token contracts. The goal is probably to be able to interact with different implementations/interfaces of token contracts.

The token contracts are:

**RootTokenContract:** The root token contract, shared by all the wallet contracts for a given token;

**TONTokenWallet:** The wallet contract, containing the balance associated either with a public key or (exclusive) a contract address;

Compared to https://github.com/broxus/broxus/ton-eth-bridge-token-contracts/, the two token contracts have only been modified to change the ton-solidity pragma version.

All the DEX contracts use a static souINT field to be able to instanciate several ones for a given public key or other static field.

## General Remarks

In this chapter, we introduce some general remarks about the code, that are not specific to this project, but whose occurrences have been found in the project in several locations.

## 3.1 Readability

### 3.1.1 Typography

#### Minor issue: Typography of static variables

A good coding convention is to use typography to visually discriminate static variables from other variables, for example using a prefix such as  $s_{-}$ .

This issue was found everywhere in the code of DEX and token contracts.

#### Minor issue: Typography of global variables

A good coding convention is to use typography to visually discriminate global variables from local variables, for example using a prefix such as  $m_{-}$  or  $g_{-}$ .

This issue was found everywhere in the code of DEX and token contracts.

#### Minor issue: Typography of internal function

A good coding convention is to use typography to visually discriminate public functions and internal functions, for example using a prefix such as \_.

This issue was found everywhere in the code of DEX and token contracts.

## 3.1.2 Naming of Errors

#### Minor issue: Naming of Errors

A good coding convention is to define constants instead of using direct numbers for errors in require().

This issue was found everywhere in the code of DEX contracts, but not for token contracts.

## 3.2 Security

#### Critical issue: No Accept All Methods

Public methods using tvm.accept() without any prior check should not exist. Indeed, such methods could be used by attackers to drain the balance of the contracts, even with minor amounts but unlimited number of messages.

This issue was found in the code the DEX contracts, especially with the alwaysAccept() modifier. Methods using this modifier should check the origin of the message and limit tvm.accept() to either the user or known contracts.

#### Critical issue: No Require after Accept

Methods using twm.accept() should never use require() after the accept. Indeed, a require() failing after twm.accept() will cost a huge amount of gas, as all shards will execute the failing method.

This issue was found in the code of the DEX contracts. Methods should always keep calls to require() before twm.accept(), and if it is not possible, should not fail but should *return* an error code instead.

# Contract DEXClient

In file DEXClient.sol

## 4.1 Contract Inheritance

ITokensReceivedCallback	
IDEXClient	
IDEXConnect	

## 4.2 Type Definitions

#### Advise

Check that types have the correct integer types (Pubkey: uint256, Amount: uint128, Time: uint64).

#### 4.2.1 Struct Connector

root_address	address	
souint	uint256	
status	bool	

```
29    struct Connector {
30        address root_address;
31        uint256 souint;
32        bool status;
33    }
```

#### 4.2.2 Struct Callback

token_wallet	address	
token_root	address	
amount	uint128	
sender_public_key	uint256	
sender_address	address	
sender_wallet	address	
original_gas_to	address	
updated_balance	uint128	
payload_arg0	uint8	
payload_arg1	address	
payload_arg2	address	

```
struct Callback {
43
44
      address token_wallet;
45
      address token_root;
46
      uint128 amount;
      uint256 sender_public_key;
47
48
      address sender_address;
49
      address sender_wallet;
50
       address original_gas_to;
51
       uint128 updated_balance;
       uint8 payload_arg0;
52
     address payload_arg1;
      address payload_arg2;
54
   }
55
```

#### 4.2.3 Struct Pair

status	bool	
rootA	address	
walletA	address	
rootB	address	
walletB	address	
rootAB	address	

```
60 struct Pair {
61 bool status;
62 address rootA;
63 address walletA;
64 address rootB;
65 address walletB;
66 address rootAB;
67 }
```

## 4.3 Constant Definitions

#### Advises

Use a naming convention to distinguish constants from other, such as all uppercase names.

Use ton unit instead of nanotons for cost constants to avoid numbers with too many zeroes.

uint128	GRAMS_CONNECT_PAIR	Initialized to 500000000
uint128	GRAMS_SET_CALLBACK_ADDR	Initialized to 100000000
uint128	GRAMS_SWAP	Initialized to 500000000
uint128	GRAMS_PROCESS_LIQUIDITY	Initialized to 500000000
uint128	GRAMS_RETURN_LIQUIDITY	Initialized to 500000000

```
uint128 constant GRAMS_CONNECT_PAIR = 500000000;

uint128 constant GRAMS_SET_CALLBACK_ADDR = 100000000;

uint128 constant GRAMS_SWAP = 500000000;

uint128 constant GRAMS_PROCESS_LIQUIDITY = 500000000;

uint128 constant GRAMS_RETURN_LIQUIDITY = 500000000;
```

## 4.4 Static Variable Definitions

#### Advises

Use a naming convention to distinguish static variables from global variables, such as  $s_-$  prefix.

address	rootDEX			
		used	in	@1.DEX-
		Client.cr	eateNewPa	ir
		used	in	@1.DEX-
		Client.cr	eateNewPa	ir
		used	in	@1.DEX-
		Client.:ce	onstructor	
uint256	soUINT			
TvmCell	codeDEXConnector			
		used	in	@1.DEX-
		Client.co	nnectRoot	
		used	in	@1.DEX-
		Client.computeConnectorAddress		

```
18 address static public rootDEX;

19 uint256 static public soUINT;

20 TvmCell static public codeDEXConnector;
```

## 4.5 Variable Definitions

### Advises

Use a naming convention to distinguish global variables from local variables, such as  $g_-$  or  $m_-$  prefix.

address []	rootKeys	
		used in @1.DEX-
		Client.getAllDataPreparation
		used in @1.DEX-
		Client.connectCallback
mapping (address => address)	rootWallet	
		used in @1.DEX-
		Client.sendTokens
		used in @1.DEX-
		Client.returnLiquidity
		used in @1.DEX-
		Client.returnLiquidity
		used in @1.DEX-
		Client.processSwapB
		used in @1.DEX-
		Client.processSwapA
		used in @1.DEX-
		Client.processLiquidity used in @1.DEX-
		Client.processLiquidity used in @1.DEX-
		Client.isReadyToProvide
		used in @1.DEX-
		Client.isReadyToProvide
		used in @1.DEX-
		Client.isReadyToProvide
		used in @1.DEXClient.isReady
		used in @1.DEXClient.isReady
		used in @1.DEX-
		Client.connectRoot
		assigned in @1.DEX-
		Client.connectCallback
		used in @1.DEX-
		Client.connectCallback
mapping (address => address)	rootConnector	
		used in @1.DEX-
		Client.sendTokens
		used in @1.DEX-
		Client.sendTokens
		used in @1.DEX-
		Client.returnLiquidity
		used in @1.DEX-
		Client.returnLiquidity
		used in @1.DEX-
		Client.processSwapB
		used in @1.DEX-
	16	Client.processSwapA
	10	used in @1.DEX-
		Client.processLiquidity
		used in @1.DEX-
		Client.processLiquidity used in @1.DEX-
		Client.isReadyToProvide used in @1.DEX-
		Client.isReadyToProvide

```
address[] public rootKeys;

mapping (address => address) public rootWallet;

mapping (address => address) public rootConnector;

mapping (address => Connector) connectors;

uint public counterCallback;

mapping (uint => Callback) callbacks;

mapping(address => Pair) public pairs;

address[] public pairKeys;
```

#### 4.6 Modifier Definitions

#### Advises

Calling tvm.accept() without checking pubkey should not be allowed

#### 4.6.1 Modifier alwaysAccept

```
73 modifier alwaysAccept {
74    tvm.accept();
75    _;
76 }
```

#### 4.6.2 Modifier checkOwnerAndAccept

```
79  modifier checkOwnerAndAccept {
80    require(msg.pubkey() == tvm.pubkey(), 102);
81    tvm.accept();
82    _;
83  }
```

#### 4.7 Constructor Definitions

#### 4.7.1 Constructor

#### Advises

Check who can call the constructor. If the constructor sets global values, only legitimate users should be allowed.

Check that every argument is protected by a require().

If external users are allowed, their pubkey should be verified (require(msg.pubkey() != 0 && msg.pubkey() == tvm.pubkey(),100) , and tvm.accept() should be called.

```
85    constructor() public {
86     require(msg.sender == rootDEX, 103);
87     tvm.accept();
88     counterCallback = 0;
89    }
```

### 4.8 Public Method Definitions

#### 4.8.1 Receive function

```
413 receive() external {
414 }
```

#### 4.8.2 Function connectCallback

Parameters		
address	wallet	
Modifiers		
alwaysAccept	no args	

```
181
      function connectCallback(address wallet) public override
          alwaysAccept {
182
        address connector = msg.sender;
183
        if (connectors.exists(connector)) {
          Connector cc = connectors[connector];
184
185
          rootKeys.push(cc.root_address);
186
          rootWallet[cc.root_address] = wallet;
187
          rootConnector[cc.root_address] = connector;
          TvmCell bodySTC = tvm.encodeBody(IDEXConnector(connector).
188
               setTransferCallback);
189
          {\tt connector.transfer(\{value:~\tt GRAMS\_SET\_CALLBACK\_ADDR~,~bounce:}
              true, flag: 0, body:bodySTC});
          TvmCell bodySBC = tvm.encodeBody(IDEXConnector(connector).
190
              setBouncedCallback);
191
          connector.transfer({value: GRAMS_SET_CALLBACK_ADDR, bounce:
              true, flag: 0, body:bodySBC});
          cc.status = true;
192
193
          connectors[connector] = cc;
194
195
```

#### 4.8.3 Function connectPair

Parameters		
address	pairAddr	
Returns		
bool	statusConnection	
Modifiers		
checkOwnerAndAccept	no args	

```
function connectPair(address pairAddr) public checkOwnerAndAccept
92
            returns (bool statusConnection) {
93
        statusConnection = false;
94
        if (!pairs.exists(pairAddr)){
          Pair cp = pairs[pairAddr];
cp.status = false;
95
96
97
          pairs[pairAddr] = cp;
98
          pairKeys.push(pairAddr);
99
           TvmCell body = tvm.encodeBody(IDEXPair(pairAddr).connect);
100
           pairAddr.transfer({value:GRAMS_CONNECT_PAIR, body:body});
101
          statusConnection = true;
102
      }
103
```

#### 4.8.4 Function connectRoot

Parameters		
address	root	
uint256	souint	
uint128	gramsToConnector	
uint128	gramsToRoot	
Returns		
bool	statusConnected	
Modifiers		
checkOwnerAndAccept	no args	

```
161
          TvmCell stateInit = tvm.buildStateInit({
162
             contr: DEXConnector,
            varInit: { soUINT: souint, dexclient: address(this) },
163
164
            code: codeDEXConnector,
165
            pubkey: tvm.pubkey()
166
          });
167
          TvmCell init = tvm.encodeBody(DEXConnector);
          address connector = tvm.deploy(stateInit, init,
168
               gramsToConnector, address(this).wid);
169
          Connector cr = connectors[connector];
170
          cr.root_address = root;
171
          cr.souint = souint;
172
          cr.status = false;
           connectors[connector] = cr;
173
174
          TvmCell body = tvm.encodeBody(IDEXConnector(connector).
               deployEmptyWallet, root);
175
           \verb|connector.transfer({value:gramsToRoot, bounce:true, body:body}|\\
              });
176
           statusConnected = true;
177
        }
178
      }
```

#### 4.8.5 Function createNewPair

Parameters		
address	root0	
address	root1	
uint256	pairSoArg	
uint256	connectorSoArg0	
uint256	connectorSoArg1	
uint256	rootSoArg	
bytes	rootName	
bytes	rootSymbol	
uint8	rootDecimals	
uint128	grammsForPair	
uint128	grammsForRoot	
uint128	grammsForConnector	
uint128	grammsForWallet	
uint128	grammsTotal	
Modifiers		
checkOwnerAndAccept	no args	

```
356 function createNewPair(
357 address root0,
358 address root1,
```

```
359
         uint256 pairSoArg,
360
         uint256 connectorSoArg0,
        uint256 connectorSoArg1,
361
362
         uint256 rootSoArg,
363
         bytes rootName,
364
         bytes rootSymbol,
         uint8 rootDecimals,
365
366
        uint128 grammsForPair,
367
         uint128 grammsForRoot,
368
         uint128 grammsForConnector,
369
         uint128 grammsForWallet,
370
        uint128 grammsTotal
371
      ) public view checkOwnerAndAccept {
         require (!(grammsTotal < (grammsForPair+2*grammsForConnector+2*</pre>
372
             grammsForWallet+grammsForRoot)) && !(grammsTotal < 5 ton)</pre>
             ,106);
373
        require (!(address(this).balance < grammsTotal),105);</pre>
374
         TvmCell body = tvm.encodeBody(IDEXRoot(rootDEX).createDEXpair,
             root0,root1,pairSoArg,connectorSoArg0,connectorSoArg1,
             rootSoArg,rootName,rootSymbol,rootDecimals,grammsForPair,
             grammsForRoot,grammsForConnector,grammsForWallet);
375
         rootDEX.transfer({value:grammsTotal, bounce:false, flag: 1,
             body:body});
376
```

#### 4.8.6 Function getAllDataPreparation

Returns		
address []	pairKeysR	
address []	rootKeysR	
Modifiers		
alwaysAccept	no args	

#### 4.8.7 Function getBalance

Returns		
uint128	no name	

```
351 function getBalance() public pure responsible returns (uint128) {
352    return { value: 0, bounce: false, flag: 64 } thisBalance();
353 }
```

### 4.8.8 Function getCallback

Parameters		
uint256	id	
Returns		
address	token_wallet	
address	token_root	
uint128	amount	
uint256	sender_public_key	
address	sender_address	
address	sender_wallet	
address	original_gas_to	
uint128	updated_balance	
uint8	payload_arg0	
address	payload_arg1	
address	payload_arg2	
Modifiers		
checkOwnerAndAccept	no args	

```
318
      function getCallback(uint id) public view checkOwnerAndAccept
          returns (
319
        address token_wallet,
320
        address token_root,
321
        uint128 amount,
322
        uint256 sender_public_key,
        address sender_address,
323
324
        address sender_wallet,
325
        address original_gas_to,
326
        uint128 updated_balance,
327
        uint8 payload_arg0,
328
        address payload_arg1,
329
        address payload_arg2
330
331
        Callback cc = callbacks[id];
332
        token_wallet = cc.token_wallet;
333
        token_root = cc.token_root;
334
        amount = cc.amount;
335
         sender_public_key = cc.sender_public_key;
336
         sender_address = cc.sender_address;
337
         sender_wallet = cc.sender_wallet;
338
        original_gas_to = cc.original_gas_to;
```

```
339     updated_balance = cc.updated_balance;
340     payload_arg0 = cc.payload_arg0;
341     payload_arg1 = cc.payload_arg1;
342     payload_arg2 = cc.payload_arg2;
343 }
```

## 4.8.9 Function getConnectorAddress

Parameters		
uint256	connectorSoArg	
Returns		
address	no name	

## 4.8.10 Function getPairData

Parameters		
address	pairAddr	
Returns		
bool	pairStatus	
address	pairRootA	
address	pairWalletA	
address	pairRootB	
address	pairWalletB	
address	pairRootAB	
address	curPair	
Modifiers		
alwaysAccept	no args	

```
379    function getPairData(address pairAddr) public view alwaysAccept
    returns (
380    bool pairStatus,
381    address pairRootA,
```

```
382
        address pairWalletA,
383
         address pairRootB,
384
        address pairWalletB,
385
         address pairRootAB,
386
        address curPair
387
      ) {
388
        Pair cp = pairs[pairAddr];
389
        pairStatus = cp.status;
390
        pairRootA = cp.rootA;
391
        pairWalletA = cp.walletA;
        pairRootB = cp.rootB;
392
        pairWalletB = cp.walletB;
393
394
        pairRootAB = cp.rootAB;
395
         curPair = pairAddr;
396
```

#### 4.8.11 Function processLiquidity

Parameters		
address	pairAddr	
uint128	qtyA	
uint128	qtyB	
Returns		
bool	processLiquidityStatus	
Modifiers		
checkOwnerAndAccept	no args	

```
251
      function processLiquidity(address pairAddr, uint128 qtyA, uint128
           qtyB) public view checkOwnerAndAccept returns (bool
          processLiquidityStatus) {
252
        processLiquidityStatus = false;
253
        if (isReadyToProvide(pairAddr)) {
254
          Pair cp = pairs[pairAddr];
255
          address connectorA = rootConnector[cp.rootA];
256
          address connectorB = rootConnector[cp.rootB];
257
          TvmBuilder builderA;
258
          builderA.store(uint8(2), address(this), rootWallet[cp.rootAB
              ]);
259
          TvmCell payloadA = builderA.toCell();
260
          TvmBuilder builderB;
261
          builderB.store(uint8(2), address(this), rootWallet[cp.rootAB
              ]);
262
          TvmCell payloadB = builderB.toCell();
263
          TvmCell bodyA = tvm.encodeBody(IDEXConnector(connectorA).
              transfer, cp.walletA, qtyA, payloadA);
          TvmCell bodyB = tvm.encodeBody(IDEXConnector(connectorB).
264
              transfer, cp.walletB, qtyB, payloadB);
```

## 4.8.12 Function processSwapA

Parameters		
address	pairAddr	
uint128	qtyA	
Returns		
bool	processSwapStatus	
Modifiers		
checkOwnerAndAccept	no args	

```
221
      function processSwapA(address pairAddr, uint128 qtyA) public view
           {\tt checkOwnerAndAccept\ returns\ (bool\ processSwapStatus)\ \{}
222
        processSwapStatus = false;
223
        if (isReady(pairAddr)) {
224
          Pair cp = pairs[pairAddr];
225
          address connector = rootConnector[cp.rootA];
226
          TvmBuilder builder;
227
          builder.store(uint8(1), cp.rootB, rootWallet[cp.rootB]);
          TvmCell payload = builder.toCell();
228
229
          TvmCell body = tvm.encodeBody(IDEXConnector(connector).
              230
          connector.transfer({value: GRAMS_SWAP, bounce:true, body:body
             });
231
          processSwapStatus = true;
232
233
```

#### 4.8.13 Function processSwapB

Parameters		
address	pairAddr	
uint128	qtyB	
Returns		
bool	processSwapStatus	
Modifiers		
checkOwnerAndAccept	no args	

```
236
      function processSwapB(address pairAddr, uint128 qtyB) public view
            checkOwnerAndAccept returns (bool processSwapStatus) {
237
         processSwapStatus = false;
238
         if (isReady(pairAddr)) {
239
           Pair cp = pairs[pairAddr];
240
           address connector = rootConnector[cp.rootB];
241
           TvmBuilder builder;
242
           builder.store(uint8(1), cp.rootA, rootWallet[cp.rootA]);
243
           TvmCell payload = builder.toCell();
244
           TvmCell body = tvm.encodeBody(IDEXConnector(connector).
           transfer, cp.walletB, qtyB, payload);
connector.transfer({value: GRAMS_SWAP, bounce:true, body:body
245
               });
246
           processSwapStatus = true;
247
248
```

#### 4.8.14 Function returnLiquidity

Parameters		
address	pairAddr	
uint128	tokens	
Returns		
bool	returnLiquidityStatus	
Modifiers		
checkOwnerAndAccept	no args	

```
function returnLiquidity(address pairAddr, uint128 tokens) public
272
           view checkOwnerAndAccept returns (bool returnLiquidityStatus
          ) {
273
        returnLiquidityStatus = false;
274
        if (isReadyToProvide(pairAddr)) {
275
        Pair cp = pairs[pairAddr];
276
        TvmBuilder builder;
277
         builder.store(uint8(3), rootWallet[cp.rootA], rootWallet[cp.
            rootB]);
278
        TvmCell callback_payload = builder.toCell();
        TvmCell body = tvm.encodeBody(IDEXConnector(rootConnector[cp.
279
            rootAB]).burn, tokens, pairAddr, callback_payload);
280
         rootConnector[cp.rootAB].<mark>transfer({value:GRAMS_RETURN_LIQUIDITY</mark>
             , body:body});
281
         returnLiquidityStatus = true;
282
283
```

#### 4.8.15 Function sendTokens

Parameters		
address	tokenRoot	
address	to	
uint128	tokens	
uint128	grams	
Returns		
bool	sendTokenStatus	
Modifiers		
checkOwnerAndAccept	no args	

```
399
    function sendTokens(address tokenRoot, address to, uint128 tokens
          , uint128 grams) public checkOwnerAndAccept view returns (
          bool sendTokenStatus) {
400
        sendTokenStatus = false;
        if (rootConnector[tokenRoot] != address(0)) {
401
          address connector = rootConnector[tokenRoot];
402
403
          TvmBuilder builder;
          builder.store(uint8(4), address(this), rootWallet[tokenRoot])
404
          TvmCell payload = builder.toCell();
405
          TvmCell body = tvm.encodeBody(IDEXConnector(connector).
406
              transfer, to, tokens, payload);
407
          connector.transfer({value: grams, bounce:true, body:body});
408
          sendTokenStatus = true;
409
410
      }
```

#### 4.8.16 Function setPair

Parameters		
address	arg0	
address	arg1	
address	arg2	
address	arg3	
address	arg4	
Modifiers	•	
alwaysAccept	no args	

```
127
      function setPair(address arg0, address arg1, address arg2,
          address arg3, address arg4) public alwaysAccept override {
        address dexpair = msg.sender;
128
129
        if (pairs.exists(dexpair)){
130
          Pair cp = pairs[dexpair];
131
          cp.status = true;
          cp.rootA = arg0;
132
          cp.walletA = arg1;
133
134
          cp.rootB = arg2;
135
          cp.walletB = arg3;
          cp.rootAB = arg4;
136
137
          pairs[dexpair] = cp;
138
139
      }
```

#### 4.8.17 Function tokensReceivedCallback

Parameters		
address	token_wallet	
address	token_root	
uint128	amount	
uint256	sender_public_key	
address	sender_address	
address	sender_wallet	
address	original_gas_to	
uint128	updated_balance	
TvmCell	payload	
Modifiers		
alwaysAccept	no args	

```
286
    function tokensReceivedCallback(
287
        address token_wallet,
        address token_root,
288
289
        uint128 amount,
290
        uint256 sender_public_key,
291
        address sender_address,
292
        address sender_wallet,
        address original_gas_to,
293
        uint128 updated_balance,
294
295
        TvmCell payload
296
      ) public override alwaysAccept {
297
        Callback cc = callbacks[counterCallback];
298
        cc.token_wallet = token_wallet;
        cc.token_root = token_root;
299
300
        cc.amount = amount;
301
        cc.sender_public_key = sender_public_key;
302
        cc.sender_address = sender_address;
```

```
303
        cc.sender_wallet = sender_wallet;
304
        cc.original_gas_to = original_gas_to;
        cc.updated_balance = updated_balance;
305
306
        TvmSlice slice = payload.toSlice();
        (uint8 arg0, address arg1, address arg2) = slice.decode(uint8,
307
            address, address);
308
        cc.payload_arg0 = arg0;
309
        cc.payload_arg1 = arg1;
310
        cc.payload_arg2 = arg2;
311
        callbacks[counterCallback] = cc;
312
        counterCallback++;
        if (counterCallback > 10){delete callbacks[getFirstCallback()
313
314
```

## 4.9 Internal Method Definitions

## 4.9.1 Function computeConnectorAddress

Parameters		
uint256 souint		
Returns		
address	no name	

```
function computeConnectorAddress(uint256 souint) private inline
142
          view returns (address) {
143
        TvmCell stateInit = tvm.buildStateInit({
          contr: DEXConnector,
144
          varInit: { soUINT: souint, dexclient: address(this) },
145
          code: codeDEXConnector,
146
147
          pubkey: tvm.pubkey()
148
        });
149
        return address(tvm.hash(stateInit));
150
```

#### 4.9.2 Function getFirstCallback

Returns		
uint256	no name	

```
function getFirstCallback() private view returns (uint) {
  optional(uint, Callback) rc = callbacks.min();
  if (rc.hasValue()) {(uint number, ) = rc.get();return number;}
    else {return 0;}
}
```

## 4.9.3 Function getQuotient

Parameters		
uint128	arg0	
uint128	arg1	
uint128	arg2	
Returns		
uint128	no name	

```
function getQuotient(uint128 arg0, uint128 arg1, uint128 arg2)
    private inline pure returns (uint128) {
    (uint128 quotient, ) = math.muldivmod(arg0, arg1, arg2);
    return quotient;
}
```

### 4.9.4 Function getRemainder

Paramet	ers	
uint128	arg0	
uint128	arg1	
uint128	arg2	
Returns		
uint128	no name	

```
function getRemainder(uint128 arg0, uint128 arg1, uint128 arg2)
    private inline pure returns (uint128) {
    (, uint128 remainder) = math.muldivmod(arg0, arg1, arg2);
    return remainder;
}
```

#### 4.9.5 Function is Ready

Paramet	ers	
address	pair	
Returns		
bool	no name	

```
function isReady(address pair) private inline view returns (bool)
{

Pair cp = pairs[pair];

Connector ccA = connectors[rootConnector[cp.rootA]];

Connector ccB = connectors[rootConnector[cp.rootB]];

return cp.status && rootWallet.exists(cp.rootA) && rootWallet.

exists(cp.rootB) && rootConnector.exists(cp.rootA) &&

rootConnector.exists(cp.rootB) && ccA.status && ccB.status;

}
```

### 4.9.6 Function is Ready To Provide

Paramet	ers	
address	pair	
Returns		
bool	no name	

```
function isReadyToProvide(address pair) private inline view
returns (bool) {

Pair cp = pairs[pair];

Connector ccA = connectors[rootConnector[cp.rootA]];

Connector ccB = connectors[rootConnector[cp.rootB]];

return cp.status && rootWallet.exists(cp.rootA) && rootWallet.
exists(cp.rootB) && rootWallet.exists(cp.rootAB) &&
rootConnector.exists(cp.rootA) && rootConnector.exists(cp.
rootB) && ccA.status && ccB.status;

}
```

#### 4.9.7 Function this Balance

Returns		
uint128	no name	

```
function thisBalance() private inline pure returns (uint128) {
return address(this).balance;
}
```

# Contract DEXConnector

In file DEXConnector.sol

### 5.1 Contract Inheritance

I Expected Wall et Address Callback	
IDEXConnector	

### 5.2 Constant Definitions

#### Advises

Use a naming convention to distinguish constants from other, such as all uppercase names.

Use ton unit instead of nanotons for cost constants to avoid numbers with too many zeroes.

uint128	GRAMS_TO_ROOT	Initialized to 500000000
uint128	GRAMS_TO_NEW_WALLET	Initialized to 250000000

19 uint128 constant GRAMS\_TO\_ROOT = 500000000;

20 uint128 constant GRAMS\_TO\_NEW\_WALLET = 250000000;

## 5.3 Static Variable Definitions

#### Advises

Use a naming convention to distinguish static variables from global variables, such as  $s_-$  prefix.

uint256	soUINT		
address	dexclient		
		used in @2.DEXConnec-	
		tor.transfer	
		used in @2.DEXConnec-	
		tor.transfer	
		used in @2.DEXConnec-	
		tor.setTransferCallback	
		used in @2.DEXConnec-	
		tor.setTransferCallback	
		used in @2.DEXConnec-	
		tor.setBouncedCallback	
		used in @2.DEXConnec-	
		tor.setBouncedCallback	
		used in @2.DEXConnec-	
		tor. expected Wallet Address Callback	
		used in @2.DEXConnec-	
		tor. expected Wallet Address Callback	
		used in @2.DEXConnec-	
		tor.deployEmptyWallet	
		used in @2.DEXConnec-	
		tor.deployEmptyWallet	
		used in @2.DEXConnec-	
		tor.deployEmptyWallet	
		used in @2.DEXConnec-	
		tor.deployEmptyWallet	
		used in @2.DEXConnector.burn	
		used in @2.DEXConnector.burn	

```
15   uint256   static public soUINT;
16   address static public dexclient;
```

## 5.4 Variable Definitions

#### Advises

Use a naming convention to distinguish global variables from local variables, such as  ${\tt g\_}$  or  ${\tt m\_}$  prefix.

address	drivenRoot	
		used in @2.DEXConnec-
		tor.expectedWalletAddressCallback
		assigned in @2.DEXConnec-
		tor.deployEmptyWallet
		used in @2.DEXConnec-
		tor.deployEmptyWallet
address	driven	
		used in @2.DEXConnec-
		tor.transfer
		used in @2.DEXConnec-
		tor.transfer
		used in @2.DEXConnec-
		tor.setTransferCallback
		used in @2.DEXConnec-
		tor.setTransferCallback
		used in @2.DEXConnec-
		tor.setBouncedCallback
		used in @2.DEXConnec-
		tor.setBouncedCallback
		assigned in @2.DEXConnec-
		tor. expected Wallet Address Callback
		used in @2.DEXConnec-
		tor. expected Wallet Address Callback
		used in @2.DEXConnector.burn
		used in @2.DEXConnector.burn
bool	statusConnected	
		assigned in @2.DEXConnec-
		tor. expected Wallet Address Callback
		used in @2.DEXConnec-
		tor. expected Wallet Address Callback
		used in @2.DEXConnec-
		tor.deployEmptyWallet
		assigned in @2.DEXConnec-
		tor.:constructor
		used in @2.DEXConnec-
		tor.:constructor

- 22 address public drivenRoot;
- 23 address public driven;
- 24 bool public statusConnected;

# 5.5 Modifier Definitions

#### Advises

Calling tvm.accept() without checking pubkey should not be allowed

# 5.5.1 Modifier alwaysAccept

```
27  modifier alwaysAccept {
28    tvm.accept();
29    _;
30 }
```

# ${\bf 5.5.2}\quad {\bf Modifier\ checkOwnerAndAccept}$

```
32  modifier checkOwnerAndAccept {
33     // Check that message from contract owner.
34     require(msg.sender == dexclient, 101);
35     tvm.accept();
36     _;
37  }
```

## 5.6 Constructor Definitions

#### 5.6.1 Constructor

#### Advises

Check who can call the constructor. If the constructor sets global values, only legitimate users should be allowed.

Check that every argument is protected by a require().

If external users are allowed, their pubkey should be verified (require(msg.pubkey() != 0 && msg.pubkey() == tvm.pubkey(),100) , and tvm.accept() should be called.

```
Modifiers
checkOwnerAndAccept no args
```

```
39    constructor() public checkOwnerAndAccept {
40       statusConnected = false;
41    }
```

# 5.7 Public Method Definitions

## 5.7.1 Receive function

```
129 receive() external {
130 }
```

## 5.7.2 Function burn

Paramet	ers	
uint128	tokens	
address	callback_address	
TvmCell	callback_payload	

# 5.7.3 Function deployEmptyWallet

```
Parameters
address root
```

```
function deployEmptyWallet(address root) public override {
   require(msg.sender == dexclient, 101);
   require(!(msg.value < GRAMS_TO_ROOT * 2), 103);
   tvm.rawReserve(address(this).balance - msg.value, 2);
   if (!statusConnected) {
        drivenRoot = root;
   }
}</pre>
```

```
TvmCell bodyD = tvm.encodeBody(IRootTokenContract(root).
              deployEmptyWallet, GRAMS_TO_NEW_WALLET, 0, address(this),
              dexclient);
67
         root.transfer({value:GRAMS_TO_ROOT, bounce:true, body:bodyD})
68
         TvmCell bodyA = tvm.encodeBody(IRootTokenContract(root).
             sendExpectedWalletAddress, 0, address(this), address(this
             ));
69
         root.transfer({value:GRAMS_TO_ROOT, bounce:true, body:bodyA})
70
         dexclient.transfer({value: 0, bounce:true, flag: 128});
71
       } else {
72
         dexclient.transfer({value: 0, bounce:true, flag: 128});
73
       }
74
     }
```

## 5.7.4 Function expectedWalletAddressCallback

Paramet	ers	
address	wallet	
uint256	wallet_public_key	
address	owner_address	

```
function expectedWalletAddressCallback(address wallet, uint256
         wallet_public_key, address owner_address) public override {
       require(msg.sender == drivenRoot && wallet_public_key == 0 &&
78
           owner_address == address(this), 102);
       tvm.rawReserve(address(this).balance - msg.value, 2);
79
80
       statusConnected = true;
81
       driven = wallet;
       TvmCell body = tvm.encodeBody(IDEXConnect(dexclient).
82
           connectCallback, wallet);
83
       dexclient.transfer({value: 0, bounce:true, flag: 128, body:body
           });
     }
84
```

## 5.7.5 Function getBalance

Returns		
uint128	balance	
Modifiers	•	
checkOwnerAndAccept	no args	

```
function getBalance() public pure checkOwnerAndAccept returns (
          uint128 balance){
    balance = address(this).balance;
}
```

## 5.7.6 Function setBouncedCallback

```
95  function setBouncedCallback() public override {
96    require(msg.sender == dexclient, 101);
97    tvm.rawReserve(address(this).balance - msg.value, 2);
98    TvmCell body = tvm.encodeBody(ITONTokenWallet(driven).
        setBouncedCallback, dexclient);
99    driven.transfer({value: 0, bounce:true, flag: 128, body:body});
100  }
```

#### 5.7.7 Function setTransferCallback

#### 5.7.8 Function transfer

Paramet	ers	
address	to	
uint128	tokens	
TvmCell	payload	

```
function transfer(address to, uint128 tokens, TvmCell payload)
    public override {
    require(msg.sender == dexclient, 101);
    tvm.rawReserve(address(this).balance - msg.value, 2);
```

# 5.8 Internal Method Definitions

# 5.8.1 Function getQuotient

Paramet	ers	
uint128	arg0	
uint128	arg1	
uint128	arg2	
Returns		
uint128	no name	

# 5.8.2 Function getRemainder

Paramet	ers	
uint128	arg0	
uint128	arg1	
uint128	arg2	
Returns		
uint128	no name	

# Chapter 6

# Contract DEXPair

In file DEXPair.sol

# 6.1 Contract Inheritance

IDEXPair	
IDEXConnect	
ITokensReceivedCallback	
IBurnTokensCallback	

# 6.2 Type Definitions

#### Advises

Check that types have the correct integer types (Pubkey: uint256, Amount: uint128, Time: uint64).

## 6.2.1 Struct Connector

$root\_address$	address	
souint	uint256	
status	bool	

```
37 struct Connector {
38 address root_address;
39 uint256 souint;
40 bool status;
41 }
```

## 6.2.2 Struct Callback

token_wallet	address	
token_root	address	
amount	uint128	
sender_public_key	uint256	
sender_address	address	
sender_wallet	address	
original_gas_to	address	
updated_balance	uint128	
payload_arg0	uint8	
payload_arg1	address	
payload_arg2	address	

```
struct Callback {
48
49
      address token_wallet;
50
       address token_root;
51
       uint128 amount;
       uint256 sender_public_key;
52
53
       address sender_address;
54
       address sender_wallet;
       address original_gas_to;
55
       uint128 updated_balance;
57
       uint8 payload_arg0;
       address payload_arg1;
58
59
       address payload_arg2;
   }
60
```

# 6.3 Constant Definitions

## Advises

Use a naming convention to distinguish constants from other, such as all uppercase names.

Use ton unit instead of nanotons for cost constants to avoid numbers with too many zeroes.

uint128	GRAMS_SET_CALLBACK_ADDR	Initialized to 500000000
uint128	GRAMS_SEND_UNUSED_RETURN	Initialized to 100000000
uint128	GRAMS_MINT	Initialized to 50000000
uint128	GRAMS_RETURN	Initialized to 200000000

# 6.4 Static Variable Definitions

# Advises

Use a naming convention to distinguish static variables from global variables, such as  $s_-$  prefix.

address	rootDEX	
uint256	soUINT	
address	creator	
TvmCell	codeDEXConnector	
		used in @3.DEX-
		Pair.connectRoot
		used in @3.DEX-
		Pair.computeConnectorAddress
address	rootA	
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX- Pair.tokensReceivedCallback
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback
		used in @3.DEX-
		Pair.tokensReceivedCallback

```
19 address static public rootDEX;

20 uint256 static public soUINT;

21 address static public creator;

22 TvmCell static public codeDEXConnector;

23 address static public rootA;

24 address static public rootB;

25 address static public rootAB;
```

# 6.5 Variable Definitions

## Advises

Use a naming convention to distinguish global variables from local variables, such as  ${\tt g\_}$  or  ${\tt m\_}$  prefix.

mapping (address => address)	walletReserve	
, , , , , , , , , , , , , , , , , , ,		used in @3.DEX
		Pair.tokensReceivedCallback
		used in @3.DEX
		Pair.tokensReceivedCallback
		assigned in @3.DEX
		Pair.connectCallback
		used in @3.DEX
		Pair.connectCallback
		used in @3.DEXPair.connect
		used in @3.DEXPair.connect
mapping (address $=>$ bool)	syncStatus	
		assigned in @3.DEX
		Pair.tokensReceivedCallback
		used in @3.DEX
		Pair.tokensReceivedCallback
		assigned in @3.DEX
		Pair.tokensReceivedCallback
		used in @3.DEX
		Pair.tokensReceivedCallback
		assigned in @3.DEX
		Pair.connectCallback
		used in @3.DEX
		Pair.connectCallback
mapping (address $=> uint128$ )	balanceReserve	
		assigned in @3.DEX
		Pair.tokensReceivedCallback
		used in @3.DEX
		Pair.tokensReceivedCallback
		assigned in @3.DEX
		Pair.tokensReceivedCallback
		used in @3.DEX
		Pair.tokensReceivedCallback
		assigned in @3.DEX Pair.tokensReceivedCallback
		Pair.tokensReceivedCallback assigned in @3.DEX
		e e e e e e e e e e e e e e e e e e e
		Pair.tokensReceivedCallback used in @3.DEX
		⊥ usea — m
		Pair.tokensReceivedCallback
		Pair.tokensReceivedCallback used in @3.DEX
		Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback
		Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback used in @3.DEX
		Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback
		Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback used in @3.DEX used in @3.DEX
46		Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback Pair.tokensReceivedCallback
46		Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback assigned in @3.DEX
46		Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback assigned in @3.DEX Pair.tokensReceivedCallback
46		Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback used in @3.DEX Pair.tokensReceivedCallback assigned in @3.DEX

assigned in @3.DEX
Pair.tokensReceivedCallback
used in @3.DEX

Pair.tokensReceivedCallback

```
mapping(address => address) public walletReserve;
mapping(address => bool) public syncStatus;
mapping(address => uint128) public balanceReserve;

uint128 public totalSupply;

mapping(address => mapping(address => bool)) public processingStatus;

mapping(address => mapping(address => uint128)) public processingData;

mapping(address => mapping(address => address)) public processingDest;

mapping (address => address) public rootConnector;

mapping (address => connector) public connectors;

uint public counterCallback;

mapping (uint => Callback) callbacks;
```

# 6.6 Modifier Definitions

#### Advises

Calling tvm.accept() without checking pubkey should not be allowed

## 6.6.1 Modifier alwaysAccept

```
71 modifier alwaysAccept {
72 tvm.accept();
73 _;
74 }
```

## 6.6.2 Modifier checkOwnerAndAccept

```
76  modifier checkOwnerAndAccept {
77   require(msg.sender == rootDEX, 102);
78   tvm.accept();
79   _;
80  }
```

# 6.6.3 Modifier checkPubKeyAndAccept

```
82  modifier checkPubKeyAndAccept {
83    require(msg.pubkey() == tvm.pubkey(), 103);
84    tvm.accept();
85    _;
86  }
```

# 6.7 Constructor Definitions

## 6.7.1 Constructor

#### Advises

Check who can call the constructor. If the constructor sets global values, only legitimate users should be allowed.

Check that every argument is protected by a require().

If external users are allowed, their pubkey should be verified (require(msg.pubkey() != 0 && msg.pubkey() == tvm.pubkey(),100) , and tvm.accept() should be called.

Parameters		
uint256	souintA	
uint256	souintB	
uint128	gramsDeployConnector	
uint128	gramsDeployWallet	
Modifiers		
checkOwnerAndAccept	no args	

```
88 constructor(uint256 souintA, uint256 souintB, uint128
    gramsDeployConnector, uint128 gramsDeployWallet) public
    checkOwnerAndAccept {
    counterCallback = 0;
    connectRoot(rootA, souintA, gramsDeployConnector,
        gramsDeployWallet);
    connectRoot(rootB, souintB, gramsDeployConnector,
        gramsDeployWallet);
    souintB, gramsDeployConnector,
    gramsDeployWallet);
}
```

# 6.8 Public Method Definitions

## 6.8.1 Receive function

```
609 receive() external {
610 }
```

## 6.8.2 Function burnCallback

Parameters		
uint128	tokens	
TvmCell	payload	
uint256	sender_public_key	
address	sender_address	
address	wallet_address	
address	send_gas_to	
Modifiers		
alwaysAccept	no args	

```
522 function burnCallback(
523
    uint128 tokens,
524
      TvmCell payload,
525
     uint256 sender_public_key,
    address sender_address,
526
527
     address wallet_address,
528
     address send_gas_to
529 ) public override alwaysAccept {
      if (msg.sender == rootAB) {
530
531
        tvm.rawReserve(address(this).balance - msg.value, 2);
532
        TvmSlice slice = payload.toSlice();
        (uint8 arg0, address arg1, address arg2) = slice.decode(uint8,
533
            address, address);
534
        counterCallback++;
        Callback cc = callbacks[counterCallback];
535
536
        cc.token_wallet = wallet_address;
537
        cc.token_root = msg.sender;
538
        cc.amount = tokens;
539
        cc.sender_public_key = sender_public_key;
        cc.sender_address = sender_address;
540
541
        cc.sender_wallet = wallet_address;
542
        cc.original_gas_to = address(0);
543
     cc.updated_balance = 0;
```

```
544
        cc.payload_arg0 = arg0;
545
         cc.payload_arg1 = arg1;
        cc.payload_arg2 = arg2;
546
547
        callbacks[counterCallback] = cc;
        if (arg0 == 3 && arg1 != address(0) && arg2 != address(0)) {
548
549
          uint128 returnA = math.muldiv(balanceReserve[rootA], tokens,
               totalSupply);
550
          uint128 returnB = math.muldiv(balanceReserve[rootB], tokens,
               totalSupply);
551
          if (!(returnA > balanceReserve[rootA]) && !(returnB >
               balanceReserve[rootB])) {
552
             totalSupply -= tokens;
553
             balanceReserve[rootA] -= returnA;
554
             balanceReserve[rootB] -= returnB;
555
             TvmBuilder builder;
556
             builder.store(uint8(6), address(0), address(0));
557
             TvmCell new_payload = builder.toCell();
             TvmCell bodyA = tvm.encodeBody(IDEXConnector(rootConnector[
558
                 rootA]).transfer, arg1, returnA, new_payload);
559
             TvmCell bodyB = tvm.encodeBody(IDEXConnector(rootConnector[
                 rootB]).transfer, arg2, returnB, new_payload);
             rootConnector[rootA].transfer({value: GRAMS_RETURN, bounce:
560
                 true, body:bodyA});
561
             rootConnector[rootB].transfer({value: GRAMS_RETURN, bounce:
                 true, body:bodyB});
562
             if (counterCallback > 10){delete callbacks[getFirstCallback
                 ()];}
             send_gas_to.transfer({value: 0, bounce:true, flag: 128});
563
          }
564
565
          if (counterCallback > 10) {delete callbacks[getFirstCallback()
566
        }
567
        if (counterCallback > 10){delete callbacks[getFirstCallback()
            1:}
      }
568
569
    }
```

#### 6.8.3 Function connect

## 6.8.4 Function connectCallback

Parameters		
address	wallet	
Modifiers		
alwaysAccept	no args	

```
132
    function connectCallback(address wallet) public override
          alwaysAccept {
        address connector = msg.sender;
133
134
        if (connectors.exists(connector)) {
          Connector cr = connectors[connector];
135
136
          walletReserve[cr.root_address] = wallet;
137
          syncStatus[cr.root_address] = true;
          rootConnector[cr.root_address] = connector;
138
139
          TvmCell bodySTC = tvm.encodeBody(IDEXConnector(connector).
              setTransferCallback);
140
          connector.transfer({value: GRAMS_SET_CALLBACK_ADDR, bounce:
              true, flag: 0, body:bodySTC});
141
          TvmCell bodySBC = tvm.encodeBody(IDEXConnector(connector).
              setBouncedCallback);
142
          connector.transfer({value: GRAMS_SET_CALLBACK_ADDR, bounce:
              true, flag: 0, body:bodySBC});
          cr.status = true;
143
144
          connectors[connector] = cr;
145
        }
146
      }
```

## 6.8.5 Function getBalance

Returns		
uint128	no name	

```
function getBalance() public pure responsible returns (uint128) {
   return { value: 0, bounce: false, flag: 64 } thisBalance();
   606 }
```

## 6.8.6 Function getCallback

Parameters		
uint256	id	
Returns		
address	token_wallet	
address	token_root	
uint128	amount	
uint256	sender_public_key	
address	sender_address	
address	sender_wallet	
address	original_gas_to	
uint128	updated_balance	
uint8	payload_arg0	
address	payload_arg1	
address	payload_arg2	
Modifiers		
checkPubKeyAndAccept	no args	

```
571 function getCallback(uint id) public view checkPubKeyAndAccept
        returns (
      address token_wallet,
    address token_root,
    uint128 amount,
574
575
      uint256 sender_public_key,
576
      address sender_address,
577
      address sender_wallet,
578
      address original_gas_to,
579
      uint128 updated_balance,
580
      uint8 payload_arg0,
581
      address payload_arg1,
      address payload_arg2
582
583 ) {
584
      Callback cc = callbacks[id];
585
      token_wallet = cc.token_wallet;
      token_root = cc.token_root;
586
      amount = cc.amount;
587
588
      sender_public_key = cc.sender_public_key;
589
      sender_address = cc.sender_address;
590
      sender_wallet = cc.sender_wallet;
591
      original_gas_to = cc.original_gas_to;
      updated_balance = cc.updated_balance;
593
      payload_arg0 = cc.payload_arg0;
594
      payload_arg1 = cc.payload_arg1;
595
      payload_arg2 = cc.payload_arg2;
596 }
```

# 6.8.7 Function getConnectorAddress

Paramet	ers	
uint256	connectorSoArg	
Returns		
address	no name	

## 6.8.8 Function tokensReceivedCallback

Parameters		
address	token_wallet	
address	token_root	
uint128	amount	
uint256	sender_public_key	
address	sender_address	
address	sender_wallet	
address	original_gas_to	
uint128	updated_balance	
TvmCell	payload	
Modifiers		
alwaysAccept	no args	

```
248
    function tokensReceivedCallback(
249
        address token_wallet,
250
        address token_root,
251
        uint128 amount,
252
        uint256 sender_public_key,
253
        address sender_address,
254
        address sender_wallet,
255
        address original_gas_to,
256
        uint128 updated_balance,
257
        TvmCell payload
    ) public override alwaysAccept {
258
```

```
259
        if (msg.sender == walletReserve[rootA] || msg.sender ==
            walletReserve[rootB]) {
260
          if (counterCallback > 10) {
261
            Callback cc = callbacks[counterCallback];
            cc.token_wallet = token_wallet;
262
263
            cc.token_root = token_root;
264
            cc.amount = amount;
265
            cc.sender_public_key = sender_public_key;
266
            cc.sender_address = sender_address;
267
            cc.sender_wallet = sender_wallet;
268
            cc.original_gas_to = original_gas_to;
269
            cc.updated_balance = updated_balance;
270
            TvmSlice slice = payload.toSlice();
271
            (uint8 arg0, address arg1, address arg2) = slice.decode(
                uint8, address, address);
272
            cc.payload_arg0 = arg0;
273
            cc.payload_arg1 = arg1;
274
            cc.payload_arg2 = arg2;
275
            callbacks[counterCallback] = cc;
276
            counterCallback++;
277
            delete callbacks[getFirstCallback()];
278
            if (arg0 == 1) {
279
               tvm.rawReserve(address(this).balance - msg.value, 2);
280
               uint128 amountOut = getAmountOut(amount, token_root, arg1
281
               if (!(amountOut > balanceReserve[arg1])){
282
                balanceReserve[token_root] += amount;
283
                 balanceReserve[arg1] -= amountOut;
284
                 syncStatus[token_root] = balanceReserve[token_root] ==
                     updated_balance ? true : false;
285
                 TvmBuilder builder;
286
                 builder.store(uint8(0), address(0), address(0));
287
                 TvmCell new_payload = builder.toCell();
288
                 TvmCell body = tvm.encodeBody(IDEXConnector(
                     rootConnector[arg1]).transfer, arg2, amountOut,
                     new_payload);
289
                 rootConnector[arg1].transfer({value: 0, bounce:true,
                     flag: 128, body:body});
290
              } else {
291
                 TvmBuilder builder;
292
                 builder.store(uint8(8), address(0), address(0));
293
                 TvmCell new_payload = builder.toCell();
294
                 TvmCell body = tvm.encodeBody(IDEXConnector(
                     rootConnector[token_root]).transfer, token_wallet,
                     amount, new_payload);
295
                 rootConnector[token_root].transfer({value: 0, bounce:
                     true, flag: 128, body:body});
              }
296
297
298
            if (arg0 == 2) {
299
               tvm.rawReserve(address(this).balance - msg.value, 2);
300
              processingStatus[token_root][arg1] = true;
301
               processingData[token_root][arg1] += amount;
302
              processingDest[token_root][arg1] = sender_wallet;
               if (processingStatus[rootA][arg1] == true &&
303
                   processingStatus[rootB][arg1] == true) {
304
                 uint128 amountA = processingData[rootA][arg1];
```

```
305
                 uint128 amountB = processingData[rootB][arg1];
306
                 if (totalSupply == 0 && balanceReserve[rootA] == 0 &&
                     balanceReserve[rootB] == 0) {
307
                   uint128 liquidity = math.min(amountA, amountB);
308
                   balanceReserve[rootA] += amountA;
309
                   balanceReserve[rootB] += amountB;
310
                   totalSupply += liquidity;
311
                   TvmCell body = tvm.encodeBody(IRootTokenContract(
                       rootAB).mint, liquidity, arg2);
312
                   rootAB.transfer({value: GRAMS_MINT, bounce:true, body
                       :body});
313
                   cleanProcessing(arg1);
314
                   arg1.transfer({ value: 0, flag: 128});
315
                 } else {
316
                   (uint128 provideA, uint128 provideB) =
                       acceptForProvide(amountA, amountB);
317
                   if (provideA > 0 && provideB > 0) {
318
                     uint128 liquidity = math.min(liquidityA(provideA),
                         liquidityB(provideB));
                     uint128 unusedReturnA = amountA - provideA;
319
320
                     uint128 unusedReturnB = amountB - provideB;
                     balanceReserve[rootA] += provideA;
321
                     balanceReserve[rootB] += provideB;
322
323
                     totalSupply += liquidity;
324
                     TvmCell body = tvm.encodeBody(IRootTokenContract(
                         rootAB).mint, liquidity, arg2);
325
                     rootAB.transfer({value: GRAMS_MINT, bounce:true,
                         body:body});
326
                     if (unusedReturnA > 0 && unusedReturnB > 0) {
327
                       TvmBuilder builder;
328
                       builder.store(uint8(7), address(0), address(0));
                       TvmCell new_payload = builder.toCell();
329
330
                       TvmCell bodyA = tvm.encodeBody(IDEXConnector(
                           rootConnector[rootA]).transfer,
                           processingDest[rootA][arg1], unusedReturnA,
                           new_payload);
331
                       TvmCell bodyB = tvm.encodeBody(IDEXConnector(
                           rootConnector[rootB]).transfer,
                           processingDest[rootB][arg1], unusedReturnB,
                           new_payload);
332
                       rootConnector[rootA].transfer({value:
                           GRAMS_SEND_UNUSED_RETURN, bounce:true, body:
                           bodyA});
333
                       rootConnector[rootB].transfer({value:
                           GRAMS_SEND_UNUSED_RETURN, bounce:true, body:
                           bodyB});
334
                       cleanProcessing(arg1);
335
                       arg1.transfer({ value: 0, flag: 128});
336
                      else if (unusedReturnA > 0) {
337
                       TvmBuilder builder;
338
                       builder.store(uint8(7), address(0), address(0));
339
                       TvmCell new_payload = builder.toCell();
340
                       TvmCell bodyA = tvm.encodeBody(IDEXConnector(
                           rootConnector[rootA]).transfer,
                           processingDest[rootA][arg1], unusedReturnA,
                           new_payload);
```

```
341
                       rootConnector[rootA].transfer({value:
                           GRAMS_SEND_UNUSED_RETURN, bounce:true, body:
                           bodyA});
342
                       cleanProcessing(arg1);
                       arg1.transfer({ value: 0, flag: 128});
343
344
                     } else if (unusedReturnB > 0) {
345
                       TvmBuilder builder;
346
                       builder.store(uint8(7), address(0), address(0));
347
                       TvmCell new_payload = builder.toCell();
348
                       TvmCell bodyB = tvm.encodeBody(IDEXConnector(
                           rootConnector[rootB]).transfer,
                           processingDest[rootB][arg1], unusedReturnB,
                           new_payload);
349
                       rootConnector[rootB].transfer({value:
                           GRAMS_SEND_UNUSED_RETURN, bounce:true, body:
                           bodyB});
350
                       cleanProcessing(arg1);
351
                       arg1.transfer({ value: 0, flag: 128});
352
                     } else {
                       cleanProcessing(arg1);
353
354
                       arg1.transfer({ value: 0, flag: 128});
355
356
                   } else {
                     TvmBuilder builder;
357
358
                     builder.store(uint8(9), address(0), address(0));
359
                     TvmCell new_payload = builder.toCell();
360
                     TvmCell bodyA = tvm.encodeBody(IDEXConnector(
                         rootConnector[rootA]).transfer, processingDest[
                         rootA][arg1], amountA, new_payload);
361
                     TvmCell bodyB = tvm.encodeBody(IDEXConnector(
                         rootConnector[rootB]).transfer, processingDest[
                         rootB][arg1], amountB, new_payload);
362
                     rootConnector[rootA].transfer({value:
                         GRAMS_SEND_UNUSED_RETURN , bounce:true , body:
                         bodyA});
363
                     rootConnector[rootB].transfer({value:
                         GRAMS_SEND_UNUSED_RETURN, bounce:true, body:
                         bodyB});
                     cleanProcessing(arg1);
364
365
                     arg1.transfer({ value: 0, flag: 128});
366
367
368
               } else {
369
                 arg1.transfer({ value: 0, flag: 128});
370
               }
371
            }
372
          } else {
373
             Callback cc = callbacks[counterCallback];
374
             cc.token_wallet = token_wallet;
375
             cc.token_root = token_root;
376
             cc.amount = amount;
377
             cc.sender_public_key = sender_public_key;
378
             cc.sender_address = sender_address;
379
             cc.sender_wallet = sender_wallet;
380
             cc.original_gas_to = original_gas_to;
             cc.updated_balance = updated_balance;
381
382
             TvmSlice slice = payload.toSlice();
```

```
383
             (uint8 arg0, address arg1, address arg2) = slice.decode(
                 uint8, address, address);
384
            cc.payload_arg0 = arg0;
385
            cc.payload_arg1 = arg1;
386
            cc.payload_arg2 = arg2;
387
            callbacks[counterCallback] = cc;
388
             counterCallback++;
389
            if (arg0 == 1) {
390
               tvm.rawReserve(address(this).balance - msg.value, 2);
391
              uint128 amountOut = getAmountOut(amount, token_root, arg1
392
              if (!(amountOut > balanceReserve[arg1])){
393
                 balanceReserve[token_root] += amount;
394
                 balanceReserve[arg1] -= amountOut;
395
                 syncStatus[token_root] = balanceReserve[token_root] ==
                     updated_balance ? true : false;
                 TvmBuilder builder;
396
397
                 builder.store(uint8(0), address(0), address(0));
398
                 TvmCell new_payload = builder.toCell();
399
                 TvmCell body = tvm.encodeBody(IDEXConnector(
                     rootConnector[arg1]).transfer, arg2, amountOut,
                     new_payload);
400
                 rootConnector[arg1].transfer({value: 0, bounce:true,
                     flag: 128, body:body});
401
              } else {
402
                 TvmBuilder builder;
403
                 builder.store(uint8(8), address(0), address(0));
404
                 TvmCell new_payload = builder.toCell();
                 TvmCell body = tvm.encodeBody(IDEXConnector(
405
                     rootConnector[token_root]).transfer, token_wallet,
                     amount, new_payload);
406
                 rootConnector[token_root].transfer({value: 0, bounce:
                     true, flag: 128, body:body});
              }
407
            }
408
409
            if (arg0 == 2) {
410
              tvm.rawReserve(address(this).balance - msg.value, 2);
411
              processingStatus[token_root][arg1] = true;
412
              processingData[token_root][arg1] += amount;
413
              processingDest[token_root][arg1] = sender_wallet;
               if (processingStatus[rootA][arg1] == true &&
414
                   processingStatus[rootB][arg1] == true) {
415
                 uint128 amountA = processingData[rootA][arg1];
416
                 uint128 amountB = processingData[rootB][arg1];
417
                 if (totalSupply == 0 && balanceReserve[rootA] == 0 &&
                     balanceReserve[rootB] == 0) {
418
                   uint128 liquidity = math.min(amountA, amountB);
419
                   balanceReserve[rootA] += amountA;
420
                   balanceReserve[rootB] += amountB;
421
                   totalSupply += liquidity;
422
                   TvmCell body = tvm.encodeBody(IRootTokenContract(
                       rootAB).mint, liquidity, arg2);
423
                   rootAB.transfer({value: GRAMS_MINT, bounce:true, body
                       :body});
424
                   cleanProcessing(arg1);
425
                   arg1.transfer({ value: 0, flag: 128});
426
                 } else {
```

```
427
                   (uint128 provideA, uint128 provideB) =
                        acceptForProvide(amountA, amountB);
                   if (provideA > 0 && provideB > 0) {
428
429
                     uint128 liquidity = math.min(liquidityA(provideA),
                         liquidityB(provideB));
430
                     uint128 unusedReturnA = amountA - provideA;
uint128 unusedReturnB = amountB - provideB;
431
                     balanceReserve[rootA] += provideA;
432
433
                     balanceReserve[rootB] += provideB;
434
                     totalSupply += liquidity;
435
                     TvmCell body = tvm.encodeBody(IRootTokenContract(
                         rootAB).mint, liquidity, arg2);
                     rootAB.transfer({value: GRAMS_MINT, bounce:true,
436
                         body:body});
437
                     if (unusedReturnA > 0 && unusedReturnB > 0) {
438
                       TvmBuilder builder;
439
                       builder.store(uint8(7), address(0), address(0));
440
                       TvmCell new_payload = builder.toCell();
441
                       TvmCell bodyA = tvm.encodeBody(IDEXConnector(
                           rootConnector[rootA]).transfer,
                           processingDest[rootA][arg1], unusedReturnA,
                           new_payload);
442
                       TvmCell bodyB = tvm.encodeBody(IDEXConnector(
                           rootConnector[rootB]).transfer,
                           processingDest[rootB][arg1], unusedReturnB,
                           new_payload);
443
                       rootConnector[rootA].transfer({value:
                           GRAMS_SEND_UNUSED_RETURN, bounce:true, body:
                           bodyA});
444
                       rootConnector[rootB].transfer({value:
                           GRAMS_SEND_UNUSED_RETURN, bounce:true, body:
                           bodyB});
445
                       cleanProcessing(arg1);
                       arg1.transfer({ value: 0, flag: 128});
446
447
                     } else if (unusedReturnA > 0) {
448
                       TvmBuilder builder;
449
                       builder.store(uint8(7), address(0), address(0));
450
                       TvmCell new_payload = builder.toCell();
451
                       TvmCell bodyA = tvm.encodeBody(IDEXConnector(
                           rootConnector[rootA]).transfer,
                           processingDest[rootA][arg1], unusedReturnA,
                           new_payload);
452
                       rootConnector[rootA].transfer({value:
                           GRAMS_SEND_UNUSED_RETURN, bounce:true, body:
                           bodyA});
453
                       cleanProcessing(arg1);
454
                       arg1.transfer({ value: 0, flag: 128});
455
                     } else if (unusedReturnB > 0) {
456
                       TvmBuilder builder;
457
                       builder.store(uint8(7), address(0), address(0));
                       TvmCell new_payload = builder.toCell();
458
459
                       TvmCell bodyB = tvm.encodeBody(IDEXConnector(
                           rootConnector[rootB]).transfer,
                           processingDest[rootB][arg1], unusedReturnB,
                           new_payload);
460
                       rootConnector[rootB].transfer({value:
                           GRAMS_SEND_UNUSED_RETURN, bounce:true, body:
```

```
bodyB});
461
                       cleanProcessing(arg1);
                       arg1.transfer({ value: 0, flag: 128});
462
463
464
                       cleanProcessing(arg1);
465
                       arg1.transfer({ value: 0, flag: 128});
                     }
466
467
                   } else {
468
                     TvmBuilder builder;
469
                     builder.store(uint8(9), address(0), address(0));
470
                     TvmCell new_payload = builder.toCell();
471
                     TvmCell bodyA = tvm.encodeBody(IDEXConnector(
                         rootConnector[rootA]).transfer, processingDest[
                         rootA][arg1], amountA, new_payload);
472
                     TvmCell bodyB = tvm.encodeBody(IDEXConnector(
                         rootConnector[rootB]).transfer, processingDest[
                         rootB][arg1], amountB, new_payload);
473
                     rootConnector[rootA].transfer({value:
                         GRAMS_SEND_UNUSED_RETURN , bounce:true , body:
                         bodyA});
474
                     rootConnector[rootB].transfer({value:
                         GRAMS_SEND_UNUSED_RETURN , bounce:true , body:
                         bodyB});
475
                     cleanProcessing(arg1);
476
                     arg1.transfer({ value: 0, flag: 128});
                   }
477
478
                 }
479
               } else {
                 arg1.transfer({ value: 0, flag: 128});
480
481
482
            }
483
484
485
        }
486
```

# 6.9 Internal Method Definitions

## 6.9.1 Function acceptForProvide

Paramet	ers	
uint128	arg0	
uint128	arg1	
Returns		
uint128	no name	
uint128	no name	

```
214
      function acceptForProvide(uint128 arg0, uint128 arg1) private
          inline view returns (uint128, uint128) {
        require(balanceReserve[rootA] > 0 && balanceReserve[rootB] > 0,
215
             106);
216
        uint128 qtyB = qtyBforA(arg0);
217
        uint128 qtyA = qtyAforB(arg1);
218
        uint128 minAmountA = math.min(arg0, qtyA);
        uint128 minAmountB = math.min(arg1, qtyB);
219
220
        uint128 crmin = math.min(balanceReserve[rootA], balanceReserve[
            rootB]);
221
        uint128 crmax = math.max(balanceReserve[rootA], balanceReserve[
            rootB]);
        uint128 crquotient = getQuotient(crmin, crmax);
222
223
        uint128 crremainder = getRemainder(crmin, crmax);
224
        uint128 amountMin = math.min(minAmountA, minAmountB);
225
        uint128 amountOther = amountMin * crquotient + math.muldiv(
            amountMin,crremainder,crmin);
226
        uint128 acceptForProvideA = minAmountA < minAmountB ? amountMin</pre>
             : amountOther;
227
        uint128 acceptForProvideB = minAmountB < minAmountA ? amountMin</pre>
             : amountOther;
228
        return (acceptForProvideA, acceptForProvideB);
229
```

## 6.9.2 Function cleanProcessing

Paramet	ers	
address	dexclient	

```
function cleanProcessing(address dexclient) private inline {
    delete processingStatus[rootA][dexclient];
    delete processingStatus[rootB][dexclient];
    delete processingData[rootA][dexclient];
    delete processingData[rootB][dexclient];
    delete processingDest[rootA][dexclient];
    delete processingDest[rootB][dexclient];
    delete processingDest[rootB][dexclient];
}
```

## 6.9.3 Function computeConnectorAddress

Paramet	ers	
uint256 souint		
Returns		
address	no name	

```
95
      function computeConnectorAddress(uint256 souint) private inline
          view returns (address) {
96
        TvmCell stateInit = tvm.buildStateInit({
97
          contr: DEXConnector,
98
          varInit: { soUINT: souint, dexclient: address(this) },
99
          code: codeDEXConnector,
100
          pubkey: tvm.pubkey()
101
        });
102
        return address(tvm.hash(stateInit));
103
```

## 6.9.4 Function connectRoot

Parameters		
address	root	
uint256	souint	
uint128	gramsToConnector	
uint128	gramsToRoot	

```
function connectRoot(address root, uint256 souint, uint128
113
          gramsToConnector, uint128 gramsToRoot) private inline {
114
        TvmCell stateInit = tvm.buildStateInit({
115
          contr: DEXConnector,
          varInit: { soUINT: souint, dexclient: address(this) },
116
117
          code: codeDEXConnector,
118
          pubkey: tvm.pubkey()
119
        });
120
        TvmCell init = tvm.encodeBody(DEXConnector);
121
        address connector = tvm.deploy(stateInit, init,
            gramsToConnector, address(this).wid);
122
        Connector cr = connectors[connector];
123
        cr.root_address = root;
124
        cr.souint = souint;
125
        cr.status = false;
126
        connectors[connector] = cr;
127
        TvmCell body = tvm.encodeBody(IDEXConnector(connector).
            deployEmptyWallet, root);
128
        connector.transfer({value:gramsToRoot, bounce:true, body:body})
129
```

# 6.9.5 Function getAmountOut

Paramet	ers	
uint128	amountIn	
address	rootIn	
address	rootOut	
Returns		
uint128	no name	

```
function getAmountOut(uint128 amountIn, address rootIn, address
    rootOut) private inline view returns (uint128){
    uint128 amountInWithFee = math.muldiv(amountIn,997,1);
    uint128 numerator = math.muldiv(amountInWithFee, balanceReserve[
        rootOut],1);
    uint128 denominator = amountInWithFee + math.muldiv(
        balanceReserve[rootIn],1000,1);
    return math.muldiv(1,numerator,denominator);
}
```

# 6.9.6 Function getFirstCallback

Returns		
uint256	no name	

```
function getFirstCallback() private view returns (uint) {
  optional(uint, Callback) rc = callbacks.min();
  if (rc.hasValue()) {(uint number, ) = rc.get();return number;}
    else {return 0;}
}
```

# 6.9.7 Function getQuotient

Parameters		
uint128	min	
uint128	max	
Returns		
uint128	no name	

```
function getQuotient(uint128 min, uint128 max) private inline
    pure returns (uint128) {
    (uint128 quotient, ) = math.muldivmod(1, max, min);
    return quotient;
}
```

# 6.9.8 Function getRemainder

Parameters		
uint128	min	
uint128	max	
Returns		
uint128	no name	

```
function getRemainder(uint128 min, uint128 max) private inline
    pure returns (uint128) {
    (, uint128 remainder) = math.muldivmod(1, max, min);
    return remainder;
}
```

# 6.9.9 Function liquidityA

Parameters		
uint128	arg0	
Returns		
uint128	no name	

# 6.9.10 Function liquidityB

Parameters		
uint128	arg1	
Returns		
uint128	no name	

# 6.9.11 Function qtyAforB

Parameters		
uint128	arg1	
Returns		
uint128	no name	

# 6.9.12 Function qtyBforA

Parameters		
uint128	arg0	
Returns		
uint128	no name	

# 6.9.13 Function this Balance

Returns		
uint128	no name	

```
599 function thisBalance() private inline pure returns (uint128) {
600 return address(this).balance;
601 }
```

# Chapter 7

# Contract DEXroot

In file DEXRoot.sol

# 7.1 Contract Inheritance

IDEXRoot

# 7.2 Type Definitions

#### Advises

Check that types have the correct integer types (Pubkey: uint256, Amount: uint128, Time: uint64).

## 7.2.1 Struct Pair

root0	address	
root1	address	
rootLP	address	

```
24 struct Pair {
25 address root0;
26 address root1;
27 address rootLP;
28 }
```

# 7.3 Constant Definitions

## Advises

Use a naming convention to distinguish constants from other, such as all uppercase names.

Use ton unit instead of nanotons for cost constants to avoid numbers with too many zeroes.

uint128 | GRAMS\_CREATE\_DEX\_CLIENT | Initialized to 1 ton

uint128 constant public GRAMS\_CREATE\_DEX\_CLIENT = 1 ton;

# 7.4 Static Variable Definitions

#### Advises

Use a naming convention to distinguish static variables from global variables, such as  $s_-$  prefix.

uint256 soUINT

13 uint256 static public soUINT;

# 7.5 Variable Definitions

## Advises

Use a naming convention to distinguish global variables from local variables, such as  $g\_$  or  $m\_$  prefix.

TvmCell	codeDEXclient	
1 11110011	COUCLETACHOID	assigned in @-
		root.setDEXclientCode
		used in @
		root.setDEXclientCode
		used in @
		root.createDEXclient
		used in @4
		root.computeClientAddre
TvmCell	codeDEXpair	
	-	assigned in @4
		root.setDEXpairCode
		used in @4
		root.setDEXpairCode
		used in @4
		root.createDEXpair
		used in @4
		root.computePairAddress
TvmCell	codeDEXconnector	
		assigned in @4
		root.setDEXconnectorCo
		used in @4
		root.setDEXconnectorCo
		used in @4
		root.createDEXpair
		used in @4
		root.createDEXclient
		used in @4
		root.computePairAddress
		used in @4
		root.computeConnectorA
		used in @4
T. C. II	1.D. /T. '	root.computeClientAddre
TvmCell	codeRootToken	. 1
		assigned in @4
		root.setRootTokenCode
		used in @4
		root.setRootTokenCode
		used in @4
		root.createDEXpair used in @4
TvmCell	codeTONTokenWallet	root.computeRootTokenA
1 VIII OCII	code i On iokeli wallet	assigned in @4
		root.setTONTokenWallet
		used in @4
		root.setTONTokenWallet
68		used in @4
		root.createDEXpair
		used in @4
		root.computeRootTokenA
mapping (address => mapping (address => address))	roots	1000.computcitoot token
mapping (address –> mapping (address –> address))	10005	used in @.
		root.getPairByRoots10
		used in @4

```
TvmCell public codeDEXclient;
     TvmCell public codeDEXpair;
     TvmCell public codeDEXconnector;
17
     TvmCell public codeRootToken;
18
     TvmCell public codeTONTokenWallet;
19
21
     mapping(address => mapping(address => address)) roots;
     mapping(address => Pair) public pairs;
30
   address[] public pairKeys;
31
     mapping(uint256 => address) public pubkeys;
     mapping(address => uint256) public clients;
   address[] public clientKeys;
35
37
   mapping(address => uint128) public balanceOf;
   mapping(uint256 => address) public creators;
```

# 7.6 Modifier Definitions

# Advises Calling tvm.accept() without checking pubkey should not be allowed

# 7.6.1 Modifier alwaysAccept

```
45 modifier alwaysAccept {
46 tvm.accept();
47 _;
48 }
```

## 7.6.2 Modifier checkOwnerAndAccept

```
51  modifier checkOwnerAndAccept {
52   require(msg.pubkey() == tvm.pubkey(), 101);
53   tvm.accept();
54   _;
55  }
```

# 7.6.3 Modifier checkCreatorAndAccept

```
58  modifier checkCreatorAndAccept {
59    require(msg.pubkey() != 0, 103);
60    tvm.accept();
61    _;
62  }
```

# 7.7 Constructor Definitions

## 7.7.1 Constructor

#### Advises

Check who can call the constructor. If the constructor sets global values, only legitimate users should be allowed.

Check that every argument is protected by a require().

If external users are allowed, their pubkey should be verified (require(msg.pubkey() != 0 && msg.pubkey() == tvm.pubkey(),100) , and tvm.accept() should be called.

```
65    constructor()    public {
66        require(tvm.pubkey() == msg.pubkey(), 102);
67        tvm.accept();
68    }
```

# 7.8 Public Method Definitions

## 7.8.1 Receive function

```
76  receive() external {
77   balanceOf[msg.sender] += msg.value;
78  }
```

# 7.8.2 Function checkPubKey

Parameters		
uint256	pubkey	
Returns		
bool	status	
address	dexclient	
Modifiers		
alwaysAccept	no args	

```
328  function checkPubKey(uint256 pubkey) public view alwaysAccept
    returns (bool status, address dexclient) {
329    status = pubkeys.exists(pubkey);
330    dexclient = pubkeys[pubkey];
331 }
```

## 7.8.3 Function createDEXclient

Parameters		
uint256	pubkey	
uint256	souint	
Returns		
address	deployedAddress	
bool	statusCreate	
Modifiers		
alwaysAccept	no args	

```
122
      function createDEXclient(uint256 pubkey, uint256 souint) public
           alwaysAccept returns (address deployedAddress, bool
           statusCreate){
123
         statusCreate = false;
         deployedAddress = address(0);
uint128 prepay = balanceOf[creators[pubkey]];
124
125
         require (!pubkeys.exists(pubkey) && !(prepay <
126
             GRAMS_CREATE_DEX_CLIENT), 106);
127
         delete balanceOf[creators[pubkey]];
128
         TvmCell stateInit = tvm.buildStateInit({
129
           contr: DEXClient,
130
           varInit: {rootDEX:address(this),soUINT:souint,
               codeDEXConnector:codeDEXconnector},
```

```
131
           code: codeDEXclient,
132
           pubkey: pubkey
133
134
         deployedAddress = new DEXClient{
135
           stateInit: stateInit,
           flag: 0,
136
           bounce : false,
value : (prepay - 3100000)
137
138
139
         }();
140
         pubkeys[pubkey] = deployedAddress;
141
         clients[deployedAddress] = pubkey;
142
         clientKeys.push(deployedAddress);
143
         statusCreate = true;
144
```

# 7.8.4 Function createDEXpair

Paramet	ers	
address	root0	
address	root1	
uint256	pairSoArg	
uint256	connectorSoArg0	
uint256	connectorSoArg1	
uint256	rootSoArg	
bytes	rootName	
bytes	rootSymbol	
uint8	rootDecimals	
uint128	grammsForPair	
uint128	grammsForRoot	
uint128	grammsForConnector	
uint128	grammsForWallet	

```
237
    function createDEXpair(
238
        address root0,
239
        address root1,
240
        uint256 pairSoArg,
241
        uint256 connectorSoArg0,
        uint256 connectorSoArg1,
242
        uint256 rootSoArg,
243
244
        bytes rootName,
245
        bytes rootSymbol,
246
        uint8 rootDecimals,
247
        uint128 grammsForPair,
248
        uint128 grammsForRoot,
        uint128 grammsForConnector,
249
        uint128 grammsForWallet
```

```
251
      ) public override {
252
         require(root0 != address(0) && root1 != address(0) ,104);
         require(!(grammsForPair < 500000000) && !(grammsForRoot <
253
             500000000) && !(grammsForConnector < 500000000) && !(
             grammsForWallet < 500000000),105);</pre>
254
         tvm.rawReserve(address(this).balance - msg.value, 2);
         uint128 grammsNeeded = grammsForPair + (2 * grammsForConnector)
255
              + (2 * grammsForWallet) + grammsForRoot;
256
         if (clients.exists(msg.sender) && !(msg.value < grammsNeeded)</pre>
             && !(root0 == root1) && !roots[root0].exists(root1) && !
             roots[root1].exists(root0)) {
257
           TvmCell stateInitR = tvm.buildStateInit({
258
             contr: RootTokenContract,
259
             varInit: {
260
               _randomNonce:rootSoArg,
261
               name:rootName,
262
               symbol:rootSymbol,
263
               decimals:rootDecimals,
264
               wallet_code:codeTONTokenWallet
265
            },
266
             code: codeRootToken,
267
             pubkey : clients[msg.sender]
268
           });
           address root01 = address(tvm.hash(stateInitR));
269
           TvmCell stateInitP = tvm.buildStateInit({
270
             contr: DEXPair,
271
272
             varInit: {
273
               rootDEX:address(this),
274
               soUINT: pairSoArg,
275
               creator: msg. sender,
276
               codeDEXConnector:codeDEXconnector,
277
               rootA:root0.
278
               rootB:root1,
279
               rootAB:root01
280
             },
281
             code: codeDEXpair,
282
             pubkey : clients[msg.sender]
           });
283
           address pairAddress = new DEXPair{
284
285
             stateInit: stateInitP,
286
             flag: 0,
287
             bounce : false,
             value : grammsForPair + (2 * grammsForConnector) + (2 *
288
                 {\tt grammsForWallet})
289
           }(connectorSoArg0, connectorSoArg1, grammsForConnector,
               grammsForWallet);
290
           address rootAddress = new RootTokenContract{
291
             stateInit: stateInitR,
292
             flag: 0,
293
             bounce : false,
294
             value : grammsForRoot
295
           }(0, pairAddress);
296
           roots[root0][root1] = pairAddress;
297
           roots[root1][root0] = pairAddress;
          Pair cp = pairs[pairAddress];
cp.root0 = root0;
298
299
300
           cp.root1 = root1;
```

# 7.8.5 Function getBalanceTONgrams

Returns		
uint128	balanceTONgrams	
Modifiers		
alwaysAccept	no args	

# 7.8.6 Function getClientAddress

Parameters		
uint256	clientPubKey	
uint256	clientSoArg	
Returns		
address	no name	

# 7.8.7 Function getConnectorAddress

Parameters		
uint256	connectorPubKey	
uint256	connectorSoArg	
address	connectorCommander	
Returns		
address	no name	

```
function getConnectorAddress(uint256 connectorPubKey, uint256 connectorSoArg, address connectorCommander) public view responsible returns (address) {

return { value: 0, bounce: false, flag: 64 } computeConnectorAddress(connectorPubKey, connectorSoArg, connectorCommander);
}
```

# 7.8.8 Function getPairAddress

Paramet	ers	
uint256	pairPubKey	
uint256	pairSoArg	
address	pairCreator	
address	pairRootA	
address	pairRootB	
address	pairRootAB	
Returns		
address	no name	

```
171
     function getPairAddress(
172
          uint256 pairPubKey,
           uint256 pairSoArg,
173
174
           address pairCreator,
          address pairRootA,
175
176
           address pairRootB,
177
          address pairRootAB
        ) public view responsible returns (address) {
  return { value: 0, bounce: false, flag: 64 } computePairAddress
178
179
                (\verb"pairPubKey", \verb"pairSoArg", \verb"pairCreator", \verb"pairRootA", \verb"pairRootB",
                pairRootAB);
```

# 7.8.9 Function getPairByRoots01

Parameters		
address	root0	
address	root1	
Returns		
address	pairAddr	
Modifiers	pairaddi	
	I	
alwaysAccept	no args	

```
314 function getPairByRoots01(address root0, address root1) public
     view alwaysAccept returns (address pairAddr) {
    pairAddr = roots[root0][root1];
316 }
```

# 7.8.10 Function getPairByRoots10

Parameters		
address	root1	
address	root0	
Returns		
address	pairAddr	
Modifiers		
alwaysAccept	no args	

```
function getPairByRoots10(address root1, address root0) public
    view alwaysAccept returns (address pairAddr) {
    pairAddr = roots[root1][root0];
}
```

# $7.8.11 \quad Function \ getRootTokenAddress$

Parameters		
uint256	rootPubKey	
uint256	rootSoArg	
bytes	rootName	
bytes	rootSymbol	
uint8	rootDecimals	
Returns		
address	no name	

```
213
     function getRootTokenAddress(
214
         uint256 rootPubKey,
         uint256 rootSoArg,
215
216
         bytes rootName,
217
         bytes rootSymbol,
218
         uint8 rootDecimals
       ) public view responsible returns (address) {
  return { value: 0, bounce: false, flag: 64 }
219
220
              computeRootTokenAddress(rootPubKey,rootSoArg,rootName,
              rootSymbol,rootDecimals);
221
     }
```

# 7.8.12 Function getRootsByPair

Parameters		
address	pairAddr	
Returns		
address	root0	
address	root1	
Modifiers		
alwaysAccept	no args	

# 7.8.13 Function sendTransfer

Parameters	Parameters		
address	dest		
uint128	value		
bool	bounce		
Modifiers			
checkOwnerAndAccept	no args		

```
function sendTransfer(address dest, uint128 value, bool bounce)
    public pure checkOwnerAndAccept {
    dest.transfer(value, bounce, 0);
}
```

# 7.8.14 Function setCreator

Parameters		
address	giverAddr	
Modifiers		
checkCreatorAndAccept	no args	

## 7.8.15 Function setDEXclientCode

Parameters		
TvmCell	code	
Modifiers		
checkOwnerAndAccept	no args	

# 7.8.16 Function setDEXconnectorCode

Parameters		
TvmCell code		
Modifiers		
checkOwnerAndAccept	no args	

# 7.8.17 Function setDEXpairCode

Parameters		
TvmCell code		
Modifiers		
checkOwnerAndAccept	no args	

```
84  function setDEXpairCode(TvmCell code) public checkOwnerAndAccept
      {
85       codeDEXpair = code;
86  }
```

## 7.8.18 Function setRootTokenCode

Parameters		
TvmCell	code	
Modifiers		
checkOwnerAndAccept	no args	

# 7.8.19 Function setTONTokenWalletCode

Parameters		
TvmCell code		
Modifiers		
checkOwnerAndAccept	no args	

# 7.9 Internal Method Definitions

# 7.9.1 Function computeClientAddress

Parameters		
uint256	pubkey	
uint256	souint	
Returns		
address	no name	

```
{\tt function} \  \, {\tt computeClientAddress(uint256 \ pubkey, \ uint256 \ souint)}
108
          private inline view returns (address) {
109
         TvmCell stateInit = tvm.buildStateInit({
110
           contr: DEXClient,
111
           varInit: {rootDEX:address(this), soUINT: souint,
               codeDEXConnector:codeDEXconnector},
112
           code: codeDEXclient,
113
           pubkey: pubkey
         });
114
115
         return address(tvm.hash(stateInit));
116
```

# $7.9.2 \quad Function\ compute Connector Address$

Parameters		
uint256	pubkey	
uint256	souint	
address	commander	
Returns		
address	no name	

```
223
    function computeConnectorAddress(uint256 pubkey, uint256 souint,
         address commander) private inline view returns (address) {
224
        TvmCell stateInit = tvm.buildStateInit({
          contr: DEXConnector,
225
226
          varInit: { soUINT: souint, dexclient: commander },
227
          code: codeDEXconnector,
228
         pubkey: pubkey
        });
229
230
        return address(tvm.hash(stateInit));
231
```

## 7.9.3 Function computePairAddress

Paramet	ers	
uint256	pubkey	
uint256	souint	
address	creator	
address	rootA	
address	rootB	
address	rootAB	
Returns		
address	no name	

```
function computePairAddress(
uint256 pubkey,
uint256 souint,
address creator,
address rootA,
address rootB,
address rootAB
) private inline view returns (address){
```

```
154
        TvmCell stateInit = tvm.buildStateInit({
155
           contr: DEXPair,
156
          varInit: {
157
            rootDEX:address(this),
158
             soUINT:souint,
159
             creator: creator,
160
             codeDEXConnector:codeDEXconnector,
161
             rootA:rootA,
162
             rootB:rootB,
163
             rootAB:rootAB
164
          },
165
          code: codeDEXpair,
166
          pubkey : pubkey
167
        });
168
         return address(tvm.hash(stateInit));
169
```

# 7.9.4 Function computeRootTokenAddress

Paramet	ers	
uint256	pubkey	
uint256	souint	
bytes	name	
bytes	symbol	
uint8	decimals	
Returns		
address	no name	

```
182
    function computeRootTokenAddress(
        uint256 pubkey,
        uint256 souint,
184
185
        bytes name,
186
        bytes symbol,
        uint8 decimals
187
188
      ) private inline view returns (address){
        TvmCell stateInit = tvm.buildStateInit({
189
190
          contr: RootTokenContract,
191
          varInit: {
             _randomNonce:souint,
192
193
             name:name,
194
             symbol:symbol,
195
             decimals: decimals,
196
             {\tt wallet\_code:codeTONTokenWallet}
197
          },
198
          code: codeRootToken,
199
          pubkey: pubkey
200
201
        return address(tvm.hash(stateInit));
```

202 }

# Chapter 8

# Contract RootTokenContract

In file RootTokenContract.sol

# 8.1 Contract Inheritance

IRootTokenContract	
IBurnableTokenRootContract	
IBurnable By Root Token Root Contract	
IPausable	
ITransferOwner	
ISendSurplusGas	
IVersioned	

# 8.2 Static Variable Definitions

#### Advises

Use a naming convention to distinguish static variables from global variables, such as  $s_-$  prefix.

uint256	_randomNonce	
bytes	name	
		used in @5.RootTokenCon-
		tract.getDetails
bytes	symbol	
		used in @5.RootTokenCon-
		tract.getDetails
uint8	decimals	
		used in @5.RootTokenCon-
		tract.getDetails
TvmCell	wallet_code	
		used in @5.RootTokenCon-
		tract.getWalletCode
		used in @5.RootTokenCon-
		tract.getExpectedWalletAddress
		used in @5.RootTokenCon-
		tract.getExpectedWalletAddress
		used in @5.RootTokenCon-
		tract.deployWallet
		used in @5.RootTokenCon-
		tract.deployWallet
		used in @5.RootTokenCon-
		tract.deployEmptyWallet

```
28 uint256 static _randomNonce;

30 bytes public static name;

31 bytes public static symbol;

32 uint8 public static decimals;

34 TvmCell static wallet_code;
```

# 8.3 Variable Definitions

#### Advises

Use a naming convention to distinguish global variables from local variables, such as  ${\tt g\_}$  or  ${\tt m\_}$  prefix.

uint128	total_supply	
		assigned in @5.RootTokenCon-
		tract.tokensBurned
		used in @5.RootTokenCon-
		tract.tokensBurned
		assigned in @5.RootTokenCon-
		tract.mint
		used in @5.RootTokenCon-
		tract.mint
		used in @5.RootTokenCon-
		tract.getTotalSupply
		used in @5.RootTokenCon-
		tract.getDetails
		assigned in @5.RootTokenCon-
		tract.deployWallet
		used in @5.RootTokenCon-
		tract.deployWallet
		assigned in @5.RootTokenCon-
		tract.:onBounce
		used in @5.RootTokenCon-
		tract.:onBounce
		assigned in @5.RootTokenCon-
		tract.:constructor
		used in @5.RootTokenCon-
		tract.:constructor
uint256	root_public_key	
		assigned in @5.RootTokenCon-
		tract.transferOwner
		used in @5.RootTokenCon-
		tract.transferOwner
		used in @5.RootTokenCon-
		tract.isExternalOwner
		used in @5.RootTokenCon-
		tract.isExternalOwner
		used in @5.RootTokenCon-
		tract.getDetails
		assigned in @5.RootTokenCon-
		tract.:constructor
		used in @5.RootTokenCon-
- 11		tract.:constructor
address	root_owner_address	. 1
		assigned in @5.RootTokenCon-
		tract.transferOwner
		used in @5.RootTokenCon-
		tract.transferOwner
		used in @5.RootTokenCon-
		tract.isInternalOwner
		used <sup>86</sup> in @5.RootTokenCon-
		tract.isInternalOwner
		used in @5.RootTokenCon-
		tract.getDetails
		used in @5.RootTokenCon-
		tract.deployWallet
		used in @5.RootTokenCon-
		tract.deployWallet

```
36     uint128 total_supply;
38     uint256 root_public_key;
39     address root_owner_address;
40     uint128 public start_gas_balance;
42     bool public paused;
```

# 8.4 Modifier Definitions

#### Advises

Calling tvm.accept() without checking pubkey should not be allowed

#### 8.4.1 Modifier onlyOwner

```
458 modifier onlyOwner() {
459 require(isOwner(), RootTokenContractErrors.
error_message_sender_is_not_my_owner);
460 _;
461 }
```

# 8.4.2 Modifier onlyInternalOwner

```
463 modifier onlyInternalOwner() {
464 require(isInternalOwner(), RootTokenContractErrors.
error_message_sender_is_not_my_owner);
465 _;
466 }
```

# 8.5 Constructor Definitions

## 8.5.1 Constructor

#### Advises

Check who can call the constructor. If the constructor sets global values, only legitimate users should be allowed.

Check that every argument is protected by a require().

If external users are allowed, their pubkey should be verified (require(msg.pubkey() != 0 && msg.pubkey() == tvm.pubkey(),100) , and tvm.accept() should be called.

Paramet	ers	
uint256	root_public_key_	
address	root_owner_address_	

```
constructor(uint256 root_public_key_, address
48
            root_owner_address_) public {
            require((root_public_key_ != 0 && root_owner_address_.value
49
                 == 0) ||
                    (root_public_key_ == 0 && root_owner_address_.value
50
                         != 0),
51
                    {\tt RootTokenContractErrors}\:.
                        error_define_public_key_or_owner_address);
52
            tvm.accept();
53
54
            root_public_key = root_public_key_;
55
            root_owner_address = root_owner_address_;
56
57
            total_supply = 0;
58
            paused = false;
59
60
            start_gas_balance = address(this).balance;
```

# 8.6 Public Method Definitions

#### 8.6.1 Fallback function

```
523 fallback() external {
524 }
```

# 8.6.2 OnBounce function

Paramete	rs	
TvmSlice	slice	

```
514     onBounce(TvmSlice slice) external {
515         tvm.accept();
516         uint32 functionId = slice.decode(uint32);
517         if (functionId == tvm.functionId(ITONTokenWallet.accept)) {
518              uint128 latest_bounced_tokens = slice.decode(uint128);
519              total_supply -= latest_bounced_tokens;
520         }
521    }
```

# 8.6.3 Function deployEmptyWallet

Parameters				
uint128	deploy_grams			
uint256	wallet_public_key_			
address	owner_address_			
address	gas_back_address			
Returns				
address	no name			

```
237
        function deployEmptyWallet(
238
             uint128 deploy_grams,
239
             uint256 wallet_public_key_,
240
             address owner_address_,
241
             address gas_back_address
242
243
             override
244
             external
245
         returns (
246
             address
247
248
             require((owner_address_.value != 0 && wallet_public_key_ ==
                  0) ||
                     (owner_address_.value == 0 && wallet_public_key_ !=
249
                          0),
250
                     {\tt RootTokenContractErrors}\:.
                          error_define_public_key_or_owner_address);
251
252
             tvm.rawReserve(address(this).balance - msg.value, 2);
253
254
             address wallet = new TONTokenWallet{
                 value: deploy_grams,
255
256
                 flag: 1,
257
                 code: wallet_code,
258
                 pubkey: wallet_public_key_,
259
                 varInit: {
260
                     root_address: address(this),
261
                     code: wallet_code,
262
                     wallet_public_key: wallet_public_key_,
263
                     owner_address: owner_address_
264
265
             }();
266
267
             if (gas_back_address.value != 0) {
268
                 gas_back_address.transfer({ value: 0, flag: 128 });
269
             } else {
270
                 msg.sender.transfer({ value: 0, flag: 128 });
271
272
273
            return wallet;
```

274 }

# 8.6.4 Function deployWallet

Parameters			
uint128	tokens		
uint128	deploy_grams		
uint256	wallet_public_key_		
address	owner_address_		
address	gas_back_address		
Returns			
address	no name		
Modifiers	Modifiers		
onlyOwner	no args		

```
164
         function deployWallet(
165
             uint128 tokens,
166
             uint128 deploy_grams,
167
             uint256 wallet_public_key_,
             address owner_address_,
168
169
             address gas_back_address
170
171
             override
172
             external
173
             onlyOwner
174
         returns(
175
             address
176
             require(tokens >= 0);
177
178
             require((owner_address_.value != 0 && wallet_public_key_ ==
                  0) ||
179
                      (owner_address_.value == 0 && wallet_public_key_ !=
                           0),
180
                     {\tt RootTokenContractErrors}\:.
                          error_define_public_key_or_owner_address);
181
182
             if(root_owner_address.value == 0) {
183
                 tvm.accept();
184
             } else {
185
                 tvm.rawReserve(math.max(start_gas_balance, address(this
                     ).balance - msg.value), 2);
186
             }
187
188
             TvmCell stateInit = tvm.buildStateInit({
189
                 contr: TONTokenWallet,
190
                 varInit: {
191
                     root_address: address(this),
```

```
192
                     code: wallet_code,
193
                     wallet_public_key: wallet_public_key_,
194
                     owner_address: owner_address_
195
196
                 pubkey: wallet_public_key_,
197
                 code: wallet_code
             });
198
199
200
             address wallet;
201
202
             if(deploy_grams > 0) {
203
                 wallet = new TONTokenWallet{
204
                     stateInit: stateInit,
205
                     value: deploy_grams,
206
                     wid: address(this).wid,
207
                     flag: 1
208
                 }();
209
             } else {
210
                 wallet = address(tvm.hash(stateInit));
211
212
213
             ITONTokenWallet(wallet).accept(tokens);
214
             total_supply += tokens;
215
216
             if (root_owner_address.value != 0) {
217
                 if (gas_back_address.value != 0) {
218
219
                     gas_back_address.transfer({ value: 0, flag: 128 });
220
                 } else {
221
                     msg.sender.transfer({ value: 0, flag: 128 });
222
223
            }
224
225
             return wallet;
226
```

# 8.6.5 Function getDetails

Returns		
IRootTokenContractDetails	no name	

```
function getDetails() override external view responsible
77
           returns (IRootTokenContractDetails) {
78
            return { value: 0, bounce: false, flag: 64 }
                IRootTokenContractDetails(
79
                name,
80
                symbol,
81
                decimals,
82
                root_public_key,
83
                root_owner_address,
```

# 8.6.6 Function getTotalSupply

Returns		
uint128	no name	

```
92 function getTotalSupply() override external view responsible
returns (uint128) {
93 return { value: 0, bounce: false, flag: 64 } total_supply;
94 }
```

# 8.6.7 Function getVersion

Returns	5	
uint32	no name	

```
function getVersion() override external pure responsible
returns (uint32) {
return 4;
}
```

# $8.6.8 \quad Function \ getWalletAddress$

Parameters			
uint256	wallet_public_key_		
address	address owner_address_		
Returns			
address	no name		

```
111
        function getWalletAddress(
112
             uint256 wallet_public_key_,
113
             address owner_address_
114
115
             override
116
             external
117
             view
118
            responsible
119
        returns (
120
             address
121
             require((owner_address_.value != 0 && wallet_public_key_ ==
122
                  0) ||
123
                     (owner_address_.value == 0 && wallet_public_key_ !=
                          0),
124
                     {\tt RootTokenContractErrors.}
                          error_define_public_key_or_owner_address);
125
             return { value: 0, bounce: false, flag: 64 }
                 getExpectedWalletAddress(wallet_public_key_,
                 owner_address_);
126
```

# 8.6.9 Function getWalletCode

Returns		
TvmCell	no name	

```
function getWalletCode() override external view responsible
    returns (TvmCell) {
    return { value: 0, bounce: false, flag: 64 } wallet_code;
}
```

## 8.6.10 Function mint

Parameters		
uint128	tokens	
address	to	
Modifiers		
onlyOwner	no args	

```
282
         function mint(
283
             uint128 tokens,
284
             address to
285
286
             override
287
             external
288
             onlyOwner
289
290
             tvm.accept();
291
292
             ITONTokenWallet(to).accept(tokens);
293
294
             total_supply += tokens;
295
```

# 8.6.11 Function proxyBurn

Parameters		
uint128	tokens	
address	sender_address	
address	send_gas_to	
address	callback_address	
TvmCell	callback_payload	
Modifiers		
onlyInternalOwner	no args	

```
307
         function proxyBurn(
308
            uint128 tokens,
309
             address sender_address,
             address send_gas_to,
310
311
             address callback_address,
312
            TvmCell callback_payload
313
314
            override
315
             external
316
            onlyInternalOwner
317
            tvm.rawReserve(address(this).balance - msg.value, 2);
318
319
320
             address send_gas_to_ = send_gas_to;
321
             address expectedWalletAddress = getExpectedWalletAddress(0,
                  sender_address);
322
323
             if (send_gas_to.value == 0) {
324
                 send_gas_to_ = sender_address;
325
326
```

```
327 IBurnableByRootTokenWallet(expectedWalletAddress).

burnByRoot{value: 0, flag: 128}(
328 tokens,
329 send_gas_to_,
330 callback_address,
331 callback_payload
332 );
333 }
```

# 8.6.12 Function sendExpectedWalletAddress

Parameters				
uint256	wallet_public_key_			
address	owner_address_			
address	to			

```
134
         function sendExpectedWalletAddress(
135
             uint256 wallet_public_key_,
136
             address owner_address_,
137
             address to
138
139
             override
140
             external
141
142
             tvm.rawReserve(address(this).balance - msg.value, 2);
143
144
             address wallet = getExpectedWalletAddress(
                 wallet_public_key_, owner_address_);
145
             IExpectedWalletAddressCallback(to).
                 expectedWalletAddressCallback{value: 0, flag: 128}(
146
                 wallet,
147
                 wallet_public_key_,
148
                 owner_address_
149
             );
150
```

## 8.6.13 Function sendPausedCallbackTo

Parameters		
uint64	callback_id	
address	callback_addr	

```
423
         {\tt function} \  \, {\tt sendPausedCallbackTo} \, (
424
             uint64 callback_id,
425
             address callback_addr
426
427
              override
428
             external
429
             tvm.rawReserve(address(this).balance - msg.value, 2);
430
431
             IPausedCallback(callback_addr).pausedCallback{ value: 0,
                  flag: 128 }(callback_id, paused);
432
```

# 8.6.14 Function sendSurplusGas

Parameters		
address to		
Modifiers		
onlyInternalOwner	no args	

```
386
        function sendSurplusGas(
387
             address to
388
389
             override
390
             external
391
             onlyInternalOwner
392
393
             tvm.rawReserve(start_gas_balance, 2);
394
             IReceiveSurplusGas(to).receiveSurplusGas{ value: 0, flag:
                 128 }();
395
```

# 8.6.15 Function setPaused

Parameters		
bool	value	
Modifiers		
onlyOwner	no args	

```
407 function setPaused(
408 bool value
409 )
```

#### 8.6.16 Function tokensBurned

Parameters		
uint128	tokens	
uint256	sender_public_key	
address	sender_address	
address	send_gas_to	
address	callback_address	
TvmCell	callback_payload	

```
347
         function tokensBurned(
348
            uint128 tokens,
349
            uint256 sender_public_key,
350
            address sender_address,
351
             address send_gas_to,
352
             address callback_address,
353
             TvmCell callback_payload
354
        ) override external {
355
356
             require(!paused, RootTokenContractErrors.error_paused);
357
358
             address expectedWalletAddress = getExpectedWalletAddress(
                 sender_public_key, sender_address);
359
360
             require(msg.sender == expectedWalletAddress,
                 RootTokenContractErrors.
                 error_message_sender_is_not_good_wallet);
361
362
             tvm.rawReserve(address(this).balance - msg.value, 2);
363
364
             total_supply -= tokens;
365
366
             if (callback_address.value == 0) {
367
                 send_gas_to.transfer({ value: 0, flag: 128 });
368
             } else {
369
                 IBurnTokensCallback(callback_address).burnCallback{
                     value: 0, flag: 128}(
370
                     tokens,
371
                     callback_payload,
372
                     sender_public_key,
```

## 8.6.17 Function transferOwner

Parameters		
uint256	root_public_key_	
address	root_owner_address_	
Modifiers		
onlyOwner	no args	

```
440
        function transferOwner(
441
            uint256 root_public_key_,
442
            address root_owner_address_
443
444
            override
445
            external
446
            onlyOwner
447
             require((root_public_key_ != 0 && root_owner_address_.value
448
                  == 0) ||
449
                     (root_public_key_ == 0 && root_owner_address_.value
                          != 0),
450
                     RootTokenContractErrors.
                         error_define_public_key_or_owner_address);
451
            tvm.accept();
452
            root_public_key = root_public_key_;
453
            root_owner_address = root_owner_address_;
454
```

# 8.7 Internal Method Definitions

# 8.7.1 Function getExpectedWalletAddress

Parameters		
uint256	wallet_public_key_	
address	owner_address_	
Returns		
address	no name	

```
485
         function getExpectedWalletAddress(
486
             uint256 wallet_public_key_,
487
             address owner_address_
488
489
             private
490
             inline
491
             view
492
        returns (
493
             address
494
495
             TvmCell stateInit = tvm.buildStateInit({
                 contr: TONTokenWallet,
496
497
                 varInit: {
498
                     root_address: address(this),
499
                     code: wallet_code,
500
                     wallet_public_key: wallet_public_key_,
501
                     owner_address: owner_address_
502
503
                 pubkey: wallet_public_key_,
504
                 code: wallet_code
505
             });
506
507
             return address(tvm.hash(stateInit));
508
```

#### 8.7.2 Function is External Owner

Retur	rns	
bool	no name	

#### 8.7.3 Function isInternalOwner

```
Returns
bool | no name |
```

472 function isInternalOwner() private inline view returns (bool) {

```
473 return root_owner_address.value != 0 && root_owner_address
== msg.sender;
474 }
```

# 8.7.4 Function isOwner

Returns		
bool	$no \ name$	

```
468  function isOwner() private inline view returns (bool) {
469    return isInternalOwner() || isExternalOwner();
470 }
```

# Chapter 9

# Contract TONTokenWallet

In file TONTokenWallet.sol

# 9.1 Contract Inheritance

ITONTokenWallet	
IDestroyable	
IBurnableByOwnerTokenWallet	
IBurnableByRootTokenWallet	
IVersioned	

# 9.2 Static Variable Definitions

#### Advises

Use a naming convention to distinguish static variables from global variables, such as  $s_-$  prefix.

1.1	1.1	
address	root_address	0 movm 1 HV 1
		used in @6.TONTokenWal-
		let.transferToRecipient
		used in @6.TONTokenWal-
		let.internalTransfer
		used in @6.TONTokenWal-
		let.getExpectedAddress
		used in @6.TONTokenWal-
		let.getDetails
		used in @6.TONTokenWal-
		let.burnByRoot
		used in @6.TONTokenWal-
		let.burnByOwner
		used in @6.TONTokenWal-
		let.burnByOwner
		used in @6.TONTokenWal-
		let.:onBounce
		used in @6.TONTokenWal-
m C 11	1	let.:constructor
TvmCell	code	1 · OCHONEL WIL
		used in @6.TONTokenWal-
		let.transferToRecipient
		used in @6.TONTokenWal-
		let.transferToRecipient
		used in @6.TONTokenWal-
		let.getWalletCode used in @6.TONTokenWal-
		let.getExpectedAddress used in @6.TONTokenWal-
uint256	wallet_public_key	let.getExpectedAddress
umt250	wanet_public_key	used in @6.TONTokenWal-
		let.transferToRecipient
		used in @6.TONTokenWal-
		let.transferToRecipient
		used in @6.TONTokenWal-
		let.transferToRecipient
		used in @6.TONTokenWal-
		let.transfer
		used in @6.TONTokenWal-
		let.transfer
		used in @6.TONTokenWal-
		let.internalTransferFrom
		used in @6.TONTokenWal-
		let.internalTransfer
		used in @6.TONTokenWal-
		let.getDetails
		used <sup>102</sup> in @6.TONTokenWal-
		let.burnByRoot
		used in @6.TONTokenWal-
		let.burnByOwner
		used in @6.TONTokenWal-
		let.burnByOwner
		used in @6.TONTokenWal-
		let.:constructor
	I.	-55.0032001 40001

```
24 address static root_address;

25 TvmCell static code;

27 uint256 static wallet_public_key;

29 address static owner_address;
```

# 9.3 Variable Definitions

## Advises

Use a naming convention to distinguish global variables from local variables, such as  ${\tt g\_}$  or  ${\tt m\_}$  prefix.

uint128	balance_	
		assigned in @6.TONTokenWal-
		let.transferToRecipient
		used in @6.TONTokenWal-
		let.transferToRecipient
		assigned in @6.TONTokenWal-
		let.transferToRecipient
		used in @6.TONTokenWal-
		let.transferToRecipient
		used in @6.TONTokenWal-
		let.transferToRecipient
		assigned in @6.TONTokenWal-
		let.transfer
		used in @6.TONTokenWal-
		let.transfer
		assigned in @6.TONTokenWal-
		let.transfer
		used in @6.TONTokenWal-
		let.transfer
		used in @6.TONTokenWal-
		let.transfer
		assigned in @6.TONTokenWal-
		let.internalTransferFrom
		used in @6.TONTokenWal-
		let.internalTransferFrom
		used in @6.TONTokenWal-
		let.internalTransferFrom
		used in @6.TONTokenWal-
		let.internalTransfer
		assigned in @6.TONTokenWal-
		let.internalTransfer
		used in @6.TONTokenWal-
		let.internalTransfer
		used in @6.TONTokenWal-
		let.getDetails
		used in @6.TONTokenWal-
		let.destroy
		assigned in @6.TONTokenWal-
		let.burnByRoot
		used in @6.TONTokenWal-
		let.burnByRoot
		used in @6.TONTokenWal-
		let.burnByRoot
		assigned in @6.TONTokenWal-
		let.burnByOwner
		used in @6.TONTokenWal-
		let.burnByOwner
	104	assigned in @6.TONTokenWal-
		let.burnByOwner
		used in @6.TONTokenWal-
		let.burnByOwner
		used in @6.TONTokenWal-
		let.burnByOwner
		used in @6.TONTokenWal-
		let.balance

```
31     uint128 balance_;
32     optional(AllowanceInfo) allowance_;
34     address receive_callback;
35     address bounced_callback;
36     bool allow_non_notifiable;
```

# 9.4 Modifier Definitions

#### Advises

Calling tvm.accept() without checking pubkey should not be allowed

## 9.4.1 Modifier onlyRoot

## 9.4.2 Modifier onlyOwner

## 9.4.3 Modifier onlyInternalOwner

```
610 modifier onlyInternalOwner() {
611 require(owner_address.value != 0 && owner_address == msg.
sender);
612 _;
613 }
```

# 9.5 Constructor Definitions

## 9.5.1 Constructor

#### Advises

Check who can call the constructor. If the constructor sets global values, only legitimate users should be allowed.

Check that every argument is protected by a require().

If external users are allowed, their pubkey should be verified (require(msg.pubkey() != 0 && msg.pubkey() == tvm.pubkey(),100) , and tvm.accept() should be called.

```
constructor() public {
43
44
           require(wallet_public_key == tvm.pubkey() && (owner_address
               .value == 0 || wallet_public_key == 0));
45
           tvm.accept();
46
47
           allow_non_notifiable = true;
48
49
           if (owner_address.value != 0) {
50
               ITokenWalletDeployedCallback(owner_address).
                   notifyWalletDeployed{value: 0.00001 ton, flag: 1}(
                   root_address);
51
```

# 9.6 Public Method Definitions

## 9.6.1 Fallback function

```
683 fallback() external {
684 }
```

## 9.6.2 OnBounce function

Parameters		
TvmSlice	body	

```
653
         onBounce(TvmSlice body) external {
654
             tvm.accept();
655
656
             uint32 functionId = body.decode(uint32);
             if (functionId == tvm.functionId(ITONTokenWallet.
657
                 internalTransfer)) {
658
                 uint128 tokens = body.decode(uint128);
659
                 balance_ += tokens;
660
661
                 if (bounced_callback.value != 0) {
662
                      tvm.rawReserve(address(this).balance - msg.value,
                          2);
663
                      ITokensBouncedCallback(bounced_callback).
                          tokensBouncedCallback{ value: 0, flag: 128 }(
664
                          address(this),
665
                          root_address,
666
                          tokens,
667
                          msg.sender,
668
                          balance_
669
                     );
670
                 } else if (owner_address.value != 0) {
671
                     \verb|tvm.rawReserve| (\verb|math.max| (\verb|TONTokenWalletConstants|.
                          target_gas_balance, address(this).balance - msg
                          .value), 2);
                      owner_address.transfer({ value: 0, flag: 128 });
672
                 }
673
674
             } else if (functionId == tvm.functionId(
                 IBurnableTokenRootContract.tokensBurned)) {
675
                 balance_ += body.decode(uint128);
676
                 if (owner_address.value != 0) {
677
                      {\tt tvm.rawReserve\,(math.max\,(TONTokenWalletConstants\,.}
                          target_gas_balance, address(this).balance - msg
                          .value), 2);
678
                      owner_address.transfer({ value: 0, flag: 128 });
679
680
             }
681
```

# 9.6.3 Function accept

Parameters		
uint128 tokens		
Modifiers		
onlyRoot	no args	

```
96 function accept(
97 uint128 tokens
98 )
99 override
```

### 9.6.4 Function allowance

Returns		
AllowanceInfo	$no \ name$	

## 9.6.5 Function approve

Parameters		
address	spender	
uint128	remaining_tokens	
uint128	tokens	
Modifiers		
onlyOwner	no args	

```
119
        function approve(
120
            address spender,
121
            uint128 remaining_tokens,
122
            uint128 tokens
123
124
            override
125
             external
126
            onlyOwner
127
        {
             require(remaining_tokens == 0 || !allowance_.hasValue(),
128
                 TONTokenWalletErrors.error_non_zero_remaining);
129
             if (owner_address.value != 0 ) {
```

```
130
                 {\tt tvm.rawReserve\,(math.max\,(TONTokenWalletConstants\,.}
                     target_gas_balance, address(this).balance - msg.
                     value), 2);
131
             } else {
132
                 tvm.accept();
133
134
135
             if (allowance_.hasValue()) {
136
                 if (allowance_.get().remaining_tokens ==
                     remaining_tokens) {
137
                     allowance_.set(AllowanceInfo(tokens, spender));
                 }
138
139
             } else {
140
                 allowance_.set(AllowanceInfo(tokens, spender));
141
142
             if (owner_address.value != 0 ) {
143
144
                 msg.sender.transfer({ value: 0, flag: 128 });
145
             }
146
```

### 9.6.6 Function balance

Returns		
uint128	$no \ name$	

### 9.6.7 Function burnByOwner

Parameter	s	
uint128	tokens	
uint128	grams	
address	send_gas_to	
address	callback_address	
TvmCell	callback_payload	
Modifiers		
onlyOwner	no args	

```
473
         function burnByOwner(
474
             uint128 tokens,
475
             uint128 grams,
476
             address send_gas_to,
477
             address callback_address,
478
             TvmCell callback_payload
479
         ) override external onlyOwner {
480
             require(tokens > 0);
481
             require(tokens <= balance_, TONTokenWalletErrors.</pre>
                 error_not_enough_balance);
482
             require((owner_address.value != 0 && msg.value > 0) ||
                      (owner_address.value == 0 && grams <= address(this)</pre>
483
                          .balance && grams > 0), TONTokenWalletErrors.
                          error_low_message_value);
484
485
             if (owner_address.value != 0 ) {
486
                  {\tt tvm.rawReserve\,(math.max\,(TONTokenWalletConstants\,.}
                     target_gas_balance, address(this).balance - msg.
                      value), 2);
487
                 balance_ -= tokens;
488
                  IBurnableTokenRootContract(root_address)
                      .tokensBurned{ value: 0, flag: 128, bounce: true }(
489
490
                          tokens,
491
                          wallet_public_key,
492
                          owner_address,
493
                          send_gas_to.value != 0 ? send_gas_to :
                             owner_address,
494
                          callback_address,
495
                          callback_payload
496
                     );
             } else {
497
498
                 tvm.accept();
499
                 balance_ -= tokens;
500
                  IBurnableTokenRootContract(root_address)
501
                      .tokensBurned{ value: grams, bounce: true }(
502
                          tokens,
503
                          wallet_public_key,
504
                          owner_address,
505
                          send_gas_to.value != 0 ? send_gas_to : address(
                              this),
506
                          callback_address,
507
                          callback_payload
508
                      );
509
             }
510
```

# 9.6.8 Function burnByRoot

Paramete	rs	
uint128	tokens	
address	send_gas_to	
address	callback_address	
TvmCell	callback_payload	
Modifiers		
onlyRoot	no args	

```
520
        function burnByRoot(
             uint128 tokens,
521
522
             address send_gas_to,
523
             address callback_address,
524
             TvmCell callback_payload
525
        ) override external onlyRoot {
             require(tokens > 0);
526
527
             require(tokens <= balance_, TONTokenWalletErrors.</pre>
                 error_not_enough_balance);
528
529
             tvm.rawReserve(address(this).balance - msg.value, 2);
530
531
             balance_ -= tokens;
532
533
             IBurnableTokenRootContract(root_address)
534
                 .tokensBurned{ value: 0, flag: 128, bounce: true }(
535
                     tokens,
536
                     wallet_public_key,
537
                     owner_address,
538
                     send_gas_to,
539
                     callback_address,
540
                     callback_payload
541
                 );
542
```

### 9.6.9 Function destroy

Parameter	S	
address	${\tt gas\_dest}$	
Modifiers		
onlyOwner	no args	

```
584
         function destroy(
585
             address gas_dest
586
587
             override
588
             public
589
             onlyOwner
590
591
             require(balance_ == 0);
592
             tvm.accept();
593
             selfdestruct(gas_dest);
594
```

### 9.6.10 Function disapprove

Modifiers		
onlyOwner	no args	

```
148
         function disapprove() override external onlyOwner {
149
              if (owner_address.value != 0 ) {
150
                   tvm.rawReserve(math.max(TONTokenWalletConstants.
                       {\tt target\_gas\_balance} \ , \ {\tt address(this).balance} \ - \ {\tt msg} \, .
                       value), 2);
151
             } else {
152
                   tvm.accept();
153
154
155
              allowance_.reset();
156
157
              if (owner_address.value != 0 ) {
                  msg.sender.transfer({ value: 0, flag: 128 });
158
159
160
```

### 9.6.11 Function getDetails

```
Returns
ITONTokenWalletDetails | no name |
```

```
function getDetails() override external view responsible returns (ITONTokenWalletDetails) {
    return { value: 0, bounce: false, flag: 64 }
    ITONTokenWalletDetails(
```

```
74
                root_address,
75
                wallet_public_key,
76
                owner_address,
77
                balance_,
78
                receive_callback,
79
                bounced_callback,
80
                allow_non_notifiable
            );
81
```

# 9.6.12 Function getVersion

Returns	<b>S</b>	
uint32	no name	

```
function getVersion() override external pure responsible
returns (uint32) {

return 4;

}
```

## 9.6.13 Function getWalletCode

Returns		
TvmCell	no name	

```
function getWalletCode() override external view responsible returns (TvmCell) {
    return { value: 0, bounce: false, flag: 64 } code;
}
```

### 9.6.14 Function internalTransfer

Paramet	ers	
uint128	tokens	
uint256	sender_public_key	
address	sender_address	
address	send_gas_to	
bool	notify_receiver	
TvmCell	payload	

```
370
        function internalTransfer(
371
             uint128 tokens,
372
             uint256 sender_public_key,
373
             address sender_address,
374
             address send_gas_to,
375
             bool notify_receiver,
376
             TvmCell payload
377
378
             override
379
             external
380
381
             require(notify_receiver || allow_non_notifiable ||
                 receive_callback.value == 0,
382
                     TONTokenWalletErrors.
                         error_recipient_has_disallow_non_notifiable);
383
             address expectedSenderAddress = getExpectedAddress(
                 sender_public_key, sender_address);
384
             require(msg.sender == expectedSenderAddress,
                 {\tt TONTokenWalletErrors.}
                 error_message_sender_is_not_good_wallet);
385
             require(sender_address != owner_address ||
                 sender_public_key != wallet_public_key,
                 TONTokenWalletErrors.error_wrong_recipient);
386
387
             if (owner_address.value != 0 ) {
                 uint128 reserve = math.max(TONTokenWalletConstants.
388
                     target_gas_balance, address(this).balance - msg.
                     value);
389
                 require(address(this).balance > reserve,
                     TONTokenWalletErrors.error_low_message_value);
390
                 tvm.rawReserve(reserve, 2);
391
             } else {
392
                 tvm.rawReserve(address(this).balance - msg.value, 2);
393
             }
394
395
             balance_ += tokens;
396
397
             if (notify_receiver && receive_callback.value != 0) {
398
                 ITokensReceivedCallback(receive_callback).
                     tokensReceivedCallback{ value: 0, flag: 128 }(
399
                     address(this),
400
                     root_address,
401
                     tokens,
402
                     sender_public_key,
403
                     sender_address,
404
                     msg.sender.
405
                     send_gas_to,
406
                     balance_,
407
                     payload
408
                 );
409
             } else {
410
                 send_gas_to.transfer({ value: 0, flag: 128 });
             }
411
412
```

#### 9.6.15 Function internal Transfer From

Paramet	ers	
address	to	
uint128	tokens	
address	$\mathtt{send\_gas\_to}$	
bool	notify_receiver	
TvmCell	payload	

```
423
        function internalTransferFrom(
424
             address to,
             uint128 tokens,
425
426
             address send_gas_to,
427
             bool notify_receiver,
428
             TvmCell payload
429
430
             override
431
             external
432
             require(allowance_.hasValue(), TONTokenWalletErrors.
433
                 error_no_allowance_set);
434
             require(msg.sender == allowance_.get().spender,
                 TONTokenWalletErrors.error_wrong_spender);
435
             require(tokens <= allowance_.get().remaining_tokens,</pre>
                 TONTokenWalletErrors.error_not_enough_allowance);
             require(tokens <= balance_, TONTokenWalletErrors.</pre>
436
                 error_not_enough_balance);
437
             require(tokens > 0);
             require(to != address(this), TONTokenWalletErrors.
438
                 error_wrong_recipient);
439
440
             if (owner_address.value != 0 ) {
441
                 uint128 reserve = math.max(TONTokenWalletConstants.
                     target_gas_balance, address(this).balance - msg.
                     value);
442
                 require(address(this).balance > reserve +
                     {\tt TONTokenWalletConstants.target\_gas\_balance}\ ,
                     TONTokenWalletErrors.error_low_message_value);
443
                 tvm.rawReserve(reserve, 2);
444
                 tvm.rawReserve(math.max(TONTokenWalletConstants.
                     target_gas_balance, address(this).balance - msg.
                     value), 2);
             } else {
445
                 require(msg.value > TONTokenWalletConstants.
446
                     target_gas_balance, TONTokenWalletErrors.
                     error_low_message_value);
447
                 tvm.rawReserve(address(this).balance - msg.value, 2);
448
449
450
             balance_ -= tokens;
```

```
451
452
                                                                                                  allowance_.set(AllowanceInfo(allowance_.get().
                                                                                                                                remaining_tokens - tokens, allowance_.get().spender));
 453
454
                                                                                                 {\tt ITONTokenWallet(to).internalTransfer\{\ value:\ 0,\ bounce:\ and\ bounce:\ and\ bounce:\ 
                                                                                                                                true, flag: 129 }(
 455
                                                                                                                                tokens,
456
                                                                                                                                wallet_public_key,
 457
                                                                                                                                owner_address,
458
                                                                                                                                send_gas_to,
459
                                                                                                                                notify_receiver,
460
                                                                                                                                payload
461
                                                                                                );
462
```

### 9.6.16 Function setBouncedCallback

Parameters		
address	bounced_callback_	
Modifiers		
onlyOwner	no args	

```
568
         function setBouncedCallback(
569
             address bounced_callback_
570
571
             override
572
             external
573
             onlyOwner
574
575
             tvm.accept();
576
             bounced_callback = bounced_callback_;
577
```

### 9.6.17 Function setReceiveCallback

Parameters		
address	receive_callback_	
bool	allow_non_notifiable_	
Modifiers		
onlyOwner	no args	

```
550
         function setReceiveCallback(
551
             address receive_callback_,
552
             bool allow_non_notifiable_
553
554
             override
555
             external
556
             onlyOwner
557
         {
558
             tvm.accept();
559
             receive_callback = receive_callback_;
560
             allow_non_notifiable = allow_non_notifiable_;
561
```

### 9.6.18 Function transfer

Parameters		
address	to	
uint128	tokens	
uint128	grams	
address	send_gas_to	
bool	notify_receiver	
TvmCell	payload	
Modifiers		
onlyOwner	no args	

```
262
         function transfer(
263
             address to,
264
             uint128 tokens,
265
            uint128 grams,
             address send_gas_to,
266
267
             bool notify_receiver,
268
            TvmCell payload
269
        ) override external onlyOwner {
270
             require(tokens > 0);
             require(tokens <= balance_, TONTokenWalletErrors.</pre>
271
                 error_not_enough_balance);
272
             require(to.value != 0, TONTokenWalletErrors.
                 error_wrong_recipient);
273
             require(to != address(this), TONTokenWalletErrors.
                 error_wrong_recipient);
274
275
             if (owner_address.value != 0 ) {
276
                 uint128 reserve = math.max(TONTokenWalletConstants.
                     target_gas_balance, address(this).balance - msg.
                     value);
277
                 require(address(this).balance > reserve +
                     TONTokenWalletConstants.target_gas_balance,
                     TONTokenWalletErrors.error_low_message_value);
```

```
278
                 tvm.rawReserve(reserve, 2);
279
                 balance_ -= tokens;
280
281
                 ITONTokenWallet(to).internalTransfer{ value: 0, flag:
                     129, bounce: true }(
282
                     tokens,
283
                     wallet_public_key,
284
                     owner_address,
285
                     send_gas_to.value != 0 ? send_gas_to :
                         owner_address,
286
                     notify_receiver,
287
                     payload
288
                 );
289
            } else {
290
                 require(address(this).balance > grams,
                     TONTokenWalletErrors.error_low_message_value);
291
                 require(grams > TONTokenWalletConstants.
                     target_gas_balance, TONTokenWalletErrors.
                     error_low_message_value);
292
                 tvm.accept();
293
                 balance_ -= tokens;
294
295
                 ITONTokenWallet(to).internalTransfer{ value: grams,
                     bounce: true, flag: 1 }(
                     tokens,
296
297
                     wallet_public_key,
298
                     owner_address,
299
                     send_gas_to.value != 0 ? send_gas_to : address(this
                         ),
300
                     notify_receiver,
301
                     payload
302
                 );
            }
303
304
```

## 9.6.19 Function transferFrom

Parameters		
address	from	
address	to	
uint128	tokens	
uint128	grams	
address	send_gas_to	
bool	notify_receiver	
TvmCell	payload	
Modifiers		
only0wner	no args	

```
317
         function transferFrom(
318
             address from,
319
             address to.
320
             uint128 tokens,
             uint128 grams,
321
322
             address send_gas_to,
             bool notify_receiver,
323
324
            TvmCell payload
325
326
             override
327
             external
328
             onlyOwner
329
330
             require(to.value != 0, TONTokenWalletErrors.
                 error_wrong_recipient);
331
             require(tokens > 0);
332
             require(from != to, TONTokenWalletErrors.
                 error_wrong_recipient);
333
334
             if (owner_address.value != 0 ) {
335
                 uint128 reserve = math.max(TONTokenWalletConstants.
                     target_gas_balance, address(this).balance - msg.
                     value);
336
                 require(address(this).balance > reserve + (
                     TONTokenWalletConstants.target_gas_balance * 2),
                     TONTokenWalletErrors.error_low_message_value);
337
                 tvm.rawReserve(reserve, 2);
338
339
                 ITONTokenWallet(from).internalTransferFrom{ value: 0,
                     flag: 129 }(
340
341
                     tokens.
342
                     send_gas_to.value != 0 ? send_gas_to :
                         owner_address,
343
                     notify_receiver,
344
                     payload
345
                 );
346
            } else {
                 require(address(this).balance > grams,
347
                     TONTokenWalletErrors.error_low_message_value);
                 require(grams > TONTokenWalletConstants.
348
                     target_gas_balance * 2, TONTokenWalletErrors.
                     error_low_message_value);
349
                 tvm.accept();
350
                 ITONTokenWallet(from).internalTransferFrom{ value:
                     grams, flag: 1 }(
351
                     to,
352
                     tokens,
                     send_gas_to.value != 0 ? send_gas_to : address(this
353
354
                     notify_receiver,
355
                     payload
356
                 );
357
            }
358
```

## 9.6.20 Function transferToRecipient

Parameters		
uint256	recipient_public_key	
address	${ t recipient\_address}$	
uint128	tokens	
uint128	deploy_grams	
uint128	transfer_grams	
address	send_gas_to	
bool	notify_receiver	
TvmCell	payload	
Modifiers		
onlyOwner	no args	

```
177
         function transferToRecipient(
178
            uint256 recipient_public_key,
179
             address recipient_address,
            uint128 tokens,
180
            uint128 deploy_grams,
181
182
            uint128 transfer_grams,
             address send_gas_to,
183
184
            bool notify_receiver,
185
            TvmCell payload
186
        ) override external onlyOwner {
187
             require(tokens > 0);
188
             require(tokens <= balance_, TONTokenWalletErrors.</pre>
                 error_not_enough_balance);
189
             require(recipient_address.value == 0 ||
                 recipient_public_key == 0, TONTokenWalletErrors.
                 error_wrong_recipient);
190
191
             if (owner_address.value != 0 ) {
192
                 uint128 reserve = math.max(TONTokenWalletConstants.
                     target_gas_balance, address(this).balance - msg.
                     value);
193
                 require(address(this).balance > reserve +
                     TONTokenWalletConstants.target_gas_balance +
                     deploy_grams, TONTokenWalletErrors.
                     error_low_message_value);
194
                 require(recipient_address != owner_address,
                     TONTokenWalletErrors.error_wrong_recipient);
195
                 tvm.rawReserve(reserve, 2);
196
            } else {
197
                 require(address(this).balance > deploy_grams +
                     transfer_grams, TONTokenWalletErrors.
                     error_low_message_value);
198
                 require(transfer_grams > TONTokenWalletConstants.
                     target_gas_balance, TONTokenWalletErrors.
```

```
error_low_message_value);
199
                 require(recipient_public_key != wallet_public_key);
200
                 tvm.accept();
201
             }
202
203
             TvmCell stateInit = tvm.buildStateInit({
204
                 contr: TONTokenWallet,
205
                 varInit: {
206
                     root_address: root_address,
207
                     code: code,
208
                     wallet_public_key: recipient_public_key,
209
                     owner_address: recipient_address
210
211
                 pubkey: recipient_public_key,
212
                 code: code
             });
213
214
215
             address to;
216
217
             if(deploy_grams > 0) {
218
                 to = new TONTokenWallet{
219
                     stateInit: stateInit,
220
                     value: deploy_grams,
221
                     wid: address(this).wid,
222
                     flag: 1
223
                 }();
224
             } else {
225
                 to = address(tvm.hash(stateInit));
226
227
228
             if (owner_address.value != 0 ) {
                 balance_ -= tokens;
229
                 ITONTokenWallet(to).internalTransfer{ value: 0, flag:
230
                     129, bounce: true }(
231
                     tokens,
232
                     wallet_public_key,
233
                     owner_address,
234
                     send_gas_to.value != 0 ? send_gas_to :
                          owner_address,
235
                     notify_receiver,
236
                     payload
237
                 );
238
             } else {
239
                 balance_ -= tokens;
240
                 ITONTokenWallet(to).internalTransfer{ value:
                     transfer_grams, flag: 1, bounce: true }(
241
                     tokens,
242
                     wallet_public_key,
                      owner_address,
243
                      send_gas_to.value != 0 ? send_gas_to : address(this
244
245
                     notify_receiver,
246
                     payload
247
                 );
             }
248
249
```

## 9.7 Internal Method Definitions

## 9.7.1 Function getExpectedAddress

Parameters		
uint256	wallet_public_key_	
address	owner_address_	
Returns		
address	no name	

```
620
        function getExpectedAddress(
             uint256 wallet_public_key_,
621
622
             address owner_address_
623
624
             private
625
             inline
626
            view
627
        returns (
628
             address
629
630
             TvmCell stateInit = tvm.buildStateInit({
631
                 contr: TONTokenWallet,
632
                 varInit: {
633
                     root_address: root_address,
634
                     code: code,
635
                     wallet_public_key: wallet_public_key_,
636
                     owner_address: owner_address_
637
638
                 pubkey: wallet_public_key_,
639
                 code: code
640
             });
641
642
             return address(tvm.hash(stateInit));
643
```