Operating Systems COMS(3010A) Paging

Branden Ingram

branden.ingram@wits.ac.za

Recap

- Memory Virtualisation
- Address Translation
- Segmentation
- Free Space Management

• In Operating Systems, Paging is a storage mechanism used to retrieve processes from the secondary storage into the main memory in the form of pages.

- In Operating Systems, Paging is a storage mechanism used to retrieve processes from the secondary storage into the main memory in the form of pages.
- The main idea behind the paging is to divide each process(Address Space) into a fixed-sized unit called a page

- In Operating Systems, Paging is a storage mechanism used to retrieve processes from the secondary storage into the main memory in the form of pages.
- The main idea behind the paging is to divide each process(Address Space) into a fixed-sized unit called a page
 - Segmentation: variable size of logical segments (code, stack, heap, etc.)

- In Operating Systems, Paging is a storage mechanism used to retrieve processes from the secondary storage into the main memory in the form of pages.
- The main idea behind the paging is to split each process(Address Space) into a fixed-sized unit called a page
 - Segmentation: variable size of logical segments (code, stack, heap, etc.)
- With paging, physical memory is also split into some number of pages called a page frame.

Paging Translation?

- Page table per process is needed to translate the virtual address to physical address.
 - Similar to the segment register

Segment Register

Segment	Base	Size
Code	256KB	4KB
Heap	260KB	60KB
Stack	128KB	64KB

Paging Translation?

- Page table per process is needed to translate the virtual address to physical address.
 - Similar to the segment register

Segment Register

Segment	Base	Size
Code	256KB	4KB
Heap	260KB	60KB
Stack	128KB	64KB

Page Table


Page	Page Frame
0	3
1	7
2	5
3	2

Advantages of Paging


- Flexibility: Supporting the abstraction of address space effectively
 - Don't need assumption how heap and stack grow and are used.


Advantages of Paging

- Flexibility: Supporting the abstraction of address space effectively
 - Don't need assumption how heap and stack grow and are used.
- Simplicity: ease of free-space management
 - The page in address space and the page frame are the same size.
 - Easy to allocate and keep a free list




64-byte address space with 16 bytes pages





Physical Memory


- Two components in the virtual address
 - VPN: virtual page number
 - Offset: offset within the page




- Two components in the virtual address
 - VPN: virtual page number
 - Offset: offset within the page




Example: virtual address 21 in 64-byte address space



• Example: virtual address 21 in 64-byte address space



Example: virtual address 21 in 64-byte address space




How do I know the Virtual Address is x bits?

Address space= 64bytes log_2(64) = 6

Example: virtual address 21 in 64-byte address space

Virtual Address



How do I know the Virtual Address is x bits?


Address space = 64bytes log_2(64) = 6 (Virtual Address)

How do I know its 2 bits for VPN and 4 bits for Offset

Page Size = 16 log_2(16) = 4 (offset)

Example: virtual address 21 in 64-byte address space

Virtual Address



How do I know the Virtual Address is 6 bits?


Address space = 64bytes log₂(64) = 6 (Virtual Address)


How do I know its 2 bits for VPN and 4 bits for Offset

Page Size = 16bytes $log_2(16) = 4$ (offset)


How do I know 21 = 010101

 $21_{10} = 10101_2(5bits) = 010101_2(6bits)$






64-byte address space with 16 bytes pages





VPN = 01


PFN = 3bits



Physical Memory







Paging Translation?

- Page table per process is needed to translate the virtual address to physical address.
 - Similar to the segment register

Page Table

Page	Page Frame
0	3
1	7
2	5
3	2


Ok well where are these tables stored?

- Page tables can get large quickly
 - 32 bit address space with 4KB pages, 20bits for the VPN
 - 4MB = 2²⁰ entries x 4 bytes per page table entry
- This is too large to store entries in dedicated CPU register

Ok well where are these tables stored?

- Page tables can get large quickly
 - 32 bit address space with 4KB pages, 20bits for the VPN
 - 4MB = 2²⁰ entries x 4 bytes per page table entry
- And Therefore all of that is stored in memory

Page Table in Kernel Memory



What is in the Page Table?

• The page table is just a data structure that is used to map the virtual address to the physical address

Page Table

Page	Page Frame
0	3
1	7
2	5
3	2

In its simplest form it is just an array

What is in the Page Table?

• The page table is just a data structure that is used to map the virtual address to the physical address

Page Table Page Page Frame O 3 1 7 2 5 3 2

- In its simplest form it is just an array
- The OS indexes the array by VPN and looks up the page table entry

Page Table Entry: Example x86




- P: present bit
- R/W: read/write bit
- U/S: supervisor
- A: accessed bit
- D: dirty bit
- PFN: the page frame number

Page Table Entry: Example x86



- Valid Bit(P): Indicating whether the particular translation is valid.
- Protection Bit(R/W): Indicating whether the page could be read from, written to, or executed from
- Present Bit(P): Indicating whether this page is in physical memory or on disk(swapped out)
- **Dirty Bit(D)**: Indicating whether the page has been modified since it was brought into memory
- Reference Bit(Accessed Bit -A): Indicating that a page has been accessed

What is the issue with Paging?



What is the issue with Paging?

Size – Page tables and entries take up a lot of space in memory



What is the issue with Paging?

- Size Page tables and entries take up a lot of space in memory
- Slow 2 references per memory references

Paging is Slow?

- We need to first reference the correct page table (1 reference)
 - To find a location of the desired PTE, the starting location of the page table is needed
- Then we can reference the correct page table entry (1 reference)

Paging is Slow?

- We need to first reference the correct page table (1 reference)
 - To find a location of the desired PTE, the starting location of the page table is needed
- Then we can reference the correct page table entry (1 reference)
- Therefore, for every memory reference, paging requires the OS to perform one extra memory reference

Accessing Memory with Paging

```
// Extract the VPN from the virtual address
2 VPN = (VirtualAddress & VPN MASK) >> SHIFT
3 // Form the address of the page-table entry (PTE)
4 PTEAddr = PTBR + (VPN * sizeof(PTE))
   // Check if process can access the page
   if (PTE.Valid == False)
          RaiseException (SEGMENTATION FAULT)
   else if (CanAccess(PTE.ProtectBits) == False)
          RaiseException (PROTECTION FAULT)
10
   else
11
          // Access is OK: form physical address and fetch it
12
          offset = VirtualAddress & OFFSET MASK
13
          PhysAddr = (PTE.PFN << PFN SHIFT) | offset
14
          Register = AccessMemory(PhysAddr)
```

Accessing Memory with Paging


Example : A Simple Memory Access

Compile and Execute


```
prompt> gcc -o array array.c -Wall -o
prompt> ./array
```


Resulting Assembly code


```
0x1024 : movl $0x0, (%edi,%eax,4)
0x1028 : incl %eax
0x102c : cmpl $0x03e8,%eax
0x1030 : jne 0x1024
```















Paging is Slow?

- We need to first reference the correct page table (1 reference)
 - To find a location of the desired PTE, the starting location of the page table is needed
- Then we can reference the correct page table entry (1 reference)
- Therefore, for every memory reference, paging requires the OS to perform one extra memory reference
- How can we improve this access speed

Part of the chip's memory-management unit(MMU).




Part of the chip's memory-management unit(MMU).







Address Translation without TLB




Address Translation without TLB






• The TLB is a hardware cache of popular virtual-to-physical address translation




Address Translation with TLB

The TLB is a hardware cache of popular virtual-to-physical address translation




Address Translation with TLB

The TLB is a hardware cache of popular virtual-to-physical address translation



Address Translation with TLB

The TLB is a hardware cache of popular virtual-to-physical address translation



TLB ALgortihm

```
1: VPN = (VirtualAddress & VPN_MASK ) >> SHIFT

2: (Success , TlbEntry) = TLB_Lookup(VPN)

3: if(Success == Ture) { // TLB Hit

4: if(CanAccess(TlbEntry.ProtectBit) == True ) {

5: offset = VirtualAddress & OFFSET_MASK

6: PhysAddr = (TlbEntry.PFN << SHIFT) | Offset

7: AccessMemory( PhysAddr )

8: }else RaiseException(PROTECTION_ERROR)
```

- (1) extract the virtual page number(VPN).
- (2) check if the TLB holds the translation for this VPN.
- (5-8) extract the page frame number from the relevant TLB entry, and form the desired physical address and access memory.


TLB ALgortihm

```
}else{ //TLB Miss
11:
12:
           PTEAddr = PTBR + (VPN * sizeof(PTE))
13:
           PTE = AccessMemory(PTEAddr)
14:
           if (PTE.VALID == FALSE) {
15:
                RaiseException (SEGMENTATION FAULT)
           else if (CanAccess(PTE.ProtectBits) == False) {
16:
17:
                RaiseException (PROTECTION FAULT)
18:
           }else{
19:
                TLB Insert ( VPN , PTE.PFN , PTE.ProtectBits)
20:
                RetryInstruction()
21:
22:}
```

- (12-13) The hardware accesses the page table to find the translation.
- (19) updates the TLB with the translation.

A TLB Entry

The TLB is a hardware cache of popular virtual-to-physical address translation




A TLB Entry

- TLB is managed by Full Associative method.
 - A typical TLB might have 32, 64, or 128 entries.
 - Hardware search the entire TLB in parallel to find the desired translation.
 - Other bits: valid bits, protection bits, address-space identifier, dirty bit




Typical TLB entry look like this

```
0: int sum = 0 ;
1: for( i=0; i<10; i++) {
2:     sum+=a[i];
3: }</pre>
```




```
0:    int sum = 0 ;
1:    for( i=0; i<10; i++) {
2:       sum+=a[i];
3:    }</pre>
```

 When the first array element (a[0]) is accessed, the CPU will see a load to virtual address 100




```
0:    int sum = 0 ;
1:    for( i=0; i<10; i++) {
2:       sum+=a[i];
3:    }</pre>
```

- When the first array element (a[0]) is accessed, the CPU will see a load to virtual address 100
- The hardware extracts the VPN from this (VPN=06), and uses that to check the TLB for a valid translation.




VPN	PFN	other bits
06	03	-

- When the first array element (a[0]) is accessed, the CPU will see a load to virtual address 100
- The hardware extracts the VPN from this (VPN=06), and uses that to check the TLB for a valid translation.
- Assuming this is the first time the program accesses the array, the result will be a TLB miss.
- Add new TLB Entry




VPN	PFN	other bits
06	03	-

- The next access is to a[1]
- The hardware extracts the VPN from this (VPN=06), and uses that to check the TLB for a valid translation.




VPN	PFN	other bits
06	03	-


- The next access is to a[1]
- The hardware extracts the VPN from this (VPN=06), and uses that to check the TLB for a valid translation.
- Some good news here: a TLB hit! Because the second element of the array is packed next to the first, it lives on the same page which had already been loaded into the TLB





VPN	PFN	other bits
06	03	-


- The next access is to a[2]
- (VPN=06)
- TLB hit!













VPN	PFN	other bits
06	03	-
07	08	-
08	02	-

- The next access is to a[7]
- (VPN=08)
- TLB miss!
- Load translation into TLB






-	_			_
				_
				_
		L	_	_

VPN	PFN	other bits
06	03	-
07	08	-
08	02	-


- The next access is to a[9]
- (VPN=08)
- TLB hit!



Locality

Temporal Locality

 An instruction or data item that has been recently accessed will likely be re-accessed soon in the future




Virtual Memory

Locality

Temporal Locality


 An instruction or data item that has been recently accessed will likely be re-accessed soon in the future



Virtual Memory

Spatial Locality

• If a program accesses memory at address \mathbf{x} , it will likely soon access memory near \mathbf{x}



Virtual Memory

• Well there are 2 approaches

Hardware handle the TLB miss entirely on CISC

- Hardware handle the TLB miss entirely on CISC
 - The hardware has to know exactly where the page tables are located in memory.
 - The hardware would "walk" the page table, find the correct page-table entry and extract the desired translation, update and retry instruction.
 - hardware-managed TLB.

- Hardware handle the TLB miss entirely on CISC
 - The hardware has to know exactly where the page tables are located in memory.
 - The hardware would "walk" the page table, find the correct page-table entry and extract the desired translation, update and retry instruction.
 - hardware-managed TLB.
- RISC have what is known as a software-managed TLB

Hardware handle the TLB miss entirely on CISC

- The hardware has to know exactly where the page tables are located in memory.
- The hardware would "walk" the page table, find the correct page-table entry and extract the desired translation, update and retry instruction.
- hardware-managed TLB
- Complex Instruction Set Computing


RISC have what is known as a software-managed TLB

- On a TLB miss, the hardware raises exception(trap handler).
- Trap handler is code within the OS that is written with the express purpose of handling TLB miss.
- Reduced instruction set computer


Ok so job Done?

• The TLB in its current form solves all our problems

TLB Issue: Context Switching



TLB Issue: Context Switching



TLB Issue: Context Switching

Process A

Process B

Page 0
Page 1
Page 2
...
Page n

Virtual Memory

Page 0
Page 1
Page 2
...
Page n
Virtual Memory

TLB Table

	VPN	PFN	valid	prot	
<u></u>	10	100	1	rwx	
	-	-	-		
<u> </u>	10	170	1	rwx	
	-	-	-	-	

Can't Distinguish which entry is meant for which process

TLB Issue: Page Sharing

- Two processes share a page.
 - Process 1 is sharing physical page 101 with Process2
 - P1 maps this page into the 10th page of its address space
 - P2 maps this page to the 50th page of its address space

VPN	PFN	valid	prot
10	101	1	rwx
-	-	-	-
50	101	1	rwx
-	-	-	-


Sharing of pages is useful as it reduces the number of physical pages in use.

TLB Issue: Context Switching - Solution

 Provide an address space identifier(ASID) field in the TLB

Process A

Process B



Page 0
Page 1
Page 2
...
Page n

Virtual Memory

TLB Table

VPN	PFN	valid	prot	ASID
10	100	1	rwx	1
-	-	-	-	0-/
10	170	1	rwx	2
-	-	-	-	-

What happens when we want to add a new entry

- Problem We need to add a new entry to the TLB
 - Well where do we put it and if needed which entry do we replace

TLB Issue : Replacement Policy

- In order to add new entries a replacement policy is used
- The general idea with these policies is that you want to minimize the miss rate and hence maximise the hit rate

TLB Issue : Replacement Policy

- In order to add new entries a replacement policy is used
- The general idea with these policies is that you want to minimize the miss rate and hence maximise the hit rate
- LIFO
- FIFO
- Random
- LRU

TLB Issue: Replacement Policy - Solution


- LRU (LEAST RECENTLY USED)
 - Evict an entry that has not recently been used.
 - Take advantage of locality in the memory-reference stream

TLB Issue: Replacement Policy - Solution

- LRU (LEAST RECENTLY USED)
 - Evict an entry that has not recently been used.
 - Take advantage of locality in the memory-reference stream
 - Add a register to every page frame contain the last time that the page in that frame was accessed
 - Use a "logical clock" that advance by 1 tick each time a memory reference is made.
 - Each time a page is referenced, update its register


TLB Issue: Replacement Policy - Solution

- LRU (LEAST RECENTLY USED)
 - Evict an entry that has not recently been used.
 - Take advantage of locality in the memory-reference stream



A Real TLB Entry

All 64 bits of this TLB entry(example of MIPS R4000)



Flag	Content
19-bit VPN	The rest reserved for the kernel.
24-bit PFN	Systems can support with up to 64GB of main memory($2^{24}*4KB$ pages)
Global bit(G)	Used for pages that are globally-shared among processes.
ASID	OS can use to distinguish between address spaces.
Coherence bit(C)	determine how a page is cached by the hardware.
Dirty bit(D)	marking when the page has been written.
Valid bit(V)	tells the hardware if there is a valid translation present in the entry.