Kernel 8.0 & Kernel Toolkit 7.3 Systems Management Guide



August 2016

Department of Veterans Affairs (VA)

Office of Information and Technology (OI&T)

Enterprise Program Management Office (EPMO)

Revision History

Date	Version	Description	Author
08/10/2016	7.2	 Tech Edits: Updated Section 15.1.3.2 and 15.6.4.2 for additional HOST file examples and clarifications. Updated all TOCs, lists, cross-references, etc. 	Developer: H. W. Technical Writer: T. B.
08/09/2016	7.1	Tech Edits based on Kernel patches XU*8.0*655, 659, and 667: Updated Directive 6402 reference in the "Software Disclaimer" section. Updated/Added the following sections for 2-factor authentication-related information: 2.1, 3.1, 3.1.2.16 (new), 3.5.4, 4.2.8.1, 6.7.1, 6.7.2, and 6.7.3. Updated Section 2.1.1 to indicate that the caret (^) is a reserved symbol and added a reference to and VA Directive and Handbook 6500. Updated Section 2.1.1.1 for long password future changes pending. Updated Figure 8. Added TITLE and ELECTRONIC SIGNATURE COD fields to Table 3. Updated Figure 13 for 2-factor authentication. Added the NETWORK USERNAME field to Table 4. Updated Figure 25. Added Cautionary note to Section 3.4.2.1. Added references to Broker Security Enhancement (BSE) in Sections 3.5.8 and 3.5.11. Updated references to CPRS documentation in Section 6.1. Updated the "XU USER START-UP Option" section; merged from (deleted) Section 6.4.15. Software Versions: Kernel 8.0 Toolkit 7.3	Developer: H. W. Technical Writer: T. B.
07/19/2016	7.0	Updates:Moving the "System Management Menus" section and sub-sections from this	Technical Writer: T. B.

Date	Version	Description	Author
		document into the Kernel Technical Manual. Updated Figure 51 and Figure 53 to remove extraneous/test-only options from the menu. Updated the "Prohibited Times" section to include information regarding TaskMan scheduled options. Added Caution note regarding modification of Kernel routines in the "Software Disclaimer" section. Converted Word document to .docx format. Reformatted document to follow latest documentation standards and formatting rules. Also, formatted document for online presentation vs. print presentation (i.e., for double-sided printing). These changes include: Revised section page setup. Removed section headers. Revised document footers. Revised document footers. Revised all heading style formatting. Updated organizational references (e.g., "Product Development [PD]" to "Enterprise Program Management Office [EPMO]). Redacted document for the following information: Names (replaced with role and initials). Production IP addresses and ports. VA Intranet websites. Server geographic locations and node names. Software Versions: Kernel 8.0 Toolkit 7.3	
05/31/2013	6.2	Updates: • Updates for patch XU*8.0*614 based on feedback from H. W.: • Added the Single User Menu Tree Rebuild option [XQBUILDUSER] to the "Single User Menu Tree Rebuild" It was attached to the Menu Rebuild Menu option [XQBUILDMAIN]. • Added the XQBUILDMAIN option.	Developer: H. W. Technical Writer: T. B.

Date	Version	Description	Author
		 Added the XQ LIST UNREFERENCED OPTIONS option. Added the XQ MENUMANAGER PROMPT parameter to the "Menu Startup Parameter" section. Added the "System Management Menus" section. This section lists and briefly describes all Kernel operations, management, user, and developer-related menus and options. It also includes cross-reference links to existing sections that further describe a menu or option elsewhere in this document. Renamed and updated the "User Management Menu" section. Software Versions: Kernel 8.0 	
04/30/2013	6.1	Toolkit 7.3 Tech edit updates: XU*8.0*580: Updated document for Kernel patch XU*8.0*580 in support of the Drug Enforcement Agency (DEA) e-Prescribing of Controlled Substances (CS) (ePCS) using Public Key Infrastructure (PKI). Added the "DEA ePCS Utility" section with the following subsections: Processes Configuring the DEA ePCS Utility, including instructions to: Set the XUEPCS REPORT DEVICE Parameter. Add DEA ePCS Utility Users. Using the DEA ePCS Utility (includes description of all Menus/Options). Prescription Validation and Verification Process—PKIServer.exe Application PIV Card Validation—Revocation Server Windows Authentication and Cryptographic Operations Reformatted document to follow current style guide and standards. Replaced references from "VA FileMan"	Developers: C. A., J. I., A. L., R. Men., and H. W. Technical Writer: T. B.

Date	Version	Description	Author
		22.n software version will create a new "VA FileMan Getting Started Manual." Patches XU*8.0*602: Updated the following sections, as per H. W.: "Processing Alerts" section. "Surrogates and Alerts" section. "Surrogates and Alerts" section. "Updated the "Understanding DUZ (User Number)" section to give a more detailed explanation and examples of the DUZ array. Updated the "KEEP AT TERMINATE" section as per email from C. A., J. I., A. L., and H. W. Patch XU*8.0*546: Support for Device Hunt Groups was removed. This includes removal of the *HUNT GROUP (#29) and HUNT GROUP DEVICE (#30) fields in the DEVICE file (#3.5). Sites had to remove any HUNT GROUP devices before installing this patch using VA FileMan to find any existing Hunt Groups. "Hunt Groups" section was deleted from this manual. Also, any references to "Hunt Groups" were removed. Added blue font highlighting and underline to signify internal links to figures, tables, or sections for ease of use, similar to what one sees to hyperlinks on a Web page. Updated document for Section 508 conformance using word's built-in Accessibility check: Added table bookmarks. Added screen tips for all URL links. Changed all floating callout boxes to in-line, causing reformatting of numerous dialogue screen captures. Software Versions: Kernel 8.0 Toolkit 7.3	
06/06/2012	6.0	 Updates: Added the "XU USER START-UP Option" section. The XU USER START-UP option was added with Kernel patch XU*8.0*593. Added Section 15.6.4 "Verify HFS and Null Device Setup (required)," in the "Troubleshooting" section in "Device Handler: System Management." Updated all VA organizational references. 	Office of Information Field Office (OIFO): • Maintenance Development Manager—J. Sch. • Developers—G. B., R. D., J. I., R. Men., R. Met., B. T., and H. W. • Technical Writer—T. B.

Date	Version	Description	Author
		 Revised all version numbers in the "Revision History" section. Updated the "Orientation" section. Updated the overall document for current national documentation standards and style guides. For example: Changed all Heading n styles to use Arial font. Changed all Heading n styles to be left justified. Software Versions: Kernel 8.0 	
03/22/2010	5.3	Updates: • Added Section 24.3, "Edit Install Status Option released with Kernel patch XU*8.0*539. • Added Figure 24-4 Edit Install Status option—Sample user dialogue. Software Versions: Kernel 8.0 Toolkit 7.3	Office of Information Field Office (OIFO): • Maintenance Development Manager—J. Sch. • Developers—G. B., A. C., R. D., W. F., J. G., J. I., R. Men., R. Met., and B. T. • Technical Writers—T. B. and S. S.
11/16/2009	5.2	 Updated references to the CHCKSUM^XTSUMBLD direct mode utility throughout. Updated organizational references. Minor format updates (e.g., reordered document revision history table to display latest to earliest, added outline numbering). Other minor format updates to correspond with the latest standards and style guides. Updated the "Automatically Deactivating Users" section in "Signon/Security: System Management" for Kernel patch XU*8.0*514. Re-ordered and edited all topics in the "Device Handler: System Management" section. Also, added updates to the Device handler based on Kernel patch XU*8.0*440. Moved the following section content from the Kernel Systems Management Guide to the Kernel Developer's Guide, because the 	OIFO: Maintenance Development Manager—J. Sch. Developers—G. B., A. C., R. D., W. F., J. G., J. I., R. Men., R. Met., and B. T. Technical Writers—T. B. and S. S.

functions documented are more developer- related than system management-related: Miscellaneous Programmer Tools: Programmer Options Menu and %Z Editor; see the "Miscellaneous Developer Tools" section in the Kernel Developer's Guide. Routine Tools; see the "Routine Tools" section in the "Toolkit: Developer Tools" section in the Kernel Developer's Guide. Verification Tools; see the "Verification Tools" section in the "Toolkit: Developer Tools" section in the Kernel Developer's Guide. XGF Function Library; see the "XGF Function Library" section in the Kernel	
Developer's Guide.	
 Updated Section <u>9.1.3</u> and <u>9.1.6.2</u> for Kernel patch XU*8.0*482. Reviewed and updated all sections for minor format changes (e.g., bulleted lists and tables), style updates, spelling, and grammar fixes. Software Versions: Kernel 8.0 	
Toolkit 7.3	
 Updates: Updated the "<u>Defining a Strong Verify Code</u>" section. Updated the "<u>File Access Security</u>" section based on the newly created VA FileMan (Version 22) and Kernel (Version 8.0) File Access Security supplemental document on the VA Software Document Library (VDL). Deleted "Default Task Priority" section from this manual. Moved the "<u>Error Screens</u>" section from the "<u>TaskMan: System Management—Operation</u>" section to the "<u>Error Processing</u>" section. 	 OIFO: Maintenance Development Manager—J. Sch. Developers—G. B., A. C., R. D., W. F., J. G., J. I., R. Men., R. Met., S. O., and B. T. Technical Writer—T. B. and S. S.

Date	Version	Description	Author
		and the document properties (e.g., Title, Author, Creation Dates, Keywords, etc.). • Updated references to the VDL. • Removed all references to HSD&D. • Updated Alert options in Figure 10-3 and added the missing descriptions for those Alert-related options. • Completed updates to remove obsolete references to MSM, PDP, 486, VAX Alpha, etc. and updated references to DSM for OpenVMS to Caché where appropriate. • Updated content references to checksum compares based on Kernel patch XU*8.0*393. • Changed references from "%INDEX" to "XINDEX" where appropriate. • Updated Section III, Device Handler. • Deleted "Kermit" section. • Updated "Special Queueing" section in "TaskMan: System Management—Operation." Added Table 40. • Updated "Security Forms" section in "Signon/Security: System Management." Software Versions: Kernel 8.0 Toolkit 7.3	
02/08/2007	5.0	The Kernel Toolkit documentation set is being combined with the Kernel documentation set. All Kernel Toolkit content will be moved to the appropriate Kernel manual, section, and chapter. In the Kernel Systems Management Guide, the following Kernel Toolkit chapters have been added to the Section VI, "Toolkit:" • Multi-Term Look-Up (MTLU) • Routine Tools • Verification Tools • Also Changed Kernel document title references to: • Kernel Developer's Guide (previously known as the Kernel Programmer Manual). • Kernel Systems Management Guide (previously known as the Kernel Systems Manual). Software Versions:	 OIFO: Maintenance Development Manager—J. Sch. Developers—A. C., W. F., J. G., J. I., M. M., R. Men., R. Met., S. O., and B. T. Technical Writer—T. B. and S. S.

Date	Version	Description	Author
		Kernel 8.0	
		Toolkit 7.3	
07/13/2006	4.0	 Made minor formatting updates throughout. Changed the original "Other Tools" section to become the "Toolkit" section, see note below. Added "Multi-Term Look-Up (MTLU)" and "Tools" chapters from the original Toolkit User Manual (7.3), see note below. Removed the "Response Time Measures" section from the original "Capacity Management" chapter in the Toolkit User Manual (7.3), see note below. Kernel Toolkit patch XT*7.3*102 removed all Response Time Log Option menu options [XURTL*]. All Kernel Toolkit content currently in the Kernel Toolkit User Manual and Kernel Toolkit Technical Manual is being absorbed by the Kernel Systems Management Guide, Kernel Developer's Guide, and Kernel Technical Manual. Other Toolkit content has been replaced by other manual sets, including: Duplicate Record Merge: Patient Merge Resource Usage Monitor (RUM) Statistical Analysis of Global Growth (SAGG) Capacity Management (CM) Tools Software Versions: Kernel 8.0 Toolkit 7.3 	OIFO: • Maintenance Development Manager—J. Sch. • Developers—A. C., W. F., and J. I. • Technical Writer:—T. B. and S. S.
02/03/2006	3.0	 Updates: Reformatted document to the latest SOP and Style Guidelines. Updated files, routines, options, APIs, security keys, etc. Software Version: 8.0 	OIFO Legacy VistA Maintenance Team
12/20/2004	2.1	Reviewed document and edited for the "Data Scrubbing" and the "PDF 508 Compliance" projects. Data Scrubbing—Changed all patient/user TEST data to conform to OI&T standards and conventions as indicated below:	Technical Writer—T. B.

Date	Version	Description	Author
		The first three digits (prefix) of any Social Security Numbers (SSN) start with "000" or "666." Patient or user names are formatted as follows: XUPATIENT,[N] or XUUSER,[N] respectively, where the N is a number written out and	
		incremented with each new entry (e.g., XUPATIENT, ONE, XUPATIENT, TWO, etc.).	
		Other personal demographic-related data (e.g., addresses, phones, IP addresses, etc.) were also changed to be generic.	
		PDF 508 Compliance—The final PDF document was recreated and now supports the minimum requirements to be 508 compliant (i.e., accessibility tags, language selection, alternate text for all images/icons, fully functional Web links, successfully passed Adobe Acrobat Quick Check).	
		Software Version: 8.0	
12/09/2004	2.0	Kernel 8.0 documentation reformatting/revision.	Technical Writer—T. B.
		This is the initial complete reformatting of the Kernel Systems Management Guide since its original release in July 1995.	
		The largest change with the <i>Kernel Systems Management Guide</i> is that all developerspecific content has been extracted and placed into a new <i>Kernel Developer's Guide</i> .	
		Also, at this point in time, only minimal content updates have been made based on select released Kernel patches. Due to time constraints, not all released Kernel patches with content changes have been added at this time. We wanted to get a new baseline document published so that in the future we can more easily update the Kernel Systems Management Guide.	
		As time allows, we will be updating this reformatted manual with all released patch information that affects its content. Because of the chapter-numbering scheme, future additions can be made with minimal disruption to the entire manual page flow.	
		Thanks for your patience! Software Version: 8.0	
07//1995	1.0	Initial Kernel 8.0 software and documentation release	Office of Information Field Office (OIFO):
		Software Version: 8.0	Project Manager—H.

Date	Version	Description	Author
			V.B.
			Developers—Kernel Development Team
			Technical Writer—K. C.

Patch Revisions

For the current patch history related to this software, see the Patch Module on FORUM.

Table of Contents

Re	vision History		ii
Lis	st of Figures		xxv
Lis	st of Tables		xxxv
Or	ientation		xxxvii
1	Introduction	n	1
	1.1 Users		1
	1.2 System	Managers	2
l.	Signon/Se	curity	4
2	Signon/Sed	curity: User Interface	4
	2.1 Signing	On	4
	2.1.1 De	fining a Strong Verify Code	6
	2.1.1.1	Why Longer Passwords?	7
	2.1.2 LO	GIN Menu Template	7
	2.1.3 Sig	gnon Shortcuts	8
		rmal Signoff	
		normal Signoff and Error Handling	
		rminal Type Prompt	
	-	ng from a Jumbled Screen	
		Toolbox Menu	
	_	my Division Option	
		er Characteristics Option	
	• •	User Characteristics Option	
		UCI Option	
		ry	
3	Signon/Sed	curity: System Management	15
	3.1 Signon	Process	15
	3.1.1 Inti	roductory Text	15
		rameters Checked during Signon	
	3.1.2.1	Signon Attempts and Device Lock-out Times	16
	3.1.2.2		
	3.1.2.3		
	3.1.2.4	1 9	
	3.1.2.5		
	3.1.2.6		
	3.1.2.7	1 7 ' '	
	3.1.2.8		
		LIFETIME OF VERIFY CODE	
		0 AUTO-GENERATE ACCESS CODES	
	3.1.2.1	1 DEFAULT INSTITUTION and AGENCY	19

	3.1.2	2.12 AUTO MENU	20
	3.1.2	2.13 TYPE-AHEAD	20
	3.1.2	2.14 TIMED READ	20
	3.1.2	2.15 POST SIGN-IN MESSAGE	20
	3.1.2	2.16 2-Factor Authentication	21
3.1	1.3	XU USER SIGN-ON Option	21
3.1	1.4	XU USER START-UP Option2	21
3.1	1.5 (Clear all users at startup Option	22
3.1	I.6 I	Enabling and Disabling Logons2	22
3.2	Addin	ng New Users	22
3.2	2.1	Add a New User to the System Option2	22
	3.2.	1.1 NEW PERSON File (#200) Required Fields	23
3.2	2.2	Grant Access by Profile Option	23
3.2	2.3	Security Forms2	24
3.3	Edit a	n Existing User Option	31
3.3	3.1	Additional Attributes Editable by Users	38
3.3	3.2 I	Edit User Characteristics Form and Template	39
3.4	Deact	tivating and Reactivating Users	39
3.4	↓.1 I	Deactivating Users	40
3.4	1.2	Automatically Deactivating Users4	
	3.4.2	2.1 Termination Process	41
	3.4.2	2.2 Academic Affiliation Waiver	42
3.4	1.3 I	Purging Mail and Security Keys for Inactive Users4	42
3.4		Reactivating Users	
3.5	User I	Management Menu4	43
3.5	5.1 I	Find a User Option4	43
3.5	5.2 I	Proxy User List Option	43
3.5	5.3 I	List Users Option	43
3.5		Print Sign-on Log Option4	
3.5		Proxy (Connector) Detail Report Option	
3.5		Proxy (Connector) Inquire Option	
3.5		Release user Option4	
3.5		Remote Access User Sign-on Log Option4	
3.5		User Inquiry Option	
		User Status Report Option4	
		Users with Foreign Visits Option	
3.6	_	on Audits	
3.6		Signon Statistics	
3.6		Failed Access Attempts Audit	
3.6		Purge Old Access and Verify Codes	
File	Acce	ess Security4	19
4.1	User l	Interface	49
4.2 System Management		50	

4

	4.2.1	When is File Access Security Checked?	51
	4.2.2	What in VA FileMan is Still Protected by the File Manager Access Code?	51
	4.2.3	Purpose for Granting File Access	51
	4.2.4	Who Needs File Access?	52
	4.2.5	Levels of File Access Security	52
	4.2.6	Audit Access to Files	55
	4.2.7	How to Grant File Access	55
	4.2.8	Using the File Access Options	
	4.2	.8.1 Understanding DUZ (User Number)	
	4.2	.8.2 Using Ranges of File Numbers	
		.8.3 Queuing File Access Specifications	
	4.3 Runi	ning the File Access Security Conversion	
	4.3.1	Advantages	
	4.3.2	Advance Preparation for the Conversion	
		.2.1 ^DISV Global	
	_	.2.2 Adding Explicit File Access for System Administrators	
	4.3.3	Summary of the File Access Security Conversion	
	4.3.4	File Access Security Conversion Instructions	
	4.3.5	After the File Access Security Conversion	
5	Electron	iic Signatures	67
	5.1 User	Interface	67
	5.1.1	Electronic Signature code Edit Option	67
	5.2 Syst	em Management	67
	5.2.1	Electronic Signature Block Edit Option	67
	5.2.2	Clear Electronic signature code Option	68
3	DEA eP	CS Utility	69
		view	
	6.1.1	History	
	6.1.2	Requirements	70
	6.1.3	Benefits	71
	6.1.4	Intended Audience	
	6.2 Proc	esses	72
	6.2.1	Manual Paper-based Process	72
	6.2.2	e-Prescribing Process	73
	6.3 Conf	figuring the DEA ePCS Utility	75
	6.3.1	Set the XUEPCS REPORT DEVICE Parameter	75
	6.3	.1.1 General Parameter Tools Menu	75
	6.3	.1.2 XPAREDIT Routine	77
	6.3.2	Add DEA ePCS Utility Users	78
	6.3	.2.1 Assign the XUEPCSEDIT Security Key	78
	6.3	.2.2 Assign the XU EPCS EDIT DATA Option	80
	6.3	.2.3 Assign the XUSSPKI UPN SET Option	83
	6.4 Usin	g the DEA ePCS Utility	86

	6.4.1	DEA ePCS Utility Functions Main Menu	86
	6.4.2	Print DEA Expiration Date Null Option	89
	6.4.3	Print DISUSER DEA Expiration Date Null Option	90
	6.4.4	Print DEA Expiration Date Expires 30 days Option	92
	6.4.5	Print DISUSER DEA Expiration Date Expires 30 days Option	93
	6.4.6	Print Prescribers with Privileges Option	94
	6.4.7	Print DISUSER Prescribers with Privileges Option	96
	6.4.8	Print PSDRPH Key Holders Option	98
	6.4.9	Print Setting Parameters Privileges Option	99
	6.4.10	Print Audits for Prescriber Editing Option	100
	6.4.11	Task Changes to DEA Prescribing Privileges Report Option	
	6.4.12	Task Allocation Audit of PSDRPH Key Report Option	106
	6.4.13	Allocate/De-Allocate of PSDRPH Key Option	
	6.4.14	Edit Facility DEA# and Expiration Date Option	
	6.4.15	ePCS Edit Prescriber Data Option	
	6.4.16	ePCS Set SAN from PIV Card Option	
		4.16.1 XUSSPKI SAN Bulletin	
	6.5 Pre	scription Validation and Verification Process—PKIServer.exe Ap	
	6.6 PIV	Card Validation—Revocation Server	
		ndows Authentication and Cryptographic Operations	
	6.7.1	History	
	6.7.2	Current Capabilities	
	6.7.3	Future Capabilities	
I.	Menu M	Manager	
7		Manager: User Interface	
•		vigating Kernel's Menus	
	7.1.1	Choosing Options	
	7.1.2	Listing Options	
	7.1.3	Displaying Option Help	
	7.1.4	Listing Secondary and Common Options	
	7.1.5	Displaying Option Descriptions	
	7.1.6	Jumping to Options—"Up-arrow Jump")	
	7.1.7	Jumping to Options—"Rubber-band Jump"	
	7.1.8	Common Menu	
	7.	1.8.1 Selecting Common Options with the Double Quote	121
	7.2 Mei	nu Templates Option	122
	7.2.1	LOGIN Menu Template	122
	7.3 Sur	mmary	123
8	Menu N	Manager: System Management	124
		ating Menus and Options	
	8.1.1	Option Name and Menu Text	
	8.1.2	Synonyms and Display Order	126

	8.1.	.3	PRIORITY	126
	8.1.	.4	HELP FRAME	126
	8.1.	.5	DISPLAY OPTION	126
	8.1.	.6	If the Option Invokes Non-VistA Applications	126
	8.1.	.7	If the Option Should Be Regularly Scheduled	126
	8.1.	.8	Auditing Option Use	127
8.2		Disp	lay Menus and Options Menu	128
	8.2.	.1	Diagramming Options	128
	8.2.	.2	Option Descriptions	129
	8.2.	.3	Displaying Options	129
	8.2.	.4	Option Access by User Option	129
8.3		Mana	aging Menus and Options	130
	8.3.	.1	Managing Primary Menus	130
	8.3.	.2	Assigning Secondary Menus	130
	8.3.	.3	ALWAYS SHOW SECONDARIES Field	130
	8.3.	.4	Redefining the Common Menu	130
	8.3.	.5	Altering Exported Menus	131
	8.3.	.6	Delete Unreferenced Options Option	
	8.3.	.7	Fix Option File Pointers Option	131
	8.3.	.8	Testing a User's Menus	
	8.3.	.9	Managing Out-Of-Order Option Sets	132
8.4		Rest	ricting Option Usage	133
	8.4.	.1	Setting Options Out of Order	
	8.4.		Locks	
	8.4.	.3	Prohibited Times	
	8.4.		Permitted Devices	
	8.4.		QUEUING REQUIRED Flag	
8.5			u Manager Options that Should Be Scheduled	
	8.5.		Clean Old Job Nodes in XUTL Option	
	8.5.		Rebuilding Primary Menu Trees	
			r Messages during Menu Jumping	
8.7			ΓL Global: Structure and Function	
	8.7.		User Stacks	
	8.7.		XQT Nodes (MENU Templates)	
	8.7.		Display Nodes	
	8.7.		Jump Nodes	
8.8			u Startup Parameter	
8.9			u Manager Variables (Troubleshooting)	
8.1			ırity Keys	
8.1			Interface	
8.1		-	em Management	
	8.12		Identifying Locked Options	
	8.12		Key Management	
	8.12	2.3	Allocating and De-allocating Security Keys	144

8.12.5 Creating and Editing Security Keys 8.12.5.1 PERSON LOOKUP 8.12.5.2 SLEPAT TERMINATE 8.12.5.3 SUBORDINATE KEY (Exploding Keys) 8.12.6 Deleting Security Keys. 8.12.7 Reindexing All Users' Security Keys Option. 8.12.8 Using Security Keys with Reverse Locks 8.12.9 Security Key Delegation Levels. 9 Secure Menu Delegation. 9.1 User Interface: Acting as a Delegate. 9.1.1 Delegate's Menu. 9.1.2 Edit a User's Options Option. 9.1.3 Build a New Menu Option 9.1.4 Copy Everything About an Option to a New Option Option 9.1.5 Copy One Users Menus and Keys to others Option. 9.1.6 Limited File Manager Options (Build) Option 9.1.6.1 Characteristics of Intended Users. 9.1.6.2 System Administrator Setup to Enable Building Options from Template 9.1.6.3 Building Options 9.2 System Management: Managing Delegates. 9.2.1 Delegating Options: Select Options to be Delegated Option 9.2.1 Delegating Options Select Options to be Delegated Option 9.2.1 Delegating Security Keys. 9.2.1 Delegating Security Keys. 9.2.2 Further Delegation Level (Options and Keys) 9.2.3 Options too Sensitive to Delegate 9.2.4 Replicate or Replace a Delegate Option 9.2.5 Remove Options Previously Delegated Option 9.2.6 Specify Allowable New Menu Prefix Option. 9.2.7 Reports. 10. Alerts. 10.1 User Interface. 10.1.1 Processing Alerts. 10.1.2 Deleting Alerts. 10.1.3 Forwarding Alerts. 10.1.4 Surrogates and Alerts. 10.2.1 Alert Management Menu. 10.2.1.1 Alerts - Set/Remove Surrogate for Users Option 10.2.1.2 Delete Old (>14 d) Alerts Option. 10.2.1.3 Make an Alert on the Fly Option.		8.12.4	Delegating Security Keys	145
8.12.5.2 KEEP AT TERMINATE 8.12.5.3 SUBORDINATE KEY (Exploding Keys). 8.12.6 Deleting Security Keys. 8.12.7 Reindexing All Users' Security Keys Option. 8.12.8 Using Security Keys with Reverse Locks. 8.12.9 Security Key Delegation Levels. 9 Secure Menu Delegation. 19.1 User Interface: Acting as a Delegate		8.12.5	Creating and Editing Security Keys	146
8.12.5.3 SUBORDINATE KEY (Exploding Keys) 8.12.6 Deleting Security Keys. 8.12.7 Reindexing All Users' Security Keys Option		8.′	12.5.1 PERSON LOOKUP	146
8.12.6 Deleting Security Keys 8.12.7 Reindexing All Users' Security Keys Option 8.12.8 Using Security Keys with Reverse Locks 8.12.9 Security Key Delegation Levels. 9 Secure Menu Delegation		8.1	12.5.2 KEEP AT TERMINATE	146
8.12.6 Deleting Security Keys 8.12.7 Reindexing All Users' Security Keys Option 8.12.8 Using Security Keys with Reverse Locks 8.12.9 Security Key Delegation Levels. 9 Secure Menu Delegation		8.1	12.5.3 SUBORDINATE KEY (Exploding Keys)	146
8.12.8 Using Security Keys with Reverse Locks 8.12.9 Security Key Delegation Levels. 9 Secure Menu Delegation		8.12.6	Deleting Security Keys	147
8.12.9 Security Key Delegation Levels		8.12.7	Reindexing All Users' Security Keys Option	147
9 Secure Menu Delegation		8.12.8	Using Security Keys with Reverse Locks	147
9.1 User Interface: Acting as a Delegate 9.1.1 Delegate's Menu 9.1.2 Edit a User's Options Option 9.1.3 Build a New Menu Option 9.1.4 Copy Everything About an Option to a New Option Option 9.1.5 Copy One Users Menus and Keys to others Option 9.1.6 Limited File Manager Options (Build) Option 9.1.6.1 Characteristics of Intended Users 9.1.6.2 System Administrator Setup to Enable Building Options from Template 9.1.6.3 Building Options 9.2 System Management: Managing Delegates 9.2.1 Delegating Options: Select Options to be Delegated Option 9.2.1.1 Delegating Security Keys 9.2.1.2 Delegation Level (Options and Keys) 9.2.3 Options too Sensitive to Delegate 9.2.4 Replicate or Replace a Delegate Option 9.2.5 Remove Options Previously Delegated Option 9.2.6 Specify Allowable New Menu Prefix Option 9.2.7 Reports 10.1 User Interface		8.12.9	Security Key Delegation Levels	147
9.1.1 Delegate's Menu	9	Secure	Menu Delegation	149
9.1.2 Edit a User's Options Option 9.1.3 Build a New Menu Option 9.1.4 Copy Everything About an Option to a New Option Option 9.1.5 Copy One Users Menus and Keys to others Option 9.1.6 Limited File Manager Options (Build) Option 9.1.6.1 Characteristics of Intended Users 9.1.6.2 System Administrator Setup to Enable Building Options from Template 9.1.6.3 Building Options 9.2 System Management: Managing Delegates 9.2.1 Delegating Options: Select Options to be Delegated Option 9.2.1.1 Delegating Security Keys 9.2.1.2 Delegation Level (Options and Keys) 9.2.2 Further Delegation 9.2.3 Options too Sensitive to Delegate 9.2.4 Replicate or Replace a Delegate Option 9.2.5 Remove Options Previously Delegated Option 9.2.6 Specify Allowable New Menu Prefix Option 9.2.7 Reports 10 Alerts 11.1 User Interface 10.1.1 Processing Alerts 10.1.2 Deleting Alerts 10.1.4 Surrogates and Alerts 10.2.1 Alert Management 10.2.1.1 Alerts - Set/Remove Surrogate for Users Option 10.2.1.2 Delete Old (>14 d) Alerts Option.		9.1 Use	r Interface: Acting as a Delegate	149
9.1.3 Build a New Menu Option		9.1.1	Delegate's Menu	149
9.1.4 Copy Everything About an Option to a New Option Option 9.1.5 Copy One Users Menus and Keys to others Option 9.1.6 Limited File Manager Options (Build) Option 9.1.6.1 Characteristics of Intended Users. 9.1.6.2 System Administrator Setup to Enable Building Options from Template 9.1.6.3 Building Options. 9.2 System Management: Managing Delegates. 9.2.1 Delegating Options: Select Options to be Delegated Option 9.2.1.1 Delegating Security Keys 9.2.1.2 Delegation Level (Options and Keys). 9.2.2 Further Delegation. 9.2.3 Options too Sensitive to Delegate 9.2.4 Replicate or Replace a Delegate Option 9.2.5 Remove Options Previously Delegated Option 9.2.6 Specify Allowable New Menu Prefix Option. 9.2.7 Reports. 10 Alerts 10.1 User Interface. 10.1.1 Processing Alerts 10.1.2 Deleting Alerts 10.1.4 Surrogates and Alerts 10.1.5 System Management 10.2.1 Alert Management Menu 10.2.1.1 Alerts - Set/Remove Surrogate for Users Option 10.2.1.2 Delete Old (>14 d) Alerts Option.		9.1.2	Edit a User's Options Option	150
9.1.5 Copy One Users Menus and Keys to others Option 9.1.6 Limited File Manager Options (Build) Option. 9.1.6.1 Characteristics of Intended Users. 9.1.6.2 System Administrator Setup to Enable Building Options from Template 9.1.6.3 Building Options. 9.2 System Management: Managing Delegates. 9.2.1 Delegating Options: Select Options to be Delegated Option 9.2.1.1 Delegating Security Keys. 9.2.1.2 Delegation Level (Options and Keys) 9.2.2 Further Delegation. 9.2.3 Options too Sensitive to Delegate 9.2.4 Replicate or Replace a Delegate Option 9.2.5 Remove Options Previously Delegated Option 9.2.6 Specify Allowable New Menu Prefix Option. 9.2.7 Reports. 10 Alerts. 10.1.1 Processing Alerts. 10.1.2 Deleting Alerts. 10.1.3 Forwarding Alerts. 10.1.4 Surrogates and Alerts. 10.1.5 System Management 10.2.1 Alert Management Menu 10.2.1.1 Alerts - Set/Remove Surrogate for Users Option. 10.2.1.2 Delete Old (>14 d) Alerts Option.		9.1.3	Build a New Menu Option	151
9.1.6 Limited File Manager Options (Build) Option. 9.1.6.1 Characteristics of Intended Users. 9.1.6.2 System Administrator Setup to Enable Building Options from Template. 9.1.6.3 Building Options. 9.2 System Management: Managing Delegates. 9.2.1 Delegating Options: Select Options to be Delegated Option 9.2.1.1 Delegating Security Keys. 9.2.1.2 Delegation Level (Options and Keys). 9.2.2 Further Delegation. 9.2.3 Options too Sensitive to Delegate. 9.2.4 Replicate or Replace a Delegate Option. 9.2.5 Remove Options Previously Delegated Option. 9.2.6 Specify Allowable New Menu Prefix Option. 9.2.7 Reports. 10 Alerts. 11.1 Processing Alerts. 11.1.2 Deleting Alerts. 11.1.3 Forwarding Alerts. 11.4 Surrogates and Alerts. 11.5 System Management. 11.6 Alert Management Menu. 11.7 Alert Management Menu. 11.8 Interface Option. 11.9 Delete Old (>14 d) Alerts Option.		9.1.4	Copy Everything About an Option to a New Option Option	151
9.1.6.1 Characteristics of Intended Users. 9.1.6.2 System Administrator Setup to Enable Building Options from Template 9.1.6.3 Building Options. 9.2 System Management: Managing Delegates. 9.2.1 Delegating Options: Select Options to be Delegated Option 9.2.1.1 Delegating Security Keys. 9.2.1.2 Delegation Level (Options and Keys) 9.2.2 Further Delegation. 9.2.3 Options too Sensitive to Delegate 9.2.4 Replicate or Replace a Delegate Option. 9.2.5 Remove Options Previously Delegated Option. 9.2.6 Specify Allowable New Menu Prefix Option. 9.2.7 Reports. 10 Alerts 11.1 Processing Alerts. 10.1.2 Deleting Alerts. 10.1.3 Forwarding Alerts. 10.1.4 Surrogates and Alerts. 10.1.5 System Management Menu. 10.2.1 Alert Management Menu. 10.2.1.1 Alerts - Set/Remove Surrogate for Users Option. 10.2.1.2 Delete Old (>14 d) Alerts Option.		9.1.5	Copy One Users Menus and Keys to others Option	151
9.1.6.2 System Administrator Setup to Enable Building Options from Template 9.1.6.3 Building Options 9.2 System Management: Managing Delegates 9.2.1 Delegating Options: Select Options to be Delegated Option 9.2.1.1 Delegating Security Keys 9.2.1.2 Delegation Level (Options and Keys) 9.2.2 Further Delegation 9.2.3 Options too Sensitive to Delegate 9.2.4 Replicate or Replace a Delegate Option 9.2.5 Remove Options Previously Delegated Option 9.2.6 Specify Allowable New Menu Prefix Option 9.2.7 Reports 10 Alerts 10.1 User Interface 10.1.1 Processing Alerts 10.1.2 Deleting Alerts 10.1.3 Forwarding Alerts 10.1.4 Surrogates and Alerts 10.2.1 Alert Management Menu 10.2.1.1 Alerts - Set/Remove Surrogate for Users Option 10.2.1.2 Delete Old (>14 d) Alerts Option		9.1.6	Limited File Manager Options (Build) Option	151
9.1.6.3 Building Options 9.2 System Management: Managing Delegates		9.1	I.6.1 Characteristics of Intended Users	152
9.1.6.3 Building Options 9.2 System Management: Managing Delegates 9.2.1 Delegating Options: Select Options to be Delegated Option 9.2.1.1 Delegating Security Keys 9.2.1.2 Delegation Level (Options and Keys) 9.2.2 Further Delegation 9.2.3 Options too Sensitive to Delegate 9.2.4 Replicate or Replace a Delegate Option 9.2.5 Remove Options Previously Delegated Option 9.2.6 Specify Allowable New Menu Prefix Option 9.2.7 Reports 10 Alerts 11.1 Processing Alerts 10.1.2 Deleting Alerts 10.1.3 Forwarding Alerts 10.1.4 Surrogates and Alerts 10.2.1 Alert Management 10.2.1 Alert Management Menu 10.2.1.1 Alerts - Set/Remove Surrogate for Users Option 10.2.1.2 Delete Old (>14 d) Alerts Option 10.2.1.3 Make an Alert on the Fly Option		9.1		
9.2 System Management: Managing Delegates 9.2.1 Delegating Options: Select Options to be Delegated Option 9.2.1.1 Delegating Security Keys 9.2.1.2 Delegation Level (Options and Keys) 9.2.2 Further Delegation 9.2.3 Options too Sensitive to Delegate 9.2.4 Replicate or Replace a Delegate Option 9.2.5 Remove Options Previously Delegated Option 9.2.6 Specify Allowable New Menu Prefix Option 9.2.7 Reports 10 Alerts 11.1 Processing Alerts 10.1.2 Deleting Alerts 10.1.3 Forwarding Alerts 10.1.4 Surrogates and Alerts 10.2.1 Alert Management 10.2.1 Alert Management Menu 10.2.1.1 Alerts - Set/Remove Surrogate for Users Option 10.2.1.2 Delete Old (>14 d) Alerts Option		_		
9.2.1 Delegating Options: Select Options to be Delegated Option 9.2.1.1 Delegating Security Keys 9.2.1.2 Delegation Level (Options and Keys) 9.2.2 Further Delegation 9.2.3 Options too Sensitive to Delegate 9.2.4 Replicate or Replace a Delegate Option 9.2.5 Remove Options Previously Delegated Option 9.2.6 Specify Allowable New Menu Prefix Option 9.2.7 Reports 10 Alerts 11 10.1 User Interface 11 10.1.2 Deleting Alerts 11 10.1.3 Forwarding Alerts 11 10.1.4 Surrogates and Alerts 11 10.2 System Management 11 10.2.1 Alert Management Menu 11 10.2.1.1 Alerts - Set/Remove Surrogate for Users Option 11 10.2.1.2 Delete Old (>14 d) Alerts Option			· · · · · · · · · · · · · · · · · · ·	
9.2.1.1 Delegating Security Keys 9.2.1.2 Delegation Level (Options and Keys) 9.2.2 Further Delegation 9.2.3 Options too Sensitive to Delegate 9.2.4 Replicate or Replace a Delegate Option 9.2.5 Remove Options Previously Delegated Option 9.2.6 Specify Allowable New Menu Prefix Option 9.2.7 Reports 10 Alerts 11.1 Processing Alerts 10.1.2 Deleting Alerts 10.1.3 Forwarding Alerts 10.1.4 Surrogates and Alerts 10.1.5 System Management 10.2.1 Alert Management Menu 10.2.1.1 Alerts - Set/Remove Surrogate for Users Option 10.2.1.2 Delete Old (>14 d) Alerts Option		•		
9.2.1.2 Delegation Level (Options and Keys) 9.2.2 Further Delegation 9.2.3 Options too Sensitive to Delegate 9.2.4 Replicate or Replace a Delegate Option 9.2.5 Remove Options Previously Delegated Option 9.2.6 Specify Allowable New Menu Prefix Option 9.2.7 Reports 10 Alerts 11 Alerts 12 Deleting Alerts 13 Deleting Alerts 14 Surrogates and Alerts 15 Alert Management 16 Alerts Alert Management Menu 17 Alerts - Set/Remove Surrogate for Users Option 18 Deleting Alerts Option 19 Delete Old (>14 d) Alerts Option				
9.2.2 Further Delegation 9.2.3 Options too Sensitive to Delegate 9.2.4 Replicate or Replace a Delegate Option 9.2.5 Remove Options Previously Delegated Option 9.2.6 Specify Allowable New Menu Prefix Option 9.2.7 Reports 10 Alerts 11.1 Processing Alerts 10.1.2 Deleting Alerts 10.1.3 Forwarding Alerts 10.1.4 Surrogates and Alerts 10.1.5 System Management 10.2.1 Alert Management Menu 10.2.1.1 Alerts - Set/Remove Surrogate for Users Option 10.2.1.2 Delete Old (>14 d) Alerts Option				
9.2.3 Options too Sensitive to Delegate 9.2.4 Replicate or Replace a Delegate Option 9.2.5 Remove Options Previously Delegated Option 9.2.6 Specify Allowable New Menu Prefix Option 9.2.7 Reports 10 Alerts 11.1 Processing Alerts 10.1.2 Deleting Alerts 10.1.3 Forwarding Alerts 10.1.4 Surrogates and Alerts 10.1.5 System Management 10.2.1 Alert Management Menu 10.2.1.1 Alerts - Set/Remove Surrogate for Users Option 10.2.1.2 Delete Old (>14 d) Alerts Option 10.2.1.3 Make an Alert on the Fly Option				
9.2.4 Replicate or Replace a Delegate Option 9.2.5 Remove Options Previously Delegated Option 9.2.6 Specify Allowable New Menu Prefix Option. 9.2.7 Reports				
9.2.5 Remove Options Previously Delegated Option 9.2.6 Specify Allowable New Menu Prefix Option			·	
9.2.6 Specify Allowable New Menu Prefix Option. 9.2.7 Reports				
9.2.7 Reports				
10.1 User Interface			· · · ·	
10.1.1 Processing Alerts	<i>1</i> (-		
10.1.1 Processing Alerts 10.1.2 Deleting Alerts 10.1.3 Forwarding Alerts 10.1.4 Surrogates and Alerts 10.2 System Management 10.2.1 Alert Management Menu 10.2.1.1 Alerts - Set/Remove Surrogate for Users Option 10.2.1.2 Delete Old (>14 d) Alerts Option 10.2.1.3 Make an Alert on the Fly Option	I			
10.1.2 Deleting Alerts 10.1.3 Forwarding Alerts 10.1.4 Surrogates and Alerts 10.2 System Management 10.2.1 Alert Management Menu 10.2.1.1 Alerts - Set/Remove Surrogate for Users Option 10.2.1.2 Delete Old (>14 d) Alerts Option 10.2.1.3 Make an Alert on the Fly Option				
10.1.3 Forwarding Alerts		_	•	
10.1.4 Surrogates and Alerts 10.2 System Management			•	
10.2 System Management			· · · · · · · · · · · · · · · · · · ·	
10.2.1 Alert Management Menu		_		
10.2.1.1 Alerts - Set/Remove Surrogate for Users Option		-		
10.2.1.2 Delete Old (>14 d) Alerts Option		_		
10.2.1.3 Make an Alert on the Fly Option			·	
• •			· · ·	
			2.1.4 Purge Alerts for a User Ontion	

	10	.2.1.5 Report Menu for Alerts Menu	164
	10	.2.1.6 Set Backup Reviewer for Alerts Option	166
	10	.2.1.7 Surrogate for which Users? Option	167
11	Server	Options	168
	11.1 Sys	tem Management	168
	11.1.1	What is a Server Option?	168
	11.1.2	What Can Server Options Do?	168
	11.1.3	Can Server Requests Be Denied?	168
	11.1.4	How Can the Number of Instances of a Server Option Be Controlled?	169
	11.1.5	Setting Up a Server Option	170
	11.1.6	Testing if a Site is Reachable: XQSPING Server Option	173
	11.1.7	Testing a Server Option: XQSCHK	
	11.1.8	Errors and Warnings from the XQSCHK Server Option	174
12	Help Pr	ocessor	176
	12.1 Use	r Interface	176
	12.1.1	Help Frames in the Menu System	
	12.2 Sys	tem Management	
	12.2.1	Display/Edit Help Frames Option	178
	12.2.2	List Help Frames Option	
	12.2.3	New/Revised Help Frames Option	178
	12.2.4	Cross Reference Help Frames Option	179
	12.2.5	Fix Help Frame File Pointers Option (Deleting Help Frames)	179
	12.2.6	Assigning/De-assigning Help Frame Editors	
	12.2.7	Disk Space Concerns	179
	12.2.8	Creating and Editing Help Frames	179
	12	.2.8.1 Namespacing of Help Frames	180
	12	.2.8.2 Help Frame Layout Considerations	180
	12	.2.8.3 Linking a Help Frame as Help for an Option or Menu	180
13	Error Pi	ocessing	181
	13.1 Use	r Interface	181
	13.2 Sys	tem Management	181
	13.2.1	Error Screens	181
	13	.2.1.1 List Error Screens Option	182
	13	.2.1.2 Add Error Screens Option	182
	13	.2.1.3 Edit Error Screens Option	182
	13	.2.1.4 Remove Error Screens Option	183
	13.2.2	Enhanced Error Processing	183
	13.2.3	Print 1 Occurrence of Each Error for T-1 (QUEUE) Option	183
	13.2.4	Print 2 Occurrences of Errors on T-1 (QUEUED) Option	183
	13.2.5	Clean Error Trap Option	184
	13.2.6	Error Trap Display Option	184
	12 2 7	Interactive Print of Error Massages Ontion	196

III.	Dev	vice Handler	187
14	Dev	vice Handler: User Interface	187
	14.1	Printing to Devices	
	14	1.1.1 Specifying Right Margin and Page Length	
	14.2	Queuing	
	14.3	Specifying a Special Subtype	190
	14	.3.1 Spool Document Names—An Exception	192
	14.4	Alternate Syntax for Device Specification	192
	14.5	Summary	193
15	Dev	vice Handler: System Management	194
	15.1	DEVICE File (#3.5)	194
	15	i.1.1 DEVICE File Fields	195
		15.1.1.1 OpenVMS-Specific DEVICE Fields	198
	15	5.1.2 Device Edit Menu	
	15	5.1.3 Sample Device File Entries	200
		15.1.3.1 HFS Devices	
		15.1.3.2 NULL Devices	
		15.1.3.3 BROWSER Devices	
		15.1.3.4 P-MESSAGE Devices	
		15.1.3.5 TELNET Devices	
	15.2	Mixed OS Environment Fields	
	_	5.2.1 Edit Logical/Physical Mapping Option	
	15. 3	5.2.2 Enter/Edit Kernel Site Parameters option	
	15.4	Device SecurityTERMINAL TYPE File (#3.2)	
	_	5.4.1 Terminal Type Naming Conventions	
	_	5.4.2 How Shared Device and Terminal Type Attributes are Used	
		5.4.3 Terminal Type Information Retained by User	
	15.5	•	
		5.5.1 Device Selection at Signon and Virtual Terminal Devices	
		5.5.2 Terminal Type Selection at Signon	
		15.5.2.1 Managing Display Attributes (DA) Return Codes	
	15.6	Troubleshooting	209
	15	i.6.1 Loopback Test of Device Port Option	210
	15	5.6.2 Send Test Pattern to Terminal Option	210
	15	i.6.3 Out of Service Set/Clear Option	210
	15	5.6.4 Verify HFS and Null Device Setup (required)	210
		15.6.4.1 HFS Device	
		15.6.4.2 Null Device	
	15.7	Device Identification and Cross-references	211
16	Hos	st Files	213
	16.1	Host Files: User Interface	213
	16 2	Host Files: System Management	214

16.2.1	Host File Server Device Edit Option	214
16.2.2	Caché and GT.M HFS Device Setup	215
17 Spoolin	g	216
17.1 Spo	oling: User Interface	216
17.1.1	Sending Output to the Spooler	216
17.1.2	Retrieving Spooled Documents	218
17	7.1.2.1 List Spool Documents Option	218
17	'.1.2.2 Delete A Spool Document option	218
17.1.3	Browsing a Spool Document	218
17	'.1.3.1 Browse a Spool Document Option	218
17.1.4	Printing Spool Documents	219
17	'.1.4.1 Print A Spool Document Option	219
17.1.5	Making Spool Documents into Mail Messages	
	1.1.5.1 Make spool document into a mail message Option	
17.2 Spo	oling: System Management	
17.2.1	Spool Document Storage	
17.2.2	Overflowing Spool Document Storage	
17.2.3	Granting Spooling Privileges	220
17.2.4	Managing Spool Documents	
17.2.5	Spooler Site Parameters Edit Option	222
17.2.6	Purge old Spool documents Option	222
17.2.7	Defining Spool Device Types	223
17	7.2.7.1 Caché and GT.M	223
17.2.8	Spool Device Edit Option	223
17.2.9	Auto-despooling	223
17.2.10	Generating Spool Document Names	224
18 Special	Devices	225
18.1 Brov	wser Device	225
18.1.1	User Interface	
18.1.2	System Management	227
18	3.1.2.1 Storing Host Files in a Specific Directory	
18.2 Forr	m Feeds	228
18.2.1	User Interface	228
18.2.2	System Management	228
18.3 Mag	ytape	
18.3.1	System Management	229
18.4 Netv	work Channel Devices	230
18.4.1	System Management	230
18	3.4.1.1 Network Channel Device Edit	
18.5 Res	ources	231
18.5.1	System Management	
18	8.5.1.1 Limiting Simultaneous Running of a Particular Task	
	5.1.2 Running Sequences of Tasks	

		18.	5.1.3 Creating Resource Devices	232
	18.6	Sequ	ential Disk Processors (Obsolete)	232
	18.7	Slave	ed Printers	233
	18.	7.1	User Interface	233
	18.	7.2	System Management	233
			7.2.1 Device and Terminal Type File Entries	
			7.2.2 Use of Slaved Printer: Processing Steps	
		18.	7.2.3 Queuing to Slaved Printers	235
IV.	. Tas	kMa	n	236
19	Tas	kMaı	n: User Interface	236
	19.1	Crea	ting Tasks	236
	19.	1.1	Background Jobs	236
	19.	1.2	Queuing Output	236
	19.	1.3	Other Sources of Tasks	236
	19.2	Work	king with Tasks	237
	19.	2.1	Selecting Tasks	238
	19.	2.2	Tasks in the Task List	238
	19.	2.3	Display Status of Tasks	239
	19.	2.4	Stopping Tasks	239
	19.	2.5	Editing Tasks	
		2.6	Listing and Printing Tasks	
	_	2.7	Selecting Another Task	
			mary	
20	Tas	kMaı	n: System Management—Overview	241
	20.1	Task	Man's Division of Labor	241
	20.	1.1	Queuers	241
			1.1.1 Programs that Use the TaskMan API	
		20.	1.1.2 Option Scheduling through the OPTION SCHEDULING File (#19.2)	242
	20.	1.2	Manager	
		1.3	Submanagers	
			Man's Files	
	20.		TaskMan Globals: ^%ZTSCH and ^%ZTSK	
	_		SCHEDULE File	
			TASKS File (#14.4)	
	_		Other Files	
	20.3	•	em Configuration Terminology	
			Man Security Key	
21	Tas	kMaı	n: System Management—Configuration	249
	21.1	Defin	ning TaskMan Environments	249
	21.2		iguring TaskMan	
	21.		TaskMan's Reach	
	21.	2.2	TASKMAN SITE PARAMETERS File (#14.7)	250

21.	.2.3	VOLUME SET File (#14.5)	253
21.	.2.4	UCI ASSOCIATION File (#14.6)	256
	21.	2.4.1 Partial File Entries	256
	21.	2.4.2 Complete File Entries	257
21.	.2.5	Sample Configuration: Standardized VA Caché and GT.M Configuration	258
21.3	Mana	ager Startup	259
21.4	Multi	iple TaskMan Managers and Load Balancing	259
21.	.4.1	Configuration for Multiple Managers	259
21.	.4.2	Starting Up, Pausing, and Stopping Multiple Managers	259
21.	.4.3	Load Balancing	259
21.	.4.4	Monitor Taskman Option	
21.5	Devi	ce Handler's Influence on TaskMan	261
21.6	Runr	ning TaskMan with a DCL Context	
21.	.6.1	Setup for Running TaskMan in a DCL Context in a Cache/VMS Environment	
21	.6.2	How to Restart TaskMan when Running in a DCL Context	
	_	•	
		n: System Management—Operation	
22.1		Man Management Menu	
22.	.1.1	List Tasks Option	
		1.1.1 All your tasks Option	
		1.1.2 Your future tasks Option	
		1.1.3 List of tasks Option	
		1.1.4 Unsuccessful tasks Option	
		1.1.5 Future tasks Option	
		1.1.6 Tasks waiting for a device Option	
		1.1.7 Running tasks Option	
	.1.2	Dequeue Tasks Option	
	.1.3	Requeue Tasks Option	
	.1.4	Delete Tasks Option	
	.1.5	Cleanup Task List Option	
		man Management Utilities	
22.	.2.1	Monitor Taskman Option	
		2.1.2 Status List	
		2.1.3 Schedule List	
		2.1.4 IO List	
		2.1.5 Job List	
		2.1.6 Task List	
		2.1.7 Monitor Action Prompt	
		2.1.8 Inspecting the Tasks in the Monitor's Lists	
າາ	.2.2 .2.2	Check Taskman's Environment Option	
	.2.2	Restart Task Manager Option	
	.2.3 .2.4	Place Taskman in a WAIT State Option	
		Remove Taskman from WAIT State Option	

22.2.	6 Stop Task Manager Option	283
22.2.	7 SYNC flag file control Option	283
22.2.	8 Clean Task File Option	284
22.2.	9 Queuable Task Log Clean Up Option	284
22.3 S	cheduling Options	285
22.3.	1 Which Options to Queue	285
	22.3.1.1 PARENT OF QUEUABLE OPTIONS Menu	285
	22.3.1.2 Printing Options Recommended to Run and Scheduled to Run	285
	22.3.1.3 Schedule/Unschedule Options	286
	22.3.1.4 Queued to Run At What Time	286
	22.3.1.5 How to Delete a Regularly Scheduled Task	
	22.3.1.6 How to Requeue a Regularly Scheduled Task	286
	22.3.1.7 Device For Queued Job Output	287
	22.3.1.8 Queued To Run On Volume Set	
	22.3.1.9 Reschedule Frequency	
	22.3.1.10Task Parar	
	22.3.1.11 Special Que	U
	22.3.1.12 Problems With Scheduled O	
	22.3.1.13One-time Option Queue (Option
22.4 T	askman Error Log Menu	
22.4.	_	
22.4.	2 Clean Error Log Over Range Of Dates Option	292
22.4.	3 Purge Error Log Of Type Of Error Option	292
22.4.		
22.5 T	roubleshooting	293
22.5.	1 SCHEDULE File	293
22.5.	2 TASKS File (#14.4)	297
22.5.	3 Task Status Codes	298
22.5.	4 Task Rejection Messages	300
22.5.	5 TaskMan State Messages	301
	22.5.5.1 BALANCE State	
	22.5.5.2 ERROR State	301
	22.5.5.3 PAUSE State	
	22.5.5.4 RUN State	
	22.5.5.5 WAIT State	
V. Kerne	el Installation and Distribution System	.304
23 KIDS	: System Management—Installations	.304
	(IDS Options	
23.1.	•	
	2 Installations	307

	23.2	Build Entries and the BUILD File (#9.6)	307
	23.3	INSTALL File (#9.7)	308
	23.4	Changes in the Role of the PACKAGE File (#9.4)	308
	23.5	Transport Mechanism: Distributions	309
	23.	5.1 Two Kinds of Distributions	309
	23.6	What Happens to DIFROM?	309
	23.7	Installing Standard Distributions	310
	23.	7.1 Installation Sequence	310
		23.7.1.1 Phase 1: Loading Transport Globals from a Distribution or PackMan Message	310
		23.7.1.2 Phase 2: Answering Installation Questions for Transport Globals in a	
		Distribution	
		23.7.1.3 Phase 3: KIDS Installation of Software	
	23.		
	23.		
		23.7.3.1 When the Distribution is Split across Diskettes	
	23.		
	23.	, ,	
	23.	5	
	23.	,	
	23.	5 1 1	
	23.	5	
		23.7.9.1 Processing Each Transport Global	
		23.7.9.2 Scheduling Installations	
		7.10 When the Installation is Queued	
		7.11 Re-answering Installation Questions	
		7.12 Information Stored in the INSTALL File (#9.7)	
		7.13 Answering Installation Questions for a Distribution	
		7.14 Installation Progress	
		7.15 Once the Installation Finishes	
		7.16 Restarting Aborted Installations	
		7.17 Recovering from an Aborted Distribution Load	
	23.8	Installing Global Distributions	
	23.9	Purging the BUILD and INSTALL Files	
		Alpha/Beta Tracking	
24		S: System Management—Utilities	
	24.1	Build File Print Option	
	24.2	Install File Print Option	
	24.3	Edit Install Status Option	
	24.4	Convert Loaded Package for Redistribution Option	
	24.5	Display Patches for a Package Option	
	24.6	Purge Build or Install Files Option	
	24.		
	24.	6.2 Selecting Software Names for Purging	334

24	4.6.3	Purging Selected Entries	334
24	4.6.4	Reasons to Retain BUILD and INSTALL File Entries	335
24.7	Roll	up Patches into a Build Option	335
24.8	Upd	late Routine File Option	336
24.9	Veri	fy a Build Option	336
24.10	Veri	fy Package Integrity Option	337
VI. To	olkit		338
25 Mu	ılti-T <i>e</i>	erm Look-Up (MTLU)	341
25.1		rview	
25.1		oduction to Multi-Term Look-Up (MTLU)	
25.2		ctional Description	
25.4		ge Considerationsge	
25.5		r Interface	
	5.5.1	Multi-Term Look-Up Menu Options	
	-	5.5.1.1 Standard Device Chart	
25	5.5.2	Using the Multi-Term Lookup (MTLU) Option	
25	5.5.3	Using the Print Utility Option	
25	5.5.4	Using the Utilities for MTLU Option	
	25	5.5.4.1 Delete Entries from Look-Up Option	350
	25	5.5.4.2 Add Entries To Look-Up File Option	350
	25	5.5.4.3 Add/Modify Utility Option	353
25	5.5.5	Examples	358
	25	5.5.5.1 Example 1	358
		5.5.5.2 Example 2	
		5.5.5.3 Example 3	
25.6	Sys	tems Management	
	5.6.1	Implementation of Multi-Term Look-Up (MTLU)	
-			
Index			368
		List of Figures	
Figure 1:	Signir	ng on to VistA—Sample roll-and-scroll user authentication dialogue	<u>5</u>
Ū	•	ss denied due to no primary menu or menu "out of order" message	
-		ing the Access and Verify codes at the same time	
Figure 4:	Enter	ing the Access and Verify codes at the same time and jumping directly to	а
•		m commands: Menu options for signoff	
		m commands: View Alerts "VA" option	
		s Toolbox menu options	
Figure 8:	Edit L	Jser Characteristics option—ScreenMan form	11
Figure 9:	Displa	ay User Characteristics option—Sample output and user dialogue	13
Figure 10): Intro	ductory text edit option	15

Figure 11: Enter/Edit Kernel Site Parameters option	15
Figure 12: Enter/Edit Kernel Site Parameters option—ScreenMan form 1	16
Figure 13: Kernel Signon flow chart	17
Figure 14: Post sign-in Text Edit option	20
Figure 15: Clear all users at startup option	22
Figure 16: User Management menu options: Associated menu options when adding a new u	ıser
Figure 17: Reprint Access agreement letter option	
Figure 18: Security Forms—Sample user entries (1 of 4)	
Figure 19: Security Forms—Sample user entries (2 of 4)	
Figure 20: Security Forms—Sample User Account Notification form (3 of 4)	
Figure 21: Security Forms—Sample Computer Account Access Policy form (4 of 4)	30
Figure 22: Edit an Existing User option—Menu	
Figure 23: VA FileMan Line Editor—Sample user dialogue	
Figure 24: Edit an Existing User option—Screen 1	36
Figure 25: Edit an Existing User option—Screen 2	37
Figure 26: Edit an Existing User option—Screen 3	37
Figure 27: Edit an Existing User option—Screen 4	38
Figure 28: Edit an Existing User option—Screen 5	38
Figure 29: User Management menu options	39
Figure 30: User Management Menu options	43
Figure 31: Sample Kernel Sign-On Log report	44
Figure 32: CPU/Service/User/Device Stats option	47
Figure 33: Purge Log of Old Access and Verify Codes option	48
Figure 34: Sample VA FileMan menu options	49
Figure 35: User has not been granted security access to any VA FileMan files—Sample use	r
dialogue	
Figure 36: File Access Security menu options	56
Figure 37: Displaying the DUZ array for a signed-on user at a programmer prompt	58
Figure 38: Displaying the DUZ (Internal Entry Number) in a VA FileMan report	59
Figure 39: KILLing ^DISV—Sample code	61
Figure 40: Updating file access settings (before conversion)	62
Figure 41: Enabling File Access Security—Sample user dialogue	64
Figure 42: ^XUINCON conversion routine—Sample user dialogue	65
Figure 43: Running a conversion—Sample user dialogue	65
Figure 44: Creating a PRINT template to display file access security—Sample user dialogue	
Figure 45: User Edit menu options	
Figure 46: DEA ePCS—Manual paper-based process to prescribe Schedule II Controlled	
Substances	73
Figure 47: DEA ePCS—ePrescribing process to prescribe Schedule II - V Controlled	
Substances	
Figure 48: DEA ePCS: General Parameter Tools menu [XPAR MENU TOOLS]—Editing DE	Α
ePCS Site Parameter	
Figure 49: DEA ePCS: XPAREDIT Routine—Editing DEA ePCS Site Parameter: Test Account	unt 77
	, ,

Figure 50: DEA ePCS: Adding DEA ePCS Utility users by assigning the XUEPCSEDIT security key79
Figure 51: DEA ePCS: Assigning the XU EPCS EDIT DATA option—Sample user entries (1 of 2)
Figure 52: DEA ePCS: Assigning the XU EPCS EDIT DATA option—Sample user entries (2 of 2)
Figure 53: DEA ePCS: Assigning the XUSSPKI UPN SET option—Sample user entries (1 of 2)
Figure 54: DEA ePCS: Assigning the XUSSPKI UPN SET option—Sample user entries (2 of 2)
Figure 55: DEA ePCS: DEA ePCS Utility Functions main menu [XU EPCS UTILITY FUNCTIONS]86
Figure 56: DEA ePCS: Print DEA Expiration Date Null option—Sample user entries and report
Figure 57: DEA ePCS: Print DISUSER DEA Expiration Date Null option—Sample user entries and report91
Figure 58: DEA ePCS: Print DEA Expiration Date Expires 30 days option—Sample user entries and report
Figure 59: DEA ePCS: Print DISUSER DEA Expiration Date Expires 30 days Option—Sample user entries and report93
Figure 60: DEA ePCS: Print Prescribers with Privileges option—Sample user entries and report
Figure 61: DEA ePCS: Print DISUSER Prescribers with Privileges option—Sample user entries and report
Figure 62: DEA ePCS: Print PSDRPH Key Holders option—Sample user entries and report98
Figure 63: DEA ePCS: Print Setting Parameters Privileges option—Sample user entries and
report
Figure 64: DEA ePCS: Print Audits for Prescriber Editing option: Sort by <i>Edited By then</i> Date/time—Sample user entries and report
Figure 65: DEA ePCS: Print Audits for Prescriber Editing option: Sort by <i>User Edited then Edited By</i> —Sample user entries and report
Figure 66: DEA ePCS: Task Changes to DEA Prescribing Privileges Report option: TaskMan schedule setup—Sample user entries
Figure 67: DEA ePCS: Task Changes to DEA Prescribing Privileges Report option—Sample user entries (no report displays)105
Figure 68: DEA ePCS: Task Allocation Audit of PSDRPH Key Report option: TaskMan schedule setup—Sample user entries107
Figure 69: DEA ePCS: Task Allocation Audit of PSDRPH Key Report option—Sample user entries (no report displays)108
Figure 70: DEA ePCS: Task Allocation Audit of PSDRPH Key Report option—Sample report printed to device entered into the XUEPCS REPORT DEVICE parameter108
Figure 71: DEA ePCS: Allocate/De-Allocate of PSDRPH Key option: <i>Allocating</i> PSDRPH— Sample user entries
Figure 72: DEA ePCS: Allocate/De-Allocate of PSDRPH Key option: <i>De-allocating</i> PSDRPH—Sample user entries
Figure 73: DEA ePCS: Edit Facility DEA# and Expiration Date option—Sample user entries110
Figure 74: One question mark (?) help—Sample user dialogue

Figure 75: Using ?Option to get help on a named option—Sample user dialogue	.117
Figure 76: Two question marks (??) help—Listing Primary, Secondary, and Common menu	
options	
Figure 77: Three question marks (???) help—Sample user dialogue	
Figure 78: Using the "Up-arrow Jump"—Sample user dialogue	
Figure 79: List of choices—Sample user dialogue	
Figure 80: "Rubber-band jump"—Sample user dialogue	
Figure 81: Selecting common options via the double quote—User's Toolbox menu option	
Figure 82: Menu Templates Option	
Figure 83: Invoking a template—Sample user dialogue	
Figure 84: Edit options option	
Figure 85: Defining local primary menus (system administrators)—Sample user dialogue	.125
Figure 86: Auditing menu options	.127
Figure 87: Display Menus and Options menu	.128
Figure 88: Inquire option—Sample user dialogue	.129
Figure 89: Option Access by User option	.129
Figure 90: Delete Unreferenced Options option	.131
Figure 91: Fix Option File Pointers option	.131
Figure 92: Fix Option File Pointers option—Sample user dialogue	.132
Figure 93: Switch Identities option	.132
Figure 94: Out-Of-Order Set Management menu options	.132
Figure 95: Restrict Availability of Options option	.133
Figure 96: Clean old Job Nodes in XUTL	.134
Figure 97: Building primary menu trees options	.135
Figure 98: Menu jump error message (1 of 6)	.136
Figure 99: Menu jump error message (2 of 6)	.136
Figure 100: Menu jump error message (3 of 6)	.136
Figure 101: Menu jump error message (4 of 6)	.136
Figure 102: Menu jump error message (5 of 6)	.137
Figure 103: Menu jump error message (6 of 6)	
Figure 104: User Stack example	.138
Figure 105: Display Nodes for EVE example	.139
Figure 106: Display Nodes for a secondary menu	
Figure 107: Jump Nodes example—Lookup nodes	
Figure 108: Jump Nodes example—Menu Pathways	
Figure 109: Sample locked menu options showing required security key—Entering two ques	
marks (??)	
Figure 110: Display User Characteristics option—Sample output	.143
Figure 111: Diagram Menus option—Sample user dialogue	
Figure 112: Key Management menu options	
Figure 113: Attributes for the Provider security key—Sample user dialogue	
Figure 114: Reindex the users key's option	
Figure 115: Delegate's Menu Management options	
Figure 116: Edit a User's Options—Sample user dialogue	

Figure	117:	Limited File Manager Options (Build)—Sample user dialogue	153
Figure	118:	Delegating Options: Select Options to be Delegated option—Sample user dialog	
		AL	
•		Alert—Sample user message	
_		View Alerts "VA" option—Sample user dialogue	
•		Alert Management menu options	
•		Report Menu for Alerts menu options	
-		Sample message received when "pinging" a domain address	
		XQSCHK server option—Sample MailMan return message	
•		Help frame example Display a help frame for an option—Entering one question mark (?) and option	170
_		Display a field frame for all option—Efficiently one question mark (?) and option	177
		Display a help frame for an option—Entering three question marks (???)	
		Display a help frame for an option—Entering four question marks (????)	
-		Help Processor menu options	
Figure	130:	Display/Edit Help Frames option—Displaying help using the ?option syntax	178
•		List Help Frames option—Sample user dialogue	
_		Estimating the size of the HELP FRAME file (#9.2) using Kernel's Block Count	
	-		
Figure	133:	Linking help frames to an option—Sample user dialogue	180
•		List Error Screens option	
•		Add Error Screens option	
		Edit Error Screens option	
		Remove Error Screens option	
•		Error processing options	
-		Choosing the number of days to leave errors in the error trap	
-		Choosing a start and end date range to delete errors from the error trap	
-		Error trap display option—Sample user dialogue	
•		Local symbol table help	
-		Choosing to examine the operating system's error log—Sample user dialogue	
•		Choosing the home device	
_		Choosing a printer device	
•		Choosing the closest printer device	
-		Device syntax help—One question mark (?)	
		Displaying devices help—Two question marks (??)	
_		Sample printer listing	
-		Specifying a device and queuing a print job—Sample user dialogue (1 of 2) Specifying a device and queuing a print job—Sample user dialogue (2 of 2)	
-		Queuing a print job—Sample user dialogue	
•		Terminal-type device entry—Without pauses	
_		Terminal-type device entry— <i>With</i> pauses	
•		Partial Device specification—Unknown subtype	
•		Device specification—Four semicolon piece: Sample	
•		·	191

Figure 158: Device syntax—Specifying a spool document name: Sample formats (1 of 2)	192
Figure 159: Device syntax—Specifying a spool document name: Sample formats (2 of 2)	192
Figure 160: Specifying a device—Using alternate syntax	193
Figure 161: Device Edit options	199
Figure 162: HFS device—Sample data entry screen	200
Figure 163: HFS device—Sample DEVICE file entries	200
Figure 164: HFS device—Sample data entry screen with the Terminal Type CLOSE EXEC	CUTE 201
Figure 165: Mixed Operating System: VMS (Primary) and Linux (Secondary) NULL device	— 202
Sample data entry screen	
Sample DEVICE file entries	
Figure 167: BROWSER device—Sample DEVICE file entries	203
Figure 168: P-MESSAGE device—Sample DEVICE file entries	203
Figure 169: TELNET device—Sample DEVICE file entries (1 of 2)	203
Figure 170: TELNET device—Sample DEVICE file entries (2 of 2)	203
Figure 171: Enter/Edit Kernel Site Parameters option—ScreenMan form 3: MIXED OS (#. and SECONDARY HFS DIRECTORY (#320.2) fields	•
Figure 172: Terminal type edit options	
Figure 173: DA Return Code Edit option	
Figure 174: Device management—Troubleshooting options	
Figure 177: VMS NULL device—Sample DEVICE file entries	
Figure 177: Mixed Operating System: VMS (Primary) and Linux (Secondary) NULL device	е—
Sample DEVICE file entries	
Figure 175: Linux Null Device Example—Caché null device setup	
Figure 175: Windows Null Device Example—Caché null device setup	
Figure 176: Null Device Example—P-OTHER Terminal Type setup	
Figure 177: Displaying signon devices on a specific CPU—Sample user dialogue	
Figure 178: Displaying signon devices with a specific \$I—Sample user dialogue	
Figure 179: Global listing for device cross-references—\$I value = 99 and IEN = 251	
Figure 180: Global listing for virtual terminal device cross-references—\$I value = _TNA ar = 251	na iEN 212
Figure 181: Choosing a Host File Server (HFS) device—Sample user dialogue	
Figure 182: Host File Server Device Edit option	
Figure 183: Host File Server device for Caché and GT.M—Sample settings	
Figure 184: Unable to send output to a spool device—Sample message	
Figure 185: Specifying spooled output margin and length	
Figure 186: Spool document name prompt	
Figure 187: Specifying the spool device and document name	
Figure 188: Spooling output to a spool device on the same CPU	
Figure 189: Queuing output to a spool device	
Figure 190: Spooler Parameters at the Device prompt (summary)	
Figure 191: Spooler Menu options	
Figure 192: Formatting/Sending a document to a spool device to print as a MailMan mess	
Sample user dialogue	

Figure 193: Make spool document into a mail message option	219
Figure 194: Edit User's Spooler Access option	220
Figure 195: Edit User's Spooler Access—Sample user dialogue	221
Figure 196: Spool Management menu options	221
Figure 197: Spooler Site Parameters option	222
Figure 198: Purge old spool documents option	222
Figure 199: Spool Device for Caché and GT.M	223
Figure 200: Spool Device Edit option	223
Figure 201: Device Edit option—Sample user dialogue	223
Figure 202: Generating spool document name—Sample user dialogue	224
Figure 203: Print File Entries option—Sample user dialogue when sending a report to the Browser device	225
Figure 204: Print File Entries option—Sample Domain List report, as displayed in the Brows device	er 226
Figure 205: Caché and GT.M Browser Device—TERMINAL TYPE file (#3.2) entry	227
Figure 206: Caché and GT.M Browser Device—DEVICE file (#3.5) Entry	228
Figure 207: Device Edit option—Sample user dialogue	228
Figure 208: Terminal Type Edit option—Sample user dialogue	228
Figure 209: Edit Devices by Specific Types option	229
Figure 210: Network Channel Device Edit option	230
Figure 211: Network Channel Device Edit option—Sample output	231
Figure 212: Resource Device Edit option	232
Figure 213: Resource device—Sample output	232
Figure 214: Slaved Printer—Sample user dialogue	233
Figure 215: Home Device example (VT320)—DEVICE file (#3.5) entry	234
Figure 216: Home Device example (VT320)—TERMINAL TYPE file (#3.2) entry	234
Figure 217: Slaved Printer example: DEC LA50—DEVICE file (#3.5) entry	234
Figure 218: Slaved Printer example: DEC LA50—TERMINAL TYPE file (#3.2) entry	235
Figure 219: Slaved Printer example: Epson LQ870—DEVICE file (#3.5) entry	235
Figure 220: Slaved Printer example: Epson LQ870—TERMINAL TYPE file (#3.2) entry	235
Figure 221: Queuing output—Sample user dialogue	236
Figure 222: TaskMan User option	237
Figure 223: TaskMan User option—Sample user dialogue	238
Figure 224: Edit Task option—Sample user dialogue	240
Figure 225: TaskMan Manager and Submanager process flow diagram	244
Figure 226: Site Parameters Edit option	250
Figure 227: Volume Set Edit option	253
Figure 228: Sample Volume Set setup on FORUM	254
Figure 229: UCI Association Table Edit option	256
Figure 230: VOLUME SET file (#14.5) standardized VA Caché and GT.M configuration	258
Figure 231: UCI ASSOCIATION file (#14.6)—Standardized VA Caché and GT.M configuration	258
Figure 232: TASKMAN SITE PARAMETERS file (#14.7) standardized VA Caché and GT.M	
g = === gata = == gata =	050

Figure 233:	Customized Header Page routine	262
Figure 234:	Customized Header Page	262
	Create TASKMAN	263
Figure 236:	Create the TASKMAN directory	263
Figure 237:	Create system logical name for the directory with the COM files	264
Figure 238:	Create system logical name for the directory with the COM files	264
Figure 239:	Sample user dialogue to retrieve DCL command files	265
Figure 240:	Sample user dialogue to edit TaskMan parameters	266
Figure 241:	ZTM2WDCL.COM Command File	267
Figure 242:	ZTMS2WDCL.COM Command File	268
Figure 243:	Example of OpenVMS User TASKMAN on ALPHA AXP Systems	269
Figure 244:	Example of OpenVMS TASKMAN Queue	269
Figure 245:	List Tasks Option	270
Figure 246:	List Tasks option submenu options	271
Figure 247:	All your tasks sub	271
Figure 248:	Dequeue Tasks option	273
Figure 249:	Requeue Tasks option	273
Figure 250:	Delete Tasks option	274
Figure 251:	Cleanup Task List option	274
Figure 252:	Monitor Taskman option	275
Figure 253:	Sample Monitor TaskMan screen	276
Figure 254:	TaskMan monitor actions	278
Figure 255:	Options for inspecting tasks in the TaskMan Monitor's Lists	279
Figure 256:	Check Taskman's Environment option	279
Figure 257:	Check TaskMan's Environment option—First screen	280
Figure 258:	Check TaskMan's Environment option—Second screen	281
Figure 259:	Restart Task Manager option	282
-	· ·	282
-	<u>'</u>	283
•		283
Figure 263:	SYNC flag file control option	283
•		284
	Print Options Recommended for Queueing and Print Options that are Scheduled	
		285
•	Schedule/Unschedule Options option	
-	One-time Option Queue option	
-	Show Error Log option	
•	Clean Error Log Over Range Of Dates	
•	Purge Error Log Of Type Of Error option	
•	Delete Error Log option	
•	^%ZTSCH Global Structure	
-	TASKS File (#14.4) nodes (1 of 2)	
•	TASKS File (#14.4) nodes (2 of 2)	
Figure 275:	KIDS menu options	305

Figure 276	Edits and Distribution menu options	.306
Figure 277	Installation menu options	307
Figure 278	KIDS file diagram	308
Figure 279	KIDS Installation menu options	311
Figure 280	Load a Distribution option—Sample user dialogue	312
Figure 281	Loading transport globals from a distribution—Flowchart	314
Figure 282	Print Transport Global option—Sample printed transport global	316
Figure 283	Compare Transport Global to Current System option—Sample comparison	
output		317
-	Compare Transport Global to Current System option—Sample comparison outp	
	nar format	
•	Queued KIDS installation—Sample installation task	
-	Answering installation questions for a distribution—Flowchart	
-	Installation progress—Sample output	
•	KIDS Global distribution—Sample message	
•	Installation of a global distribution—Load a Distribution option	
Figure 290	KIDS Utilities menu options	.327
-	Build File Print option—Sample output	
Figure 292	Install File Print option—Sample output	.329
Figure 293	Edit Install Status option—Sample user dialogue	330
Figure 294	Convert Loaded Package for Redistribution—Sample user dialogue (1 of 2)	.331
Figure 295	Convert Loaded Package for Redistribution—Sample user dialogue (2 of 2)	.331
Figure 296	Transport a Distribution—Sample user dialogue	.332
Figure 297	Display Patches for a Package option—Sample user dialogue	.333
Figure 298	Purge or Install Files option—Sample user dialogue	.334
Figure 299	Rollup Patches into a Build option—Sample user dialogue	.335
Figure 300	Update Routine File option—Sample user dialogue	.336
Figure 301	Verify a Build option—Sample user dialogue	.337
Figure 302	Multi-Term Lookup Main Menu options	.343
Figure 303	Standard Device Chart	345
Figure 304	Multi-Term Lookup (MTLU) option process chart	.346
Figure 305	Multi-Term Lookup (MTLU) option—Sample user entries	.347
Figure 306	Print Utility option process chart	348
Figure 307	Print Utility option—Sample user entries and sample output	.349
Figure 308	Delete Entries From Look-Up option—Sample user entries	350
Figure 309	Add Entries To Look-Up File option process chart (1 of 2)	351
Figure 310	Add Entries To Look-Up File option process chart (2 of 2)	.352
Figure 311	Add Entries To Look-Up File option—Sample user entries	.353
	Add/Modify Utility menu options	
Figure 313	Add/Modify Utility option—Shortcuts process chart (1 of 2)	354
	Add/Modify Utility option—Shortcuts process chart (2 of 2)	
-	Add/Modify Utility option—Keywords process chart	
Figure 316	Add/Modify Utility option—Adding or editing a synonym process chart (1 of 2)	.357
-	Add/Modify Utility option—Adding or editing a synonym process chart (2 of 2)	

Figure 318: Shortcut option—Sample user entries	358
Figure 319: Keyword option—Sample user entries	359
Figure 320: Synonym option—Sample user entries	359
Figure 321: VA FileMan Utility Functions option—Sample user entries	360
Figure 322: Add Entries To Look-Up File—Sample user entries	361
Figure 323: VA FileMan Edit File option—Sample user entries	362

List of Tables

Table 1: Documentation symbol descriptions	XXXIX
Table 2: User's Toolbox menu options and documentation references	10
Table 3: Edit User Characteristics option—Editable fields	11
Table 4: Edit an Existing User option—Editable fields/attributes	31
Table 5: Deactivate a User option—Editable fields/attributes	40
Table 6: Kernel Signon Auditing Files	47
Table 7: File Access—Security level properties	52
Table 8: DEA ePCS Utility—Main Menu Options	87
Table 9: Menu diagramming options to discover tree roots and relationships between	
options/suboptions	
Table 10: Menu Manger variables (always defined)	
Table 11: Secure Menu Delegation menu options	
Table 12: Alert processing codes	
Table 13: SERVER ACTION field (#221) security values for server requests	
Table 14: OPTION file (#19) field values when setting up a server option	
Table 15: XQSCHK server option—Error/Warning messages	
Table 16: Help system command actions	
Table 17: Sample semicolon-delimited pieces at the "DEVICE:" prompt	
Table 18: Alternate device attribute codes	
Table 19: Device-related files global locations	
Table 20: DEVICE file fields	
Table 21: Device types in the TYPE Field in the DEVICE file (#3.5)	
Table 22: Queuing settings	
Table 23: Mixed OS Environment fields in the DEVICE file (#3.5)	198
Table 24: Mixed OS Environment fields in the KERNEL SYSTEM PARAMETERS file	204
(#8989.3)	
Table 26: Terminal type naming conventions	
Table 20: Terminal type framing conventions	
Table 28: HFS input/output modes of operation	
Table 29: HFS-related fields in the DEVICE file (#3.5)	
Table 30: HFS I/O operation modes for Caché and GT.M	
Table 31: User spooler-related fields in the NEW PERSON file (#200)	
Table 32: Spooler site parameter fields in the KERNEL SYSTEM PARAMETERS file	
(#8989.3)	222
Table 33: Fields in the DEVICE (#3.5) and TERMINAL TYPE (#3.2) files that may not be	
relevant for certain devices	229
Table 34: Escape sequences used to toggle the slaved printing modes for DEC VT220/VT	T320
terminals	233
Table 35: TaskMan system configuration terminology	
Table 36: TASKMAN SITE PARAMETERS File (#14.7)—Field entries	
Table 37: VOLUME SET File (#14.5)—Field entries	
Table 38: UCI ASSOCIATION file (#14.6)—Partial and complete field entries	257

Table 39: DEVICE file (#3.5)—TaskMan-related field entries	261
Table 40: Special Queueing field settings	288
Table 41: Option Scheduling frequency code formats	289
Table 42: Day codes used in Option Scheduling frequency code formats	289
Table 43: Examples of Option Scheduling frequency code formats	290
Table 44: ^%ZTSCH (SCHEDULE File) nodes	293
Table 45: TaskMan Task Status Codes	298
Table 46: TaskMan rejection messages	300
Table 47: TaskMan PAUSE states	302
Table 48: TaskMan RUN states	302
Table 49: KIDS-related terms and definitions	304

Orientation

How to Use this Manual

Throughout this manual, advice and instruction are offered about the numerous Kernel 8.0 and Kernel Toolkit 7.3 tools and functionality provided for the Veterans Health Information Systems and Technology Architecture (VistA) system management and end-users (e.g., site parameters).

The *Kernel Systems Management Guide* is divided into six major sections, based on the following functional divisions within Kernel/Kernel Toolkit:

- I. <u>Signon/Security</u> (e.g., techniques for granting user access and monitoring computing activity)
- II. Menu Manager (e.g., techniques for managing menus)
- III. Device Handler
- IV. TaskMan
- V. Kernel Installation and Distribution System
- VI. Toolkit



REF: For information on developer tools (e.g., Direct Mode Utilities and Application Program Interfaces [APIs]), see the *Kernel Developer's Guide*. Kernel and Kernel Toolkit APIs are also available in HTML format at a VA Intranet website.

Information on recommended system configuration and setting Kernel's site parameters, as well as lists of files, routines, options, and other components are documented in the *Kernel Technical Manual*.

Information about managing computer security, which includes a detailed description of techniques that can be used to monitor and audit computing activity, is presented in the *Kernel Security Tools Manual*.

Instructions for installing Kernel are provided in the *Kernel Installation Guide*. This guide also includes information about software application management (e.g., *recommended* settings for site parameters and scheduling time frames for tasked options).

This manual is further organized within each section of Kernel in the following order:

- 1. User Interface—Information of relevance to general end-users.
- 2. System Management—Information of relevance to system managers.

When a subject is large enough (e.g., Signon/Security), separate chapters are devoted to the "User Interface" and "System Management" topics. In other cases, where the subject matter is smaller (e.g., the discussion of the Browser device), the two divisions of audience are contained entirely within a chapter or sub-chapter.

Intended Audience

The intended audience of this manual is the following stakeholders:

- Enterprise Program Management Office (EPMO)—VistA legacy development teams.
- System Administrators—System administrators at Department of Veterans Affairs (VA) sites who are responsible for computer management and system security on the VistA M Servers.
- Information Security Officers (ISOs)—Personnel at VA sites responsible for system security.
- Product Support (PS)—Personnel who support Kernel-related products.

Disclaimers

Software Disclaimer

This software was developed at the Department of Veterans Affairs (VA) by employees of the Federal Government in the course of their official duties. Pursuant to title 17 Section 105 of the United States Code this software is *not* subject to copyright protection and is in the public domain. VA assumes no responsibility whatsoever for its use by other parties, and makes no guarantees, expressed or implied, about its quality, reliability, or any other characteristic. We would appreciate acknowledgement if the software is used. This software can be redistributed freely provided that any derivative works bear some notice that they are derived from it.



CAUTION: Kernel routines should *never* be modified at the site. If there is an immediate national requirement, the changes should be made by emergency Kernel patch. Kernel software is subject to FDA regulations requiring Blood Bank Review, among other limitations. Line 3 of all Kernel routines states:

Per VA Directive 6402 (pending signature), this routine should not be modified.



CAUTION: To protect the security of VistA systems, distribution of this software for use on any other computer system by VistA sites is prohibited. All requests for copies of Kernel for *non*-VistA use should be referred to the VistA site's local Office of Information Field Office (OIFO).

Documentation Disclaimer

This manual provides an overall explanation of using Kernel; however, no attempt is made to explain how the overall VistA programming system is integrated and maintained. Such methods and procedures are documented elsewhere. We suggest you look at the various VA Internet and Intranet SharePoint sites and websites for a general orientation to VistA. For example, visit the Office of Information and Technology (OI&T) Enterprise Program Management Office (EPMO) Intranet Website.



DISCLAIMER: The appearance of any external hyperlink references in this manual does *not* constitute endorsement by the Department of Veterans Affairs (VA) of this Website or the information, products, or services contained therein. The VA does *not* exercise any editorial control over the information you find at these locations. Such links are provided and are consistent with the stated purpose of this VA Intranet Service.

Documentation Conventions

This manual uses several methods to highlight different aspects of the material:

• Various symbols are used throughout the documentation to alert the reader to special information. Table 1 gives a description of each of these symbols:

Table 1: Documentation symbol descriptions

Symbol	Description
1	NOTE / REF: Used to inform the reader of general information including references to additional reading material.
A	CAUTION / RECOMMENDATION / DISCLAIMER: Used to caution the reader to take special notice of critical information.

- Descriptive text is presented in a proportional font (as represented by this font).
- Conventions for displaying TEST data in this document are as follows:
 - The first three digits (prefix) of any Social Security Numbers (SSN) begin with either "000" or "666".
 - o Patient and user names are formatted as follows:
 - <Application Name/Abbreviation/Namespace>PATIENT,<N>
 - < Application Name/Abbreviation/Namespace > USER, < N >

Where:

- < Application Name/Abbreviation/Namespace > is defined in the Approved Application Abbreviations document.
- <N> represents the first name as a number spelled out and incremented with each new entry.

For example, in Kernel (XU or KRN) test patient and user names would be documented as follows:

KRNPATIENT,ONE; KRNPATIENT,TWO; KRNPATIENT,THREE; ... KRNPATIENT,14; etc.

KRNUSER,ONE; KRNUSER,TWO; KRNUSER,THREE; ... KRNUSER,14; etc.

- "Snapshots" of computer commands and online displays (i.e., screen captures/dialogues) and computer source code, if any, are shown in a *non*-proportional font and may be enclosed within a box.
 - O User's responses to online prompts are **boldface** and (optionally) highlighted in yellow (e.g., <<u>Enter></u>).
 - o Emphasis within a dialogue box is **boldface** and (optionally) highlighted in blue (e.g., STANDARD LISTENER: RUNNING).
 - o Some software code reserved/key words are **boldface** with alternate color font.
 - References to "<Enter>" within these snapshots indicate that the user should press the Enter key on the keyboard. Other special keys are represented within <> angle brackets. For example, pressing the PF1 key can be represented as pressing <PF1>.
 - o Author's comments are displayed in italics or as "callout" boxes.



NOTE: Callout boxes refer to labels or descriptions usually enclosed within a box, which point to specific areas of a displayed image.

- This manual refers to the M programming language. Under the 1995 American National Standards Institute (ANSI) standard, M is the primary name of the MUMPS programming language, and MUMPS is considered an alternate name. This manual uses the name M.
- Descriptions of direct mode utilities are prefaced with the standard M ">" prompt to emphasize that the call is to be used *only in direct mode*. They also include the M command used to invoke the utility. The following is an example:

>D ^XUP

• All uppercase is reserved for the representation of M code, variable names, or the formal name of options, field/file names, and security keys (e.g., the XUPROGMODE security key).



NOTE: Other software code (e.g., Delphi/Pascal and Java) variable names and file/folder names can be written in lower or mixed case (i.e., CamelCase).

Documentation Navigation

This document uses Microsoft® Word's built-in navigation for internal hyperlinks. To add **Back** and **Forward** navigation buttons to your toolbar, do the following:

- 1. Right-click anywhere on the customizable Toolbar in Word 2007 or higher (*not* the Ribbon section).
- 2. Select Customize Quick Access Toolbar from the secondary menu.
- 3. Select the drop-down arrow in the "Choose commands from:" box.
- 4. Select **All Commands** from the displayed list.
- 5. Scroll through the command list in the left column until you see the **Back** command (circle with arrow pointing left).
- 6. Select/Highlight the **Back** command and select **Add** to add it to your customized toolbar.
- 7. Scroll through the command list in the left column until you see the **Forward** command (circle with arrow pointing right).
- 8. Select/Highlight the **Forward** command and select **Add** to add it to the customized toolbar.
- 9. Select **OK**.

You can now use these **Back** and **Forward** command buttons in the Toolbar to navigate back and forth in the Word document when selecting hyperlinks within the document.



NOTE: This is a one-time setup and is automatically available in any other Word document once you install it on the Toolbar.

How to Obtain Technical Information Online

Exported VistA M Server-based software file, routine, and global documentation can be generated through the use of Kernel, MailMan, and VA FileMan utilities.



NOTE: Methods of obtaining specific technical information online are indicated where applicable under the appropriate section.

REF: See the *Kernel Technical Manual* for further information.

Help at Prompts

VistA M Server-based software provides online help and commonly used system default prompts. Users are encouraged to enter question marks at any response prompt. At the end of the help display, you are immediately returned to the point from which you started. This is an easy way to learn about any aspect of VistA M Server-based software.

August 2016

Obtaining Data Dictionary Listings

Technical information about VistA M Server-based files and the fields in files is stored in data dictionaries (DD). You can use the List File Attributes option [DILIST] on the Data Dictionary Utilities menu [DI DDU] in VA FileMan to print formatted data dictionaries.



REF: For details about obtaining data dictionaries and about the formats available, see the "List File Attributes" chapter in the "File Management" section in the *VA FileMan Advanced User Manual*.

Assumptions

This manual is written with the assumption that the reader is familiar with the following:

- VistA computing environment:
 - o Kernel—VistA M Server software
 - o VA FileMan data structures and terminology—VistA M Server software
- Microsoft® Windows environment
- M programming language

Reference Materials

Readers who wish to learn more about Kernel should consult the following:

- Kernel Release Notes
- Kernel Installation Guide
- Kernel Systems Management Guide (this manual)
- Kernel Developer's Guide
- Kernel Technical Manual
- Kernel Security Tools Manual
- Kernel VA Intranet Website.

This site contains other information and provides links to additional documentation.

VistA documentation is made available online in Microsoft[®] Word format and in Adobe[®] Acrobat Portable Document Format (PDF). The PDF documents *must* be read using the Adobe[®] Acrobat Reader, which is freely distributed by Adobe[®] Systems Incorporated at: http://www.adobe.com/

VistA documentation can be downloaded from the VA Software Document Library (VDL): http://www.va.gov/vdl/



REF: Kernel manuals are located on the VDL at: http://www.va.gov/vdl/application.asp?appid=10

VistA documentation and software can also be downloaded from the Product Support (PS) Anonymous Directories.

1 Introduction

This manual provides descriptive information about Kernel for use by system administrators, application developers, Automated Data Processing Application Coordinators (ADPACs), and other end-users.

This manual assumes that the reader is familiar with the computing environment of the VA's Veterans Health Information Systems and Technology Architecture (VistA), and understands VA FileMan data structures and terminology. Some understanding of the M programming language is helpful for some parts of the manual. No attempt is made to explain how the overall VistA programming system is integrated and maintained; such methods and procedures are documented elsewhere. This manual does, however, provide an explanation of Kernel utilities, describing how they can be used to establish a standard user interface, monitor and manage the computer system, customize the environment according to local site needs, and define new areas of computing activities for users.

Kernel is a vendor-independent applications development environment, as well as a run-time environment providing standard vendor-independent services to applications software. It is not an operating system, but a set of utilities and associated files that are executed in an M environment. Kernel is central to VA VistA software strategy, in that it permits any VistA software application to run without modification on any hardware/software platform that supports American National Standards Institute (ANSI) Standard M. All operating system-specific, M implementation-specific, or hardware-specific code is isolated to Kernel. Therefore, porting VistA to a new environment requires modification only to a handful of Kernel routines.

As a whole, Kernel provides a computing environment that permits controlled user access, presents menus for choosing from various computing activities, allows device selection for output, enables the tasking of background processes, and offers numerous tools for system management and application programming. Kernel also provides tools for software distribution and installation.

VistA users see the same user interface, regardless of the underlying system architecture, because VistA applications are built using Kernel facilities for signon, database access, option selection, and device selection. As a result, user interaction with the system is constant across VistA applications.

1.1 Users

Kernel provides the doorway into the VistA computer system, the menus that tie together the options and utilities to enhance those options.

For the doorway, Kernel provides the Access and Verify code system that you use to establish your identity to the VistA computer system.

Once you have signed on, Kernel provides your menus. Each user on the computer system, as identified by their Access code, has their own individual set of menus and options.

The person or department managing the computer system organizes each user's menus. From your menu, you can run any application the computer system managers have made available to you. Kernel's menu system is what is used to make VistA applications (e.g., Scheduling, Nursing, and Personnel) available to users.

To produce output from VistA applications (e.g., to printers or to the terminal screen), Kernel provides a common device interface called the Device Handler. To queue a job rather than run it directly, the Device Handler links to a common queuing system called TaskMan.

This manual contains information about these and other parts of Kernel. The intent of this manual is to help you learn to use Kernel and take fullest advantage of the facilities it provides. This manual also includes information for system managers and developers; to find the information of interest to you, the general user, look for chapters and sub-chapters containing the phrase "User Interface" in their titles.

ADP Application Coordinators (ADPACs) may want to skim through the *Kernel Systems Management Guide* and concentrate on the user interface chapters and sub-chapters, particularly issues concerning every Kernel user (e.g., signon process and menu navigation).

1.2 System Managers

Kernel provides the backbone of an M computing platform, providing a mechanism to organize M programs as options, and a way to organize those options into a menu system for users. Kernel provides the following major system management components:

- Alerts provide an integrated notification system.
- Device Handler provides a common device interface.
- Electronic Signature Codes provide a secure electronic approval system.
- File Access Security system manages access to VA FileMan files.
- Kernel Installation and Distribution System (KIDS) provides an application distribution and installation system.
- Menu Manager provides a common menu management system.
- Signon/Security organizes users and allows secure logons.
- TaskMan provides a common job queuing system.

Kernel provides the system manager the means to manage a secure, multi-user M-based computer system. Some typical daily tasks performed by system managers using Kernel system management tools include:

- Setting up accounts for new users and terminating accounts for expired users.
- Adding and subtracting options from users' menus.
- Controlling file access for users.
- Monitoring TaskMan task queues.
- Terminating unwanted tasks.
- Monitoring devices.
- Creating and modifying links to output devices in the DEVICE file (#3.5).
- Installing software applications.

Within chapters and sub-chapters of this manual you can find general user information in the "User Interface" section and system manager information in the "System Management" section.



REF: For information on developer tools (e.g., Direct Mode Utilities and Application Program Interfaces [APIs]), see the *Kernel Developer's Guide*. Kernel and Kernel Toolkit APIs are also available in HTML format at a VA Intranet Website.

Information on recommended system configuration and setting Kernel's site parameters, as well as lists of files, routines, options, and other components are documented in the *Kernel Technical Manual*.

Information about managing computer security, which includes a detailed description of techniques that can be used to monitor and audit computing activity, is presented in the *Kernel*

Security Tools Manual.

Instructions for installing Kernel are provided in the *Kernel Installation Guide*. This guide also includes information about software application management (e.g., recommended settings for site parameters and scheduling time frames for tasked options).

I. Signon/Security

2 Signon/Security: User Interface

The first step you take each time you access the computer system is called signing on. When you sign on to the VistA computer system, you are required to enter an Access and Verify code. These codes identify you to the computer system, and, as these codes are private to you, serve to prevent unauthorized access to your account.

You are shielded from most steps in the signon process. In the background, Kernel's Signon/Security establishes the proper environment, records and monitors the signon event, and takes you to Menu Manager. Menu Manager presents a list of menu options that let you interact with other parts of Kernel and software applications. When you complete a session on the computer system, you sign out to exit.

2.1 Signing On

To authenticate yourself to VistA (Kernel's "front door"), you need to sign onto the system by entering your Access and Verify codes. The user signon (authentication) interface varies based on the type of Vista application software being run:

- 2-Factor Authentication—VistA supports delegated 2-factor authentication through Identity and Access Management (IAM). A smart card containing Public Key Infrastructure (PKI) digital certificates combined with a private security is used to authenticate and uniquely identify the user. The user is prompted for a Personal Identification Number (PIN) to unlock the security key and authenticate. This method of authentication provides a higher level of security and takes precedence over all other forms of authentication. As client applications are migrated to 2-factor authentication, other forms of authentication may be deprecated and disabled.
- Character User Interface (CHUI)-based applications—This includes M-based roll-and-scroll applications used to access Kernel on the VistA M Server (e.g., Laboratory, Pharmacy). With this type of authentication interface, users are first prompted with an "ACCESS CODE:" prompt. Entering an Access code and pressing the **Enter**> key brings up the "VERIFY CODE:" prompt.



REF: For a sample of the roll-and-scroll signon prompts, please see Figure 1.

Graphical User GUI client/server applications—This includes rich client or client/server applications used to access Kernel on the VistA M Server via RPC Broker (Delphi/Pascal)- or VistALink (Java)-based components (e.g., Computerized Patient Record System [CPRS] or Care Management). With this type of authentication interface, users are presented with a GUI signon dialogue box. Users can click in or tab to the Access and Verify code entry fields and press OK.



REF: For a sample of the RPC Broker signon dialogue box and more information on RPC Broker, see the RPC Broker documentation located on the VA Software Document Library (VDL) at: http://www.va.gov/vdl/application.asp?appid=23

• Web-based applications—This includes Web-based applications that use a client Web browser and Kernel Authentication and Authorization Java (2) Enterprise Edition (KAAJEE) to access Kernel on the VistA M Server (e.g., Blind Rehab). With this type of authentication interface, users are presented with a GUI signon dialogue Web page. Users can click in or tab to the Access and Verify code entry fields and press **Login**.




REF: For a sample of the KAAJEE signon dialogue Web page and more information on KAAJEE, see the KAAJEE documentation located on the VA Software Document Library (VDL) at: http://www.va.gov/vdl/application.asp?appid=151

Your Access code establishes your unique identity to Kernel. Your matching Verify code corroborates your identity completing the VistA Kernel authentication process. Asterisks only are displayed when you enter your Access and Verify codes so that the actual characters are *not* displayed (echoed back) on the screen. Codes are encrypted after they are entered and compared with the encrypted stored values for a match.



REF: For a description of valid and strong Access and Verify codes, see the "<u>Defining a Strong</u> Verify Code" section.

Figure 1: Signing on to VistA—Sample roll-and-scroll user authentication dialogue



Entering a valid Access and Verify code combination completes the signon authentication process and takes you beyond Signon/Security into Kernel's Menu Manager (or other security role-based access keys) used to authorize your appropriate level of access to data or application functionality.

If you have not been assigned a primary menu, Kernel displays a message indicating that access is not allowed, and signs you out from the computer system. Similarly, if your primary menu has been marked as "out-of-order" (an option attribute), Kernel also denies you access (see <u>Figure 2</u>).



REF: For more information on primary menus, see the "Menu Manager" section.

Figure 2: Access denied due to no primary menu or menu "out of order" message

ACCESS CODES: *******

VERIFY CODES: *******

Device: _TNA8628: <Enter>
No access allowed for this user.

2.1.1 Defining a Strong Verify Code

While Access codes are a unique identifier (i.e., username) for your user record in Kernel's NEW PERSON file (#200), Verify codes are secret passwords assuring that the person signing on is the one for whom the user record was established. You rarely need to be issued a new Access code, but you *must* change your Verify code (i.e., password) if you suspect that someone else has used it to gain access to the system or when your Verify code has expired (i.e., every 90 days or less). You can change your Verify code with the Edit User Characteristics option, which is available from the Common menu User's Toolbox menu.

As of Kernel patch XU*8.0*180, strong Access and Verify codes must adhere to the following criteria:

- Access and Verify codes *cannot* be identical.
- Verify codes (i.e., passwords) *must* be at least 8 characters in length.
- Strong passwords in general contain at least three of the following four character types:
 - o Uppercase letters
 - Lowercase letters
 - Numbers
 - o Special characters/symbols that are neither letters nor numbers (e.g., -, _, #, &, \$, *, @)



NOTE: The caret (^) is a reserved symbol and *cannot* be used as part of a Verify code. Also, some *non*-VistA-based systems restrict certain special characters/symbols used as part of a username or password.

Because VistA is case-insensitive, VistA only has three sets of characters from which to build a strong Verify code (i.e., password):

- o Letters (of any case)
- o Numbers
- o Special characters/symbols that are neither letters nor numbers (e.g., -, _, #, &, \$, *, @)



NOTE: Some *non*-VistA-based systems restrict certain special characters/symbols used as part of a username or password.

- Verify codes *must* be changed at least every 90 days (or less). You *must* change your Verify code at periodic intervals as specified by the system administrators. Information systems shall *not* permit re-assignment of the last three passwords used. When required, you are prompted during signon to pick a new Verify code.
- Accounts that have been inactive for 90 days shall be disabled.
- To preclude password guessing, an intruder lockout feature shall suspend accounts after five invalid attempts to log on. Where around-the-clock system administration service is available,

system administrator intervention shall be required to clear a locked account. Where around-the-clock system administration service is *not* available, accounts shall remain locked out for at least ten minutes.



NOTE: These rules are taken from the *VA Account and Password Management Interim Policy* document.

All of these restrictions are enforced whenever Access or Verify codes are created or changed.

These changes were made to meet VA Directive 6500 and VA Handbook 6500.



REF: For more tips and general advice regarding Access and Verify codes and security in general, see the *Kernel Security Tools Manual*.

2.1.1.1 Why Longer Passwords?

Passwords used to access VA systems *must* be at least 8 characters long because longer passwords are stronger, and thus, harder to guess than shorter ones. While VistA currently supports 8-character passwords (Verify codes), current security policy *recommends* that a minimum of 15 characters be used. This policy will be enforced in a future VistA Kernel patch.

The more tries it takes a hacker or a program to guess a password, the more secure the system is. Adding just one character to the length of a password greatly increases the difficulty of guessing the password.

If you have forgotten your Verify code (password), the site's Information Security Officer (ISO) should delete the existing code, and then instruct you to sign on again. At the "Verify code" prompt simply press the **Enter**> key without making any other entries. You are prompted to enter a new Verify code and then re-prompted to enter the same Verify code again as confirmation. If you do not want to bother inventing a Verify code, entering a question mark ("?") at the Verify code prompt displays a possible although cryptic choice (e.g., DKMl&493). Entering a question mark a second time displays another choice. When you log off, you're reminded to remember the new Verify code for use at your next signon.

2.1.2 LOGIN Menu Template

You can execute a script of options on your first signon of the day by having a MENU template called LOGIN.



REF: For more information, see the "Menu Manager: User Interface" chapter.

2.1.3 Signon Shortcuts

In roll-and-scroll VistA, to reach the primary menu in one step at the "ACCESS CODES:" prompt, you can enter the Access and Verify code as one string separated by a semicolon:

Figure 3: Entering the Access and Verify codes at the same time

```
ACCESS CODES: ACCESSCODE; VERIFYCODE
Good afternoon. You last signed on today at 12:00
```

To "jump start" directly to a particular option, you can specify the name of an option after another semicolon:

Figure 4: Entering the Access and Verify codes at the same time and jumping directly to a specified option

```
ACCESS CODES: ACCESSCODE; VERIFYCODE; INTRO
Good afternoon. You last signed on today at 12:00
INTROductory text edit
```

To force the Kernel query of the terminal type identity, you can include a colon anywhere in the string.



REF: If you want to avoid the terminal type query, see the "Terminal Type Prompt" section.

2.1.4 Normal Signoff

When you complete a session on the computer system, you should sign off the system so that no one can come along and use the computer system under your identity. There are several ways you can sign off of the system.

Figure 5: System commands: Menu options for signoff

SYSTEM COMMAND OPTIONS	[XUCOMMAND]
Halt Continue	[XUHALT] [XUCONTINUE]
Restart Session	[XURELOG]

One way to sign off is to enter "halt" at any menu prompt. When you sign off using "halt," at next signon, after entering Access and Verify codes, your normal primary menu is your first menu.

Or, to sign off, you can enter "continue." At your next signon, after entering Access and Verify codes, your last-used menu when you signed off is your first menu for that session.

If remotely connected via modem or other network device, you can enter "restart" to sign out of Kernel without dropping the communication line.

Finally, you can sign off without using any of these shortcuts simply by pressing **<Enter>** at each menu prompt to step back up the menu pathway and finally exit.



REF: For more information on menus and menu prompts, see the "<u>Menu Manager: User Interface</u>" section.

2.1.5 Abnormal Signoff and Error Handling

If you encounter an error while using the VistA computer system, Kernel traps it, issue the message "Sorry 'bout that", and attempt to return you to your primary menu. Kernel can recover from most error conditions and, given a suitable environment, permits you to continue. Some error conditions, however, cause an abnormal exit such that you are immediately logged off the computer system. When this happens, you can sign on again if you still need to use the computer system.

2.1.6 Terminal Type Prompt

When signing on, you may be prompted to enter a terminal type. You should not see this prompt very often, however, since Kernel usually can identify your terminal type without needing to prompt you to enter one. If you are prompted, you should enter the name of the actual terminal type to use (e.g., C-VT220). The entered terminal type tells Kernel how to support screen-oriented and other enhanced displays. If unusual circumstances arise and the wrong terminal type is in effect, you can redefine it by using the Edit User Characteristics option (available through the User's Toolbox menu, discussed below).

The Edit User Characteristics option lets you edit a setting (ASK DEVICE TYPE AT SIGN-ON) that allows you to decide whether to bypass the usual terminal type query. If you always work at the same terminal and want to save a small amount of time during the signon process, you can set ASK DEVICE TYPE AT SIGN-ON to DON'T ASK. Kernel then assumes that your last terminal type should be used as the default.

If you have ASK DEVICE TYPE AT SIGN-ON set to DON'T ASK, and sign on using a terminal whose terminal type is different from the one normally used, you should signon by including a colon (":") after your Access code. This forces Kernel to query the terminal for its identity. Alternatively, once signed on, you could invoke the Edit User Characteristics option to change your terminal type to the one currently in use. Or, you could use this option to reset the ASK DEVICE TYPE AT SIGN-ON question to ASK, log off and sign back on (whereby Signon/Security obtains the correct terminal type identification).

2.2 Escaping from a Jumbled Screen

One consequence of your signon terminal type not matching the actual one being used is that full-screen display could appear jumbled. To escape from a ScreenMan form (e.g., Edit User Characteristics), all you need to do is enter two carets ("^"), each followed by the **Enter>** key. To escape from VA FileMan's Screen Editor, you should press **PF1>E** to exit.

2.3 Alerts

After signing on, you could be presented with an alert notice just before the menu prompt. If so, you need to pick the View Alerts "VA" option [XQALERT] for viewing alerts to take care of urgent, pending matters.



REF: For more information about alerts, see the "Alerts" chapter.

Figure 6: System commands: View Alerts "VA" option

SYSTEM COMMAND OPTIONS ... [XUCOMMAND]
View Alerts "VA" [XQALERT]

2.4 User's Toolbox Menu

The User's Toolbox menu [XUSERTOOLS] is available from any menu prompt, by entering the toolbox synonym (e.g., "TBOX") or "User's Toolbox." It makes available, from one menu, some of the most frequently used Kernel options.

Figure 7: User's Toolbox menu options

```
Select User's Toolbox Option:
                                                                       [XUSER DIV CHG]
          Change my Division
          Display User Characteristics
                                                                          [XUUSERDISP]
          Edit User Characteristics
                                                                       [XUSEREDITSELF]
          Electronic Signature code Edit
                                                                             [XUSESIG]
          Menu Templates ...
                                                                             [XQTUSER]
          Spooler Menu ...
                                                                         [XU-SPL-MENU]
             **> Locked with XUMGR
                                                                       [XU SWITCH UCI]
          Switch UCI
                                                                          [XUTM USER]
          TaskMan User
          User Help
                                                                          [XUUSERHELP]
```

<u>Table 2</u> lists the options contained in the User's Toolbox menu and the chapters where each option is described:

Table 2: User's Toolbox menu options and documentation references

Option Text	Chapter Described	
Change my Division [XUSER DIV CHG]	Signon/Security: User Interface	
Display User Characteristics [XUUSERDISP]	Signon/Security: User Interface	
Edit User Characteristics [XUSEREDITSELF]	Signon/Security: User Interface	
Electronic Signature code Edit [XUSESIG]	Electronic Signatures	
Menu Templates [XU-SPL-MENU]	Menu Manager: User Interface	
Spooler Menu [XU-SPL-MENU] (locked with XUMGR security key)	Spooling	
Switch UCI [XU SWITCH UCI]	Signon/Security: User Interface	
TaskMan User [XUTM USER]	TaskMan: User Interface	
User Help [XUUSERHELP]	(accesses online help)	

2.5 Change my Division Option

The Change my Division option [XUSER DIV CHG] allows users to select from a list of divisions, if any, stored for that user in the NEW PERSON file (#200).

2.6 Edit User Characteristics Option

The Edit User Characteristics option [XUSEREDITSELF] is one of the options available from the User's Toolbox menu. It allows you define some characteristics of your online environment via ScreenMan, as shown below:

Figure 8: Edit User Characteristics option—ScreenMan form

EDIT USER CHARACTERISTICS NAME: XUUSER, ONE PAGE 1 OF 1 INITIAL: OX PHONE: NICK NAME: ONE OFFICE PHONE: (555) 555-5555 TITLE: DOCTOR VOICE PAGER: DIGITAL PAGER: ASK DEVICE TYPE AT SIGN-ON: DON'T ASK AUTO MENU: YES, MENUS GENERATED TYPE-AHEAD: ALLOWED TEXT TERMINATOR: PREFERRED EDITOR: SCREEN EDITOR - VA FILEMAN NETWORK USERNAME: VHAIXXXUUSERO ELECTRONIC SIGNATURE CODE: <Hidden> Want to edit VERIFY CODE (Y/N): Exit Save Refresh Enter a command or '^' followed by a caption to jump to a specific field. COMMAND: Press <PF1>H for help Insert

There are a number of NEW PERSON file (#200) field values that you can edit with the Edit User Characteristics option:

Table 3: Edit User Characteristics option—Editable fields

Field	Description		
INITIAL (#1)	Enter your initials, which can serve as an alternate way for users to specify your account (e.g., when sending mail to you).		
NICK NAME (#13)	Enter a nick name, which can serve as an alternate way for users to specify your account (e.g., when sending mail to you).		
TITLE (#8)	Enter a title from a given list of choices or enter a new TITLE.		
Telephone Contact Information: PHONE (HOME) (#.131) OFFICE PHONE (#.132) VOICE PAGER (#.137) DIGITAL PAGER (#.138)	Enter the appropriate phone numbers in the fields indicated.		
ASK DEVICE TYPE AT SIGN-ON (#200.05)	This field controls whether Kernel should determine what kind of terminal you are using when you sign on. If this is set to DON'T ASK, Kernel assumes you are using the same kind of terminal you used the last time you signed on. This can cause problems if you are using a		

Field	Description		
	different kind of terminal (screen displays may not work properly), so this should normally be set to ASK.		
AUTO MENU (#200.06)	This field determines whether, in the menu system, a list of items on the current menu is displayed with the menu prompt. Beginning users should usually set AUTO MENU to YES so that they can see menu items for each menu. Experienced users who are familiar with their menus may prefer to set this field to NO , which makes menu displays speedier, since individual items on each menu are <i>not</i> displayed.		
TYPE-AHEAD (#200.09)	This field controls whether characters you type faster than the system can process end up being processed or not. Normally you should set TYPE-AHEAD to YES , so that keystrokes you enter are not lost due to system slowness.		
TEXT TERMINATOR (#31.2)	The TEXT TERMINATOR is a setting used by VA FileMan's Line Editor. When you are using the Line Editor and are importing text from an external source, you may not want a blank line to indicate the end-of-file, which could prematurely terminate the text transfer. By default, the TEXT TERMINATOR in VA FileMan's Line Editor is the carriage return character (<enter>). Setting this to another character string, like ZZ (something that is <i>not</i> encountered in the target text) can permit downloading without interruption. If you change the setting of the TEXT TERMINATOR from the default of the carriage return character, you need to remember your TEXT TERMINATOR when using the Line Editor; otherwise, you are unable to exit the Line Editor.</enter>		
PREFERRED EDITOR (#31.3)	VA FileMan User Manual. Users can choose which text editor Kernel uses when you edit word-processing fields on the system. You can choose any editor defined on		
NETWORK USERNAME (#501.1)	your system. Enter your network user name. This is the username that is used by the Windows Active Directory (AD). It allows VISN data extracts to link the VistA user with their network user name. Format: "VHA" + 3 character station ID + first 5 characters of last name + first character of first name		
	For example, for user One Xuuser at Station ID 999, the network user name would be: VHA999XUUSEO		
	Holders of the XUMGR security key can override this field.		
	NOTE: This field was added to the NEW PERSON file (#200) with Kernel patch XU*8.0*514.		
ELECTRONIC SIGNATURE CODE (#20.4)	Enter a new electronic signature code. This is a code (similar to a password) used to electronically sign documents within VistA. When you press Enter , the code is hidden for security purposes.		
VERIFY CODE (#7.2)	Users can change their VERIFY CODE by answering YES to this field. First enter your current VERIFY CODE; then, enter a new VERIFY		

Field	Description
	CODE. You are asked to confirm the new VERIFY CODE by entering it a second time; if you confirm it, the new VERIFY CODE takes effect immediately.

2.7 Display User Characteristics Option

The Display User Characteristics option [XUUSERDISP], like Edit User Characteristics, is an option in the User's Toolbox menu. It prints out a description of many of the characteristics of your current computing environment, including some of the characteristics that can be set through the Edit User Characteristics option.

Figure 9: Display User Characteristics option—Sample output and user dialogue

```
JOB: 541754169
XUUSER, TWO (#9999) DEVICE: DEVICE: TELNET
                                            ($I: TNA730:)
ENVIRONMENT
                                         ATTRIBUTES
_____
                                         _____
   Site ..... TESTSITE
                                          Type-ahead ..... Y
   UCI ..... KRN, KDE
                                         Time-out ..... 300
   Signed on ... 08:48
                                         Fileman code(s) .. #
   Terminal type C-VT100
Person Class: Physicians (M.D. and D.O.)
                Physician/Osteopath
                  Pathology, Anatomic
KEYS HELD
XMMGR
                   XUPROG
                                       XUPROGMODE
MENU PATH
  SYSTEM COMMAND OPTIONS (XUCOMMAND)
   User's Toolbox (XUSERTOOLS)
     Display User Characteristics (XUUSERDISP)
'^' to escape, <CR> to view Mailman user info: <Enter>
Current Banner: Technical Writer
Last used MailMan: 07/12/06@15:09
NEW messages: 274 (274 in the IN basket)
Office phone: (555) 555-5555
Fax: (555) 555-5555
Add'l phone: (555) 555-5555
Add'l phone: (555) 555-5555
Introduction:
  My name is One Xmuser and I am one of the Technical Writers for the
  Common Services (CS) products/projects (e.g., Broker, Components,
  Kernel, VA FileMan, MailMan, Toolkit).
Mail Groups:
  FO-SITE STAFF
                                                 (Public)
  KERNEL PROGRAMMERS
                                                 (Public)
```

2.8 Switch UCI Option

The Switch UCI option [XU SWITCH UCI] allows users to select from a list of UCIs, if any, stored for that user in the NEW PERSON file (#200).

2.9 Summary

VistA's Kernel's Signon/System Security module provides the means for signing into Kernel with a unique identity. Once you complete the signon process, you are sent to Kernel's menu system, where you can run any option your system manager has placed in your menus. When you finish a computer session, always be sure to sign off; this protects your account from misuse by someone else.

3 Signon/Security: System Management

This chapter describes the system management tools for Kernel's Signon/Security module.

3.1 Signon Process

If signons are enabled, as shown in the Signon Flow Chart in Figure 13, the signon process begins with a gathering of information from the KERNEL SYSTEM PARAMETERS file (#8989.3) and then from the DEVICE file (#3.5) to determine whether to allow signon for this session and, if so, how to create an appropriate environment. If, for example, the MAX SIGNON ALLOWED limit has been reached, the signon attempt fails. If the current device is tied to a routine (as specified in the TIED ROUTINE field of the DEVICE file [#3.5]), that routine is executed and the session is halted. If not, the user is prompted for Access and Verify codes. After a successful signon, attributes for that user are then retrieved from the NEW PERSON file (#200). Signon/Security then sends the user to Menu Manager. If a primary menu is associated with the device (PRIMARY MENU OPTION field in the DEVICE file [#3.5]), that menu is presented. Otherwise, the user's primary menu is presented. If the user does not have a primary menu (the PRIMARY MENU OPTION field in the NEW PERSON file [#200] is **NULL**), the session is halted.

The signon flow chart in this section (see Figure 13) illustrates the procedural steps taken by Kernel's Signon/Security system to determine whether to permit signons and, if so, how to create an appropriate computing environment. Typically, after site parameters and device characteristics are checked, the user is prompted for Access and Verify codes, user attributes are collected, and a primary menu prompt is presented. Client applications that are enabled to use 2-factor authentication will automatically enter a token obtained from Identity and Access Management (IAM) instead of an Access and Verify code to authenticate and identify the user.

3.1.1 Introductory Text

Before gathering system parameters or prompting for Access and Verify codes, Signon/Security displays contents of the INTRO TEXT field in the KERNEL SYSTEM PARAMETERS file (#8989.3). The text can be edited with the Enter/Edit Kernel Site Parameters option or with the Introductory text edit option [XUSERINT], an option specially designed for this purpose).

Figure 10: Introductory text edit option

```
SYSTEMS MANAGER MENU ... [EVE]
Operations Management ... [XUSITEMGR]
Introductory text edit [XUSERINT]
```

3.1.2 Parameters Checked during Signon

Various parameters are checked as an initial step in the signon process. The KERNEL SYSTEM PARAMETERS file (#8989.3) stores the default values for most of the parameters. Values for critical fields should be defined by system administrators when Kernel is installed. The values in the KERNEL SYSTEM PARAMETERS file (#8989.3) can be edited any time, though, with the Enter/Edit Kernel Site Parameters option [XUSITEPARM].

Figure 11: Enter/Edit Kernel Site Parameters option

```
SYSTEMS MANAGER MENU ... [EVE]
Operations Management ... [XUSITEMGR]
Kernel Management Menu ... [XUKERNEL]
Enter/Edit Kernel Site Parameters [XUSITEPARM]
```

Figure 12: Enter/Edit Kernel Site Parameters option—ScreenMan form 1

```
Kernel Site Parameter edit
           DOMAIN: XXX.FO-SITE.MED.VA.GOV
       DEFAULT # OF ATTEMPTS: 3
                                                   AGENCY CODE: VA
       DEFAULT LOCK-OUT TIME: 600
    DEFAULT MULTIPLE SIGN-ON: Only one MULTIPLE SIGN-ON LIMIT: 2
          DEFAULT AUTO-MENU: YES DEFAULT AUTO SIGN-ON: Disabled
           DEFAULT LANGUAGE: 1
         DEFAULT TYPE-AHEAD: YES
DEFAULT TIMED-READ (SECONDS): 300
                                                BROKER TIMEOUT: 180
     BYPASS DEVICE LOCK-OUT: NO
                                            CCOW TOKEN TIMEOUT:6000:
     LIFETIME OF VERIFY CODE: 90
                                       ASK DEVICE TYPE AT SIGN-ON: YES
        DEFAULT INSTITUTION: SAN FRANCISCO
  AUTO-GENERATE ACCESS CODES: NO
        LOG RESOURCE USAGE?: YES
Exit
        Save
                 Next Page
                               Refresh
Enter a command or '^' followed by a caption to jump to a specific field.
COMMAND:
                                                                       Insert
                                              Press <PF1>H for help
```

3.1.2.1 Signon Attempts and Device Lock-out Times

The DEFAULT # OF ATTEMPTS field in the KERNEL SYSTEM PARAMETERS file (#8989.3) holds the default limit of the number of times a user can try to enter a valid Access and Verify code pair. When the limit is reached, Signon/Security is unresponsive for the duration specified by the DEFAULT LOCK-OUT TIME field. The values for number of attempts and lock-out time are overridden by any values for the current device specified by comparable fields in the DEVICE file (#3.5). Device values are ignored, however, if the BYPASS DEVICE LOCK-OUT site parameter in the KERNEL SYSTEM PARAMETERS file (#8989.3) is set to YES. In particular, the fields that are bypassed are OUT-OF-SERVICE DATE, SECURITY, and PROHIBITED TIMES FOR SIGN-ON. Device values are put back into effect for the current device if the DEVICE file's PERFORM DEVICE CHECKING field is set to YES.

3.1.2.2 MAX SIGNON ALLOWED

One Kernel site parameter used in the initial signon screening is MAX SIGNON ALLOWED. It is a field within the VOLUME SET field (Multiple) in the KERNEL SYSTEM PARAMETERS file (#8989.3). Its value sets an upper limit for number of M processes (interactive, background, and system) that can run concurrently on the specified Volume Set or CPU. The TASKMAN JOB LIMIT, a field in the TASKMAN SITE PARAMETERS file (#14.7), should be set to a number slightly lower than MAX SIGNON ALLOWED to leave room for a few interactive logons when TaskMan is busiest.



NOTE: OpenVMS Sites: The OpenVMS interactive logins parameter (set by the DCL command SET LOGINS/INTERACTIVE) should be set to a number less than the Kernel MAX SIGNON ALLOWED to conserve system resources. If the OpenVMS limit is set too high in relation to the Kernel limit, users try to access Kernel only to be rejected when reaching Signon/Security. That means that they would waste system resources by creating a new OpenVMS process and activating a Caché image, all to no avail.

REF: For more information about alerts, see "Alerts."

3.1.2.3 PROHIBITED TIMES FOR SIGN-ON

Time periods can be specified, during which interval signons can be barred by device or by user. This is controlled by the PROHIBITED TIMES FOR SIGN-ON field in the DEVICE file (#3.5) and a comparable field in the NEW PERSON file (#200).

Begin Display Introductory Text Get system parameters from KERNEL SYSTEMS PARAMETERS file Update system parameters from DEVICE file: 1. Number of bad attempts allowed. 2. Lockout time after bad sign-on. 3. Prohibited time after bad sign-on. 4. Time to wait for a response Yes TIED ROUTINE Check if device is "tied" to a function Enter Access and Verify codes No (2-Factor Authentication clients will automatically enter a Secure Token Service token Halt here to authenticate and identify the user) Check if DISUSER flag is set for user Halt No Retrieve Post Sign-in Text Append one-line greeting Execute XU USER SIGN-ON extended-action option Display Post Sign-in Text Update system parameters from NEW PERSON file Query Terminal Type Yes DEVICE PRIMARY MENU Check if terminal is tied to a menu No USER PRIMARY MENU Check if user is tied to a menu No Execute the Routine Menu Manager Halt

Figure 13: Kernel Signon flow chart

3.1.2.4 Multiple Sign-On Restriction

The DEFAULT MULTIPLE SIGN-ON field in the KERNEL SYSTEM PARAMETERS file (#8989.3) controls whether users can create two or more simultaneous sessions by signing on to more than one device. The setting is overridden by comparable fields in the DEVICE (#3.5) and NEW PERSON (#200) files, respectively. The value is checked at signon to prevent unauthorized multiple sessions.

If multiple signons are prohibited, problems can occur if users experience an abnormal exit such that the signon record cannot be cleared. To clear an individual user, the Release User option can be used (described later in this chapter). To make sure all users are clear when the system is brought up after a crash, system administrators can use the Clear all users at startup option.

3.1.2.5 INTERACTIVE USER'S PRIORITY

The INTERACTIVE USER'S PRIORITY parameter in the KERNEL SYSTEM PARAMETERS file (#8989.3) should usually be left **NULL**. A setting here affects the job priority of interactive users and could result in poor response time.

3.1.2.6 ASK DEVICE TYPE AT SIGN-ON

The ASK DEVICE TYPE AT SIGN-ON parameter controls whether the user's current device at signon is queried for its display attributes (DA). Thus, the correct terminal type can be identified without prompting the user.

It is recommended that ASK DEVICE TYPE AT SIGN-ON be set to ASK so that Signon/Security performs the DA query and allows the Device Handler to set up the correct terminal type attributes. This has become more important with the advent of screen control. VA FileMan's Screen Editor and Screen Manager, for example, does *not* function properly if the terminal type recorded by Kernel fails to match the actual terminal type being used.

As with other parameters, the site default (ASK DEVICE TYPE AT SIGN-ON field in the KERNEL SYSTEM PARAMETERS file [#8989.3]) is overridden by a DON'T ASK setting for the device (likenamed field in the DEVICE file [#3.5]), which would similarly be overridden by a DON'T ASK setting for the user (likenamed field in the NEW PERSON file [#200]). A **NULL** value functions as ASK. The user override can be set by any user via the Edit User Characteristics option.

If the parameter is set to DON'T ASK, Signon/Security does not perform the DA query and assumes the user's last terminal type is still appropriate. Although the difference in resource consumption is negligible, the user can appreciate a split second's savings in time. Thus, bypassing the DA query can be acceptable, if the same terminal type is always being used. But if the user should sign onto another terminal type, problems can occur with the presentation of screen-oriented displays unless the user knows how to change the terminal type to match the actual current one.

If the device is non-ANSI-standard, Signon/Security may not find a DA but continues to determine the terminal's identity by querying its answerback message. All known non-ANSI devices (e.g., Qume 102 terminal) should have their answerback messages programmed. This is accomplished by using the terminal type setup mechanism and entering C-QUME as the Qume 102's answerback message. The name *must* match an entry in Kernel's TERMINAL TYPE file (#3.2) to take effect. If the answerback message contains additional characters (e.g., a serial number), the message does *not* match an entry in the TERMINAL TYPE file (#3.2) and is useless for signon purposes.

If the terminal's DA return code does not match an entry in the DA RETURN CODES file (#3.22), or if the terminal is non-ANSI and cannot be programmed with an appropriate answerback message, Signon/Security prompts the user to identify the terminal type if the user's ASK DEVICE TYPE AT SIGN-ON setting is set to ASK. This is the only case in which the terminal type prompt is asked during signon. The last terminal type used is presented as the default (it is stored in the NEW PERSON file

[#200]). If ASK DEVICE TYPE AT SIGN-ON is set to DON'T ASK, Signon/Security assumes that the last terminal type is appropriate and does not prompt the user for validation.

3.1.2.7 Display Attributes (DA) Return Codes

The DA RETURN CODES file (#3.22) is used to equate DA return codes to entries in the TERMINAL TYPE file (#3.2). You can use the DA Return Code Edit option to automate the population of the DA RETURN CODES file (#3.22).



REF: For more information, see the "<u>Managing Display Attributes (DA) Return Codes</u>" section in the "<u>Device Handler: System Management</u>" chapter.

3.1.2.8 SELECTABLE AT SIGNON

System administrators can also control which devices can be selected at signon with a field in the TERMINAL TYPE file (#3.2). The SELECTABLE AT SIGN-ON flag should be set to **YES** for all devices commonly used for sign on. Ordinarily, it should not be set for printers (e.g., P- terminal types P-DEC or P-OTHER). To allow the loading of ScreenMan forms and proper functioning of other screen-oriented displays, the flag should also not be set for PK- types, that is, printers with keyboards. This is not an actual restriction, however, but a recommendation.

3.1.2.9 LIFETIME OF VERIFY CODE

To insure that users change their Verify codes at periodic intervals, system administrators should set the LIFETIME OF VERIFY CODE parameter in the KERNEL SYSTEM PARAMETERS file (#8989.3) to a certain number of days. The maximum number is 90 days and the minimum number is 1 day. Thus, sites can choose any number from 1-90 days before requiring users to change their Verify code. At the end of that period (e.g., every 90 days), users *must* then change their Verify codes. Signon/Security checks whether the Verify code needs to be changed, and if so, prompts the user at signon to enter a new Verify code.

3.1.2.10 AUTO-GENERATE ACCESS CODES

When assigning Access codes, the security officer or system administrators can invent an alphanumeric string or can ask Kernel to generate one. If the AUTO-GENERATE ACCESS CODES site parameter in the KERNEL SYSTEM PARAMETERS file (#8989.3) is set to **YES**, only generated, cryptic codes can be assigned. It is not necessary to pick the first one presented; others can be generated for selection.

3.1.2.11 DEFAULT INSTITUTION and AGENCY

The institution running Kernel software is defined during the Kernel installation when prompted for the DEFAULT INSTITUTION in the KERNEL SYSTEM PARAMETERS file (#8989.3). This field is a pointer to the INSTITUTION file (#4). One or more institutional affiliations can also be associated with a user (e.g., a VA Outpatient Clinic and an Army Medical Center). This data is stored in the DIVISION field (Multiple) in the NEW PERSON file (#200). If a user is associated with more than one institution (division), the user is prompted at signon to select a division. In this way, the local variable DUZ(2) can be set to the appropriate value. If the user's DIVISION field (Multiple) is blank, the DEFAULT INSTITUTION field (File #8989.3) is used to define DUZ(2). Since the INSTITUTION file (#4) contains a pointer to the AGENCY file (#4.11), the signed-on user's agency affiliation can also be determined.

The KERNEL SYSTEM PARAMETERS file (#8989.3) also contains the AGENCY CODE (#9). This field is *not* a pointer but is instead a Set of Codes (e.g., "N" for Navy or "V" for VA). This field is presented for editing during Kernel installation. Its value is used at sign on to set the DUZ("AG") local variable. Thus, the agency associated with the overall Kernel system can be determined.

3.1.2.12 AUTO MENU

The AUTO MENU flag, stored in the local variable DUZ("AUTO"), is used by Menu Manager to control whether all items on a menu are presented automatically after each cycle through the menu system. If the items are not displayed, the user can always invoke the display by entering a question mark ("?"). New users often like to see all the menu choices. Experienced users probably do not need to see the choices and the display can be suppressed to save system resources. The user setting for AUTO MENU (in the NEW PERSON file [#200]) overrides any comparable device setting (File #3.5), which will, in turn, override the site parameter default (File #8989.3). Users can edit the setting with the Edit User Characteristics option.

3.1.2.13 TYPE-AHEAD

If TYPE-AHEAD is disabled, any keystrokes that the user enters while computer system processes previously issued instructions do *not* register. If TYPE-AHEAD is enabled, keystrokes entered in advance of processing are stored in the TYPE-AHEAD buffer and is interpreted when the earlier process is finished. New users may experience unwanted results if TYPE-AHEAD is enabled and they had not anticipated the effect. Experienced users may prefer TYPE-AHEAD for efficiency. The user setting overrides the device setting, which, in turn, overrides the site parameter setting. Users can edit the setting with the Edit User Characteristics option.

3.1.2.14 TIMED READ

The value for the TIMED READ parameter is stored in the local variable DTIME and is used to calculate how long Kernel should wait before terminating a READ. If, for example, a user does not respond to a menu prompt in the number of seconds defined by the TIMED READ, Kernel takes steps towards signoff and, without subsequent user response, halts the user session. The user setting overrides the device setting, which, as usual, overrides the site default.

3.1.2.15 POST SIGN-IN MESSAGE

The POST SIGN-IN MESSAGE is similar to introductory text (i.e., INTRO TEXT field in File #8989.3), except that Kernel displays it only after a successful signon. Like the introductory text, you can edit the message text using the Enter/Edit Kernel Site Parameters option; alternately, you can use the Post sign-in Text Edit option [XUSERPOST], which is specially designed for this purpose:

Figure 14: Post sign-in Text Edit option

```
SYSTEMS MANAGER MENU ... [EVE]
Operations Management ... [XUSITEMGR]
Post sign-in Text Edit [XUSERPOST]
```

Applications can append information to the POST SIGN-IN MESSAGE (on a per-user, per signon basis only) by attaching to the new XU USER SIGN-ON option.



REF: For more information on the XU USER SIGN-ON option, see the "Signon/Security: Developer Tools" chapter in the *Kernel Developer's Guide*.

3.1.2.16 2-Factor Authentication

The KERNEL SYSTEM PARAMETERS file (#8989.3) also contains fields that are required to enable 2-factor authentication. These fields are *not* included in the Enter/Edit Kernel Site Parameters option [XUSITEPARM], because they should *not* be edited in VA production systems. If VistA is being installed in a *non*-VA environment, they can be edited using VA FileMan.

Field descriptions:

- SECURITY TOKEN SERVICE (#200.1): When using brokered authentication with a security token issued by a Security Token Service (STS), this field contains the identification of the issuer of the token. The STS is trusted by both the client and the service to provide the interoperable security tokens. Security Assertion Markup Language (SAML) tokens are standards-based XML tokens that are used to exchange security information, including:
 - Attribute statements
 - Authentication decision statements
 - Authorization decision statements

They can be used as part of a Single Sign-On (SSO) solution allowing a client to talk to services running on disparate technologies. The value of this field should be set to the domain name of the STS as found in the "Issued to:" field of the STS PKI certificate used to digitally sign the token. For VA production systems, the value should be set to the following value:

eauth.va.gov

ORGANIZATION (#200.2): Identity and Access Management field used to identify the VistA instance organization. For internally authenticated users, this field matches the SUBJECT ORGANIZATION field (#205.2) of the user identified in the NEW PERSON file (#200). For VA production systems, this field should always contain the following value:

Department of Veterans Affairs

• ORGANIZATION ID (#200.3): Identity and Access Management field used to uniquely identify the VistA instance organization. For internally authenticated users, this field matches the SUBJECT ORGANIZATION ID field (#205.3) of the user identified in the NEW PERSON file (#200). For VA production systems, this field should always contain the following value:

urn:oid:2.16.840.1.113883.4.349

3.1.3 XU USER SIGN-ON Option

The XU USER SIGN-ON option can attach action-type options to this extended-action-type option, so that software-specific actions can be performed at signon.



REF: For more information, see the "Signon/Security: Developer Tools" chapter in the *Kernel Developer's Guide*.

3.1.4 XU USER START-UP Option

The User start-up event option [XU USER START-UP] is a protocol option used exclusively during a VistA user signon event. Items attached to this option are "TYPE: action" options in the OPTION file (#19), which can be used for software-specific actions that prompt users for input upon VistA signon before their Primary Menu Option is displayed. Unlike the XU USER SIGN-ON option, it can provide interactive prompting to users. It is *not* used for GUI signon. It is called from the XQ12 routine.



REF: This option was added with Kernel patch XU*8.0*593. For more information, see the "Signon/Security: Developer Tools" chapter in the *Kernel Developer's Guide*.

3.1.5 Clear all users at startup Option

Figure 15: Clear all users at startup option

```
PARENT OF QUEUABLE OPTIONS ... [ZTMQUEUABLE OPTIONS]
Clear all users at startup [XUSER-CLEAR-ALL]
```

If multiple signons are prohibited, users may be prevented from signing on to the system when it is brought up after a crash (which can cause numerous abnormal exits). To prevent this problem from occurring, system administrators can use the Clear all users at startup option [XUSER-CLEAR-ALL]. Kernel recommends this option be scheduled to run at system startup. Although this option can be invoked interactively without ill effects, it was designed as a background process, thus, it is placed along with other tasked options on the PARENT OF QUEUABLE OPTIONS menu.



REF: For information on how to release a single user, see the "Proxy (Connector) Detail Report Option" section.

3.1.6 Enabling and Disabling Logons

System administrators have full control over whether logons are enabled. Access to a particular Volume Set can be disabled by setting the INHIBIT LOGONS? flag in the VOLUME SET file (#14.5). Setting the flag to **YES** sets the ^%ZIS("14.5","LOGON","volume set") node, whose presence disallows user logons. That is, logons through Signon/Security, invoking the ^ZU routine, fails (terminals for user access are usually linked to ZU within the operating system setup. Some special terminals, like the console, are untied.) The ^%ZIS("14.5","LOGON","volume set") node is also checked after each cycle through the menu system; signed-on users are logged off as soon as they return to a menu prompt.

3.2 Adding New Users

Creating a new user account involves adding a record to the NEW PERSON file (#200), assigning an Access code, and assigning a primary menu. You need the XUMGR security key to assign primary menu options. Even the at-sign ("@"; programmer access) is insufficient, as checked by the PRIMARY MENU OPTION field's input transform.

Figure 16: User Management menu options: Associated menu options when adding a new user

```
SYSTEMS MANAGER MENU ... [EVE]
User Management ... [XUSER]
Add a New User to the System [XUSERNEW]
Grant Access by Profile <locked: XUMGR> [XUSERBLK]
User Inquiry [XUSERINQ]
```

3.2.1 Add a New User to the System Option

You can use the Add a New User to the System option [XUSERNEW] to set up user accounts one-by-one. The option presents a standard scrolling-mode editing sequence for user attributes.

When using this option, entry of a social security number in the SSN field (#9) is usually required. While SSN is not required in the NEW PERSON file (#200) data dictionary, it is a required field when using

this option. If the option is used by someone who holds the XUSPF200 security key, however, entry of an SSN is *not* required.

You can also print security forms for the new user with this option.

When signing on for the first time, the new user should simply press **<Enter>** at the "Verify code" prompt, which then lets them enter their own secret Verify code.

3.2.1.1 NEW PERSON File (#200) Required Fields

When adding new users, a default set of fields is required, at a minimum. This set is defined by the NEW PERSON IDENTIFIERS field in the KERNEL SYSTEM PARAMETERS file (#8989.3). If it is **NULL**, the default set of required fields for the NEW PERSON file (#200) entries is:

- INITIAL (#1)
- SEX (#4)
- SSN (#9)

If, given local site policy, a different set should be used, system administrators can use this field to specify other identifiers.



NOTE: SSN is *not* required if the person entering accounts holds the XUSPF200 security key.

3.2.2 Grant Access by Profile Option

The Grant Access by Profile option [XUSERBLK] includes features unavailable in the Add a New User to the System option [XUSERNEW]. With the Grant Access by Profile option you can grant access to one or more people based on a typical user profile. All characteristics of the typical user, including menus, keys, and service/section, are copied to the new user or replace the characteristics of an existing user. For new users, access security forms are generated as part of the process. These forms can be delivered to the service/section coordinator by inter-office mail and can be distributed to the new users.

The Grant Access by Profile option is locked with the XUMGR security key and is strictly limited for use by system administrators. It *must* be restricted, because any user profile, even that of a developer, can be copied to another user. As with the Add a New User option, the SSN field (#9) is required when adding new records except by holders of the XUSPF200 security key or if another default set of New Person Identifiers has been defined.

Access is assigned according to an existing user profile. Characteristics of the new user are cloned from the existing one. Rather than copying the characteristics from an actual user, creating several dummy users with profiles of typical positions can be worthwhile. A user (e.g., PHARMACY, TECH or RESIDENT, SURGERY) could be created with the appropriate user attributes, including menu options, keys, and service/section codes.

Several steps are involved in copying access to new or existing users. First you enter the name of the user account to clone from. Then, optionally, you can specify a TERMINATION DATE. Next, you enter the names of the new users to create. The system pauses for each new user as it verifies identifiers, checks for duplicates, and updates the NEW PERSON file (#200). You *must* enter a device upon which to print the computer account notification letters. You can either run the access assignment immediately or queue it for a later time.

3.2.3 Security Forms

Figure 17: Reprint Access agreement letter option

```
SYSTEMS MANAGER MENU ... [EVE]
User Management ... [XUSER]
Reprint Access agreement letter [XUSERREPRINT]
```

Two security forms are printed for each new user:

- The Computer Account Notification—Includes the user's auto-generated Access code and the name of the service/section coordinator who can answer questions.
- The Computer Access Policy—A contract to which users *must* adhere. It states the terms of granting access to sensitive information; the user *must* accept these terms as a condition of being given system access.

These security forms are stored in the XUSER COMPUTER ACCOUNT help frame and should be edited for local use as follows:

- 1. Copy the XUSER COMPUTER ACCOUNT help frame into a new site help frame (e.g., SFO COMPUTER ACCOUNT).
- 2. Edit the security forms for local use. Replace the "placeholder" text with the actual name and address of the facility.
- 3. Repoint the Kernel Parameter to the new site XUSER COMPUTER ACCOUNT help frame using VA FileMan.

Figure 18: Security Forms—Sample user entries (1 of 4)

```
>D ^XUP
Setting up programmer environment
This is a TEST account.
Terminal Type set to: C-VT320
You have 13 new messages.
Select OPTION NAME: SYSTEMS MANAGER MENU
          Device Management ...
          Programmer Options ...
          Operations Management ...
          Spool Management ...
          Information Security Officer Menu ...
          Taskman Management ...
          User Management ...
          Application Utilities ...
          Capacity Management ...
          Manage Mailman ...
          Menu Management ...
          VA FileMan ...
          Verifier Tools Menu ...
Select Systems Manager Menu Option: VA FILEMAN
          VA FileMan Version 22.0
          Enter or Edit File Entries
          Print File Entries
          Search File Entries
          Modify File Attributes
          Inquire to File Entries
          Utility Functions ...
          Data Dictionary Utilities ...
          Transfer Entries
          Other Options ...
Select VA FileMan Option: TRANSFER ENTRIES
Select TRANSFER OPTION: TRANSFER FILE ENTRIES
INPUT TO WHAT FILE: HELP FRAME// HELP FRAME <Enter>
                                                        (562 entries)
TRANSFER FROM FILE: HELP FRAME// <Enter>
TRANSFER DATA INTO WHICH HELP FRAME: ISC COMPUTER ACCESS
Not a known package or a local namespace.
 Are you adding 'ISC COMPUTER ACCESS' as a new HELP FRAME (the 563RD)? No// Y
<Enter> (Yes)
  HELP FRAME NUMBER: 742// <Enter>
   HELP FRAME HEADER: Computer Access
TRANSFER FROM HELP FRAME: XUSER COMPUTER ACCOUNT < Enter> Batch user access document
  WANT TO DELETE THIS ENTRY AFTER IT'S TRANSFERRED? No// <Enter> (No)
...SORRY, LET ME THINK ABOUT THAT A MOMENT...
SINCE THE TRANSFERRED ENTRY MAY HAVE BEEN 'POINTED TO'
BY ENTRIES IN THE 'HELP FRAME' FILE, ETC.,
DO YOU WANT THOSE POINTERS UPDATED (WHICH COULD TAKE QUITE A WHILE)? No// <Enter>
(No)
          Enter or Edit File Entries
```

```
Print File Entries
          Search File Entries
          Modify File Attributes
          Inquire to File Entries
          Utility Functions ...
         Data Dictionary Utilities ...
          Transfer Entries
          Other Options ...
Select VA FileMan Option: ENTER OR EDIT FILE ENTRIES
INPUT TO WHAT FILE: HELP FRAME// <Enter>
EDIT WHICH FIELD: ALL// TEXT <Enter> (word-processing)
Select HELP FRAME NAME: ISC COMPUTER ACCESS <Enter>
                                                       Computer Access
NAME: ISC COMPUTER ACCESS// <Enter>
HEADER: Computer Access// <Enter>
TEXT: . . .
suspension/termination of access privileges.
I affirm with my signature that I have read, understand, and agree to
fulfill the provisions of this User Access notice.
|INDENT(5)||WIDTH(75)||NOWRAP|
Signature:
          |#20.2| |#29|
RETURN THIS FORM TO: IRMS - NEW ACCTS (xxx/xxx)
 Edit? NO// YES
```

Figure 19: Security Forms—Sample user entries (2 of 4)

```
==[ WRAP ]==[ INSERT ]=========< TEXT >========[ <PF1>H=Help ]====
|INDENT(5)| |WIDTH(70)|
NOWRAP |
CENTER("USER ACCOUNT NOTIFICATION")
 Read through and edit entries specific to your site information and save your
 changes.
| CENTER("Department of Veterans Affairs") |
CENTER("SuperStar VAMC")
CENTER("123 Any Street")
CENTER("Any Town, ST., 99999")
XUVT(12)
#20.2
#29|
       ( |#29:#1.5| )
XUVT(19)
 |WRAP|
A user account has been created in your name to enable you to access
on-line clinical and/or administrative data required to perform your
duties as an employee of the Department of Veterans Affairs. Please read
Select RELATED FRAME KEYWORD: <Enter>
Want to LOAD KEYWORDS (Y/N)?: N
Select INVOKED BY ROUTINE: <Enter>
Select EDITOR: <Enter>
Select OBJECT: <Enter>
ENTRY EXECUTE STATEMENT: <Enter>
EXIT EXECUTE STATEMENT: <Enter>
Select HELP FRAME NAME: <Enter>
         Enter or Edit File Entries
         Print File Entries
         Search File Entries
         Modify File Attributes
         Inquire to File Entries
         Utility Functions ...
         Data Dictionary Utilities ...
         Transfer Entries
         Other Options ...
Select VA FileMan Option: ENTER OR EDIT FILE ENTRIES
INPUT TO WHAT FILE: HELP FRAME// 8989.2 <Enter> KERNEL PARAMETERS (6 entries)
EDIT WHICH FIELD: ALL// <Enter>
Select KERNEL PARAMETERS NAME: XUSER COMPUTER ACCOUNT
NAME: XUSER COMPUTER ACCOUNT Replace <Enter>
TYPE: <Enter>
DEFAULT: <Enter>
REPLACEMENT: ISC COMPUTER ACCESS
```

```
Select KERNEL PARAMETERS NAME: <Enter>
         Enter or Edit File Entries
          Print File Entries
          Search File Entries
         Modify File Attributes
          Inquire to File Entries
          Utility Functions ...
          Data Dictionary Utilities ...
          Transfer Entries
          Other Options ...
Select VA FileMan Option: <Enter>
   FM
          VA FileMan ...
          Core Applications ...
         Device Management ...
          Information Security Officer Menu \dots
          Manage Mailman ...
          Menu Management ...
          Operations Management ...
          Programmer Options ...
          Spool Management ...
          Taskman Management ...
          User Management ...
Select Systems Manager Menu Option: USER MANAGEMENT
          Add a New User to the System
          Grant Access by Profile
          Edit an Existing User
          Deactivate a User
          Reactivate a User
          List users
         User Inquiry
          Switch Identities
          File Access Security ...
          Clear Electronic signature code
         Electronic Signature Block Edit
         Manage User File ...
         OAA Trainee Registration Menu ...
         Person Class Edit
         Reprint Access agreement letter
Select User Management Option: REPRINT ACCESS AGREEMENT LETTER
Select NEW PERSON NAME: REQUEST, ACCESS <Enter>
                                                AR
                                                          COMPUTER SPECIALIST
Is REQUEST, ACCESS the one you want? YES// <Enter>
DEVICE: 0;80;60 <Enter> Telnet Terminal
```

Figure 20: Security Forms—Sample User Account Notification form (3 of 4)

USER ACCOUNT NOTIFICATION

Department of Veterans Affairs
Superstar VAMC
123 Any Street
Any Town, ST. 99999

The name of the user and location is displayed here. For this example, the user's name is "Access Request" at the "Superstar VAMC."

ACCESS REQUEST Superstar VAMC

A user account has been created in your name to enable you to access on-line clinical and/or administrative data required to perform your duties as an employee of the Department of Veterans Affairs. Please read the enclosed NEW USER INFORMATION before you attempt your first log-on to the system. Questions about access should be referred to the AIS Application Coordinator in your service, your facility Information Security Officer (ISO), or your IRM Service.

The names and contact information specific to your site will be displayed here.

Your Computer Access Coordinator is:

XUUSER,ONE
123X
510-555-9999
Your Facility Information Security Officer:
Two Xuser
Your Alternate Information Security Officer:
Three Xuser

NT Domain:

NT Username: VHA_____

NT Password:

VistA Access Code:

VistA Verify Code:

Figure 21: Security Forms—Sample Computer Account Access Policy form (4 of 4)

COMPUTER ACCOUNT ACCESS POLICY

Department of Veterans Affairs
SuperStar VAMC

The name of the user and location is displayed here. For this example, the user's name is "Access Request" at the "Superstar VAMC."

ACCESS REQUEST SuperStar VAMC

As an authorized user of VHA automated information systems (AISs) and having access to data stored in them, I will be given sufficient access to perform my assigned duties. I will use this access ONLY for its intended purpose and understand the following policies that apply to VA data and computer systems:

I agree to safeguard all passwords (e.g., Access/Verify codes, electronic signature codes) assigned to me and am strictly prohibited from disclosing these codes to anyone including family, friends, fellow workers, supervisor(s), and subordinates for ANY reason.

I understand that I may be held accountable for all entries/changes made to any government AIS using my passwords.


I am aware of the regulations and facility AIS security policies designed to ensure the confidentiality of all sensitive information. I am aware that information about patients or employees is confidential and protected from unauthorized disclosure by law. I understand that my obligation to protect VA information does not end with either the termination of my access to this facility's systems or with the termination of my government employment.

I will exercise common sense and good judgment in the use of electronic mail. I understand that electronic mail is not inherently confidential and I have no expectation of privacy in using it. I understand that technical or administrative problems may create situations which requires viewing of my messages. I also understand that facility management officials may authorize access to my electronic mail messages whenever there is a legitimate purpose for such access.

I understand that a violation of this notice constitutes disregard of a local and/or VHA policy and will result in appropriate disciplinary action as defined in VA employee conduct Regulations (VAR 820(b)) as well as suspension/termination of access privileges.

I affirm with my signature that I have read, understand, and agree to fulfill the provisions of this User Access notice.

Signature	·			
	ACCESS	REQUEST	SuperStar	VAMC



VA FileMan word-processing "windows" are used to retrieve the user's name, service/section, and service/section coordinator's name. To be effective, the SERVICE/SECTION field in the NEW PERSON file (#200) *must* be filled in for the new user. The COORDINATOR (IRM) field, a field in the SERVICE/SECTION file (#49), *must* also be filled in and updated when necessary. Word-processing "windows" are also used for formatting, like |TOP|, to separate the two forms. When using the File Access Security system, READ access to the SERVICE/SECTION file (#49) is needed to retrieve the Coordinator's name within the window command.



REF: For more information on using word-processing "windows," the File Access Security system, and navigation, see the *VA FileMan User Manual*.

The Reprint Access Agreement Letter option allows you to reprint the computer access agreement letter in case there was a problem printing the first form (e.g., the first form is jammed in the printer). It does not reprint the Access code on the letter, however.

3.3 Edit an Existing User Option

Figure 22: Edit an Existing User option—Menu

```
SYSTEMS MANAGER MENU ... [EVE]
User Management ... [XUSER]
Edit an Existing User [XUSEREDIT]
```

The attributes of an existing user can be edited with the Edit an Existing User option [XUSEREDIT]. This option invokes a screen-oriented display using ScreenMan.

It is impossible to exit the form and save changes unless all required fields (e.g., the SERVICE/SECTION field in the NEW PERSON file [#200]) are filled in.

<u>Table 4</u> describes each of the user field attributes you can edit with the Edit an Existing User option.

Table 4: Edit an Existing User option—Editable fields/attributes

Field/Attribute	Description
NAME (#.01) (Required)	The user's name should be entered in capital letters. The syntax should be "LAST,FIRST MI." with only a comma (no spaces) between the last and first name. A middle initial can follow, separated with a space and followed with a period. It is not appropriate to add credentials (e.g., M.D.), since there are other ways to specify such additional information (by the Title and the Signature Block Printed Name). Furthermore, the parsing algorithms commonly used in software applications only recognize two pieces, before and after the comma, rearranging them and using uppercase/lowercase to generate "First MI. Last".
INITIAL (#1)	The user's initials can be entered, usually two or three capital letters with no spaces. The NEW PERSON file (#200) contains a lookup-type cross-reference by INITIAL (C), so if the INITIAL field is filled in, the user can be found in the

Field/Attribute	Description			
	NEW PERSON file (#200) by entering the initials. For example, just the initials can be used at the "Select NEW PERSON Name:" prompt, or when addressing mail messages, or for other lookup purposes. Users can edit their initials at any time since this field is included in the common option Edit User Characteristics.			
TITLE (#8)	This field points to the TITLE file (#3.1), a file exported with Kernel but without data (records). The User Management options to add or edit a user's record allow LAYGO into the TITLE file (#3.1), so titles can be added via the NEW PERSON file (#200). Although not required, it may be wise to assign appropriate titles to users, so this field can be referenced by other software applications. MailMan, for example, displays titles in message headers if the user who is reading mail has so indicated with a flag in MailMan's Edit User Options called Show Titles.			
NICK NAME (#13)	Like INITIAL, NICK NAME has a lookup type cross-reference (D) in the NEW PERSON file (#200) so that lookups succeed simply by using the NICK NAME. This field is also included in Edit User Characteristics.			
SSN (#9)	The SSN field (#9) is <i>not</i> a required field in the data dictionary for the NEW PERSON file (#200). SSN is required when using the User Management options to add a new user unless the XUSPF200 security key is held by the person using the option. It is <i>highly recommended</i> that each new user have the SSN field (#9) filled in to minimize the problem of subsequent duplicate entries. Since many existing users do not have an SSN entered, however, the Edit an Existing User option does not require that one be entered.			
MAIL CODE (#28)	The user's MAIL CODE can be entered for purposes of interoffice routing of manually delivered mail.			
PRIMARY MENU OPTION (#201) (Required for functional access)	Users <i>must</i> be assigned a PRIMARY MENU OPTION in order to reach Menu Manager after successfully entering Access and Verify codes. The PRIMARY MENU OPTION should provide a route to all the computing functions the user can be expected to need. The XUMGR security key <i>must</i> be held by the person assigning the menu (unless delegated options are available for use with the Secure Menu Delegation system).			
	REF: Building and rearranging menus is discussed in the "Menu Manager: System Management" chapter.			
SECONDARY MENU OPTIONS (#203)	The SECONDARY MENU OPTIONS can be used to assign particular options to individual users to customize their menu choices. While a user may have a standard primary menu to carry out the usual functions of a department or service, additional special functions just for this user can be assigned as secondary options. This is a multiple field, unlike the PRIMARY MENU OPTION, so additional items can easily be added.			
ACCESS CODE (#2) VERIFY CODE (#7.2)	These fields can be used to edit a user's Access or Verify Code as needed. If a user has forgotten the Verify code, or needs a new one, system administrators/ISO should delete the existing code so that when the user logs on and presses the <enter> key at the "VERIFY CODE" prompt, a new (secret) password (VERIFY CODE) can be entered. To accomplish this, "Y" should be entered at the "Want to edit VERIFY CODE (Y/N):" prompt. An at-sign ("@") should then be entered to delete the existing code. The change is filed immediately, unlike other changes that are processed as part of the overall transaction when leaving the ScreenMan form.</enter>			

Field/Attribute	Description	
	Users can edit their Verify code at any time via the Edit User Characteristics option on the Common menu. If this option uses a local template, the ability to edit the VERIFY CODE field should probably remain, as a security measure. System administrators can choose to add the ability to edit the ACCESS CODE field as well.	
FILE MANAGER ACCESS CODE (#3)	The FILE MANAGER ACCESS CODE field (#3) in the NEW PERSON file [#200]) is stored in the local variable DUZ(0). If DUZ(0)=@, the user is a developer with the highest level of programmer access authority. Other non-reserved symbols can be assigned for File Access Security, depending on the user's needs. Software applications indicate which symbols are needed for site-specific File Access Security.	
	NOTE: In previous documentation and data dictionaries, it has been implied that the pound sign ("#") symbol/character was reserved for File Access Security for system administrators; however, this is not true. It has merely been used as a convention.	
	If the File Access Security conversion has been run, the FILE MANAGER ACCESS CODE field (#3) is <i>not</i> used to control file-level access security as it was <i>before</i> the conversion. The <u>File Access Security</u> system (formerly known as Part 3 of the Kernel installation) permits the association of a user with a file whereby explicit access can be granted. While the conversion process is somewhat involved, the benefits resulting from implementing the <u>File Access Security</u> system are worthwhile.	
	Even after running the file access conversion, the FILE MANAGER ACCESS CODE field (#3) field continues to serve several functions:	
	If a user has been granted full file access privileges for a particular file, a further restriction can be placed at the file or field level to prohibit modification of the definition or entry of data. Files have top-level restrictions of READ, WRITE, or DELETE access as do fields and templates.	
	If the file, field, or template is protected with the at-sign ("@"; programmer access), the user <i>must</i> also have the at-sign in the FILE MANAGER ACCESS CODE field (#3) in the NEW PERSON file (#200).	
	The Device Handler also checks the FILE MANAGER ACCESS CODE field (#3) of the user if the SECURITY field in the DEVICE file (#3.5) has been defined with a character string. The user would not be able to select the device unless at least one of the characters in the user's code matched at least one character in the device code.	
	The most important FILE MANAGER ACCESS CODE field (#3) character is the at-sign ("@"; programmer access). It has special meaning and overrides other file access restrictions or other FILE MANAGER ACCESS CODE field (#3) characters. It is <i>not</i> recommended that the at-sign be allocated unless absolutely needed. Allocation is, in part, restricted by the fact that only those few users who have developer access to the system can give other users the at-sign.	
	NOTE: A SET statement from programmer mode can be used to temporarily assign DUZ(0)="@" without storing the code in the NEW PERSON file (#200), which would give permanent programmer access.	
	Use of the at-sign ("@"; programmer access) is less common now than in the past since alternative security measures have been developed. It is still required	

Field/Attribute	Description	
	for several critically sensitive checks, however, such as entering M code into VA FileMan files (e.g., OPTION [#19] and FUNCTION [#.5] files). REF: For more information on File Access Security, see "File Access Security" in this manual and the VA FileMan (Version 22.0) and Kernel (Version 8.0) File Access Security supplemental documentation located	
	on the VA Software Document Library (VDL) at: http://www.va.gov/vdl/application.asp?appid=5	
PREFERRED EDITOR (#31.3)	If a user's PREFERRED EDITOR field is NULL, Kernel uses VA FileMan's Line Editor to edit word-processing fields. If the PREFERRED EDITOR is set to another entry in the ALTERNATE EDITOR file (#1.2), like VA FileMan's Screen Editor, Kernel uses that editor when the user edits word-processing fields. As described in VA FileMan's documentation, users can switch from the Line Editor to another editor by using the Utility suboption on the Edit option menu.	
	Figure 23: VA FileMan Line Editor—Sample user dialogue	
	Enter one space character on Line 1 and then press the <enter> key at Line 2.</enter>	
	1>_ <enter> 2><enter> EDIT Option: Utilities in Word-Processing UTILITY Option: Editor Select ALTERNATE EDITOR: SCREEN EDITOR - VA FILEMAN</enter></enter>	
	If the PREFERRED EDITOR is the Screen Editor, it is also possible to switch to another editor, like the Line Editor, to take advantage of Line Editor features such as File Transfer from Foreign CPU.	
	NOTE: Other editors (e.g., WordMan or VA LetterMan) do <i>not</i> support switching to the Line Editor, which may be a limitation in some circumstances.	
	This field is also included in Edit User Characteristics and MailMan's Edit User Options so that all users can define a PREFERRED EDITOR if they so choose.	
DIVISION (#16)	The DIVISION field (Multiple) has a corresponding site parameter, the Default Institution, that sets users' DUZ(2) if this field is not filled in. A user setting, however, takes precedence over the site parameter. This is a multiple field and if the user is associated with more than one institution, the user is prompted at signon to pick the one corresponding to the computing activities to be carried out in that session.	
SERVICE/SECTION (#29) (Required)	This field points to the SERVICE/SECTION file (#49) distributed with Kernel's virgin installation. No data is included. It is a required field since applications have begun to use it in various utilities. Kernel's CPU/Service/User/Device Stats option [XUSTAT], for example, can summarize signon information for all users in the same Service/Section. The Grant Access by Profile option also makes	

Field/Attribute	Description		
	use of this field to specify the Service/Section Coordinator to whom the access forms of the new users should be delivered.		
NETWORK USERNAME (#501.1)	This is the username that is used by the Windows Active Directory. It can be used to help identify the user; although it should <i>not</i> be relied on for accuracy as it is manually entered data that is <i>not</i> validated by Active Directory.		
TIMED READ (#200.1)	As discussed with other site parameters earlier in this chapter, TIMED READ defines the length of time Kernel should wait for a user response to a READ. A setting for the user attribute overrides the site default. It is used to define the local variable DTIME.		
MULTIPLE SIGN-ON (#200.04)	As discussed with other site parameters, this field controls whether the user is permitted to have two or more concurrent signon sessions. The user setting takes precedence.		
AUTO MENU (#200.06)	As discussed with other site parameters, this field controls whether the entire list of menu options is automatically presented or whether the user needs to enter a question mark ("?") to invoke the display. The user setting takes precedence.		
ASK DEVICE TYPE AT SIGN-ON (#200.05)	As discussed with other site parameters, this field controls whether the device being used at signon is queried for its terminal type. The user setting takes precedence.		
TYPE-AHEAD (#200.09)	This field controls whether the user can enter text faster than the computer can read it. If set to YES , the computer buffers input from the user. If set to NO , keystrokes from the user are lost if they are typed faster than the computer can process them.		
ALLOWED TO USE SPOOLER (#41)	This field controls whether a user can pick the spool device at the device prompt to send output to the spooler.		
PAC (#14, Programmer Access Code)	For users who have been granted the Programmer Mode option along with the XUPROG and XUPROGMODE security keys, a Programmer Access Code can be assigned as additional security. If a PAC is defined, Kernel prompts for the PAC just before allowing a user to enter programmer mode. If this field is NULL, a PAC is not asked.		
CAN MAKE INTO A MAIL MESSAGE (#41.2)	This field controls whether a spooled document can be transformed into a regular mail message for use within MailMan.		
DISUSER (#7)	If set to YES , disables access to the system for this user (without terminating the user's account).		
FILE RANGE (#31.1)	Users who have VA FileMan privileges to create files can be given a numeric range of numbers to use as file numbers. Assigning number ranges acts as a safeguard to keep users from picking a number within a range that is nationally reserved for VistA software applications. It can also serve local database administration needs of segmenting local development by number ranges.		
TERMINATION DATE (#9.2)	As described in the " <u>Deactivating Users</u> " section, this field indicates when a user's access privileges should be revoked.		
ALWAYS SHOW SECONDARIES (#200.11)	If set to YES , contents of a user's SECONDARY MENU OPTIONS are shown when the user enters one question mark ("?") at a menu prompt. Otherwise, the user <i>must</i> enter two question marks ("??") to see their secondary menu.		
PROHIBITED TIMES	As discussed with other signon parameters, this field can be used to regulate		

Field/Attribute	Description			
FOR SIGN-ON (#15)	when the user can sign on to the system. The user setting takes precedence over any corresponding device setting.			
PHONE (HOME) (#.131)	Set up phone numbers for the user in these fields.			
OFFICE PHONE (#.132)				
PHONE #3 (#.133)				
PHONE #4 (#.134)				
COMMERCIAL PHONE (#.135)				
FAX NUMBER (#.136)				
VOICE PAGER (#.137)	Set up pager numbers for the user in these fields.			
DIGITAL PAGER (#.138)				
LANGUAGE (#200.07)	Overrides the setting of the DEFAULT LANGUAGE field in the KERNEL SYSTEM PARAMETERS file (#8989.3). Both of these are used to set the DUZ("LANG") flag for each user. VA FileMan uses this setting to enable the display of language-specific dates and times, numeric formats, and dialogues.			

Figure 24: Edit an Existing User option—Screen 1

NAME: XUUSER, ONE	Edit an Existing User Page 1 of 5
NAME XUUSER,ONE TITLE: COMPUTER SPECIALIST SSN: 000123456 DEGREE: DISUSER: Termination Reason:	INITIAL: OX NICK NAME: ONE DOB: MAIL CODE: TERMINATION DATE:
PRIMARY MENU OPTION: Select SECONDARY MENU OPTIONS: Want to edit ACCESS CODE (Y/N): Want to edit VERIFY CODE (Y/N):	
Select DIVISION: SERVICE/SECTION:	INFORMATION SYSTEMS CENTER
Exit Save Next Page	Refresh
Enter a command or `^' followed	by a caption to jump to a specific field.
COMMAND:	Press <pf1>H for help Insert</pf1>

Figure 25: Edit an Existing User option—Screen 2

Edit an Existing User

NAME: XUUSER, ONE Page 2 of 5

NETWORK USERNAME: VHAIXXXUUSERO TIMED READ (# OF SECONDS): 999

> MULTIPLE SIGN-ON: ALLOWED MULTIPLE SIGN-ON LIMIT:

ASK DEVICE TYPE AT SIGN-ON: DON'T ASK AUTO MENU: YES, MENUS GENERATED

PROHIBITED TIMES FOR SIGN-ON: TYPE-AHEAD: ALLOWED

AUTO SIGN-ON:

Preferred Editor: SCREEN EDITOR - VA FILEMAN

ALLOWED TO USE SPOOLER: PAC:

CAN MAKE INTO A MAIL MESSAGE:

FILE RANGE:

ALWAYS SHOW SECONDARIES:

Exit Save Next Page Refresh

Enter a command or '^' followed by a caption to jump to a specific field.

COMMAND: Press <PF1>H for help Insert

Figure 26: Edit an Existing User option—Screen 3

Edit an Existing User

NAME: XUUSER, ONE Page 3 of 5

PROHIBITED TIMES FOR SIGN-ON:

PHONE: 510-768-6874 OFFICE PHONE: 510-768-6874

COMMERCIAL PHONE: FAX NUMBER: VOICE PAGER: DIGITAL PAGER:

LANGUAGE:

Person Class Expired Effective DEC 7,2005 JAN 1,2006 JAN 1,2006 DEC 7,2005 DEC 7,2005 DEC 8,2005 Technologists, Technicians and Other Tec Emergency Medical Service Providers Other Service Providers

Allopathic and Osteopathic Physicians DEC 8,2005

Exit Save Next Page Refresh

Enter a command or '^' followed by a caption to jump to a specific field.

COMMAND: Press <PF1>H for help Insert

Figure 27: Edit an Existing User option—Screen 4




Figure 28: Edit an Existing User option—Screen 5

```
Edit an Existing User
NAME: XUUSER, ONE
                                                                    Page 5 of 5
PERMANENT ADDRESS:
         Street 1:
         Street 2:
         Street 3:
             City:
             State:
          Zip Code:
   E-Mail Address:
Is this person an active Trainee?:
VHA Training Fac.:
Start Date of Training:
                                    Last Training Month & Year:
                                     Trainee Inactive (Date):
Program of Study:
Target Degree Lvl:
Exit
         Save Next Page
                                Refresh
Enter a command or '^' followed by a caption to jump to a specific field.
COMMAND:
                                               Press <PF1>H for help
                                                                        Insert
```

3.3.1 Additional Attributes Editable by Users

Some but not all of the user attribute fields can be edited by users using the Edit User Characteristics option. The only field the user can edit that is not part of the system manager's Edit an Existing User form is the TEXT TERMINATOR field.



REF: For a description of the fields users can edit (using the default Edit User Characteristics form and template), see <u>Table 3</u> in the "<u>Edit User Characteristics Option</u>" section.

3.3.2 Edit User Characteristics Form and Template

Kernel exports a ScreenMan form and a template to be used in the Edit User Characteristics option. Both are called XUEDIT CHARACTERISTICS. The INPUT template by the same name is invoked if the ScreenMan form *cannot* be loaded on the current terminal type.

System administrators can substitute a locally-developed template by entering its name in the USER CHARACTERISTICS TEMPLATE field in the KERNEL PARAMETERS file (#8989.2). System administrators can also design a customized form with the same name as the local INPUT template that is displayed instead, terminal type setup permitting. In other words, to invoke a locally modified display, an INPUT template *must* exist. If a ScreenMan form by the same name also exists, an attempt is made to display the form before defaulting to the INPUT template.



REF: For more information on creating a local Edit User Characteristics form and template, see the *Kernel Installation Guide*.

For a sample form, see the "Edit User Characteristics Option" section.

3.4 Deactivating and Reactivating Users

Kernel provides options to deactivate and reactivate users on the User Management menu [XUSER]. When users no longer need access privileges, system administrators can partially or entirely close access to their account.

Figure 29: User Management menu options

```
SYSTEMS MANAGER MENU ... [EVE]
User Management ... [XUSER]
Deactivate a User [XUSERDEACT]
Purge Inactive Users' Attributes [XUSERPURGEATT]
Reactivate a User [XUSERREACT]
```

39

3.4.1 Deactivating Users

The Deactivate a User option [XUSERDEACT] lets you temporarily or permanently disable access for users. You can schedule termination of a user for a future date. The Deactivate a User option loads a ScreenMan form with the fields described in <u>Table 5</u>:

Table 5: Deactivate a User option—Editable fields/attributes

Field/Attribute	Description			
DISABLE USER	Setting the DISABLE USER field to YES prevents a user from signing on, but leaves all of their menus, keys, and other attributes (essentially the user's entire account) still enabled. It sets the DISUSER field (#7) in the user's NEW PERSON file (#200) to YES .			
	You might want to use this feature to prevent access to your system by an external support person, except during pre-approved times (where you may want to monitor their actions). Setting DISUSER to YES prevents them from logging on to the system until you clear the field.			
	If you set this field to YES , <i>do not set any other fields</i> in the Deactivate a User form (they only apply to terminating a user). Then, to re-enable access, use the Reactivate a User option [XUSERREACT].			
	REF: For a description of the Reactivate a User option, see the "Reactivating Users" section.			
TERMINATION DATE (#9.2)	Terminating a user is the way to formally deactivate a user (as opposed to temporarily disabling their account). Setting this date effectively terminates that user's account, effective from that date forward.			
	The Deactivate a User option automatically performs the following steps when you deactivate a user:			
	Revokes the user's status as an authorized sender of any mail groups.			
	Revokes the user's status as a surrogate.			
	Revokes the user's status as a Secure Menu Delegation delegate.			
	Deletes the user's Access code, Verify code, Electronic Signature code, VA FileMan Access code (i.e., FILE MANAGER ACCESS CODE field [#3]), and Programmer Access code.			
	Deletes the user's menu templates.			
	Deletes the user's delegated options.			
	Purges the ^DISV global on that CPU for that user.			
	You can also decide whether all mail messages and all security keys for the account are deleted on the TERMINATION DATE with the final two fields in the Deactivate a User option [XUSERDEACT] (DELETE ALL MAIL ACCESS and DELETE KEYS AT TERMINATION). If the user is expected to return to the facility and needs to have the user account reopened, security keys and mail could be retained.			
	REF: For more information on cleaning up user access and privileges at termination, see the "XU USER TERMINATE Option" section in the "Signon/Security: Developer Tools" chapter in the Kernel Developer's Guide.			

Field/Attribute	Description
DELETE ALL MAIL ACCESS (#9.21)	Setting the DELETE ALL MAIL ACCESS field causes all mail messages for the user to be deleted when their account is terminated on the TERMINATION DATE.
DELETE KEYS AT TERMINATION (#9.22)	Setting the DELETE KEYS AT TERMINATION field causes all security keys for the user to be deleted at termination (except security keys marked "KEEP AT TERMINATE").
	As discussed in the "Security Keys" section, the application developer can export a security key with the KEEP AT TERMINATE field set to YES in such a situation. The Provider security key, included with Kernel, has the flag set to YES for this purpose. Although a user may have been deactivated, it could be important to continue a processing activity that the user had authorized, based on privileges associated with a security key. A medical order could continue to hold an approved status, for example, even though the authorizing provider had been deactivated.

3.4.2 Automatically Deactivating Users

The Automatic Deactivation of Users option [XUAUTODEACTIVATE] finds all users in the NEW PERSON file (#200) with a TERMINATION DATE (#9.2) in the past, but who still have an Access code. In addition, it also looks to see if there are any users who have not signed on in the last "n" days.

The XUAUTODEACTIVATE option terminates any users who fit these criteria. Any such users are users who had been scheduled for termination but were *not* terminated (usually because the task that should have terminated them did not run). It acts as a safety net to ensure that all users who were scheduled for termination are, in fact, terminated. It should be scheduled to run on a regular basis.



REF: For recommended frequency of scheduling, see the *Kernel Installation Guide*.

Because the XUAUTODEACTIVATE option is not intended for interactive use, it is placed on the ZTMQUEUABLE OPTIONS menu.

3.4.2.1 Termination Process

The termination process does the following:

- Sets the DISUSER field (#7) in the NEW PERSON file (#200) to **YES** (1).
- Deletes the user's Access code.
- Deletes the user's security keys.
- Calls the XU USER TERMINATE protocol in the OPTION file (#19) so other applications can take any action they need.
- If the DELETE ALL MAIL ACCESS field (#9.21) in the NEW PERSON file (#200) is set to YES, then the user is also removed from the VistA MailMan system, which deletes their MailMan mail boxes and deletes them from any mail groups.



CAUTION: Kernel patch XU*8*645 created the XU645 parameter. It determines if a terminated user information should be purged from the system (Inspector General investigation request). When XU645 is set to YES, then data is deleted and the

background AUTODEACTIVATE job purges those users who were previously terminated. The default value for XU645 is blank, which is equivalent to NO; it only deletes the user's Access code and does *not* delete any other information or trigger any background jobs.

3.4.2.2 Academic Affiliation Waiver

The VA Handbook 6500 page 60 (POLICY AND PROCEDURES, Technical Controls, Logical Access Controls), Item "d" states that accounts are automatically disabled if inactive for 30 days. This requirement is repeated in VA Handbook 6500 Appendix D.

The Office of Academic Affiliation requested a waiver for the 30 day disabling of inactive accounts asking it be 90 days and the waiver was approved.



REF: A copy of the approved waiver is available as an attachment to Remedy Ticket #283028.

Kernel patch XU*8.0*514 added the ACADEMIC AFFILIATION WAIVER field (#13) to the KERNEL SYSTEM PARAMETERS file (#8989.3). This field is used to control the LAST SIGN-ON DATE/TIME field (#202) in the NEW PERSON file (#200). If the Office of Academic Affiliation waiver is applicable to a site, the site can set the ACADEMIC AFFILIATION WAIVER field (#13) to **YES** (1). The default for this field is **NULL**.

When the ACADEMIC AFFILIATION WAIVER field (#13) is set to **YES**, the users is only automatically disabled if they have been inactive for over 90 days (i.e., LAST SIGN-ON DATE/TIME is over 90 days). If it is *not* set, this option works as usual (i.e., 30 day limit).

3.4.3 Purging Mail and Security Keys for Inactive Users

You can use the Purge Inactive Users' Attributes option [XUSERPURGEATT] to clean up files. It removes all mailboxes, messages, mail groups, and security keys for users who have been terminated. If any of these users still retain Access codes, they are deleted.

This is particularly significant with mail. A mail message *cannot* be completely removed from a system until all recipients have deleted it from their mail baskets. If a user is no longer active, then it becomes unlikely that the message ever gets purged.

There are two modes of running this option. You can VERIFY the process for each user that the computer selects as eligible. If you choose not to verify the process for each user, then for every user with a non-future TERMINATION DATE, their set of security keys, mail groups, messages, and mail baskets are deleted.

3.4.4 Reactivating Users

You can use the Reactivate a User option [XUSERREACT] to re-enable access for a user who has either been terminated, or whose access has been temporarily disabled. To re-enable access for someone whose account is merely disabled (with the DISUSER field set to **YES**), use this option to simply clear the DISUSER field. Otherwise, using this option, you can fill in all the fields needed for an active account (i.e., FILE MANAGER ACCESS CODE field [#3], PRIMARY MENU OPTION, etc.).

When you reactivate a user, you are asked whether to deny access to old mail messages. If the reactivated user account is a less privileged account than previously, it may be appropriate to deny the user access to messages that were received in the user's prior capacity. Even if that user's mailbox was deleted at termination, once the user is reactivated, an old message would be delivered if responded to by another recipient.

3.5 User Management Menu

Kernel provides the User Management Menu [XUOPTUSER] located under the Operations Management menu [XUSITEMGR]. This menu provides a set of options for system administrators to monitor and support users logged onto the system. It includes the following options:

Figure 30: User Management Menu options

```
SYSTEMS MANAGER MENU ...
                                                                                 [EVE]
Operations Management ...
                                                                          [XUSITEMGR]
                                                                          [XUOPTUSER]
   User Management Menu ...
         Find a user
                                                                        [XU FINDUSER]
   PXY
          Proxy User List
                                                                   [XUSAP PROXY LIST]
          List users
                                                                           [XUSERLIST]
          Print Sign-on Log
                                                                          [XUSC LIST]
          Proxy (Connector) Detail Report
                                                       [XUSAP PROXY CONN DETAIL ALL]
          Proxy (Connector) Inquire
                                                        [XUSAP PROXY CONN DETAIL INQ]
          Release user
                                                                           [XUSERREL]
                                                                [XUSEC REMOTE ACCESS]
          Remote Access User Sign-on Log
          User Inquiry
                                                                           [XUSERINO]
          User Status Report
                                                                       [XUUSERSTATUS]
          Users with Foreign Visits
                                                                    [XUS VISIT USERS]
```

3.5.1 Find a User Option

The Find a User option [XU FINDUSER] is used to find a user who is currently signed on to the system in this UCI group. If you are on the same CPU as the user, this option also shows the menu path of the user. The option finds users based on the "CUR" cross-reference of the SIGN-ON LOG file (#3.081).

3.5.2 Proxy User List Option

The Proxy User List option [XUSAP PROXY LIST] runs a report listing any users in the NEW PERSON file (#200) that have a USER CLASS field (#9.5) of APPLICATION PROXY or CONNECTOR PROXY.

3.5.3 List Users Option

The List Users option [XUSERLIST] lists all users known to the system.

3.5.4 Print Sign-on Log Option

The Print Sign-on Log option [XUSC LIST] prints out the SIGN-ON LOG file (#3.081).

The LOA field refers to "Level of Assurance" of the user's authentication into VistA. Four levels are currently defined by the <u>National Institution of Standards and Technology Special Publication (NIST SP)</u> 800-63-2 Electronic Authentication <u>Guideline</u>:

- **Level 1**—No identity proofing requirement. This generally refers to a "self-asserted" user identity and is the lowest form of authentication. This form of authentication does *not* satisfy <u>VA</u> Handbook 6500 security requirements.
- Level 2—Single factor authentication. This form of authentication includes username/password or, in the case of VistA, Access/Verify code authentication.
- Level 3—Multi-factor authentication. This form of authentication includes VA 2-factor authentication using smart cards (PKI certificates) and Personal Identification Number (PIN).

• Level 4—The highest practical authentication assurance. At this level, in-person identity proofing such as fingerprint or retinal scan is used to authenticate and identify the user.

Figure 31: Sample Kernel Sign-On Log report

USERS WHO HAVE SIGNED ONTO THE COMELAPSED	APUTER OCT	21,2015 08:4	5 PAGE 1
TIME Sign-on time (MINUTES) IPV6 ADDRESS	USER LOA	\$I 	NODE NAME
SEP 30,2015 11:54 15 0000:0000:0000:0000:0000:FFFF:07		FTA488:	ISC6A2
OCT 1,2015 06:50 3 0000:0000:0000:0000:0000:FFFF:07		FTA488:	ISC6A2
OCT 1,2015 12:20 22 0000:0000:0000:0000:0000:FFFF:07		FTA488:	ISC6A2
OCT 1,2015 12:46 11 0000:0000:0000:0000:0000:0000:0000:	•	FTA488:	ISC6A2
OCT 7,2015 07:43 2045* 0000:0000:0000:0000:0000:FFFF:02	·	FTA488:	ISC6A2
OCT 7,2015 12:47 0 0000:0000:0000:0000:0000:FFFF:02	•	FTA488:	ISC6A2
OCT 7,2015 12:52 8 0000:0000:0000:0000:0000:FFFF:07	•	FTA488:	ISC6A2

3.5.5 Proxy (Connector) Detail Report Option

The Proxy (Connector) Detail Report option [XUSAP PROXY CONN DETAIL ALL] provides information about CONNECTOR PROXY accounts for the purposes of:

- Monitoring compliance with the 3-year mandate (per VA Handbook 6500) to expire/change Verify codes for service accounts.
- Reporting any misconfigured CONNECTOR PROXY accounts.
- Listing account activity to help determine whether accounts are active, and are being accessed from which remote locations.

When running the report, the following options determine how much additional content is listed for each account:

- Check/display connector proxy fields? YES/NO (checks for misconfigured accounts).
- Scan sign-on log for connector proxy activity? YES/NO (lists account activity).

Possible categorizations for whether accounts are reported as "Compliant w/3-year Service Account Mandate?" are:

- YES (account is compliant).
- *** NO <---- MUST FIX *** (date created and date verify code last changed > 3 years in the past).
- No, but user *not* active.
- UNABLE TO DETERMINE (until patch XU*8.0*574, date verify code last changed for Connector Proxy accounts was incorrectly recorded as 4/10/2005)
- Unable to determine but *not* active.

If an account's Date Verify Code Last Changed is listed as "(changed but date not recorded)", that means the "fake" 4/10/2005" date is present, and unless the account was created within the last 3 years, it is impossible to determine if the account is in compliance with the 3-year mandate.

Also, if there is a value in the XUS LOGON ATTEMPT COUNT field, that value is displayed, as it could indicate a remote system attempting to connect and failing with an invalid Verify code.

If the option to "Check/display connector proxy fields?" is selected, the following checks are performed:

- Warnings: (any field listed in the warning section should not be populated. However, before changing, consult the National Help Desk or Customer Support as some applications may (currently) be depending (incorrectly) on a misconfigured connector configuration.)
- Values for other fields allowed/expected: (field normally populated for connector proxies).
- Other Fields Populated (not expected fields, but not problematic either).
- Other Multiples Populated (not expected, but not problematic either).

If the option to "Scan sign-on log for connector proxy activity?" is selected, the report scans the sign-on log for all signon activity associated with the account. Any activity found is displayed, organized by client IP address, and within IP address, by date of signon. The purpose of this report section is to help sites determine which accounts are active, and which external systems (by IP address) are logging onto the site with the specified account. This helps determine which remote applications a change to the account (e.g., Verify code change) might impact, and also helps a site determine whether too many remote applications/data centers are using the same account (which could result in a more widespread service disruption if an account *must* be changed).



NOTE: This option can be scheduled.

3.5.6 Proxy (Connector) Inquire Option

The Proxy (Connector) Inquire option [XUSAP PROXY CONN DETAIL INQ] provides information about CONNECTOR PROXY accounts for the same purposes as the Proxy (Connector) Detail Report Option; however, it allows the selection of a specific NEW PERSON file (#200) CONNECTOR PROXY entry.

3.5.7 Release user Option

If multiple signons are prohibited, problems can occur if users experience an abnormal exit such that the signon record cannot be cleared. System administrators can use the Release user option [XUSERREL] to

remedy the problem for individual users. To clear all users on startup, schedule the Clear all users at startup option.

3.5.8 Remote Access User Sign-on Log Option

The Remote Access User Sign-on Log option [XUSEC REMOTE ACCESS] prints sign-on log entries from remote users (VISITORS) that have been authenticated on an external system (usually another VistA server) using Broker Security Enhancement (BSE) or the (deprecated) Medical Domain Web Service (MDWS) visitor access.

The report shows:

- Remote Site Name.
- Date of First Visit.
- Date of Last Visit.

BSE allows users to be validated through the traditional VistA Access and Verify codes on their home system and then carry that authentication to other VistA systems. A packet of information is retrieved from the authenticating (home) site, and is entered in the NEW PERSON file (#200), so that a trace to the original authentication can be made.

3.5.9 User Inquiry Option

The User Inquiry Option option [XUSERINQ] displays various attributes of a specified user. If the user is currently signed on, it displays the job and device numbers, the signon time, and what option is being executed. Otherwise, it displays the last signon time. It also displays which security keys are held by the user.

3.5.10 User Status Report Option

The User Status Report option [XUUSERSTATUS] produces a report of the users currently signed on to this CPU and UCI. It shows the option each user is running and when they signed on, as well as their device and job numbers.

3.5.11 Users with Foreign Visits Option

The Users with Foreign Visits option [XUS VISIT USERS] shows NEW PERSON file (#200) entries that have been VISITORS to this site using Broker Security Enhancement (BSE) or the (deprecated) Medical Domain Web Service (MDWS) visitor access.

3.6 Signon Audits

Signon events are recorded in the SIGN-ON LOG file (#3.081). Statistics, such as the time of access and the user's identity, are stored for audit purposes. If the user exits normally (is not "bumped" off the system), the signon record includes the time of exit. If the user exits abnormally with an error or enters programmer mode, the signon record cannot include a time of exit.

Information about signon activity can be reviewed with options on the Operations and System Security menus.

The SIGN-ON LOG file (#3.081) is purged with the XUSCZONK option that should be tasked to run on a regular schedule (e.g., every night). This option *cannot* be reached from Menu Manager; like other options that should only be queued, it is on the PARENT OF QUEUABLE OPTIONS menu.

3.6.1 Signon Statistics

Statistics about active sessions can be obtained with the CPU/Service/User/Device Stats option [XUSTAT]. This option permits sorting by CPU, by the user's Service/Section (e.g., MAS) by individual users, or by particular devices.

Figure 32: CPU/Service/User/Device Stats option

```
SYSTEMS MANAGER MENU ... [EVE]
Operations Management ... [XUSITEMGR]
CPU/Service/User/Device Stats [XUSTAT]
```

3.6.2 Failed Access Attempts Audit

When a user enters invalid Access and Verify code pairs, the number of attempts is recorded and the device appears to lock after the site parameter limit of failed access attempts is reached. After this point, Signon/Security continues to record what the user types (but only to create a record in the FAILED ACCESS ATTEMPTS LOG file [#3.05]). If a valid Access code is entered, Signon/Security can link the attempt with a known user and records that user's name in the log. Since it is a valid code, its text is not recorded in the log. The text of subsequently entered invalid Verify codes can, however, be recorded as clues to the source of the access attempt. If the Access code is not valid, a user's name cannot be associated but the text of the attempt can be recorded. The log also records the time of day, device used, and CPU/UCI location.

Table 6: Kernel Signon Auditing Files

File	Global Location	Set Parameters	Display Parameters	Initiate/ Terminate	Print Reports	Purge Logs
SIGN-ON LOG (#3.081)	^XUSEC(0,	Predefined	N/A	Always done	Print Signon Log [XUSC LIST]	Purge Sign-on Log [XUSCZO NK]
FAILED ACCESS ATTEMPTS LOG (#3.05)	^%ZUA(3.05,	Establish System Audit Parameters [XUAUDIT]	Display the Kernel Audit Parameters [XU-SPY- SHOW]	On/Off switch	Devices: Device Failed Access Attempts [XUFDEV] Users: User Failed Access Attempts [XUFDISP]	Failed Access Attempts Log Purge [XUFPUR GE]
OLD ACCESS AND VERIFY CODES (#200 XREF)	^VA(200,	Predefined	N/A	Always done	N/A	Purge Log of Old Access and Verify Codes [XUSERA OLD]

3.6.3 Purge Old Access and Verify Codes

Figure 33: Purge Log of Old Access and Verify Codes option

```
SYSTEMS MANAGER MENU ... [EVE]
User Management ... [XUSER]
Purge Log of Old Access and Verify Codes [XUSERAOLD]
```

The Purge Log of Old Access and Verify Codes option [XUSERAOLD] purges all inactive Access and Verify codes, which allows for the recycling of codes. Old Access and Verify codes are stored so that users cannot pick a previously used code when required to choose a new code. If old codes are stored indefinitely, though, it may become difficult for users to invent new codes. When you use this option interactively, you can purge codes older than a retention period you specify, from 7 to 90 days. When scheduled, the retention period defaults to 90 days, but can be changed to anything from 30 to 90 days by putting the number of days in the TASK PARAMETERS field.

The log of Access codes is stored in the whole-file AOLD cross-reference of the NEW PERSON file (#200). The log of Verify codes is stored per user in the VOLD cross-reference of the NEW PERSON file (#200, not a whole-file cross-reference). Thus, Verify codes are *not* necessarily unique between users, while Access codes are.

4 File Access Security

The File Access Security system is an optional Kernel module. It provides an enhanced security mechanism for controlling user access to VA FileMan files.



REF: For more information on File Access Security, see the *VA FileMan (Version 22.0) and Kernel (Version 8.0) File Access Security* supplemental documentation located on the VA Software Document Library (VDL) at: http://www.va.gov/vdl/application.asp?appid=5

4.1 User Interface

As a user, you typically access VistA data by use of application options. You enter data into files and retrieve information from files through the menu options within the software. Except under a few unusual circumstances, your use of the system is *not* affected by the File Access Security system. If you need to work directly with files by using VA FileMan options, however, you are affected.

VA FileMan options provide direct access to data files. Figure 34 lists some sample VA FileMan options:

Figure 34: Sample VA FileMan menu options



If the File Access Security system is implemented, the only files you can access directly through VA FileMan options are those listed in your ACCESSIBLE FILE Multiple field (#32) in the NEW PERSON file (#200). System administrators grant file access by using a submenu on the User Management menu [XUSER].

There are six levels of File Access Security properties (listed alphabetically):

- AUDIT
- DATA DICTIONARY ("DD")
- DELETE ("DEL")
- LAYGO
- READ ("RD")
- WRITE ("WR")




REF: These File Access Security level properties are described in <u>Table 7</u>.

Each level of access is granted as **YES** or **NO**. If the File Access Security system is implemented, file access is controlled by these **YES/NO** flags, *not* by the matching of your FILE MANAGER ACCESS CODE field (#3) string in the NEW PERSON file (#200) with security placed on the file.

If you have *not* been granted any security access to VA FileMan files, entering two question marks ("??") when prompted for a file name/number shows no files to access:

Figure 35: User has *not* been granted security access to any VA FileMan files—Sample user dialogue



In this case, you need to contact the system administrators to get access to the VA FileMan files you need.

File Access Security is also invoked when an option uses VA FileMan's Line Editor. In particular, the Transfer Lines from Another Document option on the Line Editor's Edit menu does not permit access to other word-processing documents in the current file or other files unless READ access to that file has been explicitly granted. If you need to transfer text from other files using the Line Editor, contact the system administrators to request access to those files.

4.2 System Management

Prior to introduction of the File Access Security system, user access to VA FileMan files through VA FileMan options was controlled by matching a character in a user's FILE MANAGER ACCESS CODE field (#3) (the DUZ(0) string) in the NEW PERSON file (#200) with a character in the file's top level file security fields.

Kernel's optional File Access Security system uses a different method. It allows you to control access to files for any user using VA FileMan options directly. Access is granted (or denied) by adding (or removing) a file from a user's ACCESSIBLE FILE Multiple field (#32) in their NEW PERSON file (#200) entry.

The File Access Security system does *not* affect access to files through *non*-VA FileMan options; security in this case is managed by controlling the availability of the option.



REF: For exceptions, see the "When is File Access Security Checked?" section.

If a user's DUZ(0) is set to the at-sign ("@"; programmer access), VA FileMan options allow complete file access. If it is set to anything else (except the caret ["A"]), VA FileMan options use the ACCESSIBLE FILE Multiple field (#32) specifications in the NEW PERSON file (#200) to grant varying levels of file access.



NOTE: The caret ("^") overrides the at-sign ("@"; programmer access).

This higher degree of control over a user's file access comes at a price, because it requires more management on the system administrator's part to provide each user access to the files to which they need access. However, the payoff in using the File Access Security system is in enhanced control and security for VA FileMan files.

4.2.1 When is File Access Security Checked?

When using VA FileMan options, access to files through the File Access Security system is checked.

When initially accessing data in a file through software options (e.g., options using VA FileMan Application Program Interfaces [APIs]), File Access Security is *not* checked. File Access Security is checked, however, when calling the following APIs:

- ^DIC calls—Adding an entry to the top level of a file (i.e., LAYGO access)
- ^DIE calls—Deleting an entry at the top level of a file (i.e., DELETE access).

Developers can bypass these LAYGO and DELETE access checks using the following variables:

- DLAYGO
- DIDEL, respectively.

When accessing data through software options, File Access Security is also checked when a file is navigated to from another file (i.e., READ, WRITE, DELETE, and LAYGO access). Currently, there is no way for developers to override access checks when navigating to a file from another file, so explicit access to files navigated to/from an application option *must* be granted by the system administrators.

4.2.2 What in VA FileMan is Still Protected by the File Manager Access Code?

When the File Access Security system is enabled, access to templates (e.g., INPUT, PRINT, SORT, etc.) is denied when using VA FileMan options, if the user's DUZ(0) string does *not* contain a matching character. Similarly, when editing fields via VA FileMan's Enter or Edit File Entries option [DIEDIT], the DUZ(0) matching process is invoked to permit or deny editing for protected fields. The DUZ(0) value is also checked by some non-VA FileMan applications. Finally, if a user's DUZ(0) is "@", they are allowed complete access to all files.

4.2.3 Purpose for Granting File Access

System administrators are responsible for granting file access. The needs of each user *must* be determined and an appropriate degree of access authority assigned. Too much access may risk the security of your system, while too little may inhibit productive activity.

What is the purpose of File Access Security? Why bother specifying who has access to which files? The answer is threefold:

- To monitor the use of VA FileMan.
- To regulate the extent of VA FileMan access from among six levels of security that allow AUDIT,, DATA DICTIONARY ("DD"), DELETE ("DEL"), LAYGO, READ ("RD"), or WRITE ("WR") access.



REF: These File Access Security level properties are described in <u>Table 7</u>.

• To reserve DUZ(0), the FILE MANAGER ACCESS CODE field (#3), as a security measure to protect just templates and fields, *not* files, from VA FileMan options.

With file access security, it is possible to know who has access to which files and what kind of access they have. This information can also be retrieved by user or by file. In addition, privileges can also be entirely restricted for an individual user or for a single file that may contain sensitive information.

4.2.4 Who Needs File Access?

You need to grant File Access Security in the following cases:

- A user needs to access files directly through VA FileMan options.
- Within an application option, VA FileMan is used to navigate from one file to another.
- Within an application option that calls the ^DIE API to edit a file entry; a user is unable to add or delete entries in a pointed-to file.
- Within an application option that calls the ^DIE or ^DIC APIs to edit a file entry; a user is unable to add or delete entries in the primary file (because the application did not set the DLAYGO or DIDEL variables).
- A user needs to use VA FileMan's Line Editor's Transfer Lines from Another Document option.

Application developers can document which files need to be granted to whom, or can modify their code or data dictionary (DD) specifications to allow access.

4.2.5 Levels of File Access Security

There are six file access security properties involved with File Access Security. If a file access security property is *not* defined (i.e., the value is null), the VA FileMan exported menu options for that property are *not* open to full access for users.



REF: Table 7 is taken from the VA FileMan (Version 22.0) and Kernel (Version 8.0) File Access Security supplemental documentation located on the VA Software Document Library (VDL) at: http://www.va.gov/vdl/application.asp?appid=5

Table 7: File Access—Security level properties

Table 111 lie /165655 Goodlin, 1616. proportion				
Access	Security Property Description	Property Location (Classic VA FileMan)		
AUDIT	The AUDIT security property controls the setting of auditing characteristics and the deletion of audit trails. This property only deals with the auditing of data and <i>not</i> the auditing of data dictionary (DD) changes. To audit DD changes, users would enter "YES" at the "DD AUDIT? NO//" prompt when modifying a file's File Security Access. Examples of the VA FileMan options that this property controls are as follows:	^DIC(<file number="">,0,"AUDIT")=<value></value></file>		
	 Fields Being Audited [DIAUDITED FIELDS] 			
	 Data Dictionaries Being Audited [DIAUDIT DD] 			
	 Purge Data Audits [DIAUDIT PURGE DATA] 			
	 Purge DD Audits [DIAUDIT PURGE DD] 			

Access	Security Property Description	Property Location (Classic VA FileMan)
	Turn Data Audit On/Off [DIAUDIT TURN ON/OFF]	
DATA DICTIONARY ("DD")	The DATA DICTIONARY security property controls who has access to modify the data dictionary. Examples of the VA FileMan options that this property controls are as follows:	^DIC(<file number="">,0,"DD")=<value></value></file>
	Modify File Attributes [DIMODIFY]	
	Utility Functions [DIUTILITY]	
	Data Dictionary Utilities [DI DDU]	
	For example, to use the Map Pointer Relations option, DD access is needed to the PACKAGE file (#9.4) and to the files one selects for mapping.	
DELETE ("DEL")	The DELETE security property controls who can delete an existing record that is contained within the file. It does <i>not</i> permit deletion of the file or any of its attribute fields. Examples of the VA FileMan options that this property controls are as follows:	^DIC(<file number="">,0,"DEL")=<value></value></file>
	Enter or Edit File Entries [DIEDIT]	
	Transfer Entries [DITRANSFER]	
LAYGO	The LAYGO (Learn As You Go) security property controls who can add a new record to the file. Examples of the VA FileMan options that this property controls are as follows:	^DIC(<file number>,0,"LAYGO")=<value></value></file
	Enter or Edit File Entries [DIEDIT]	
	NOTE: You must have LAYGO and WRITE access to a file to add new entries. In addition, you must have WRITE access at the field level for all required identifier fields.	
READ ("RD")	The READ security property controls who has access to read data contained within a file. Examples of the VA FileMan options that this property controls are as follows:	^DIC(<file number="">,0,"RD")=<value></value></file>
	Print File Entries [DIPRINT]	
	Search File Entries [DISEARCH]	
	Inquire to File Entries [DIINQUIRE]	
	Statistics [DISTATISTICS]	

Access	Security Property Description	Property Location (Classic VA FileMan)
	List File Attributes [DILIST] Transfer Entries [DITRANSFER] To transfer text, the user needs READ access to the file from which text is being transferred. Similarly, WRITE access is needed for the file to which entries are being transferred with this option. Transfer File Entries (transfer-to file) NOTE: READ access is also	
WRITE ("WR")	required to use some of the Filegram and Audit options. The WRITE security property controls who can alter data in an existing record that is contained within the file. It does <i>not</i> permit the adding of new entries to the file. Examples of the VA FileMan options that this property controls are as follows: • Enter or Edit File Entries [DIEDIT] • Transfer Entries [DITRANSFER] To transfer text, the user needs READ access to the file from which text is being transferred. Similarly, WRITE access is needed for the file to which entries are being transferred with this option.	^DIC(<file number="">,0,"WR")=<value></value></file>

Any or all of these six levels of access can be enabled for each of the user's accessible files. This is done by changing the field value from **NULL** to **YES**. This flag is overridden for developers whose DUZ(0)=@.

Granting the READ, WRITE, DELETE, and LAYGO levels of access permits adding and deleting file entries as well as editing their attribute field data values. This is true unless the attribute field has been protected. If so (i.e., if there is READ, WRITE, or DELETE protection within the data dictionary [DD] for a given field), the user's FILE MANAGER ACCESS CODE field (#3), DUZ(0), is checked. Access is denied if the user's DUZ(0) does *not* contain a character matching the field protection. Again, DUZ(0)=@ overrides this restriction.

The DATA DICTIONARY ("DD") and AUDIT levels of access pertain to the structure of the file itself. While this provides a generous scope for VA FileMan data dictionary (DD) modification, it falls short of, for example, deleting a field protected with the at-sign ("@"; programmer access).

The same applies to templates. If the template is protected, the user who has access to the file does *not* have access to the template from VA FileMan options unless there is a match in the DUZ(0) character string.

4.2.6 Audit Access to Files

Audit privileges might be granted to advanced VA FileMan users who are interested in developing new audit capabilities. With AUDIT access, which *must* be accompanied by DD access, VA FileMan's Modify File Attributes option [DIMODIFY] can be used to set an audit flag for a particular field within a file. This access does *not* include setting audit conditions with M code, which is reserved for users with a FILE MANAGER ACCESS CODE field (#3) containing "@".

The data values for attribute fields can be recorded in the AUDIT file (#1.1) by setting an audit flag in the data dictionary (DD) for that field. For example, the SSN field in the PATIENT file (#2) could be audited. There are two choices for the audit in the AUDIT file (#1.1):

- An entry can be made when a value is entered or changed.
- An entry can be made *only* when the value is changed (i.e., edited or deleted).

The second method may be all that's needed. In the SSN example, you would monitor just the circumstances of the change, not of the initial SSN assignment.

To display the results of the audit, your DUZ(0) *must* equal the at-sign ("@"; programmer access). Then, you can query the AUDIT file (#1.1) in the usual way with VA FileMan's Inquire to File Entries option [DIINQUIRE].

4.2.7 How to Grant File Access

System administrators specify the particular files and levels of access for users. The File Access Security menu [XUFILEACCESS], on the User Management menu [XUSER], provides options to grant file access security. These options edit the ACCESSIBLE FILE Multiple field (#32) in the NEW PERSON file (#200).

The options for granting file access privileges fall into three functional categories:

- EDITING—To assign file access to an individual user or a group of users. One user's profile can also be duplicated or copied to another user or group of users. To simplify adding files, number ranges can be specified.
- LISTING—To display one user's profile, a name-sorted list of all user's profiles, or a file or range of files with associated users and the access levels of each.
- RESTRICTING—To entirely limit access by user or by file, or to delete a range of files for a user or group of users.

The options are designed to facilitate queries by user or by file. You can add or delete file access for one user or for many users. Or, you can begin with the file and list users with access or restrict access.

4.2.8 Using the File Access Options

Figure 36: File Access Security menu options

```
SYSTEMS MANAGER MENU ...
                                                                                [EVE]
                                                                              [XUSER]
User Management ...
   File Access Security ...
                                                                       [XUFILEACCESS]
      Grant Users' Access to a Set of Files
                                                                        [XUFILEGRANT]
      Copy One User's File Access to Others
                                                                         [XUFILECOPY]
      Single file add/delete for a user
                                                                    [XUFILESINGLEADD]
      Inquiry to a User's File Access
                                                                      [XUFILEINOUIRY]
      List Access to Files by File number
                                                                         [XUFILELIST]
      Print Users Files
                                                                        [XUFILEPRINT]
      Delete Users' Access to a Set of Files
                                                                    [XUFILESETDELETE]
      Remove All Access from a Single User
                                                                    [XUFILEREMOVEALL]
      Take away All access to a File
                                                                       [XUFILEDELETE]
      Assign/Delete a File Range
                                                                  [XUFILERANGEASSIGN]
```

When using options on the File Access Security menu [XUFILEACCESS], you may have the following questions:

- What is the DUZ# that appears next to the user's name?
- How is a range of file numbers specified?
- What are the queuing questions all about?

4.2.8.1 Understanding DUZ (User Number)

When listing the file accesses by user or by file, the user's name is followed by a number in parentheses. The heading indicates that this is the "User #," which is the same as the DUZ#.

Once the user enters an Access and Verify code, Kernel's Signon/Security uses the DUZ variable to identify an entry in the NEW PERSON file (#200). It *must* be a unique identifier, so the user's name does *not* work. Instead, the Internal Entry Number (IEN) is used. That is what becomes the value of DUZ.



NOTE: Some users have low numbers while others have high ones. This simply indicates the order their names were entered into the NEW PERSON file (#200). Users with low numbers are often people who began using the system some years ago, while users with high numbers tend to be recent entries in the file.

DUZ is a local variable array that identifies the user who has signed onto the system. It is the Internal Entry Number (IEN) for the user in the NEW PERSON file (#200). Besides the unique IEN, this array contains other variables specific to the signed-on user:

- DUZ(0)—This variable stores the level of programmer access (i.e., VA FileMan Access Code) of the user at signon (e.g., "@"). This variable is derived from the value stored in the FILE MANAGER ACCESS CODE field (#3) in the NEW PERSON file (#200).
- DUZ(1)—This variable is obsolete; it is always set to NULL.
- DUZ(2)—If a user is associated with more than one institution (division), the user is prompted at signon to select a division. This variable is set to the appropriate value. This variable is derived from the values stored in the DIVISION Multiple field (#16) in the NEW PERSON file (#200). This field points to the INSTITUTION file (#4).
- DUZ("AG")—This variable stores the agency code at signon (e.g., "V" = VA). This variable is derived from the value stored in the AGENCY CODE field (#9 in the KERNEL SYSTEM PARAMETERS file (#8989.3). This value is a defined Set of Codes.
- DUZ("AUTHENTICATION")—This variable stores the method used to authenticate the user. Examples include "ASHTOKEN", "AVCODES", "BSETOKEN", "CCOWTOKEN", "SSOI", "SSOE", "NHIN", "NONE", and "XUP".
- DUZ("AUTO")—Menu Manager uses this variable to control whether all items on a menu are presented automatically after each cycle through the menu system. This variable stores the user's menu display preference at signon (e.g., "1" = Auto Generate Menus). This variable is derived from the value stored in the AUTO MENU field (#.06) in the NEW PERSON file (#200).
- DUZ("BUF")—This variable stores the user's type ahead (buffer) preference (e.g., "1" = Allowed). This variable is derived from the value stored in the TYPE-AHEAD field (#.09) in the NEW PERSON file (#200).
- DUZ("LANG")—This variable stores the display language as it is stored in the LANGUAGE field (#.01) in the LANGUAGE file (#.85). VA FileMan uses this setting to enable the display of language-specific dates and times, numeric formats, and dialogues. VA FileMan currently distributes only the English language entry for this file (entry number 1).


The LANGUAGE field (#.01) in the LANGUAGE file (#.85) is pointed to by the following:

- o LANGUAGE field (#.01) of the TRANSLATION subfield (#.847) of the DIALOG file (#.84).
- o LANGUAGE field (#200.07) in the NEW PERSON file (#200).
- o DEFAULT LANGUAGE field (#207) in the KERNEL SYSTEM PARAMETERS file (#8989.3), which overrides the setting of the LANGUAGE field (#200.07).

- DUZ("LOA")—This variable records the "Level of Assurance" (LOA) of the user's authentication and identity. Four levels are currently defined by National Institution of Standards and Technology Special Publication (NIST SP) 800-63-2 Electronic Authentication Guideline:
 - Level 1—No identity proofing requirement. This generally refers to a "self-asserted" user identity and is the lowest form of authentication. This form of authentication does not satisfy VA HANDBOOK 6500 security requirements. Application developers may choose to programmatically deny access to sensitive data if a user's LOA equals "1".
 - Level 2—Single factor authentication. This form of authentication includes username/password or, in the case of VistA, Access/Verify code authentication.
 - o Level 3—Multi-factor authentication. This form of authentication includes VA 2-factor authentication using smart cards (PKI certificates) and Personal Identification Number (PIN).
 - o **Level 4**—The highest practical authentication assurance. At this level, in-person identity proofing such as fingerprint or retinal scan is used to authenticate and identify the user.
- DUZ("REMAPP")—This variable is used to identify an external client application whenever
 possible. Examples include "BMS", "CAPRI", "MDWS", "NUMI", "VISTA IMAGING", and
 others. The information is currently obtained from the REMOTE APPLICATION file (#8994.5), but
 plans are to obtain client application identity from the 2-factor authentication token when fully
 implemented.
- DUZ("TEST")—This variable is used during menu generation. It indicates to the user when they are in a Test account by inserting the phrase "<TEST ACCOUNT>" into the "Select..." main menu prompt. For example (see <u>Figure 38</u>):

Select VA FileMan <TEST ACCOUNT> Option:

Figure 37: Displaying the DUZ array for a signed-on user at a programmer prompt



When you want to display/print the DUZ, VA FileMan recognizes that when you enter "NUMBER" as a print field that you want to display/print the DUZ for the user entry from the NEW PERSON file (#200).

Figure 38: Displaying the DUZ (Internal Entry Number) in a VA FileMan report

```
Select VA FileMan <TEST ACCOUNT> Option: PRINT <Enter> File Entries
OUTPUT FROM WHAT FILE: <a href="NEW PERSON">NEW PERSON</a> / <Enter>
SORT BY: NAME// <Enter>
START WITH NAME: FIRST// <Enter>
FIRST PRINT FIELD: NUMBER
  VA FileMan recognizes "NUMBER" as the Internal Entry Number for the
  entry in the NEW PERSON file (#200).
THEN PRINT FIELD: NAME
     1 NAME
     2 NAME COMPONENTS
CHOOSE 1-2: 1 <Enter> NAME
THEN PRINT FIELD: <Enter>
Heading (S/C): NEW PERSON LIST// <Enter>
DEVICE: <Enter> Network
NEW PERSON LIST
                                                  APR 3,2013 09:55 PAGE 1
NUMBER NAME
1000228
            XUUSER, EIGHI
XUUSER, ELEVEN
1000084
             XUUSER, FIFTEEN
             XUUSER, FIVE
             XUUSER, FOUR
             XUUSER, FOURTEEN
             XUUSER, NINE
1000182
             XUUSER, ONE
1000166
             XUUSER, SEVEN
             XUUSER, SIX
1000108
1000039
              XUUSER, SIXTEEN
151
              XUUSER, TEN
               XUUSER, THIRTEEN
164
               XUUSER, THREE
71
               XUUSER, TWELVE
183
               XUUSER, TWO
```

4.2.8.2 Using Ranges of File Numbers

Can files be specified by number ranges? Yes; it is useful to do this when granting several files at once. First, find out the number of the files. Typing a question mark ("?") at the "to Files:" prompt displays the number and name of the files. Note the numbers and then put them together on one line. You can use hyphens to indicate a consecutive range and commas to separate the single numbers and hyphenated groups as follows:

```
2,3,4,6,7,8,125,236,799
OR
2-4,6-8,125,236,799
```

File numbers are also used when printing a group of consecutive files. The prompt asks for a place to start with a default file name presented. To print just this one file, respond to the next prompt by simply pressing the **Enter**> key, thereby accepting the default of ending after printing that one file.

To print a consecutive range of files, the lowest number is entered as the starting point and the highest number as the ending point. All files that fall in this range are printed.

4.2.8.3 Queuing File Access Specifications

Most of the options provide the opportunity to queue, after specifying who is to be granted which files. Queuing sends the specifications to TaskMan to assign to users at a later time. TaskMan can work at an off-peak time (e.g., midnight) to avoid consuming system resources during the daytime. If the system is not busy, queuing is still a good idea since your terminal is otherwise be tied up while the report is being printed.

4.3 Running the File Access Security Conversion

4.3.1 Advantages

To implement File Access Security you need to run a conversion. Some advantages of implementing File Access Security include:

- **Easier to identify levels of access**—Running the conversion makes it possible to identify the levels of access each individual user has to each file.
- **Enhanced system performance**—Checking file access by user is slightly faster in terms of global accesses and CPU time.

4.3.2 Advance Preparation for the Conversion

The File Access Security conversion is designed to allocate access privileges to all of your users according to their current FILE MANAGER ACCESS CODE field (#3) value in the NEW PERSON file (#200), DUZ(0), combined with information about their file access through options stored in the ^DISV global. After the conversion you should get only a few user requests for file access. The File Access Security menu [XUFILEACCESS], an option on the User Management menu [XUSER], should then be used to add a file to a user's ACCESSIBLE FILE Multiple field (#32) in the NEW PERSON file (#200).

The conversion uses the FILE MANAGER ACCESS CODE field (#3) (DUZ[0] string) to assign file access according to the characters in the string. If a file is protected with a particular character that matches one in the user's code, that file is entered into the user's ACCESSIBLE FILE Multiple field (#32). Levels of access are granted according to the file's original security (field-level security continues to function the same, by checking the FILE MANAGER ACCESS CODE field (#3)).



NOTE: Users with programmer-level access (FILE MANAGER ACCESS CODE field [#3] = @) does *not* need to have any files in their ACCESSIBLE FILE Multiple field (#32), since they are able to access *all* files *without* restriction.

4.3.2.1 ^DISV Global


The File Access Security conversion process makes use of the ^DISV global to identify which files have recently been accessed by which users. The conversion adds all files that the user has been able to access (select from) to the user's ACCESSIBLE FILE Multiple field (#32) list. It grants READ access to these files.

Using the ^DISV global to grant file access has the benefit of permitting option usage "as usual" the day after the conversion is run. KILLing the ^DISV global just *before* the conversion is *not* advised, since

many users suffer inappropriate access restrictions and need special attention by system administrators just after the conversion. KILLing the ^DISV global a week or two before the conversion, however, may be worthwhile as a way of purging obsolete user data. In multi-CPU environments, where each CPU has its own copy of the ^DISV global, you should choose the busiest user node upon which to run the conversion (in order to pick up the most comprehensive information from that node's ^DISV). Caché sites should run the conversion from their busiest user node.

It is assumed that ^DISV is not translated, so K ^DISV on the CPU where the conversion is run. Do this about two weeks before you perform the conversion, as advance preparation. ^DISV is reset as soon as a user responds to a "Select:" prompt.

Figure 39: KILLing ^DISV—Sample code



4.3.2.2 Adding Explicit File Access for System Administrators

If there are any files that are neither protected nor accessed by users (e.g., the DOMAIN file [#4.2]) the conversion does *not* list them in any user's ACCESSIBLE FILE Multiple field (#32). Before the conversion, these types of files are accessible to everyone, while after the conversion these files are only accessible to users with programmer-level access. Therefore, before the conversion, assign a unique symbol/character to otherwise unprotected files. This ensures that at least those users with that unique symbol (e.g., system administrators) is granted access. VA FileMan's Edit File option [DIEDFILE] can be used to edit the codes.



NOTE: In previous documentation and data dictionaries, it has been *implied* that the pound sign ("#") symbol/character was reserved for File Access Security for system administrators; however, this is *not* true. It has merely been used as a *convention*.

Figure 40: Updating file access settings (before conversion)

```
Select OPTION: UTILITY FUNCTIONS
Select UTILITY OPTION: EDIT FILE
MODIFY WHAT FILE: USER// DOMAIN <Enter>
                                                    (227 entries)
Do you want to use the screen-mode version? YES// N <Enter> NO
NAME: DOMAIN// <Enter>
DESCRIPTION:
 No existing text
 Edit? NO// <Enter>
Select APPLICATION GROUP: <Enter>
DEVELOPER: <Enter>
  Enter a unique symbol/character for each level of access, so that those unprotected
  files are assigned to system administrators.
DATA DICTIONARY ACCESS: <Enter>
READ ACCESS: <Enter>
WRITE ACCESS: <Enter>
DELETE ACCESS: <Enter>
LAYGO ACCESS: <Enter>
AUDIT ACCESS: <Enter>
```

4.3.3 Summary of the File Access Security Conversion

The File Access Security conversion prepares the NEW PERSON file (#200) for VA FileMan's method of file access (lookup into a user's record for file access). VA FileMan's ability to protect data within files on fields and templates remains the same. The summary steps that occur when the conversion is run are outlined below:

- 1. Setup structure. The structure for implementing the file access method is set up via the following:
 - a. Place the data dictionary (DD) for the ACCESSIBLE FILE Multiple field (#32) in the NEW PERSON file (#200). This multiple is permanently put in place by running the File Access Security conversion.
 - b. Install menu options, help frames, and templates used for maintaining the user file access method (i.e., entries with the XUFI namespace).
- 2. Add protected files to the ACCESSIBLE FILE Multiple field (#32). Each user's FILE MANAGER ACCESS CODE field (#3) is used to add entries to the ACCESSIBLE FILE Multiple field (#32) as follows:
 - a. Create a list of files to be processed by examining each file's protection codes. Files that meet *both* of the following requirements are temporarily stored in the ^UTILITY(\$J global:
 - Files that have protection defined.
 - Files with protection not equal to "@".



NOTE: Files that lack any protection are bypassed. Such unprotected files are *not* later listed in anyone's ACCESSIBLE FILE Multiple field (#32). Protection should therefore be applied *before* running the conversion so that at least some users (e.g., system administrators) is granted access.

- b. Examine each user in the NEW PERSON file (#200). Each user meeting *all* of the following requirements is selected for further processing:
 - Users *not* terminated.
 - Users with an Access code.
 - Users with a VA FileMan Access code (i.e., FILE MANAGER ACCESS CODE field [#3] in the NEW PERSON file [#200]).
 - Users with a FILE MANAGER ACCESS CODE field (#3) in the NEW PERSON file [#200] *not* equal to "@".

The user's FILE MANAGER ACCESS CODE field (#3) in the NEW PERSON file [#200] is parsed. Each symbol/character is compared with the list of files in the ^UTILITY(\$J global. All files that have a protection code matching this symbol/character are added to the user's ACCESSIBLE FILE Multiple field (#32) in the NEW PERSON file [#200]. If the symbol/character is used as the file's DATA DICTIONARY ("DD") file security, the user is granted DD access; if it is used as LAYGO, the user is granted LAYGO access, and so on.

- 3. Add files accessed by the user to the ACCESSIBLE FILE Multiple field (#32). Files accessed by the user through options since the last time the ^DISV global was KILLed are added to the user's ACCESSIBLE FILE Multiple field (#32) by the processing of the ^DISV global. Entries in ^DISV that meet *both* of the following requirements are added to the ACCESSIBLE FILE Multiple field (#32), with READ access:
 - The file *must* not be in VA FileMan's file number range (i.e., file number *must* be equal to or greater than 2).
 - The user does *not* already have access to this file.

4.3.4 File Access Security Conversion Instructions

The steps that occur when the file access security conversion is run are described below:

1. Identify unprotected files and assign protection codes as desired (as described in the "<u>Advance Preparation for the Conversion</u>" section). For example, the DOMAIN file (#4.2) may need to be protected so that it is granted to users having a FILE MANAGER ACCESS CODE field (#3) containing the assigned symbol/character.



NOTE: In previous documentation and data dictionaries, it has been *implied* that the pound sign ("#") symbol/character was reserved for File Access Security for system administrators; however, this is *not* true. It has merely been used as a *convention*.

- 2. Review the FILE MANAGER ACCESS CODE fields (#3) of VA FileMan users. The codes should contain symbols/characters matching those used to protect the files that these individuals use. Since the conversion automatically grants files to users according to previous privileges as indicated by the FILE MANAGER ACCESS CODE field (#3), add any additional symbols/characters to their FILE MANAGER ACCESS CODE fields (#3) to take advantage of the conversion's automated file assignment according to levels of access.
- 3. Be ready to use the File Access Security menu [XUFILEACCESS], <u>Figure 36</u>, to review and grant file access privileges *after* the conversion.
- 4. In the production account, enable File Access Security system features and options with ENABLE^XUFILE3, as illustrated below:

Figure 41: Enabling File Access Security—Sample user dialogue

In VAH:

>D ENABLE^XUFILE3

>

5. In the production account, begin the conversion with ^XUINCON:

Figure 42: ^XUINCON conversion routine—Sample user dialogue

```
>D ^XUINCON

Version 7 of the Kernel defined a new multiple-valued field in the New Person File called Accessible File. This conversion will store file access in this multiple in the following manner:

Those Users who have a FileMan Access Code (DUZ(0)) which is not null, i.e., contains some character string, will have their access string matched to the protection currently on your files. For each match between the file and the user, the file will be listed in the user's Accessible File multiple as will the type of access (dictionary, delete, laygo, read, write, audit).

NOTE: Files with no protection will NOT be assigned to any user.

Would you like to run the conversion now? NO//
```

6. If you are ready to run the conversion, answer YES:

Figure 43: Running a conversion—Sample user dialogue

```
Would you like to run the conversion now? NO// YES 56237,36565
Build Table.
Convert Users.
Give access from DISV file.
X-ref.
Done56237,36565.
```

7. Review the newly assigned access settings. Use the File Access Security menu [XUFILEACCESS], Figure 36, located on the User Management Menu [XUSER], to display file access by user and by file.

4.3.5 After the File Access Security Conversion


After the file access security conversion, users may complain about not being able to add entries to files as they previously could. This typically results from use of an option that navigates from one file to another. To be able to add entries to the navigated-to file, the user needs LAYGO access to that file. System administrators can solve the problem by granting LAYGO access using the File Access Security menu options [XUFILEACCESS], Figure 36.

If this form of security is implemented, system administrators should find that it provides a more accurate and precise knowledge of who has what level of access to which files. When the conversion is run, privileges are granted to existing users by making use of information stored in the VA FileMan record of file manipulation activity, the ^DISV global. The file access conversion grants each user READ access to files that the user had recently accessed as indicated in the ^DISV global. System administrators can grant file access privileges to new users by copying the profile of an existing user with similar duties (e.g., a laboratory application coordinator or admissions clerk).

To be sure that appropriate levels of access have been allocated, system administrators should determine who has what level of access to which files. Access to sensitive files (e.g., the NEW PERSON file [#200]) should be reviewed and readjusted for individual users as appropriate. All files on a system should be reviewed before and after running the File Access Security conversion.

Figure 44 shows how to create a PRINT template to display a report on the current file access security:

Figure 44: Creating a PRINT template to display file access security—Sample user dialogue



Once the conversion has been run, you can use the File Access Security menu [XUFILEACCESS], <u>Figure 36</u>, to print the accessible files for individual users. Thus, you can establish profiles that would be typical of groups of users (e.g., Nursing, Pharmacy, or other services). Then, when establishing an account for a new user or reactivating the access of a previously terminated user, the profile is available for copying to the new user.

5 Electronic Signatures

5.1 User Interface

An electronic signature is a security tool that software applications can use as an additional identification check. For example, software can require that an electronic signature be applied to a particular form or document before subsequent processing can continue.

Electronic signature codes are stored in the NEW PERSON (#200) file.

5.1.1 Electronic Signature code Edit Option

If you need to create an electronic signature for yourself, you can choose the Electronic Signature code Edit option [XUSESIG], available from the User's Toolbox menu.

You can enter a new electronic signature code or change an existing code. The length of the code *must* be between 6 and 20 uppercase characters. Requiring all uppercase allows the code to be verified with either uppercase or lowercase input, since lowercase is converted to uppercase in the matching process. You should choose a code that other users are not likely to guess, as this code verifies that it is actually you who are signing off on some important action.

The Electronic Signature code Edit option [XUSESIG] also allows you to edit the following fields in the NEW PERSON file (#200):

- INITIAL
- SIGNATURE BLOCK PRINTED NAME (#20.2)
- SIGNATURE BLOCK TITLE (#20.3)
- OFFICE PHONE (#.132)
- VOICE PAGER (#.137)
- DIGITAL PAGER (#.138)

Applications can print some or all of these fields when printing an electronically signed document. You should therefore ensure that the values entered in these fields are accurate.

5.2 System Management

Figure 45: User Edit menu options

```
SYSTEMS MANAGER MENU ... [EVE]
User Edit ... [XUSER]
Electronic Signature Block Edit [XUSESIG BLOCK]
Clear Electronic signature code <locked: XUMGR> [XUSESIG CLEAR]
```

5.2.1 Electronic Signature Block Edit Option

The Electronic Signature Block Edit option [XUSESIG BLOCK] lets you edit the electronic signature code for any user on the system. When you create an electronic signature code for a user, the SIGNATURE BLOCK PRINTED NAME field is initially filled in by a cross-reference on the NAME field (#.01) (and is overwritten if the NAME field [#.01] is changed). Credentials (e.g., "M.D.") can be added to customize the printed name. As a security feature, an input transform requires that the user's last

name (first comma piece of the NAME field (#.01)) be included in the printed name. (This field *cannot* be edited through VA FileMan since it is WRITE-protected with a caret ["^"].)

5.2.2 Clear Electronic signature code Option

The Clear Electronic signature code option [XUSESIG CLEAR] is another option available to system administrators that allows the clearing (deleting) of an electronic signature code. This option is locked with the XUMGR security key. This option can be used to clear a user's electronic signature code if the user has forgotten the code. The user can then enter a new code with the Electronic Signature code Edit option [XUSESIG] in the User's Toolbox menu.

6 DEA ePCS Utility

6.1 Overview

Kernel patch XU*8.0*580 was created in support of the Drug Enforcement Agency (DEA) e-Prescribing of Controlled Substances (ePCS) Utility using Public Key Infrastructure (PKI). This section describes the modifications and enhancements to Kernel (and other VistA software) to meet the requirements proposed by the DEA Interim Final Rule (IFR) for Electronic Prescriptions for Controlled Substances effective as of June 1, 2010.



NOTE: This document only describes the changes made to Kernel in support of the DEA ePCS Utility.



REF: For more information on the DEA ePCS Utility software and other VistA applications, see the following:

- Computerized Patient Record System (CPRS) documentation on the VDL: http://www.va.gov/vdl/application.asp?appid=61
- Pharmacy: Controlled Substances documentation: on the VDL: http://www.va.gov/vdl/application.asp?appid=86

6.1.1 History

The Veterans Health Administration (VHA) Patient Care Services Office Pharmacy Benefits Management Services (PBM) requested enhancements to Veterans Health Information Systems and Technology Architecture (VistA), specifically the following software applications:

- Computerized Patient Record System (CPRS)
- Outpatient Pharmacy
- Controlled Substances
- Kernel

The enhancements made to these applications is to ensure that prescriptions for Controlled Substances (i.e., drugs listed in federal Controlled Substance Schedules II through V) can be digitally signed by the Prescribers and electronically transmitted from Prescribers to a Department of Veterans Affairs (VA) Pharmacy. The request was aimed at filling in the difference between the Hines Drug Enforcement Agency (DEA) ePrescribing pilot project as it stood as of April 2014 and the proposed DEA ePrescribing of Controlled Substances as shown in the June 27, 2008 Federal Register. These regulations allowed the process and proof of concept that was demonstrated with the DEA pilot to be expanded beyond the Hines VA Hospital facility.

The Hines VA/DEA Public Key Infrastructure (PKI) project stems from a pilot initiated in 2002 to demonstrate the ability for CPRS to incorporate digital signatures for Schedule II Controlled Substance narcotic prescriptions. Hines VA Hospital was the pilot site and had previously been granted a waiver of regulations by the DEA to test the system.

The Pilot procedure was as follows:

- 1. Prescribers insert a "smart card" into a reader.
- 2. Prescribers enter an electronic prescription into CPRS.
- 3. System authenticates the Prescriber's PKI prescribing credentials on the smart card.
- 4. System digitally signs the prescription.
- 5. System delivers the order to the VA pharmacy electronically.

The initial pilot evaluation, which allowed approximately 50 users to prescribe electronically using "smart cards", was formally concluded in 2003. DEA authorized Hines VA Hospital to continue using the system in its current form until new regulations were published regarding electronic transmission of prescriptions using Personal Identity Verification (PIV) cards. Subsequently, the VistA software was modified to meet the new standards.

Under the proposed DEA ePrescribing regulations, the CPRS system *must* authenticate the Prescriber's credentials on a hard token (e.g., PIV card) and then display a mandatory message with DEA-required intent language that the Prescriber must consent to. Only after the Prescriber consents to the DEA-required wording can the prescription be transmitted to the VA Pharmacy.

The PIV card to be used for the DEA ePrescribing is the VA-wide PIV Card program mandated by Homeland Security Presidential Directive #12 (HSPD-12).



REF: For information on validating PIV cards, see the "<u>PIV Card Validation—Revocation</u> <u>Server</u>" section.



NOTE: CPRS requested the original funding of this software upgrade as part of the CPRS v29 funding submission.

6.1.2 Requirements

Once the DEA ePrescribing regulations were enacted, system changes were required to bring the VA in compliance with DEA regulations. The majority of the changes needed for the DEA ePCS Utility are in the VistA CPRS and Outpatient Pharmacy applications; however, there were also some changes needed in Kernel:

- CPRS—Allows VA Prescribers to enter and digitally sign prescriptions.
- Outpatient Pharmacy—Notifies a VA pharmacy that a prescription order was made in CPRS.
- Kernel—Provides the Application Programming Interfaces (APIs) between the VistA Pharmacy
 and CPRS applications that allow the PKI credentials on the smart card to be verified. The PIV
 technology ensures that the Prescriber's credentials are vetted and emplaced on the PIV card
 according to the DEA regulations once they are enacted into law.

The DEA regulations governing the electronic prescribing and transmission of Controlled Substances pertain to the following conditions:

- VA Prescribers of DEA-regulated Controlled Substances (Schedules II through V).
- Patients using a VA pharmacy.
- VA Pharmacists who fill the Controlled Substance prescriptions.
- Pharmacy Benefits Management (PBM), who has the accountability to minimize the abuse of Control Substances.

6.1.3 Benefits

The benefits of the DEA EPCS Utility include the following:

- Concise ordering of the correct prescriptions.
- Increased security against abuse of Controlled Substances—Test results showed a 90% reduction in the number of forged, tampered or altered Controlled Substances presented to the pharmacy.
- An electronic record of prescription history that can be monitored and reported.
- Increased patient safety—Test results showed a 75% reduction in the number of Controlled Substance prescription fill errors caused by illegible handwriting.
- Decreased wait time for patients to receive their prescriptions—Test results showed a 50% reduction in the average time from when a prescription is written to when it is process (finished) by pharmacy, primarily affected by the elimination of prescription transit time from remote clinics.

6.1.4 Intended Audience

The intended audience of this manual is all key stakeholders. The stakeholders for the DEA ePCS Utility include the following:

- (Primary) DEA-registered Prescribers of Controlled Substances—Users who do the following:
 - o Create the prescription order in the system.
 - o Digitally sign the prescription.
 - o Submit the prescription electronically to the Pharmacy.

Under the proposed DEA regulations, these users also electronically reject or agree to DEA-mandated wording prior to electronically signing the prescription.

- **System Administrators**—System administrators at Department of Veterans Affairs (VA) sites who are responsible for computer management and system security on the VistA M Servers. These users are also responsible for the following:
 - o Installing the necessary hardware and software for use of the smart card-based digital certificates.
 - o Maintaining the server that runs the Certificate Revocation List (CRL) and other signature-checking processes.
 - Assisting in the maintenance of the database containing all valid DEA registrants within the VA. This database is an entity outside of VistA. The management of this database is shared by the VA and DEA.

- **Information Security Officer (ISO)**—The ISO is responsible for information security at each VA site.
- Emerging Health Technologies (EHT)—Users who identify, explore, pilot, and move into Production those technologies that can contribute to VA business needs. In this instance, the Public Key Infrastructure (PKI) technologies.
- Personal Identification Verification (PIV) Project—This VA project provides formatted smart
 cards for use with the system. The PIV project personnel ensure that the DEA PKI expansion for
 digitally signing and transmitting electronic prescriptions fits in with the scope and objectives of
 the Veterans Health Administration (VHA)-wide Homeland Security Presidential Directive
 (HSPD)-12 mandated directives.
- **Drug Enforcement Agency (DEA)**—The Federal agency that:
 - o Enforces the Controlled Substances laws and regulations of the United States.
 - o Enforces provisions of the Controlled Substances Act as they pertain to the manufacture, distribution, and dispensing of legally produced Controlled Substances.
 - Assists in the maintenance of the database containing all valid DEA registrants within the VA. This database is an entity outside of VistA. The management of this database is shared by the VA and DEA.
- Office of Information and Technology (OI&T)—VistA legacy development teams.
- Product Support (PS).

6.2 Processes

6.2.1 Manual Paper-based Process

For Schedule II Controlled Substance prescriptions within the VA using the manual paper-based process, the procedure is as follows:

- 1. VA Prescriber either hand-writes a prescription before signing it or prints off a prescription form and hand-signs it before giving it to the patient.
- 2. Patient or courier then hand-delivers the paper prescription form to the VA pharmacist.
- 3. VA Pharmacist manually enters the script into the VistA Pharmacy package.
- 4. After filling the prescription, the VistA Outpatient Pharmacy package updates CPRS with the record of the new fill.

With this method, CPRS has no way to verify the credentials of the Prescriber when a prescription order is hand written. Additionally, when the hand-written script is illegible, the VA Pharmacist either guesses at what the Prescriber intends, or must call the Prescriber to ascertain what the Prescriber intended on the handwritten script. In either of these cases, the prescription fill is delayed and the VA patient must wait for their medically necessary medication.




Figure 46: DEA ePCS—Manual paper-based process to prescribe Schedule II Controlled Substances

6.2.2 e-Prescribing Process

For Schedule II – V Controlled Substance prescriptions within the VA using the ePrescribing process (i.e., e-Prescribing of Controlled Substances [ePCS] Utility), the procedure is as follows:

- 1. VA Prescriber inserts a common access Personal Identity Verification (PIV) card (i.e., a smart card, which uniquely identifies the Prescriber) into a card reader attached to a computer keyboard.
- 2. VA Prescriber enters the prescription order into the Computerized Patient Record System (CPRS).
- 3. VA Prescriber signs the script electronically.
- 4. CPRS prompts the Prescriber to provide the credentials for the smart card (analogous to an Automated Teller Machine [ATM] card's Personal Identification Number [PIN] code).
- 5. System verifies the PKI credentials.
- 6. System affixes a digital signature to the prescription (digitally signed).
- 7. CPRS sends the script order electronically to the VistA Pharmacy system.
- 8. VA Pharmacist fills the script in VistA Pharmacy.
- 9. VistA Pharmacy automatically sends a record of the prescription fill to CPRS.




Figure 47: DEA ePCS—ePrescribing process to prescribe Schedule II - V Controlled Substances



REF: For information on PIV and prescription validation processes, see the following sections:

- PIV Card Validation—Revocation Server
- Prescription Validation and Verification Process—PKIServer.exe Application

6.3 Configuring the DEA ePCS Utility

There are two steps to configure the DEA ePCS Utility:

- 1. Set the XUEPCS REPORT DEVICE Parameter.
- 2. Add DEA ePCS Utility Users.

6.3.1 Set the XUEPCS REPORT DEVICE Parameter

Set the XUEPCS REPORT DEVICE Parameter to the printer device. You can set this parameter by using either of the following methods:

- General Parameter Tools Menu.
- XPAREDIT Routine.

6.3.1.1 General Parameter Tools Menu

Use the **General Parameter Tools** menu [XPAR MENU TOOLS] located under the CPRS Configuration (IRM) menu [OR PARAM IRM MENU] to update the XUEPCS REPORT DEVICE parameter.

To edit the DEA ePCS Utility parameter, perform the following procedure:

- 1. From the **CPRS Manager Menu** [ORMGR], select the **IR—CPRS Configuration** (**IRM**) option [OR PARAM IRM MENU].
- 1. At the "Select CPRS Configuration (IRM) Option:" prompt, select the **XX—General Parameter Tools** option [XPAR MENU TOOLS].
- 2. At the "Select General Parameter Tools Option:" prompt, select the **EP—Edit Parameter Values** option [XPAR EDIT PARAMETER].
- 3. At the "Select PARAMETER DEFINITION NAME:" prompt, enter **XUEPCS REPORT DEVICE**.
- 4. At the "Select device for ePCS reports: XXXXXXXX//" prompt, enter the printer device appropriate for your system.

Figure 48: DEA ePCS: General Parameter Tools menu [XPAR MENU TOOLS]—Editing DEA ePCS Site Parameter

```
CL
          Clinician Menu ...
   MM
          Nurse Menu ...
          Ward Clerk Menu ...
   WC
          CPRS Configuration (Clin Coord) ...
          CPRS Configuration (IRM) ...
Select CPRS Manager Menu Option: IR <Enter> CPRS Configuration (IRM)
   \Omega
          Order Check Expert System Main Menu ...
          ORMTIME Main Menu ...
   ΤI
   UT
          CPRS Clean-up Utilities ...
          General Parameter Tools ...
          HealtheVet Desktop Configuration ...
   HD
   RD
          Remote Data Order Checking Parameters
Select CPRS Configuration (IRM) Option: GENERAL <Enter> Parameter Tools
   LV
          List Values for a Selected Parameter
   LE
          List Values for a Selected Entity
          List Values for a Selected Package
          List Values for a Selected Template
```

```
EP Edit Parameter Values

ET Edit Parameter Values with Template

EK Edit Parameter Definition Keyword

Select General Parameter Tools Option: EP <Enter> Edit Parameter Values
--- Edit Parameter Values ---

Select PARAMETER DEFINITION NAME: XUEPCS REPORT DEVICE <Enter> ePCS Device
Definition for Reports
---- Setting XUEPCS REPORT DEVICE for System: XXXXXXXX.MED.VA.GOV ----
Select device for ePCS reports: XXXXXXXX// <Printer Device>
```

Enter the printer device appropriate for your site. The system echoes back the device information after your selection.

Select PARAMETER DEFINITION NAME:


6.3.1.2 XPAREDIT Routine

Use the **XPAREDIT** routine to update the XUEPCS REPORT DEVICE parameter.

To edit the DEA ePCS Utility parameter, perform the following procedure:

- 1. From the programmer prompt, enter the following code:
 - D ^XPAREDIT
- 2. At the "Select PARAMETER DEFINITION NAME:" prompt, enter **XUEPCS REPORT DEVICE**.
- 3. At the "Select device for ePCS reports: XXXXXXXX//" prompt, enter the printer or other device appropriate for your system.

Figure 49: DEA ePCS: XPAREDIT Routine—Editing DEA ePCS Site Parameter: Test Account



6.3.2 Add DEA ePCS Utility Users

There are three steps to give a user access to the DEA ePCS Utility:

- 1. Assign the XUEPCSEDIT Security Key.
- 2. Assign the XU EPCS EDIT DATA Option.
- 3. Assign the XUSSPKI UPN SET Option.

6.3.2.1 Assign the XUEPCSEDIT Security Key

To assign the XUEPCSEDIT security key, perform the following procedure:

- 1. From the **Systems Manager Menu** [EVE], select the **Menu Management** menu [XUMAINT].
- 2. At the "Select Menu Management Option:" prompt, select the **Key Management** menu [XUKEYMGMT].
- 3. At the "Select Key Management Option:" prompt, select the **Allocation of Security Keys** option [XUKEYALL].
- 4. At the "Allocate key:" prompt, enter **XUEPCSEDIT** security key.
- 5. At the "Another key:" prompt, press **Enter** to complete your entries.
- 6. At the "Holder of key:" prompt, enter the user's name.
- 7. At the "Another holder:" prompt, enter any additional user names that need access to the DEA ePCS Utility. When complete, press **Enter**.
- 8. At the "You are allocating keys. Do you wish to proceed? YES//" prompt, press **Enter** to accept the **YES** default response.

Figure 50: DEA ePCS: Adding DEA ePCS Utility users by assigning the XUEPCSEDIT security key

```
Select Systems Manager Menu Option: MENU <Enter> Management
         Edit options
         Key Management ...
         Secure Menu Delegation ...
         Restrict Availability of Options
         Option Access By User
         List Options by Parents and Use
         Fix Option File Pointers
         Help Processor ...
   OPED
         Screen-based Option Editor
         Display Menus and Options ...
         Edit a Protocol
         Menu Rebuild Menu ...
         Out-Of-Order Set Management ...
         See if a User Has Access to a Particular Option
          Show Users with a Selected primary Menu
Select Menu Management Option: KEY <Enter> Management
         Allocation of Security Keys
         De-allocation of Security Keys
         Enter/Edit of Security Keys
         All the Keys a User Needs
         Change user's allocated keys to delegated keys
         Delegate keys
         Keys For a Given Menu Tree
         List users holding a certain key
         Remove delegated keys
         Show the keys of a particular user
Select Key Management Option: ALLOC <Enter> ation of Security Keys
Allocate key: XUEPCSEDIT
Another key: <Enter>
Holder of key: XUUSER, ONE <Enter> OX
                                                 TECHNICAL WRITER
Another holder: <Enter>
You've selected the following keys:
XUEPCSEDIT
You've selected the following holders:
XUUSER, ONE
You are allocating keys. Do you wish to proceed? YES// <Enter>
XUEPCSEDIT being assigned to:
    XUUSER, ONE
```

6.3.2.2 Assign the XU EPCS EDIT DATA Option

The XU EPCS EDIT DATA option is the context option the RPC Broker uses for the DEA ePCS Utility when making remote procedure calls.

To assign the XU EPCS EDIT DATA Option for each user, perform the following procedure:

- 1. From the **Systems Manager Menu** [EVE], select the **User Management** menu [XUSER].
- 2. At the "Select User Management Option:" prompt, select the **Edit an Existing User** option [XUSEREDIT].
- 3. At the "Select NEW PERSON NAME:" prompt, enter the user's name.
- 4. In the "Edit an Existing User" main screen, tab down to the "Select SECONDARY MENU OPTIONS:" prompt, enter the **XU EPCS EDIT DATA** option.
- 5. (Optional) In the "SECONDARY MENU OPTIONS" popup screen, tab to "SYNONYM:" prompt and enter a synonym for this context option.
- 6. Tab to the "COMMAND:" prompt, enter **Close**. The "SECONDARY MENU OPTIONS" popup screen closes.
- 7. Tab to the "COMMAND:" prompt, enter **Exit**. The "Edit an Existing User" main screen closes.

Figure 51: DEA ePCS: Assigning the XU EPCS EDIT DATA option—Sample user entries (1 of 2)

```
Select Systems Manager Menu Option: USER <Enter> Management
          Add a New User to the System
          Grant Access by Profile
          Edit an Existing User
          Deactivate a User
          Reactivate a User
          List users
          User Inquiry
          Switch Identities
          File Access Security ...
          Clear Electronic signature code
  OAA
          OAA Trainee Registration Menu ...
          Electronic Signature Block Edit
          Manage User File ...
          Person Class Edit
          Reprint Access agreement letter
Select User Management Option: EDIT <Enter> an Existing User
                                                                   TECHNICAL
Select NEW PERSON NAME: XUUSER <Enter> XUUSER,ONE
                                                       OX
WRITER
                             Edit an Existing User
NAME: XUUSER, ONE
                                                                  Page 1 of 5
                                                        INITIAL: OX
  NAME... XUUSER, ONE
   TITLE: TECHNICAL WRITER
                                                     NICK NAME: ONE
     SSN: 000123456
                                                            DOB:
  DEGREE:
                                                     MAIL CODE:
 DISUSER:
                                                TERMINATION DATE:
 Termination Reason:
           PRIMARY MENU OPTION: EVE
 Select SECONDARY MENU OPTIONS: XU EPCS EDIT DATA
 Tab to this prompt and enter the context option.
Want to edit ACCESS CODE (Y/N):
                                      FILE MANAGER ACCESS CODE: @
Want to edit VERIFY CODE (Y/N):
               Select DIVISION: SAN FRANCISCO
               SERVICE/SECTION: OIFO Field Office
COMMAND:
                                             Press <PF1>H for help
                                                                       Insert
```

Figure 52: DEA ePCS: Assigning the XU EPCS EDIT DATA option—Sample user entries (2 of 2)

Edit an Existing User NAME: XUUSER, ONE Page 1 of 5 NAME... XUUSER,ONE INITIAL: OX TITLE: TECHNICAL WRITER NICK NAME: ONE SSN: 000123456 DOB: DEGREE: MAIL CODE: DISUSER: TERMINATION DATE: Termination Reason: Select . SECONDARY MENU OPTIONS . Want to . Want to . SECONDARY MENU OPTIONS: XU EPCS EDIT DATA SYNONYM: EPCD Refresh Close Enter a command or `^' followed by a caption to jump to a specific field. COMMAND: Close Press <PF1>H for help Edit an Existing User NAME: XUUSER, ONE Page 1 of 5 NAME... XUUSER,ONE
TITLE: TECHNICAL WRITER INITIAL: OX NICK NAME: ONE SSN: 000123456 DOB: DEGREE: MAIL CODE: DISUSER: TERMINATION DATE: Termination Reason: PRIMARY MENU OPTION: EVE Select SECONDARY MENU OPTIONS: Want to edit ACCESS CODE (Y/N): FILE MANAGER ACCESS CODE: @ Want to edit VERIFY CODE (Y/N): Select DIVISION: SAN FRANCISCO SERVICE/SECTION: OIFO Field Office Exit Next Page Refresh Enter a command or '^' followed by a caption to jump to a specific field. Press <PF1>H for help COMMAND: Exit Insert

6.3.2.3 Assign the XUSSPKI UPN SET Option

The XUSSPKI UPN SET option is the context option the RPC Broker uses for the DEA ePCS Utility when making remote procedure calls.

To assign the XUSSPKI UPN SET Option for each user, perform the following procedure:

- 1. From the **Systems Manager Menu** [EVE], select the **User Management** menu [XUSER].
- 2. At the "Select User Management Option:" prompt, select the **Edit an Existing User** option [XUSEREDIT].
- 3. At the "Select NEW PERSON NAME:" prompt, enter the user's name.
- 4. In the "Edit an Existing User" main screen, tab down to the "Select SECONDARY MENU OPTIONS:" prompt, enter the **XUSSPKI UPN SET** option.
- 5. (Optional) In the "SECONDARY MENU OPTIONS" popup screen, tab to "SYNONYM." prompt and enter a synonym for this context option.
- 6. Tab to the "COMMAND:" prompt, enter **Close**. The "SECONDARY MENU OPTIONS" popup screen closes.
- 7. Tab to the "COMMAND:" prompt, enter **Exit**. The "Edit an Existing User" main screen closes.

Figure 53: DEA ePCS: Assigning the XUSSPKI UPN SET option—Sample user entries (1 of 2)

```
Select Systems Manager Menu Option: USER <Enter> Management
          Add a New User to the System
          Grant Access by Profile
          Edit an Existing User
          Deactivate a User
          Reactivate a User
          List users
          User Inquiry
          Switch Identities
          File Access Security ...
          Clear Electronic signature code
  OAA
          OAA Trainee Registration Menu ...
          Electronic Signature Block Edit
          Manage User File ...
          Person Class Edit
          Reprint Access agreement letter
Select User Management Option: EDIT <Enter> an Existing User
Select NEW PERSON NAME: XUUSER <Enter> XUUSER,ONE
                                                        OX
                                                                    TECHNICAL
WRITER
                             Edit an Existing User
NAME: XUUSER, ONE
                                                                  Page 1 of 5
  NAME... XUUSER,ONE
                                                       INITIAL: OX
   TITLE: TECHNICAL WRITER
                                                     NICK NAME: ONE
     SSN: 000123456
                                                           DOB:
  DEGREE:
                                                     MAIL CODE:
 DISUSER:
                                               TERMINATION DATE:
 Termination Reason:
           PRIMARY MENU OPTION: EVE
 Select SECONDARY MENU OPTIONS: XUSSPKI UPN SET
 Tab to this prompt and enter the context option.
                                      FILE MANAGER ACCESS CODE: @
Want to edit ACCESS CODE (Y/N):
Want to edit VERIFY CODE (Y/N):
               Select DIVISION: SAN FRANCISCO
               SERVICE/SECTION: OIFO Field Office
COMMAND:
                                             Press <PF1>H for help
                                                                       Insert
```

Figure 54: DEA ePCS: Assigning the XUSSPKI UPN SET option—Sample user entries (2 of 2)

Edit an Existing User NAME: XUUSER, ONE Page 1 of 5 NAME... XUUSER,ONE INITIAL: OX TITLE: TECHNICAL WRITER NICK NAME: ONE SSN: 000123456 DOB: DEGREE: MAIL CODE: DISUSER: TERMINATION DATE: Termination Reason: Select . SECONDARY MENU OPTIONS . Want to . Want to . SECONDARY MENU OPTIONS: XUSSPKI UPN SET SYNONYM: EPCP Close Refresh Enter a command or `^' followed by a caption to jump to a specific field. COMMAND: Close Press <PF1>H for help Edit an Existing User NAME: XUUSER, ONE Page 1 of 5 NAME... XUUSER, ONE INITIAL: OX TITLE: TECHNICAL WRITER NICK NAME: ONE SSN: 000123456 DOB: DEGREE: MAIL CODE: DISUSER: TERMINATION DATE: Termination Reason: PRIMARY MENU OPTION: EVE Select SECONDARY MENU OPTIONS: Want to edit ACCESS CODE (Y/N): FILE MANAGER ACCESS CODE: @ Want to edit VERIFY CODE (Y/N): Select DIVISION: SAN FRANCISCO SERVICE/SECTION: OIFO Field Office Exit Next Page Refresh Enter a command or '^' followed by a caption to jump to a specific field. Press <PF1>H for help COMMAND: Exit Insert

6.4 Using the DEA ePCS Utility

The DEA ePCS Utility consists of the following standalone menu and options, which are described in detail in the sections that follow:

- <u>DEA ePCS Utility Functions Main Menu</u> [XU EPCS UTILITY FUNCTIONS]
- Edit Facility DEA# and Expiration Date Option [XU EPCS EDIT DEA# AND XDATE]
- <u>ePCS Edit Prescriber Data Option</u> [XU EPCS EDIT DATA]
- ePCS Set SAN from PIV Card Option [XUSSPKI UPN SET]

6.4.1 DEA ePCS Utility Functions Main Menu

Released with Kernel patch XU*8.0*580, the DEA ePCS Utility Functions main menu [XU EPCS UTILITY FUNCTIONS] is a standalone menu that is *not* linked to any other Kernel menus. It includes the following options:

Figure 55: DEA ePCS: DEA ePCS Utility Functions main menu [XU EPCS UTILITY FUNCTIONS]

```
Select Systems Manager Menu Option:
         Print DEA Expiration Date Null
         Print DISUSER DEA Expiration Date Null
         Print DEA Expiration Date Expires 30 days
         Print DISUSER DEA Expiration Date Expires 30 days
         Print Prescribers with Privileges
         Print DISUSER Prescribers with Privileges
         Print PSDRPH Key Holders
        Print Setting Parameters Privileges
        Print Audits for Prescriber Editing
  10 Task Changes to DEA Prescribing Privileges Report
  11
       Task Allocation Audit of PSDRPH Key Report
         Allocate/De-Allocate of PSDRPH Key
  12
        Edit Facility DEA# and Expiration Date
  13
Select ePCS DEA Utility Functions Option:
```

Table 8: DEA ePCS Utility—Main Menu Options

Option Name	Option Menu Text	Description
XU EPCS UTILITY FUNCTIONS	ePCS DEA Utility Functions	This is the main menu for the DEA ePCS Utility. It includes the following options: XU EPCS EXP DATE XU EPCS DISUSER EXP DATE XU EPCS XDATE EXPIRES XU EPCS DISUSER XDATE EXPIRES XU EPCS PRIVS XU EPCS DISUSER PRIVS XU EPCS PSDRPH XU EPCS SET PARMS XU EPCS PRINT EDIT AUDIT XU EPCS PSDRPH AUDIT XU EPCS PSDRPH AUDIT XU EPCS PSDRPH KEY XU EPCS EDIT DEA# AND XDATE
XU EPCS EXP DATE (See Section <u>6.4.2</u> .)	Print DEA Expiration Date Null	This option prints all active users with an unpopulated DEA# and DEA EXPIRATION DATE. This option prints the following data: NAME DEA# DEA EXPIRATION DATE
XU EPCS DISUSER EXP DATE (See Section <u>6.4.3.</u>)	Print DISUSER DEA Expiration Date Null	This option prints all DISUSERed users with an unpopulated DEA# and DEA EXPIRATION DATE. This option prints the following data: NAME DEA# TERMINATION DATE DEA EXPIRATION DATE
XU EPCS XDATE EXPIRES (See Section <u>6.4.4</u> .)	Print DEA Expiration Date Expires 30 days	This option prints all active users with DEA # and where the DEA EXPIRATION DATE expires within 30 days. This option prints the following data: NAME DEA# DEA EXPIRATION DATE
XU EPCS DISUSER XDATE EXPIRES (See Section <u>6.4.5</u> .)	Print DISUSER DEA Expiration Date Expires 30 days	This option prints all DISUSERed users with DEA # and where the DEA EXPIRATION DATE expires within 30 days. This option prints the following data: NAME

Option Name	Option Menu Text	Description
		DEA#
		DEA EXPIRATION DATE
XU EPCS PRIVS (See Section <u>6.4.6</u> .)	Print Prescribers with Privileges	This option prints all active users who have privileges to any of the SCHEDULEs II through V and who have a DEA# or VA#. This option prints the following data:
		NAME
		• DUZ
		DEA#
		• VA#
		SCHEDULESs
XU EPCS DISUSER PRIVS (See Section <u>6.4.7</u> .)	Print DISUSER Prescribers with Privileges	This option prints all DISUSERed users who have privileges to any of the SCHEDULEs II through V and who have a DEA# or VA#. This option prints the following data:
		• NAME
		• DUZ
		• DEA#
		TERMINATION DATE
		• VA#
		SCHEDULESs
XU EPCS PSDRPH (See Section <u>6.4.8</u> .)	Print PSDRPH Key Holders	This option prints all active users holding the PSDRPH security key. This report sorts by Division, and within DIVISION, it sorts by NAME. This option prints the following data:
		NAME
		• DUZ
		GIVEN BY (Person Who Assigned Key)
		DATE GIVEN (Date Assigned)
XU EPCS SET PARMS (See Section <u>6.4.9</u> .)	Print Setting Parameters Privileges	This option prints all active users holding the XUEPCSEDIT security key. This option identifies individuals responsible for setting the parameters.
XU EPCS PRINT EDIT AUDIT (See Section <u>6.4.10</u> .)	Print Audits for Prescriber Editing	This option prints information related to the editing of prescriber information.
XU EPCS LOGICAL ACCESS (See Section <u>6.4.11</u> .)	Task Changes to DEA Prescribing Privileges Report	This tasked option prints the setting or change to DEA prescribing privileges related to issuance of a controlled substance prescription. This option only prints data from the
		previous day and with data that has been modified. The data is retrieved from the XUEPCS DATA file (#8991.6).

Option Name	Option Menu Text	Description
		This option should be scheduled to run on a daily basis.
XU EPCS PSDRPH AUDIT	Task Allocation Audit of PSDRPH Key Report	This tasked option prints the allocation of the PSDRPH security key.
(See Section <u>6.4.12</u> .)		This option only prints data from the previous day and with data that has been modified. The report prints data for the archive XUEPCS PSDRPH AUDIT file (#8991.7). This option should be scheduled to run on a daily basis.
XU EPCS PSDRPH KEY (See Section <u>6.4.13</u> .)	Allocate/De-Allocate of PSDRPH Key	This option allocates or de-allocates the PSDRPH security key.
XU EPCS EDIT DEA# AND XDATE (See Section <u>6.4.14</u> .)	Edit Facility DEA# and Expiration Date	This option edits the FACILITY DEA NUMBER (#52) and FACILITY DEA EXPIRATION DATE (#52.1) fields in the INSTITUTION file (#4).

6.4.2 Print DEA Expiration Date Null Option

Released with Kernel patch XU*8.0*580, the **Print DEA Expiration Date Null** option [XU EPCS EXP DATE] prints all active users from the NEW PERSON file (#200) with the following field values:

- DEA# field (#53.2)—Null (unpopulated).
- DEA EXPIRATION DATE (#747.44)—Not Null (populated).

- NAME (#.01)
- DEA# (#53.2)
- DEA EXPIRATION DATE (#747.44)

Figure 56: DEA ePCS: Print DEA Expiration Date Null option—Sample user entries and report

```
Select Systems Manager Menu Option: EPCS <Enter> ePCS DEA Utility Functions
         Print DEA Expiration Date Null
         Print DISUSER DEA Expiration Date Null
         Print DEA Expiration Date Expires 30 days
        Print DISUSER DEA Expiration Date Expires 30 days
         Print Prescribers with Privileges
         Print DISUSER Prescribers with Privileges
        Print PSDRPH Key Holders
        Print Setting Parameters Privileges
  8
      Print Audits for Prescriber Editing
  10 Task Changes to DEA Prescribing Privileges Report
       Task Allocation Audit of PSDRPH Key Report
  12 Allocate/De-Allocate of PSDRPH Key
  13 Edit Facility DEA# and Expiration Date
Select ePCS DEA Utility Functions Option: 1 <Enter> Print DEA Expiration Date Null
START WITH NAME: FIRST// <Enter>
DEVICE: <Enter> HOME (CRT)
                             Right Margin: 80// <Enter>
NULL 'DEA EXPIRATION DATE'
                                           APR 15,2013 16:53 PAGE 1
                                                DEA
                                                EXPIRATION
                                    DEA#
                                                DATE
______
                                    AK1662673
XUUSER, EIGHT
XUUSER, ELEVEN
                                    MT0300777
XUUSER, FIVE
                                    BH2942628
XUUSER, FOUR
XUUSER, FOURTEEN
                                    AG5333745
XUUSER, NINE
                                    BB1770773
XUUSER, ONE
                                    SF0963226
XUUSER, SEVEN
                                    AP8348458
XUUSER, SIX
                                    AM7446001
XUUSER, TEN
                                    BD9270911
XUUSER, THIRTEEN
                                    FC2158548
XUUSER, THREE
                                    FS2138572
XUUSER, TWELVE
                                    AR3287946
XUUSER, TWO
                                    BG4740850
```

6.4.3 Print DISUSER DEA Expiration Date Null Option

Released with Kernel patch XU*8.0*580, the **Print DISUSER DEA Expiration Date Null** option [XU EPCS DISUSER EXP DATE] prints all DISUSERed users from the NEW PERSON file (#200) with the following field values:

- DEA# (#53.2)—Null (*unpopulated*).
- DEA EXPIRATION DATE (#747.44)—Not Null (populated).

- NAME (#.01)
- DEA# (#53.2)
- TERMINATION DATE (#9.2)
- DEA EXPIRATION DATE (#747.44)

Figure 57: DEA ePCS: Print DISUSER DEA Expiration Date Null option—Sample user entries and report

1	Print DEA Expiration Date Null				
2	Print DISUSER DEA Expiration Date Null				
	Print DEA Expiration Date Expires 30 days				
	Print DISUSER DEA Expiration Date Expires 30 days				
	Print Prescribers with Privileges				
6	Print DISUSER Prescribers with Privileges				
	Print PSDRPH Key Holders				
	Print Setting Parameters Privileges				
	Print Audits for Prescriber Editing				
	Task Changes to DEA Prescribing Privileges Report				
	11 Task Allocation Audit of PSDRPH Key Report				
13	Edit Facility DEA# and Expiration	Date			
DEVICE: <enter> HOME (CRT) Right Margin: 80// <enter> DISUSER NULL 'DEA EXPIRATION DATE' APR 15,2013 16:55 PAGE 1 TERMINATION</enter></enter>					
-	NAME	DEA#			
AUG 16,201	0 XUUSER, SEVENTY	BC6840614			
MAR 31,201	0 XUUSER, EIGHTY	AC7045796			
MAR 18,201	0 XUUSER, NINETY	AL6010968			
FEB 1,201	0 XUUSER, ONE HUNDRED	AM8823191			
	0 XUUSER, FORTY	AJ1103910			
JUN 11,200		BM2745315			
MAY 4,200		AP9587570			
MAY 4,200		BB2243854			
MAY 4,200		AK4751815			
MAY 4,200		BN7729847			
APR 20,200	·	AD6477865			
APR 20,200		BM4942517			
APR 20,200		AA1662673			
•		FK0178132			
AUG 30,200	8 XUUSER, FIVE HUNDRED	ВЈ9947081			

6.4.4 Print DEA Expiration Date Expires 30 days Option

Released with Kernel patch XU*8.0*580, the **Print DEA Expiration Date Expires 30 days** option [XU EPCS XDATE EXPIRES] prints all active users from the NEW PERSON file (#200) with the following field values:

- DEA# field (#53.2) —Not Null (populated).
- DEA EXPIRATION DATE field (#747.44)—Date expires within 30 days.

- NAME (#.01)
- DEA# (#53.2)
- DEA EXPIRATION DATE (#747.44)

Figure 58: DEA ePCS: Print DEA Expiration Date Expires 30 days option—Sample user entries and report

```
Print DEA Expiration Date Null
         Print DISUSER DEA Expiration Date Null
         Print DEA Expiration Date Expires 30 days
     Print DEA Expiration Date Expires 30 days
        Print Prescribers with Privileges
        Print DISUSER Prescribers with Privileges
        Print PSDRPH Key Holders
        Print Setting Parameters Privileges
       Print Audits for Prescriber Editing
  10 Task Changes to DEA Prescribing Privileges Report
       Task Allocation Audit of PSDRPH Key Report
  11
  12 Allocate/De-Allocate of PSDRPH Key
        Edit Facility DEA# and Expiration Date
Select ePCS DEA Utility Functions Option: 3 <Enter> Print DEA Expiration Date
Expires 30 days
START WITH NAME: FIRST// <Enter>
DEVICE: <Enter> HOME (CRT) Right Margin: 80// <Enter>
EXPIRATION DATE EXPIRES IN 30 DAYS APR 15,2013 16:59 PAGE 1
                                                DEA
                                                EXPIRATION
NAME
                                    DEA#
                                                DATE
         *** NO RECORDS TO PRINT ***
```

6.4.5 Print DISUSER DEA Expiration Date Expires 30 days Option

Released with Kernel patch XU*8.0*580, the **Print DISUSER DEA Expiration Date Expires 30 days** option [XU EPCS DISUSER XDATE EXPIRES] prints all DISUSERed users from the NEW PERSON file (#200) with the following field values:

- DEA# field (#53.2) —Not Null (populated).
- DEA EXPIRATION DATE field (#747.44)—Date expires within 30 days.

- NAME (#.01)
- DEA# (#53.2)
- DEA EXPIRATION DATE (#747.44)

Figure 59: DEA ePCS: Print DISUSER DEA Expiration Date Expires 30 days Option—Sample user entries and report

```
Print DEA Expiration Date Null
         Print DISUSER DEA Expiration Date Null
         Print DEA Expiration Date Expires 30 days
         Print DISUSER DEA Expiration Date Expires 30 days
       Print Prescribers with Privileges
        Print DISUSER Prescribers with Privileges
        Print PSDRPH Key Holders
        Print Setting Parameters Privileges
        Print Audits for Prescriber Editing
        Task Changes to DEA Prescribing Privileges Report
  11
        Task Allocation Audit of PSDRPH Key Report
  12
       Allocate/De-Allocate of PSDRPH Key
        Edit Facility DEA# and Expiration Date
Select ePCS DEA Utility Functions Option: 4 <Enter> Print DISUSER DEA Expiration
Date Expires 30 days
DEVICE: <Enter> HOME (CRT) Right Margin: 80// <Enter>
DISUSER EXPIRATION DATE EXPIRES IN 30 DAYS APR 15,2013 17:08
                                                                   PAGE 1
                                                          DEA
TERMINATION
                                                          EXPIRATION
DATE
            NAME
                                              DEA#
                                                          DATE
          *** NO RECORDS TO PRINT ***
```

6.4.6 Print Prescribers with Privileges Option

Released with Kernel patch XU*8.0*580, the **Print Prescribers with Privileges** option [XU EPCS PRIVS] prints all active users from the NEW PERSON file (#200) who have privileges to any of the SCHEDULEs II through V and who have a DEA# or VA#.

- NAME (#.01)
- DUZ—Internal Entry Number (IEN) for the user in the NEW PERSON file (#200)
- DEA# (#53.2)
- VA# (#53.3)
- SCHEDULEs:
 - o SCHEDULE II NARCOTIC (#55.1)
 - o SCHEDULE II NON-NARCOTIC (#55.2)
 - o SCHEDULE III NARCOTIC (#55.3)
 - o SCHEDULE III NON-NARCOTIC (#55.4)
 - o SCHEDULE IV (#55.5)
 - o SCHEDULE V (#55.6)

Figure 60: DEA ePCS: Print Prescribers with Privileges option—Sample user entries and report

```
Print DEA Expiration Date Null
         Print DISUSER DEA Expiration Date Null
         Print DEA Expiration Date Expires 30 days
        Print DISUSER DEA Expiration Date Expires 30 days
      Print Prescribers with Privileges
Print DISUSER Prescribers with Privileges
   6
         Print PSDRPH Key Holders
   8
         Print Setting Parameters Privileges
   9
         Print Audits for Prescriber Editing
  10 Task Changes to DEA Prescribing Privileges Report
11 Task Allocation Audit of PSDRPH Key Report
   12 Allocate/De-Allocate of PSDRPH Key
        Edit Facility DEA# and Expiration Date
Select ePCS DEA Utility Functions Option: 5 <Enter> Print Prescribers with
Privileges
DEVICE: <Enter> HOME (CRT) Right Margin: 80// <Enter>
                              DUZ
PRESCRIBERS WITH PRIVILEGES
                                             APR 15,2013 17:13 PAGE 1
NAME
                                            DEA# VA#
       DIVISION: ALBANY, NY VAMC
                      520736424 AA1234563
XUUSER, ONE
        SCHEDULE II:
        SCHEDULE II NON:
        SCHEDULE III:
        SCHEDULE III NON: Yes
        SCHEDULE IV: Yes
        SCHEDULE V:
       DIVISION: CHEYENNE VAMC
XUUSER, TWO
                      520629114
                                                AV4538419
        SCHEDULE II:
        SCHEDULE II NON:
        SCHEDULE III:
        SCHEDULE III NON:
        SCHEDULE IV:
        SCHEDULE V:
```

6.4.7 Print DISUSER Prescribers with Privileges Option

Released with Kernel patch XU*8.0*580, the **Print DISUSER Prescribers with Privileges** option [XU EPCS DISUSER PRIVS] prints all DISUSERed users who have privileges to any of the SCHEDULEs II through V and who have a DEA# or VA#.

- NAME (#.01)
- DUZ—Internal Entry Number (IEN) for the user in the NEW PERSON file (#200)
- DEA# (#53.2)
- TERMINATION DATE (#9.2)
- VA# (#53.3) (DIVISION)
- SCHEDULEs:
 - o SCHEDULE II NARCOTIC (#55.1)
 - o SCHEDULE II NON-NARCOTIC (#55.2)
 - o SCHEDULE III NARCOTIC (#55.3)
 - o SCHEDULE III NON-NARCOTIC (#55.4)
 - o SCHEDULE IV (#55.5)
 - o SCHEDULE V (#55.6)

Figure 61: DEA ePCS: Print DISUSER Prescribers with Privileges option—Sample user entries and report

```
Print DEA Expiration Date Null
         Print DISUSER DEA Expiration Date Null
         Print DEA Expiration Date Expires 30 days
        Print DISUSER DEA Expiration Date Expires 30 days
        Print Prescribers with Privileges
        Print DISUSER Prescribers with Privileges
  7 Print PSDRPH Key Holders
       Print Setting Parameters Privileges
       Print Audits for Prescriber Editing
  10 Task Changes to DEA Prescribing Privileges Report
  11 Task Allocation Audit of PSDRPH Key Report
       Allocate/De-Allocate of PSDRPH Key
  12
        Edit Facility DEA# and Expiration Date
Select ePCS DEA Utility Functions Option: 6 <Enter> Print DISUSER Prescribers with
Privileges
DEVICE: <Enter> HOME (CRT)
                             Right Margin: 80// <Enter>
DISUSER PRESCRIBERS WITH PRIVILEGES APR 15,2013 17:16
                                                              PAGE 1
                                                       TERMINATION
NAME
                                          DEA#
                                                      DATE
       DIVISION: EMPTY
XUUSER, FIFTEEN
                            2890 AP9587570 MAY 4,2009
        SCHEDULE II:
        SCHEDULE II NON:
        SCHEDULE III:
        SCHEDULE III NON:
        SCHEDULE IV:
```

```
SCHEDULE V:
XUUSER, SIXTEEN
                            520629429 BB2243854 MAY 4,2009
        SCHEDULE II:
        SCHEDULE II NON:
        SCHEDULE III:
        SCHEDULE III NON:
        SCHEDULE IV:
        SCHEDULE V:
       DIVISION: CHEYENNE VAMC
                            1000203
XUUSER, FIFTY
                         Yes
        SCHEDULE II:
        SCHEDULE II NON:
        SCHEDULE III:
                         Yes
        SCHEDULE III NON:
        SCHEDULE IV:
        SCHEDULE V:
       DIVISION: DENVER-RO
XUUSER, SIXTY
                             520628843 BT1199125 FEB 2,2007
        SCHEDULE II:
        SCHEDULE II NON:
        SCHEDULE III:
        SCHEDULE III NON:
        SCHEDULE IV:
        SCHEDULE V:
XUUSER, SEVENTY
                            520628775 AH9494852 FEB 12,1999
        SCHEDULE II:
        SCHEDULE II NON:
        SCHEDULE III:
        SCHEDULE III NON:
        SCHEDULE IV:
        SCHEDULE V:
                           520628129 BA4578893 OCT 12,1990
XUUSER, EIGHTY
        SCHEDULE II: Yes
        SCHEDULE II NON: Yes
        SCHEDULE III: Yes
        SCHEDULE III NON: Yes
        SCHEDULE IV: Yes
        SCHEDULE V:
                         Yes
```

6.4.8 Print PSDRPH Key Holders Option

Released with Kernel patch XU*8.0*580, the **Print PSDRPH Key Holders** option [XU EPCS PSDRPH] prints all active users holding the PSDRPH security key. This report sorts by Division, and within Division, it sorts by Name.

- NAME (#.01)
- DUZ—Internal Entry Number (IEN) for the user in the NEW PERSON file (#200)
- GIVEN BY (#1) subfield of the KEYS Multiple (#51): Person who assigned the PSDRPH security key
- DATE GIVEN (#2) subfield of the KEYS Multiple (#51): Date assigned

Figure 62: DEA ePCS: Print PSDRPH Key Holders option—Sample user entries and report

```
Print DEA Expiration Date Null
             Print DISUSER DEA Expiration Date Null
            Print DEA Expiration Date Expires 30 days
           Print DISUSER DEA Expiration Date Expires 30 days
           Print Prescribers with Privileges
           Print DISUSER Prescribers with Privileges
       Print PSDRPH Key Holders
Print Setting Parameters
    8
             Print Setting Parameters Privileges
        Print Audits for Prescriber Editing
Task Changes to DEA Prescribing Privileges Report
Task Allocation Audit of PSDRPH Key Report
Allocate/De-Allocate of PSDRPH Key
    10
    11
    12
           Edit Facility DEA# and Expiration Date
Select ePCS DEA Utility Functions Option: 7 <Enter> Print PSDRPH Key Holders
DEVICE: <Enter> HOME (CRT) Right Margin: 80// <Enter>
 PSDRPH KEY HOLDERS
                                                           APR 15,2013 17:26 PAGE 1
NAME
                                  DUZ
                                                   GIVEN BY DATE GIVEN
             DIVISION: EMPTY
XUUSER,SIX 520736417 XUUSER,SIX SEP 20,2012
XUUSER,ONE 520736423 XUUSER,ONE MAR 27,2012
XUUSER,THREE 520736427 XUUSER,THREE MAR 4,2013
XUUSER,FIVE 520736422 XUUSER,FIVE JAN 23,2013
XUUSER,SEVEN 520736428 XUUSER,SEVEN MAR 2,2012
XUUSER,EIGHT 520736430 XUUSER,EIGHT MAR 30,2012
      DIVISION: ALBANY, NY VAMC
                     520736424
XUUSER NINE
                                                 XUUSER, NINE
                                                                                  JAN 29,2013
```

6.4.9 Print Setting Parameters Privileges Option

Released with Kernel patch XU*8.0*580, the **Print Setting Parameters Privileges** option [XU EPCS SET PARMS] prints all active users holding the XUEPCSEDIT security key.

This option identifies individuals responsible for setting the parameters. It prints the following data from the NEW PERSON file (#200):

- NAME (#.01)
- DUZ—Internal Entry Number (IEN) for the user in the NEW PERSON file (#200)
- GIVEN BY (#1) subfield of the KEYS Multiple (#51): Person who assigned the PSDRPH security key
- DATE GIVEN (#2) subfield of the KEYS Multiple (#51): Date assigned

Figure 63: DEA ePCS: Print Setting Parameters Privileges option—Sample user entries and report

```
Print DEA Expiration Date Null
               Print DISUSER DEA Expiration Date Null
              Print DEA Expiration Date Expires 30 days
             Print DISUSER DEA Expiration Date Expires 30 days
             Print Prescribers with Privileges
             Print DISUSER Prescribers with Privileges
    7 Print PSDRPH Key Holders
8 Print Setting Parameters Privileges
9 Print Audits for Prescriber Editing
10 Task Changes to DEA Prescribing Privileges Report
11 Task Allocation Audit of PSDRPH Key Report
             Allocate/De-Allocate of PSDRPH Key
     12
             Edit Facility DEA# and Expiration Date
Select ePCS DEA Utility Functions Option: 8 <Enter> Print Setting Parameters
Privileges
DEVICE: <Enter> HOME (CRT) Right Margin: 80// <Enter>
 USERS RESPONSIBLE FOR SETTING PARAMETERS APR 15,2013 17:28 PAGE 1
                                   DUZ GIVEN BY DATE GIVEN

      XUUSER,ONE
      520736423
      XUUSER,ONE
      AUG 22,2012

      XUUSER,TWO
      520736419
      XUUSER,TWO
      APR 3,2012

      XUUSER,THREE
      520736427
      XUUSER,THREE
      JUL 16,2012

      XUUSER,FOUR
      520736431
      XUUSER,FOUR
      MAR 19,2012

      XUUSER,FIVE
      520736422
      XUUSER,FIVE
      JUL 17,2012
```

6.4.10 Print Audits for Prescriber Editing Option

Released with Kernel patch XU*8.0*580, the **Print Audits for Prescriber Editing** option [XU EPCS PRINT EDIT AUDIT] prints information related to the editing of prescriber information.

The data for this report is retrieved from the XUEPCS DATA file (#8991.6). It prints the following data:

- DATE/TIME EDITED (#.06)
- NAME (#.01)—This is the name of user edited.
- EDITED BY (#.02)—This is the name of user who edited the data.
- FIELD EDITED (#.03)
- ORIGINAL DATA (#.04)
- EDITED DATA (#.05)

You can sort the data by any of the following data:

- Edited By then Date/Time
- Edited By then User Edited
- Date/Time then Edited By
- Date/Time then User Edited
- User Edited then Edited By
- User Edited then Date

Figure 64: DEA ePCS: Print Audits for Prescriber Editing option: Sort by *Edited By then*Date/time—Sample user entries and report

```
Print DEA Expiration Date Null
          Print DISUSER DEA Expiration Date Null
         Print DEA Expiration Date Expires 30 days
         Print DISUSER DEA Expiration Date Expires 30 days
         Print Prescribers with Privileges
         Print DISUSER Prescribers with Privileges
         Print PSDRPH Key Holders
   8
        Print Setting Parameters Privileges
         Print Audits for Prescriber Editing
   Print Audits for Prescriber Editing
Task Changes to DEA Prescribing Privileges Report
         Task Allocation Audit of PSDRPH Key Report
   11
   12
         Allocate/De-Allocate of PSDRPH Key
         Edit Facility DEA# and Expiration Date
Select ePCS DEA Utility Functions Option: 9 < Enter> Print Audits for Prescriber
Editing
     Select one of the following:
                    Sort by Edited By then Date/time
                    Sort by Edited By then User Edited
          3
                    Sort by Date/time then Edited By
                    Sort by Date/time then User Edited
                    Sort by User Edited then Edited By
                    Sort by User Edited then Date
SORT BY: 1 <Enter> Sort by Edited By then Date/time
START WITH EDITED BY: FIRST// <Enter>
 START WITH DATE/TIME EDITED: FIRST// <Enter>
    START WITH NAME: FIRST// <Enter>
DEVICE: <Enter> HOME (CRT)
                              Right Margin: 80// <Enter>
...HMMM, I'M WORKING AS FAST AS I CAN...
XUEPCS DATA LIST
                                               APR 15,2013 17:33 PAGE 1
DATE/TIME EDITED NAME
 EDITED BY
                                       FIELD EDITED
  ORIGINAL DATA
 EDITED DATA
MAR 28,2012 11:35 XUUSER,TWO
 XUUSER, ONE
                                       SCHEDULE II NARCOTIC
MAR 28,2012 11:41 XUUSER, THREE
 XUUSER, ONE
                                       SCHEDULE II NARCOTIC
  0
MAR 28,2012 14:15 XUUSER, FOUR
 XUUSER, ONE
                                       DEA#
  OX4215895
```

Figure 65: DEA ePCS: Print Audits for Prescriber Editing option: Sort by *User Edited then Edited*By—Sample user entries and report

```
SORT BY: 5 < Enter> Sort by User Edited then Edited By
START WITH NAME: FIRST// <Enter>
  START WITH EDITED BY: FIRST// <Enter>
    START WITH DATE/TIME EDITED: FIRST// <Enter>
DEVICE: <Enter> HOME (CRT) Right Margin: 80// <Enter>
...HMMM, HOLD ON...
                                              APR 15,2013 17:36 PAGE 1
XUEPCS DATA LIST
                 NAME
DATE/TIME EDITED
                                      FIELD EDITED
 EDITED BY
  ORIGINAL DATA
  EDITED DATA
MAR 28,2012 11:35 XUUSER,TWO
 XUUSER, ONE
                                      SCHEDULE II NARCOTIC
  Λ
MAR 28,2012 11:41 XUUSER, THREE
  XUUSER, ONE
                                      SCHEDULE II NARCOTIC
MAR 28,2012 14:15 XUUSER, FOUR
  XUUSER, ONE
                                      DEA#
  OX4215895
```

6.4.11 Task Changes to DEA Prescribing Privileges Report Option



CAUTION: Verify that the XUEPCS REPORT DEVICE parameter has been set before using this option.

To set the parameter, see the "Set the XUEPCS REPORT DEVICE Parameter" section.

Released with Kernel patch XU*8.0*580, the **Task Changes to DEA Prescribing Privileges Report** option [XU EPCS LOGICAL ACCESS] prints the setting or change to DEA prescribing privileges related to issuance of a controlled substance prescription.

The option only prints data from the previous day and with data that has been modified. The data is retrieved from the XUEPCS DATA file (#8991.6).

This option should be scheduled to run on a daily basis via TaskMan. The option only prints data from the *previous* day and with *data that has been modified*. The data is retrieved from the XUEPCS DATA file (#8991.6).



NOTE: No data is displayed to the screen; the data is printed to the device indicated by the XUEPCS REPORT DEVICE parameter.

To schedule the option to run daily using TaskMan, perform the following procedure:

- 1. From the **Systems Manager Menu** [EVE], select the **Taskman Management** option [XUTM MGR].
- 2. At the "Select Taskman Management Option:" prompt, select the Schedule/Unschedule Options option [XUTM SCHEDULE].
- 3. At the "Select OPTION to schedule or reschedule:" prompt, enter **XU EPCS LOGICAL ACCESS**.
- 4. At the "...OK? Yes//" prompt, enter YES. A ScreenMan dialogue is displayed.
- 5. Tab down to the following fields and enter the values shown:
 - QUEUED TO RUN AT WHAT TIME: **T+1@001** (which means start running it tomorrow at 12:01)
 - RESCHEDULING FREQUENCY: **1D** (which means run it daily)
- 6. At the "COMMAND:" prompt, enter **Save**.
- 7. At the "COMMAND:" prompt, enter **Exit**.

Figure 66: DEA ePCS: Task Changes to DEA Prescribing Privileges Report option: TaskMan schedule setup—Sample user entries

```
Device Management ...
          Programmer Options ...
          Operations Management ...
          Spool Management ...
          Information Security Officer Menu ...
          Taskman Management ...
          User Management ...
   FM1
          VA FileMan ...
   JL
          Consolidated Practitioner's Menu ...
          Application Utilities ...
          Capacity Planning ...
          Manage Mailman ...
          Menu Management ...
          Verifier Tools Menu ...
Select Systems Manager Menu Option: TASK <Enter> man Management
          Schedule/Unschedule Options
          One-time Option Queue
          Taskman Management Utilities ...
          List Tasks
          Dequeue Tasks
          Requeue Tasks
          Delete Tasks
          Print Options that are Scheduled to run
   TU
          TASK UTILITY
   VPD
          Cleanup Task List
          Print Options Recommended for Queueing
Select Taskman Management Option: SCHED <Enter> ule/Unschedule Options
Select OPTION to schedule or reschedule: XU EPCS LOGICAL ACCESS <Enter>
                                                                             Task
Changes to DEA Prescribing Privileges Report
         ...OK? Yes// <Enter> (Yes)
      (R)
                          Edit Option Schedule
    Option Name: XU EPCS LOGICAL ACCESS
    Menu Text: Task Changes to DEA Prescribing
                                                              TASK ID:
 Tab to the fields indicated, and enter the values shown.
  QUEUED TO RUN AT WHAT TIME: T+1@001
DEVICE FOR QUEUED JOB OUTPUT:
 QUEUED TO RUN ON VOLUME SET:
      RESCHEDULING FREQUENCY: 1D
             TASK PARAMETERS:
            SPECIAL QUEUEING:
Exit
                                Refresh
         Save
                  Next Page
```

```
Enter a command or '^' followed by a caption to jump to a specific field.

COMMAND: SAVE Press <PF1>H for help Insert

Exit Save Next Page Refresh

Enter a command or '^' followed by a caption to jump to a specific field.

COMMAND: EXIT Press <PF1>H for help Insert

Select OPTION to schedule or reschedule:
```

Figure 67: DEA ePCS: Task Changes to DEA Prescribing Privileges Report option—Sample user entries (no report displays)

```
Print DEA Expiration Date Null
   1
          Print DISUSER DEA Expiration Date Null
   2
  3
         Print DEA Expiration Date Expires 30 days
         Print DISUSER DEA Expiration Date Expires 30 days
         Print Prescribers with Privileges
         Print DISUSER Prescribers with Privileges
          Print PSDRPH Key Holders
         Print Setting Parameters Privileges
         Print Audits for Prescriber Editing
  10
          Task Changes to DEA Prescribing Privileges Report
  11
         Task Allocation Audit of PSDRPH Key Report
         Allocate/De-Allocate of PSDRPH Key
  12
  13
         Edit Facility DEA# and Expiration Date
Select ePCS DEA Utility Functions Option: 10 <Enter> Task Changes to DEA
Prescribing Privileges Report
 No data is displayed to the screen; the data is printed to the device
 indicated by the XUEPCS REPORT DEVICE parameter.
```

6.4.12 Task Allocation Audit of PSDRPH Key Report Option



CAUTION: Verify that the XUEPCS REPORT DEVICE parameter has been set before using this option.

To set the parameter, see the "Set the XUEPCS REPORT DEVICE Parameter" section.

Released with Kernel patch XU*8.0*580, the **Task Allocation Audit of PSDRPH Key Report** option [XU EPCS PSDRPH AUDIT] prints the allocation of the PSDRPH security key audit report to a device previously selected during setup (i.e., XUEPCS REPORT DEVICE parameter).

This option should be scheduled to run on a daily basis via TaskMan. The option only prints data from the *previous* day and with *data that has been modified*. The data is retrieved from the XUEPCS PSDRPH AUDIT file (#8991.7).



NOTE: No data is displayed to the screen; the data is printed to the device indicated by the XUEPCS REPORT DEVICE parameter.

To schedule the option to run daily using TaskMan, perform the following procedure:

- 1. From the **Systems Manager Menu** [EVE], select the **Taskman Management** option [XUTM MGR].
- 2. At the "Select Taskman Management Option:" prompt, select the Schedule/Unschedule Options option [XUTM SCHEDULE].
- 3. At the "Select OPTION to schedule or reschedule:" prompt, enter XU EPCS PSDRPH AUDIT.
- 4. At the "...OK? Yes//" prompt, enter YES. A ScreenMan dialogue is displayed.
- 5. Tab down to the following fields and enter the values shown:
 - QUEUED TO RUN AT WHAT TIME: **T+1@001** (which means start running it tomorrow at 12:01)
 - RESCHEDULING FREQUENCY: **1D** (which means run it daily)
- 6. At the "COMMAND:" prompt, enter **Save**.
- 7. At the "COMMAND:" prompt, enter **Exit**.

Figure 68: DEA ePCS: Task Allocation Audit of PSDRPH Key Report option: TaskMan schedule setup—Sample user entries

```
Device Management ...
          Programmer Options ...
          Operations Management ...
          Spool Management ...
          Information Security Officer Menu ...
          Taskman Management ...
          User Management ...
   FM1
          VA FileMan ...
   JL
          Consolidated Practitioner's Menu ...
          Application Utilities ...
          Capacity Planning ...
          Manage Mailman ...
          Menu Management ...
          Verifier Tools Menu ...
Select Systems Manager Menu Option: TASK <Enter> man Management
          Schedule/Unschedule Options
          One-time Option Queue
          Taskman Management Utilities ...
          List Tasks
          Dequeue Tasks
          Requeue Tasks
          Delete Tasks
          Print Options that are Scheduled to run
   TU
          TASK UTILITY
   VPD
          Cleanup Task List
          Print Options Recommended for Queueing
Select Taskman Management Option: SCHED <Enter> ule/Unschedule Options
Select OPTION to schedule or reschedule: XU EPCS PSDRPH AUDIT <Enter>
                                                                           Task
Allocation Audit of PSDRPH Key Report
         ...OK? Yes// <Enter> (Yes)
      (R)
                          Edit Option Schedule
    Option Name: XU EPCS PSDRPH AUDIT
    Menu Text: Task Allocation Audit of PSDRPH
                                                          TASK ID:
 Tab to the fields indicated, and enter the values shown.
  QUEUED TO RUN AT WHAT TIME: T+1@001
DEVICE FOR QUEUED JOB OUTPUT:
 QUEUED TO RUN ON VOLUME SET:
      RESCHEDULING FREQUENCY: 1D
             TASK PARAMETERS:
            SPECIAL QUEUEING:
Exit
         Save
                  Next Page
                                Refresh
Enter a command or '^' followed by a caption to jump to a specific field.
```

```
COMMAND: SAVE

Press <PF1>H for help Insert

Exit Save Next Page Refresh

Enter a command or '^' followed by a caption to jump to a specific field.

COMMAND: EXIT Press <PF1>H for help Insert

Select OPTION to schedule or reschedule:
```

Figure 69: DEA ePCS: Task Allocation Audit of PSDRPH Key Report option—Sample user entries (no report displays)

```
Print DEA Expiration Date Null
  2
          Print DISUSER DEA Expiration Date Null
  3
         Print DEA Expiration Date Expires 30 days
         Print DISUSER DEA Expiration Date Expires 30 days
         Print Prescribers with Privileges
         Print DISUSER Prescribers with Privileges
         Print PSDRPH Key Holders
         Print Setting Parameters Privileges
         Print Audits for Prescriber Editing
         Task Changes to DEA Prescribing Privileges Report
  10
          Task Allocation Audit of PSDRPH Key Report
  12
         Allocate/De-Allocate of PSDRPH Key
         Edit Facility DEA# and Expiration Date
Select ePCS DEA Utility Functions Option: 11 <Enter> Task Allocation Audit of
PSDRPH Key Report
 No data is displayed to the screen; the data is printed to the device
 indicated by the XUEPCS REPORT DEVICE parameter.
```

Figure 70: DEA ePCS: Task Allocation Audit of PSDRPH Key Report option—Sample report printed to device entered into the XUEPCS REPORT DEVICE parameter

PSDRPHKEY AUDIT LIST NAME		APR 16,2013 16:32 PAGE 1
	EDITED BY	ALLOCATION STATUS DATE/TIME EDITED
XUUSER, ONE XUUSER, ONE	XUUSER,TWO XUUSER,TWO	ALLOCATED APR 15,2013 15:33 DE-ALLOCATED APR 15,2013 16:33

6.4.13 Allocate/De-Allocate of PSDRPH Key Option

Released with Kernel patch XU*8.0*580, the **Allocate/De-Allocate of PSDRPH Key** option [XU EPCS PSDRPH KEY] allocates or de-allocates the PSDRPH security key.



NOTE: All user security keys are stored in the KEYS Multiple field (#51) in the NEW PERSON file (#200).

Figure 71: DEA ePCS: Allocate/De-Allocate of PSDRPH Key option: *Allocating* PSDRPH—Sample user entries

```
Print DEA Expiration Date Null
          Print DISUSER DEA Expiration Date Null
   2
         Print DEA Expiration Date Expires 30 days
         Print DISUSER DEA Expiration Date Expires 30 days
         Print Prescribers with Privileges
         Print DISUSER Prescribers with Privileges
         Print PSDRPH Key Holders
         Print Setting Parameters Privileges
         Print Audits for Prescriber Editing
   10
         Task Changes to DEA Prescribing Privileges Report
        Task Allocation Audit of PSDRPH Key Report
   11
          Allocate/De-Allocate of PSDRPH Key
   13
         Edit Facility DEA# and Expiration Date
Select ePCS DEA Utility Functions Option: 12 <Enter> Allocate/De-Allocate of PSDRPH
Key
Enter User Name: XUSER
     1
        XUUSER, ONE
                         OX
         XUUSER, TWO
                         TX
                                 192
                                         SYSTEMS ANALYST
     3
        XUUSER, THREE B
                              TBX
     4
        XUUSER, FOUR
                          FΧ
     5
        XUUSER, FIVE A
                            FAX
Press <RETURN> to see more, '^' to exit this list, OR
CHOOSE 1-5: 2 <Enter> XUUSER, TWO
                                   TX
                                            192
                                                    SYSTEMS ANALYST
Allocate PSDRPH for XUUSER,TWO? YES// <Enter>
```

Figure 72: DEA ePCS: Allocate/De-Allocate of PSDRPH Key option: *De-allocating* PSDRPH—Sample user entries

```
Select ePCS DEA Utility Functions Option: 12 <Enter> Allocate/De-Allocate of PSDRPH Key
Enter User Name: XUUSER,TWO <Enter> XUUSER,TWO TX 192 SYSTEMS ANALYST
De-allocate PSDRPH for XUUSER,TWO? YES// <Enter>
```



REF: To review the audit history of the allocation and de-allocation of the PSDRPH security key, see the sample report generated from the Task Allocation Audit of PSDRPH Key Report option in Figure 70.

6.4.14 Edit Facility DEA# and Expiration Date Option

Released with Kernel patch XU*8.0*580, the **Edit Facility DEA# and Expiration Date** option [XU EPCS EDIT DEA# AND XDATE] edits the FACILITY DEA NUMBER (#52) and FACILITY DEA EXPIRATION DATE (#52.1) fields in the INSTITUTION file (#4).

Figure 73: DEA ePCS: Edit Facility DEA# and Expiration Date option—Sample user entries

```
Print DEA Expiration Date Null
   2
         Print DISUSER DEA Expiration Date Null
         Print DEA Expiration Date Expires 30 days
         Print DISUSER DEA Expiration Date Expires 30 days
        Print Prescribers with Privileges
        Print DISUSER Prescribers with Privileges
        Print PSDRPH Key Holders
        Print Setting Parameters Privileges
  9
        Print Audits for Prescriber Editing
  10 Task Changes to DEA Prescribing Privileges Report
  11
         Task Allocation Audit of PSDRPH Key Report
         Allocate/De-Allocate of PSDRPH Key
  12
         Edit Facility DEA# and Expiration Date
Select ePCS DEA Utility Functions Option: 13 <Enter> Edit Facility DEA# and
Expiration Date
Select INSTITUTION NAME: SAN FRANCISCO
                        CA VAMC
    1 SAN FRANCISCO
                                           662
    2 SAN FRANCISCO
                             CA VCSFO
                                           782
    3 SAN FRANCISCO
                            CA NC
                                           903
    4 SAN FRANCISCO-OPT
                            CA
    5 SAN FRANCISCO-RO
                             CA RO
                                           343
Press <RETURN> to see more, '^' to exit this list, OR
CHOOSE 1-5: 1 <Enter> SAN FRANCISCO CA VAMC
FACILITY DEA NUMBER: BB1234563// ?
    Answer with a DEA ID, must be 9 characters in length
FACILITY DEA NUMBER: BB1234563// <Enter>
FACILITY DEA EXPIRATION DATE: SEP 9,2011// <Enter>
Select INSTITUTION NAME:
```

6.4.15 ePCS Edit Prescriber Data Option

Released with Kernel patch XU*8.0*580, the **ePCS Edit Prescriber Data** option [XU EPCS EDIT DATA] is a Broker-type context option that is given to those individuals who are permitted to edit the data related to e-prescribing of controlled substances.

This option is locked with the XUEPCSEDIT security key.

6.4.16 ePCS Set SAN from PIV Card Option

Released with Kernel patch XU*8.0*580, the **ePCS Set SAN from PIV Card** option [XUSSPKI UPN SET] is a Broker-type context option that sets the SUBJECT ALTERNATIVE NAME field (#501.2; a.k.a. SAN field or USER PRINCIPLE NAME) in the NEW PERSON file (#200) from the Personal Identification Verification (PIV) Smart Card. This is used with the DEA ePCS electronic signature (e-sig) to be sure the correct certificate is selected from the PIV card.



NOTE: This option only needs to be run once for a user at a site.

6.4.16.1 XUSSPKI SAN Bulletin

Released with Kernel patch XU*8.0*580, the XUSSPKI SAN bulletin is sent when the SUBJECT ALTERNATIVE NAME field (#501.2) in the NEW PERSON file (#200) has been changed or deleted. The bulletin is sent to users holding the PSDMGR security key.

- Subject: "Subject Alternative Name" field
- Message: The "Subject Alternative Name" field in New Person File (#200) has been changed or deleted for: |3|

Before: |1|

After: |2|



NOTE: If this value is null, the field was deleted!

- Parameters:
 - o |1|—Old value before changed or deleted.
 - o |2|—New value. If null, value was deleted.
 - o |3|—Name of the user.

6.5 Prescription Validation and Verification Process— PKIServer.exe Application

The PKIServer.exe is an application that runs as a service application to handle verification of prescriptions that have been entered using the electronic prescribing of controlled substances (ePCS) in the Computerized Patient Record System (CPRS) application. The PKIServer.exe application itself is written in the Delphi language and uses the cryptographic APIs within the Windows operating system.



REF: For more information on cryptographic functions, see the "Windows Authentication and Cryptographic Operations" section.



NOTE: The VA was the original test site (at the Hines VAMC) for ePCS for the DEA starting in 2002 with code in CPRS for this purpose. That test site has continued to use this functionality (and the functionality has been in CPRS) until the current time. The DEA has now come up with the final rules for the use of ePCS and the version of CPRS that is currently in testing moves the functionality to meet the final regulations and expands its use to all sites instead of the single Hines site.

There is code within CPRS that handles the following:

• Cryptographic functionalities involved in verifying the provider's pin value for the PIV card (the original testing used cards provided by DEA).



REF: For more information on cryptographic functions, see the "Windows Authentication and Cryptographic Operations" section.

• Validation of the PIV card with respect to expiration or revocation.



REF: For more information on revoked VA PIV cards, see the "PIV Card Validation—Revocation Server" section.

• Creation of the hash for the aggregate prescription data and signing of that hash. The signed hash is created so that it contains a copy of the signing certificate as well.

At the time that the pharmacist goes to fill the prescription there are requirements that the prescription be validated to insure that there have been no changes to the data associated with the prescription before it is filled. The pharmacist works within the VistA roll-and-scroll environment, which does *not* offer the capabilities required to provide the cryptographic checks necessary.

To validate the prescription using cryptographic checks, the system performs the following procedure:

- 1. VistA Pharmacy code passes the current data associated with the prescription and the signed hash value via Kernel utilities to a server location identified by the PKI SERVER field (#53.1) in the KERNEL SYSTEM PARAMETERS file (#8989.3). There can be up to three IP addresses separated by caret characters ("^") in this field. This connects the VistA server to the PKIServer service (identified in the services functionality as PKI_Verify_Service).
- 2. PKIServer takes the input data and extracts the signing certificate and original hash from the signed hash.
- 3. PKIServer creates a hash of the current data passed in for the prescription.
- 4. PKIServer compares the two hashes:
 - **Hashes match**—If the two hashes match, indicating no change in the data, the PKIServer then checks whether the certificate has been revoked (see Step 5).
 - **Hashes do** *not* **match**—If any changes have occurred in the data currently associated with the prescription, the two hashes differ:
 - a. PKIServer returns a value indicating prescription is returned.
 - b. Prescription is voided.
- 5. PKIServer checks whether the certificate has been revoked:
 - **Active Certificate**—If the hashes match and there is confirmation that the certificate has *not* been revoked, the prescription is approved.
 - **Revoked Certificate**—If the provider's certificate has been revoked, the prescription is voided as well.
 - **Pending Certificate Check**—There may be cases where there are problems in checking the certificate and a return value in this case may indicate that they should wait and check the prescription later.

To meet the DEA requirements, newer, higher level cryptographic methods are required than were previously used in the original Hines testing, and these may require that older server systems be patched to insure that capabilities (e.g., SHA-2) are available. Also, the VA has been moving to use functionality (e.g., Tumbleweed Desktop Validator) to assist in checking certificate statuses, etc. The PKIServer.exe application does not call these directly; however, if they are available, they are called by the Windows operating system via the cryptographic APIs.



REF: For more information on the PKIServer.exe application, see the *DEA e-Prescribing Installation and Setup Guide* located under CPRS on the VDL: http://www.va.gov/vdl/application.asp?appid=61

6.6 PIV Card Validation—Revocation Server

The Revocation Server contains a Certificate Revocation List (CRL), which is a list of all revoked VA PIV cards. The distinction is that if a physician prescribes a drug, and then the physician's certificate expires *before* the prescription is filled, it can still be filled, since it was written *before* it expired. If, however, the physician's certificate is revoked, then any orders that have *not* been filled are cancelled and *cannot* be filled. In many cases, certificates are revoked due to a change in affiliation.

To check the CRL to see if a PIV card has been revoked, perform the following procedure:

- 1. Insert the **PIV card**.
- 2. Double click on the **ActivClient Agent** to open it.
- 3. Click on the My Certificates icon.
- 4. Select and double click on one of the certificates.
- 5. Click on the **Advanced** tab.
- 6. Scroll down to find and select the **CRL Distribution Points** entry. The CRL is the Certificate Revocation List.
- 7. Scroll down and see the contents for this entry. You should probably find an entry for the following:
 - one **http:** entry
 - one **ldap:** entry. For example:
 - URL=http://cdp1.ssp-strong-id.net/CDP/vauser.crl
- 8. Copy the http:// URL address and paste it into a Web browser. It brings up a long list of all of the certificates that have been revoked (as opposed to expired, cancelled, etc.). You should get approximately 30 Megabytes for the Web page.

The Tumbleweed Desktop Validator is supposed to assist with this if it is on the desktop, and updates itself at intervals, so that the call does *not* have to be made to the site for each individual request.

6.7 Windows Authentication and Cryptographic Operations

6.7.1 History

The VA's attempt to use Microsoft[®] Windows-level authentication to access VistA accounts using a secure intermediary authentication server was set to be released in the late 1990's via the Enterprise Single Sign-On (ESSO) patch. During that time the Office of Cyber Security informed the VA that they had a better way and would implement it within six months. Subsequently, the VA stopped the release of the ESSO patch, but nothing more happened with regard to Microsoft[®] Windows level authentication.

In 2015, the VA began development of Single Sign-On Internal (SSOi) using Identity and Access Management (IAM) Secure Token Service (STS) to enable 2-factor authentication of VA employees into VistA. Kernel patches XU*8.0*655 and XU*8.0*659 enable authentication into VistA using a STS token obtained from IAM. Single Sign-On External (SSOe) authentication of veterans and *non*-VA VistA users is currently in development.

6.7.2 Current Capabilities

VistA Kernel provides the mechanism to authenticate a user with a STS token obtained from IAM. VistA does *not* do direct authentication of a user via a PIV card or similar means. Authentication via PIV card is delegated to IAM. VistA validates a PKI certificate and digital signature from IAM to secure the delegated authentication process. This process is currently enabled for Remote Procedure Call (RPC) Broker and VistALink applications.

CPRS v30 is capable of handling the electronic prescribing of controlled substances, but all of the cryptographic operations are handled via the client workstation (for the signing of the prescription). This is before the data is passed to the VistA server, along with a copy of the signed hash generated based on the data for the prescription. At the time of filling of the prescription by the VA pharmacist, the data for the prescription along with a copy of the signed hash is transferred by VistA to a PKIService application. This PKIService application runs on a separate server or workstation for verification that the data associated with the prescription has not changed. It compares the original hash value with one created based on the current data.



REF: For more information on the PKIService verification process, see the "<u>Prescription</u> Validation and Verification Process—PKIServer.exe Application" section.

6.7.3 Future Capabilities

Terminal access (roll-and-scroll) VistA 2-factor authentication is currently in development. This process will require a script within the terminal emulator software to call IAM to authenticate the user via PIV or similar means, and then send the returned STS token to VistA for authentication and identification of the user. Single Sign-On External (SSOe) is currently in development to use 2-factor authentication to authenticate and identify external (non-VistA) users to obtain or edit data within VistA. External users include:

- Veterans
- Department of Defense (DoD) users
- Non-VA providers who require access to veteran data.

External users will be required to authenticate with IAM and use the returned STS token to authenticate and identify the user within VistA. Since these users might not be currently "known" to VistA, a means of role-based authorization is required to provision the users on-

the-fly and restrict their access to specific data based upon their role. Role-based authorization for external VistA users has yet to be developed.				

II. Menu Manager

7 Menu Manager: User Interface

Kernel's menu system presents menu options within VistA software in a standard fashion. Once you become familiar with using the menu system in one application, using other applications is easier, since the same rules apply.

7.1 Navigating Kernel's Menus

When you successfully sign into the computer system, Menu Manager presents your primary menu options. Your primary menu is the top-level menu assigned to you by the system administrators. Most options that are available to you are available from your primary menu, or from a submenu attached to your primary menu.

The menu system prompts you with a "Select (menu name) Option:" prompt. For example, in a menu named Billing, Menu Manager would prompt you with "Select Billing Option:". You can navigate through the menu system by responding to this prompt in different ways, which are described in this chapter.

You can enter question marks to see option choices and obtain online help. You can enter an option's synonym or the first few letters of its menu text, using upper or lowercase, to select the option. You can also enter a caret ("^") along with the option specification (option menu text or synonym) to jump to the destination option rather than traversing the menu pathways step-by-step.

7.1.1 Choosing Options

You can choose an option from your current menu at the select prompt. Choosing the option launches the software application associated with the option. To choose an option, type in the first few letters of the option as it is displayed and press the **Enter>** key. If multiple options match those first few characters you are presented with a list of matching options from which you can choose the specific option you want to run. If the option is another menu, indicated by trailing ellipses (...), it becomes the current menu, and so on down the menu pathway.

To come back up the menu pathway, press **<Enter>** at the select prompt. Each time you press **<Enter>**, Menu Manager returns you to the next higher menu level, until you reach your highest menu, the primary menu. If you press **<Enter>** at the primary menu, Menu Manager asks if you want to halt your session. If you answer **YES**, your Kernel session is ended.

7.1.2 Listing Options

When you enter a menu, the items may or may not be displayed automatically, based on whether you have AUTO MENU turned on. The AUTO MENU feature, as described in the "Signon/Security: User Interface" section, is a flag that controls the menu display. If you do not have a setting specified for AUTO MENU, the site parameter default is used. Often, to save system resources, the site parameter can be set to disable automatic display. In this case, to display menu items, simply enter a single question mark ("?"), as shown below:

Figure 74: One question mark (?) help—Sample user dialogue

```
Select Any Level Menu Option: ?

First Item
Second Item
Third Item of Menu Choices ...
Fourth Item

Enter ?? for more options, ??? for brief descriptions, ?OPTION for help text.

Select Any Level Menu Option:
```

7.1.3 Displaying Option Help

To obtain a lengthier description of an individual option, enter a single question mark ("?"), and the first few letters of the option name. If there is an extended description of the option, or a help frame describing the option, they are displayed.

Figure 75: Using ?Option to get help on a named option—Sample user dialogue

```
Display User Characteristics
Edit User Characteristics
Electronic Signature Code Edit
Menu Templates...
Spooler Menu...
TaskMan User
User Help

Select User's Toolbox Option: PDISPLAY

'Display User Characteristics' Option name: XUUSERDISP
Display the user's name, location, and characteristics

**> Press 'RETURN' to continue, '^' to stop: <Enter>
Select User's Toolbox Option:
```

7.1.4 Listing Secondary and Common Options

At any select prompt you can enter two question marks ("??") to see options on the Secondary and Common menus, as well as options available on the current branch of your menu tree.

The Secondary menu and the Common menu contain options that you can select at any location in the menu system. Options on the Secondary menu are typically created by your system manager. Options on

the Common menu are standard Kernel options available from anywhere in the menu system. Options on the current menu, on the other hand, can only be directly selected while that menu is the current menu.

The two-question-mark display shows the option's synonym (a short abbreviation), if one exists. You can select an option by its synonym as well as by its full name. On the same line, it lists the option's full name followed by the formal option name in capital letters enclosed in square brackets. (The name is the .01 field of the OPTION file [#19].) It also shows any option restrictions such as:

- Out-of-Order
- Locked
- Prohibited times

Figure 76: Two question marks (??) help—Listing Primary, Secondary, and Common menu options

```
Select Systems Manager Menu Option: ??
          VA FileMan ...
                                                                             [DIUSER]
   FМ
          Core Applications ...
                                                                             [XUCORE]
          Device Management ...
                                                                              [XUTIO]
             **> Locked with XUPROG
          Information Security Officer Menu ...
                                                                               [XUSPY]
          Manage Mailman ...
                                                                               [XMMGR]
          Menu Management ...
                                                                            [XUMAINT]
          Operations Management ...
                                                                          [XUSITEMGR]
          Programmer Options ...
                                                                             [XUPROG]
             **> Locked with XUPROG
          Spool Management ...
                                                                         [XU-SPL-MGR]
          Taskman Management ...
                                                                           [XUTM MGR]
          User Management ...
                                                                              [XUSER]
You can also select a secondary option:
          Equipment Checked Out to Myself
                                                                     [A6A EQUIP USER]
   OUT
   PAID
          SIGN INTO MARTINEZ VIA TELNET, TYPE DUSER
                                                                       [A6A USE PAID]
   RUM
          Capacity Planning ...
                                                                          [XTCM MAIN]
          ISC OFFICE MENU OPTIONS ...
                                                                           [ISCSTAFF]
Or a Common Option:
   KNF
          Kernel New Features Help
                                                                   [XUVERSIONEW-HELP]
          Halt
                                                                             [XUHALT]
          Continue
                                                                         [XUCONTINUE]
          Restart Session
                                                                            [XURELOG]
          MailMan Menu ...
   MM
                                                                             [XMUSER]
                                                       [XUS NPI PROVIDER SELF ENTRY]
   NPI
          PROVIDER NPI SELF ENTRY
   TBOX
          User's Toolbox ...
                                                                         [XUSERTOOLS]
   VA
          View Alerts
                                                                            [XQALERT]
          Time
                                                                             [XUTIME]
                                                                         [XUSERWHERE]
          Where am I?
```

7.1.5 Displaying Option Descriptions

Entering three question marks ("???") at any select prompt displays option descriptions (from a word-processing-type field in the OPTION file [#19]). If entered at the select prompt for a menu within the primary tree, the top-level options are described; then you are prompted whether you want to see descriptions for Secondary or Common options.

Figure 77: Three question marks (???) help—Sample user dialogue

```
Select Spooler Menu Option: ???
'Allow other users access to spool documents'
                                                  Option name: XU-SPL-ALLOW
     This option edits the 'OTHER AUTHORIZED USERS' field of the SPOOL
     DOCUMENT file to allow other users access to a spool document.
'Delete A Spool Document'
                             Option name: XU-SPL-DELETE
  **> Extended help available. Type "?Delete" to see it.
    Delete a spool document from the spool document file and delete the
    associated message if they are still linked.
'List Spool Documents'
                           Option name: XU-SPL-LIST
  **> Extended help available. Type "?List" to see it.
    This option lists entries in the spool document file.
'Make spool document into a mail message'
                                             Option name: XU-SPL-MAIL
  **> Extended help available. Type "?Make" to see it.
    This option will take a spool document and post it as a mailman
    message to the user's IN basket. This doesn't move the data at all
    but does decrease the number of lines charged to the user.
  **> Press 'RETURN' to continue, '^' to stop, or '?[option text]' for more
                        help: <Enter>
                            Option name: XU-SPL-PRINT
'Print A Spool Document'
  **> Extended help available. Type "?Print" to see it.
    This allows the printing of a document that has been spooled.
 Shall I show you your secondary menus too? No// <Enter>
 Would you like to see the Common Options? No// <Enter>
Select Spooler Menu Option:
```

You should be ready to use three question marks ("???") to learn more about unfamiliar options (e.g., options distributed in a new software release).

7.1.6 Jumping to Options—"Up-arrow Jump")

The pathways of the Primary, Secondary, and Common menus have tree-like structures. You can step up or down the pathways to reach your destination, or invoke the menu system's "Up-arrow Jump" feature as a shortcut. To jump to an option, enter a caret ("^") before the option specification (the option's menu text or synonym in upper- or lowercase letters). You only need to enter the first few characters needed to uniquely identify the option. You can use the option's synonym to limit ambiguity, especially if the synonym is distinct from other synonyms or menu texts.

Figure 78: Using the "Up-arrow Jump"—Sample user dialogue

```
Select Systems Manager Menu Option: ^INTRO <Enter> ductory text edit
```

The menu system carries out the necessary footwork to reach the desired option. If, along the way, there are pathway restrictions (e.g., locks or prohibited times), access to the option is denied, just as when stepping to an option. If a match is found within the primary or secondary menus, that option is executed (the menu system does *not* search the Common menu if it can find a match in the primary or secondary menus).

If the menu system finds *more than one* matching option on *the* Primary, Secondary, or Common menu tree, the menu system presents a list of matching choices. Entering a caret ("^") followed by a question mark ("?") displays all of the options available to you.

Figure 79: List of choices—Sample user dialogue

```
Select Systems Manager Menu Option: ^LIST NAMES

1   List Namespaces [XUZ NAMESPACES]
2   List Namespaces [ZZ NAMESPACE LIST]

Type '^' to stop, or choose a number from 1 to 2:
```

System administrators should assign "shallow" secondary menus to facilitate menu jumping. When a jump is requested, the menu system searches all the way through the primary as well as the secondary, looking for a match. Users are inconvenienced and system resources are consumed if secondary menus are "deep" in terms of their hierarchical tree-like structure.

You may occasionally find jumping disabled; when you try to jump, you may get a message that quick access is temporarily disabled. Jumping stays disabled until the needed menu trees are rebuilt.

7.1.7 Jumping to Options—"Rubber-band Jump"

The menu system's jump feature includes the ability to jump out to a destination option and then back again, something like the motion of a rubber band. The syntax for the "Rubber-band Jump" request is the use of a double caret ("^^") followed by the usual option specification. For example:

Figure 80: "Rubber-band jump"—Sample user dialogue

```
Select Systems Manager Menu Option: ^^TASKMAN USER
```

As with the single "Up-arrow Jump" ("A"), restrictions along the menu pathways are checked.

If you enter two carets ("^^") without a following option specification/name, you are returned to the primary menu. This technique is a quick way for you to "go home" to the menu that is displayed at signon, and is called the "Go-home Jump."



CAUTION: It is important to note that when you invoke the "Rubber-band Jump," there is no attempt to protect variables that can be SET or KILLed, via Entry or Exit Actions, as you jump through the menu tree. Thus, the "Rubber-band Jump" can be inappropriate under certain circumstances, since it could cause significant alteration of your environment.

7.1.8 Common Menu

The Common menu is designed as a collection of options that are available to all users. The standard Common menu items are:

- User's Toolbox: As described in the "<u>User's Toolbox Menu</u>" section in the "<u>Signon/Security</u>: <u>User Interface</u>" section, the User's Toolbox is a menu containing options that allow users to control some aspects of their computing environment.
- Halt, Continue, Restart Session: As described in the "Signon/Security: User Interface" chapter, these options are three different ways to log out of the system.
- **View Alerts:** As described in the "<u>Alerts</u>" and "<u>Signon/Security: User Interface</u>" sections, View Alerts is an option that lets you process Alerts.
- **Time:** The Time option simply displays the date and time.
- Where am I?: This option lists information identifying what computer system you are signed into (e.g., UCI, Volume Set, Node, and Device).

7.1.8.1 Selecting Common Options with the Double Quote

Since Common options are intended to be readily accessible, there is a shortcut method to reach them. While you could use an "Up-arrow Jump," it is quicker to enter a quotation mark followed by the option specification (e.g., name, synonym). Figure 81 selects the User's Toolbox menu from the Common menu via its synonym, TBOX:

Figure 81: Selecting common options via the double quote—User's Toolbox menu option

```
Select Sample Menu Option: "TBOX

Display User Characteristics
Edit User Characteristics
Electronic Signature code Edit
Menu Templates ...
Spooler Menu ...
TaskMan User
User Help

Select User's Toolbox Option:
```

7.2 Menu Templates Option

Menu templates are like scripts. You can use them to execute a fixed series of options, in sequence. Tools for creating, deleting, listing, and renaming templates are options on the Menu Templates menu, part of the User's Toolbox (TBOX) menu:

Figure 82: Menu Templates Option

```
Select Menu Templates Option: ?

Create a new menu template
Delete a Menu Template
List all Menu Templates
Rename a menu template
Show all options in a Menu Template

Select Menu Templates Option:
```

When you create a MENU template, you are prompted for a series of options that lead to a final non-menu (i.e., executable) destination option. Once you choose one non-menu option to be executed, you can navigate to other options and choose them to be executed as well, if you wish. When you have selected each executable option to be part of the template, enter a plus sign ("+") to store the sequence of options. You are asked to confirm the sequence of options in the template, and then to give the template a name.

To invoke the template, simply enter a left square bracket followed by the template name:

Figure 83: Invoking a template—Sample user dialogue

```
Select Option: [MYTEMPLATE Loading MYTEMPLATE...
```

The template then executes each option that is part of the template, in the same order as the options were selected for the template.

MENU templates are stored in the MENU TEMPLATE field (Multiple) of the NEW PERSON file (#200), so you can use any name for MENU templates. If your MENU template points to options that are subsequently removed from the OPTION file (#19), you receive a message that the MENU template no longer functions properly and needs to be deleted or rebuilt.

Use menu jumping (i.e., the "Up-arrow Jump") when you want to jump immediately to an option. Use MENU templates when you have a series of options that you need to run in the same order repeatedly, over a period of time.

7.2.1 LOGIN Menu Template

Beginning with Kernel 8.0, you can have a MENU template execute automatically, on your first signon of the day. If you have a MENU template named LOGIN (all uppercase), the MENU template is executed on your first signon of the day. So if you have a series of options you execute on your first signon every day, an easy way to execute them is to create a MENU template; store the series of options in the template; and name the template LOGIN.

7.3 Summary

Once you learn how to navigate Kernel's menu tree, you can use some of Menu Manager's additional features to help increase your productivity in the VistA computer system. These features include the "Uparrow Jump," the "Rubber-band Jump," using three question marks ("???") to obtain online option help, and using MENU templates as scripts.

8 Menu Manager: System Management

Menu Manager is built around options, which are entries in the OPTION file (#19). There are several types of options:

- Menus—Options with subentries in the MENU (item) field (Multiple).
- Multiples—Options that point back to the OPTION file (#19) itself.
- Plugins—Options that are designed as items that plug into the MENU (item) field (Multiple) of a menu-type option.

Kernel provides a number of tools to create and manage menus and options.

8.1 Creating Menus and Options

Figure 84: Edit options option

```
SYSTEMS MANAGER MENU ... [EVE]
Menu Management ... [XUMAINT]
Edit options [XUEDITOPT]
```

One task system administrators perform frequently is defining local primary menus that are appropriate for their users. This task of menu creation is accomplished by grouping exported menus from various software applications together on a new master menu. You can use Edit options[XUEDITOPT], on the Menu Management menu [XUMAINT], to define a new menu if READ, WRITE, and LAYGO access to the OPTION file (#19) has been granted (either through the FILE MANAGER ACCESS CODE field [#3] or through the File Access Security system if that is enabled). Only a few fields need to be defined, as shown in Figure 85. The new menu can then be assigned to a user, as described in the "Signon/Security: User Interface" section, with one of several options on the User Edit menu.

Figure 85: Defining local primary menus (system administrators)—Sample user dialogue

```
Select OPTION to edit: ZZSTAFF MENU
 Located in the Z (Local) namespace.
 ARE YOU ADDING 'ZZSTAFF MENU' AS A NEW OPTION (THE 721ST)? Y <Enter> (YES)
  OPTION MENU TEXT: STAFF MENU
NAME: ZZSTAFF MENU// <Enter>
MENU TEXT: Staff Menu// <Enter>
PACKAGE: <Enter>
OUT OF ORDER MESSAGE: <Enter>
LOCK: <Enter>
REVERSE/NEGATIVE LOCK: <Enter>
DESCRIPTION:
 1>This is the primary menu for staff members.
EDIT Option: <Enter>
TYPE: MENU
Select ITEM: XUCORE <Enter>
                               Core Applications
 ARE YOU ADDING 'XUCORE' AS A NEW MENU (THE 1ST FOR THIS OPTION)? Y <Enter> (YES)
  MENU SYNONYM: <Enter>
  SYNONYM: <Enter>
 DISPLAY ORDER: 10
Select ITEM: XUSPY <Enter>
                            System Security
  ARE YOU ADDING 'XUSPY' AS A NEW MENU (THE 2ND FOR THIS OPTION)? Y <Enter> (YES)
  MENU SYNONYM: <Enter>
 SYNONYM: <Enter>
 DISPLAY ORDER: 20
Select ITEM: XT-KERMIT MENU <Enter>
                                       Kermit menu
 ARE YOU ADDING 'XT-KERMIT MENU' AS A NEW MENU (THE 3RD FOR THIS OPTION)?
YES <Enter> (YES)
  MENU SYNONYM: <Enter>
  SYNONYM: <Enter>
 DISPLAY ORDER: 30
Select ITEM: <Enter>
CREATOR: SITE, MANAGER// <Enter>
HELP FRAME: <Enter>
PRIORITY: <Enter>
Select TIMES PROHIBITED: <Enter>
Select TIME PERIOD: <Enter>
RESTRICT DEVICES?: <Enter>
Select PERMITTED DEVICE: <Enter>
```

8.1.1 Option Name and Menu Text

By convention, the formal option name is usually entered in all capital letters. According to namespacing conventions, it *must* begin with a namespace that identifies the associated software. It is the NAME field (#.01) of the OPTION file (#19). The menu text is what is displayed to the user at the select prompt. Like the words of a heading or title, initial capitalization is used for all words except prepositions and articles, all of which are presented in lowercase. To minimize the number of keystrokes needed to select an option, different first letters should be used for the text of each menu item. Menus should be limited to about seven items so they all appear together on one screen. The most frequently used items should be presented first.

8.1.2 Synonyms and Display Order

By default, the items on the menu are displayed in alphabetical order by menu text. If any of the items is assigned a synonym, those items are displayed before others lacking synonyms. To facilitate menu jumping, synonyms should ideally be unique; numbers are not good choices for synonyms.

To customize the order of the display, each item on the menu can be assigned a Display Order. This field is an option attribute that is presented when using Edit options. When first assigning a number for the display order, you may want to use 10, 20, and 30 rather than 1, 2, and 3 to permit easier modification in the future if another item needs to be inserted.

8.1.3 PRIORITY

You can set an option's PRIORITY field to set a run priority for an option. Experimentation is needed to determine the effect of priority settings.

8.1.4 HELP FRAME

You can specify a help frame for an option. The help frame is displayed if, at the "Select..." menu prompt, the user enters ?OPTION (where OPTION is the name of an option).

8.1.5 DISPLAY OPTION

If AUTO MENU (#200.06) is in effect for a user, the items on that user's current menu are always displayed. A problem can arise when, if an option displays output and then quits, AUTO MENU's automatic display of menu options scrolls the output off the screen. Since the AUTO MENU display usually scrolls the option's output off the screen faster than the user can read the output, it can effectively render the option unusable. You can avoid this problem by setting the option's DISPLAY OPTION field (#11) in the OPTION file (#19) to **YES**. If set to **YES** and the user has AUTO MENU turned on, Menu Manager prompts "Press RETURN to continue..." after the option completes, but before displaying the list of menu options. The user then has a chance to review the output before returning to their menu.



REF: For information on other fields in the OPTION file (#19), including how to create options of a type other than Menu, see the "Menu Manager: Developer Tools" chapter in the *Kernel Developer's Guide*.

8.1.6 If the Option Invokes Non-VistA Applications

If you create an option that invokes non-VistA applications (e.g., WordMan or CalcMan) include a call to the Device Handler with the code D HOME^%ZIS in the EXIT ACTION field of the OPTION file (#19) so that the required IO variables is present when leaving these options. Do the same for any other utility that is known to KILL IO variables upon exit.

8.1.7 If the Option Should Be Regularly Scheduled

If an option should be regularly scheduled to run through TaskMan, you *must* set its SCHEDULING RECOMMENDED field (#209) in the OPTION file (#19) to **YES**. You are *not* able to use Schedule/Unschedule Options to schedule an option unless this field is set to **YES** for the option.

8.1.8 Auditing Option Use

Figure 86: Auditing menu options

```
SYSTEM MANAGER MENU...
                                                                                 [EVE]
  System Security...
                                                                               [XUSPY]
    Audit Features ...
                                                                        [XUAUDIT MENU]
     Maintain System Audit Options ...
                                                                       [XUAUDIT MAINT]
        Establish System Audit Parameters
                                                                             [XUAUDIT]
        Audited Options Purge
                                                                          [XUOPTPURGE]
      Audit Display ...
                                                                             [XUADISP]
        Option Audit Display
                                                                           [XUOPTDISP]
```

You can establish an audit on options to record every time an option is used. You can do this with the Establish System Audit Parameters option [XUAUDIT], which is in the Audit Features [XUAUDIT MENU] menu tree. Simply enter a time to initiate audit and a time to terminate audit. Then enter the specific options you want to audit (you can also choose all options).

Each time a user uses an audited option, an entry is made in the AUDIT LOG FOR OPTIONS file (#19.081). You can display these entries using the Option Audit Display option [XUOPTDISP]. You can purge the AUDIT LOG FOR OPTIONS file (#19.081) with the Audited Options Purge option [XUOPTPURGE].

If Kernel Toolkit is installed at your site, you can also use its Alpha/Beta Test Option Usage menu to count the number of times an option is invoked.



REF: For more information, see the Kernel Toolkit documentation and the *Kernel Security Tools Manual*.

8.2 Display Menus and Options Menu

Figure 87: Display Menus and Options menu

```
SYSTEMS MANAGER MENU ...
                                                                                 [EVE]
 Menu Management ...
                                                                            [TMIAMUX]
   List Options by Parents and Use
                                                                             [XUXREF]
                                                                  [XQDISPLAY OPTIONS]
    Display Menus and Options
      Abbreviated Menu Diagrams
                                                                         [XUUSERACC2]
      Diagram Menus
                                                                          [XUUSERACC]
      Inquire
                                                                          [XUINOUIRE]
      Menu Diagrams (with Entry/Exit Actions)
                                                                         [XUUSERACC1]
      Print Option File
                                                                            [XUPRINT]
```

Kernel provides a number of options to display and diagram menus and options on the Display Menus and Options menu [XQDISPLAY OPTIONS].

8.2.1 Diagramming Options

To discover the menu tree roots of other software applications and how options and suboptions are related, you can use the following menu diagramming options:

Table 9: Menu diagramming options to discover tree roots and relationships between options/suboptions

Menu	Description	
Abbreviated Menu Diagrams	Outlines the menu tree.	
Diagram Menus	Outlines the menu tree, and shows option attributes (e.g., locks and prohibited times).	
Menu Diagrams (with Entry/Exit Actions)	Outlines the menu tree, shows option attributes, and shows entry/exit and header actions as well.	

Also, the List Options by Parents and Use option [XUXREF] identifies which options have "no parents," and thus, are standalone roots. It also indicates whether options are used as primary menus, secondary menus, or as regularly scheduled tasks.

8.2.2 Option Descriptions

To learn more about the options included in a software application, you can use the Print Option File option [XUPRINT] (from the Display Menus and Options menu [XQDISPLAY OPTIONS]) to print the option description, type, and other information. This listing can be sorted by namespace. For example, to print all the VA FileMan options, you can sort from DD to DI.

8.2.3 Displaying Options

To display an option, use the Inquire option:

Figure 88: Inquire option—Sample user dialogue

```
Select Display Menus and Options Option:
Which OPTIONS item to display: XT-KERMIT MENU <Enter>
                                                          Kermit menu
NAME: XT-KERMIT MENU
                                        MENU TEXT: Kermit menu
 TYPE: menu
                                        CREATOR: POSTMASTER
 PACKAGE: KERNEL
                                        E ACTION PRESENT: YES
 X ACTION PRESENT: YES
DESCRIPTION: This is the top level menu for kermit functions. It gives access
to the send, receive, and edit options.
                                        SYNONYM: R
ITEM: XT-KERMIT RECEIVE
ITEM: XT-KERMIT SEND
                                        SYNONYM: S
ITEM: XT-KERMIT EDIT
                                        SYNONYM: E
 EXIT ACTION: D CLEAN^XTKERM4
                                        ENTRY ACTION: D INIT^XTKERM4
  UPPERCASE MENU TEXT: KERMIT MENU
```

8.2.4 Option Access by User Option

Figure 89: Option Access by User option

```
Menu Management ... [XUMAINT]
Show Users with Selected Primary Menu [XUXREF-2]
Option Access By User [XUOPTWHO]
```

Use the Show Users with Selected Primary Menu option [XUXREF-2] to show which users have been assigned a particular option as a primary or secondary menu. The Option Access by User option [XUOPTWHO] is another cross-referencing tool.

8.3 Managing Menus and Options

8.3.1 Managing Primary Menus

When system administrators receive new software applications, existing primary menus should be modified to include the new menus. It is *not* wise to create a new primary menu for every new or unusual circumstance. This would lead to a tremendous variety of menus that would be difficult to sort out and use in the future. Primary menus can be customized with security keys.



REF: For more information on security keys, see the "Security Keys" section.

If there are a few menu options that require special privilege, they can be locked and the security keys assigned to the appropriate users. In this way, a smaller number of primary menus can serve the needs of a larger number of users.

Also, while putting new master menus onto users' secondary menus can be a quick fix, it is not a good idea to do this. Too many options on a user's secondary menu can be cumbersome for the user. In addition, in the long run, it is easier for system administrators to manage access to a menu reached from a few well-defined primary menus than to manage access to a menu reached from a large number of users' secondary menus.

8.3.2 Assigning Secondary Menus

An easy way to allocate menu options is to assign them to users individually as SECONDARY MENU OPTIONS. Secondary options are unique for each user and are stored in a multiple in the user's NEW PERSON file (#200) entry. Assignment of SECONDARY MENU OPTIONS should be limited to the essential few, and should not involve deep structures with multiple levels. Instead, new primary menus should be built or existing ones modified. During menu jumping, all branches of both the primary and secondary menu trees are searched each time a jump request is received by the menu system. Greater efficiency and user convenience results if the depth of the secondary menu trees is confined.

8.3.3 ALWAYS SHOW SECONDARIES Field

You can set the ALWAYS SHOW SECONDARIES field in a user's NEW PERSON file (#200) entry. If set to **YES** for a user, that user always has their secondary and common options listed when options on their primary menu are listed (which occurs either by the user entering two question marks ["??"] at the "Select..." menu prompt, or when AUTO MENU is turned on).

8.3.4 Redefining the Common Menu

All users automatically have access to the options on the Common menu [XUCOMMAND]) by virtue of the menu system's design. As described earlier, entering two question marks ("??") at any select prompt displays the Common menu. The only way to deny access to a particular user is to lock the Common menu option with a reverse key and then allocate the security key to the same user.



REF: For more information on security keys, see the "Security Keys" section.

The items on the Common menu can be left as they are distributed by Kernel, or modified locally as desired. For example, an item can be added to display online help about local computer access policies. This is accomplished by using Edit options to edit the XUCOMMAND menu option. The Item multiple lists the existing menu choices; other locally namespaced options can be added.

If options are locally added to the standard XUCOMMAND menu set, new installations of Kernel do *not* overwrite the changes. During installation, items on the local XUCOMMAND menu are compared with

the exported items. Any previously exported items that were removed by the site are *not* added back. Brand new items, however, are added and any matching items are updated. Other items that the site may have added are left in place.

8.3.5 Altering Exported Menus

Generally speaking, exported menu structures should stay intact. If local modifications to exported menus are made, great care *must* be taken to preserve any logic that may exist in the exported structure. For example, the entry action of one option can set up key variables that are then assumed to exist when another option, one further down on the menu tree, is invoked. Although each one of a software's options should be able to be invoked independently once the steps described in the *Kernel Technical Manual* for creating and KILLing software-wide variables have been taken (according to the Programming Standards and Conventions [SAC]), this is not always the case and cannot be assumed.

If an option cannot be invoked independently, the developer can set that option's INDEPENDENTLY INVOCABLE field to **NO**, as an alert that some other option or action *must* be done before the option can be called.

To give users the options associated with new software applications, system administrators should try to allocate the menus as whole entities. If dissection appears necessary, the "Internal Relations" section of the software documentation should be consulted before rearranging any of the items.

8.3.6 Delete Unreferenced Options Option

Figure 90: Delete Unreferenced Options option

	Programmer Options <locked:< th=""><th>XUPROG></th><th>[XUPROG]</th></locked:<>	XUPROG>	[XUPROG]
Delete Unreferenced Options			[XQ UNREF'D OPTIONS]

All options for interactive use (not designed exclusively as queueable tasks) should normally be tied to a menu that is used as a primary menu or at least as a secondary menu. Standalone options that have no parents and are not menu-type options should be reviewed. They may be obsolete software options or local test options and could be candidates for deletion. Use the Delete Unreferenced Options option [XQ UNREF'D OPTIONS] to delete unreferenced options. It can be used to cycle through the entire OPTION file (#19) and delete non-menu options that are not referenced by other options. Deletion should obviously be done with care. Use of this option is limited to those who hold the XUPROG security key.

8.3.7 Fix Option File Pointers Option

Figure 91: Fix Option File Pointers option



After performing maintenance work on the OPTION file (#19) (e.g., deleting obsolete options that may have been items on a menu), you can use the Fix Option File Pointers option [XQOPTFIX] (see Figure 92) to remove any dangling pointers that may have been left in the Item multiple. Running this option is an alternative to having VA FileMan update the pointers each time an individual option is deleted.

Figure 92: Fix Option File Pointers option—Sample user dialogue

```
Select OPTION NAME: ZZTEST3 <Enter> Test Option
NAME: ZZTEST3// ©
SURE YOU WANT TO DELETE THE ENTIRE 'ZZTEST3' OPTION? Y <Enter> (YES)
SINCE THE DELETED ENTRY MAY HAVE BEEN 'POINTED TO'
BY ENTRIES IN THE 'USER' FILE, ETC.,
DO YOU WANT THOSE POINTERS UPDATED (WHICH COULD TAKE QUITE A WHILE)? NO// <Enter>
```

8.3.8 Testing a User's Menus

Figure 93: Switch Identities option

```
User Management... [XUSER]
Switch Identities [XUTESTUSER]
```

You can test a user's menus using the Switch Identities option [XUTESTUSER]. It lets you test the user's menus and security keys. It does not allow you to execute any bottom-level menu options, however; it only lets you navigate menu trees. You are reminded at each prompt whose menu it is that you are testing. To exit this mode and return to your own menus, simply enter an asterisk ("*").

8.3.9 Managing Out-Of-Order Option Sets

Figure 94: Out-Of-Order Set Management menu options

```
Menu Management ...
                                                                            [XUMAINT]
  Out-Of-Order Set Management...
                                                                           [XOOOMAIN]
    Create a Set of Options To Mark Out-Of-Order
                                                                           [XOOOMAKE]
    List Defined Option Sets
                                                                           [XQOOSHOW]
    Mark Option Set Out-Of-Order
                                                                             [XQOOFF]
    Options in the Option File that are Out-of-Order
                                                                         [XQOOSHOFIL]
    Protocols Marked Out-of-Order in Protocol File
                                                                         [XQOOSHOPRO]
    Recover Deleted Option Set
                                                                           [XQOOREDO]
    Remove Out-Of-Order Messages from a Set of Options
                                                                              [XOOON]
    Toggle options/protocols on and off
                                                                            [XQOOTOG]
```

Menu Manager, starting with Kernel 8.0, provides a mechanism for defining sets of options and protocols, and a way to disable and enable access for these pre-defined option and protocol sets via options on the Out-Of-Order Set Management menu [XQOOMAIN]. This can be handy when you need to repeatedly disable and enable sets of options and protocols.

Use the Create a Set of Options to Mark Out-Of-Order option [XQOOMAKE] to define a set of options. You are prompted first to select options, and then to select protocols.

For both options and protocols, you can use the following to:

- Add a group of options to the set—Use the wildcard asterisk ("*") with or without a namespace.
- Add a range of options to a set—Use **NAM1-NAM2** to add a range of options from NAM1 to NAM2 to the set, where "NAM" represents a namespace.
- Subtract/Remove a group of options from a set—Use the minus sign (i.e., hyphen, "-") followed by a namespace.

Use the Mark Option Set Out-Of-Order option [XQOOFF] to disable access to a set of options. You are asked to enter the message used to place all options in the set out-of-order. The option then places the message in each option's OUT OF ORDER MESSAGE field (#2).

Use the Remove Out-Of-Order Messages from a Set of Options option [XQOON] to enable access to an option set.

To toggle the status of an individual option only, use the Toggle Options/Protocols On and Off option [XQOOTOG].

Out-of-Order Option sets are stored in the ^XTMP global, with a purge date set for seven days in the future. If you place a set of options out of order, but the option set is purged from ^XTMP before you enable access to it, you can rebuild the out-of-order option set using the Recover Deleted Option Set option [XQOOREDO]. It asks you to specify the exact text of the message used to place the set of options out of order; it then recreates an out-of-order option set containing all options currently placed out of order with the specified message



NOTE: Make sure the message you specify is unique to the set of options you are re-enabling.

You can then enable access to the rebuilt option set with the Remove Out-Of-Order Messages from a Set of Options option [XQOON].

To see what sets of options have been grouped in sets on the system, use the List the Defined Options Sets option [XQOOSHOW]. To show all options and protocols currently marked out of order, use the Options in the Option File that are Out-of-Order option [XQOOSHOFIL] and the Protocols Marked Out-of-Order in Protocol File option [XQOOSHOPRO].

8.4 Restricting Option Usage

Figure 95: Restrict Availability of Options option

```
Menu Management ... [XUMAINT]
Restrict Availability of Options [XQRESTRICT]
```

Options can be restricted in terms of when users can select them and when devices can be used to invoke them. Many of the option restrictions are included in the Restrict Availability of Options option [XQRESTRICT].

8.4.1 Setting Options Out of Order

To completely restrict access, you can mark an option to be out-of-order. Do this by entering text in an option's OUT OF ORDER MESSAGE field (#2) in the OPTION file (#19). If a user attempts to invoke the option, the Out of Order Message is displayed.

8.4.2 Locks

Both the normal lock, and also the Reverse/Negative lock can be associated with options (as described in the "Security Keys" section). Also, M code can be entered in the HEADER, ENTRY ACTION, or EXIT ACTION fields to restrict the use of an option given certain conditions.

8.4.3 Prohibited Times

You can prohibit the use of an option at certain times during the day by assigning a set of prohibited time periods at the "Select TIMES PROHIBITED" prompt. Options scheduled to run through TaskMan will also be prohibited from running during these prohibited times.

8.4.4 Permitted Devices

If the RESTRICT DEVICES flag is set to **YES**, the option can only be invoked on one of the devices listed in the PERMITTED DEVICES field (Multiple). Thus, the running of an option can be restricted. This flag does not affect the choice of devices used for the output from options. It instead controls the processing involved in the use of the option itself.

8.4.5 QUEUING REQUIRED Flag

Using the option Edit options, you can allow users to invoke an option, but force any output to be queued outside of certain times of day, by editing the option's QUEUING REQUIRED field (Multiple). In this multiple's TIME PERIOD (#.01) and DAY(S) FOR TIME PERIOD (#.02) fields enter the time periods and days in which you do not want the option's output to be produced. During these time periods, the output of the options can only be queued. When a user requests a time for queuing, the menu system determines the next permissible day and time for output. Thus, users can invoke the option and use it to define the parameters for the subsequent processing, but the actual work is done during a later time period, presumably when the system is less busy.

8.5 Menu Manager Options that Should Be Scheduled

This section describes the two Menu Manager options that should be regularly scheduled.

Kernel exports a number of other options that should be scheduled to run at regular intervals. Most of these are located on the PARENT OF QUEUABLE OPTIONS menu.



REF: For a complete list, along with suggested scheduling frequencies, see the *Kernel Installation Guide*.

8.5.1 Clean Old Job Nodes in XUTL Option

The Clean old Job Nodes in the XUTL option [XQ XUTL \$J NODES] is Kernel's purge option for Kernel globals. This option purges the following globals:

- ^XUTL
- ^UTILITY
- ^TMP
- ^XTMP
- ^XUSEC

Figure 96: Clean old Job Nodes in XUTL

```
Operations Management ... [XUSITEMGR]
Clean old Job Nodes in XUTL [XQ XUTL $J NODES]
```

User stacks for each user's job are stored in the ^XUTL global.



REF: For more information, see the "^XUTL Global: Structure and Function" section.

This is also called the compiled menu system. If a job ends abnormally (e.g., upon error, UCI switching, or developer exits that bypass ^XUS), the entries remain in the global (this explains why developers are advised to halt out of programmer mode with D ^XUSCLEAN rather than simply halting.)

The purge routine sets a purge date of seven days in the past. Any user stack in ^XUTL older than seven days is purged. Any entries with a matching \$J at the top level of ^UTILITY and ^TMP are also KILLed.

Next, after cleaning out the user stacks in ^XUTL, the purge routine checks ^UTILITY and ^TMP. Any entry at subscript (\$J) or (namespace, \$J) that does not have a matching entry in the user stacks in ^XUTL is KILLed.

Next, the purge routine checks ^XTMP. Any entry in ^XTMP at subscript (namespace) lacking a header node at (namespace,0), or with a purge date in the header node less than the purge date determined by the purge routine is KILLed.

Finally, the purge routine goes through the signon nodes stored at ^XUSEC(0,"CUR",DUZ,DATE). Any nodes older than the purge date are KILLed.

The XQ XUTL \$J NODES option should be queued to run on a regular basis. If separate copies of ^XUTL are maintained on different CPUs, separate entries should be made in the OPTION SCHEDULING file for each CPU so that a separate job purges each CPU's XUTL global. Because this option deletes any user stacks that are time-stamped with a date earlier than the purge date determined by this option (seven days) you need to take care how frequently you schedule it (in the unusual event of a seven-day long job, this option should obviously not be run).

8.5.2 Rebuilding Primary Menu Trees

Figure 97: Building primary menu trees options

PARENT OF QUEUABLE OPTIONS

Non-interactive Build Primary Menu Trees

Menu Management ...

Build Primary Menu Trees

[XQBUILDTREEQUE]

[XUMAINT]

[XQBUILDTREE]

The menu system uses local menu trees to process requests. When changes are made to the menu structure, the local menu trees are rebuilt (a process also known as microsurgery). If a user attempts an "Up-arrow Jump" when the local trees need to be rebuilt or are being rebuilt, a message is issued about quick access being temporarily disabled; the user is *not* able to jump to reach the option. Microsurgery is triggered in the following situations:

- The option Edit options is used.
- An Out-of-Order option set is enabled or disabled.
- A sufficiently large number of changes have been made to a menu tree.

It is also recommended to rebuild all primary menu trees every other day during non-peak hours, using the XQBUILDTREEQUE option. If separate copies of ^XUTL are maintained on different CPUs, separate entries should be made in the OPTION SCHEDULING file (#19.2) for each CPU so that a separate job rebuilds each CPU's ^XUTL global.

Primary menu trees can also be built/repaired immediately using the Build Primary Menu Trees option. In particular, if menu jumping has stopped working and microsurgery is not fixing the menus, use the Build Primary Menu Trees option to force a menu rebuild to fix the problem.

8.6 Error Messages during Menu Jumping

There are some conditions under which a menu jump may not be completed. In these cases the user sees one of the following error messages:

Figure 98: Menu jump error message (1 of 6)

```
I NEED TO REBUILD MENUS .... QUICK ACCESS IS TEMPORARILY DISABLED Please proceed to {target option's menu text}
```

This means that the time stamps on the OPTION file (#19) and the ^XUTL global indicate that the OPTION file (#19) has been modified since the menus were compiled in ^XUTL and the global is therefore locked until XQ8 can recompile the modified menus. This error message can be generated by both user-generated jumps and phantom jumps.

Figure 99: Menu jump error message (2 of 6)

```
*** WARNING ***

Illegal jump requested to option `{option's menu text}' Jump pathway locked at option `{locked option's menu text}'
```

This indicates that a locked option for which the user does not possess the security key has been encountered in the tree between the option where the jump was requested and the target option to which the jump was requested. This error message can be generated by both user-generated jumps and phantom jumps.

Figure 100: Menu jump error message (3 of 6)

```
*** WARNING ***
Illegal jump was requested to option '{option menu text}' Jump path out of order from '{option's menu text}' with message '{out of order message}'
```

This means that an option on the tree between the option where the phantom jump was requested and the target option has been marked as out of order (OUT OF ORDER MESSAGE Field [#2] of the OPTION file [#19]). This error message can be generated by both user-generated jumps and phantom jumps.

Figure 101: Menu jump error message (4 of 6)

```
*** WARNING ***

Illegal jump was requested to option `{option menu text}' Variable XQUIT encountered at option `{option name}'
```

This means that the jump logic has encountered the variable XQUIT (detected with a \$DATA statement). This variable is usually set by an Entry Action (Field #20 of the OPTION file [#19]) and causes the menu system to refuse to run or jump past that option. This error message can be generated by both usergenerated jumps and phantom jumps.

Figure 102: Menu jump error message (5 of 6)

```
*** WARNING *** Background jump requested to option `\{value \ in \ XQMM("J")\}' but this option does not exist on your system.
```

A VA FileMan lookup was attempted for the option set in the variable XQMM("J") but no such option was found in the OPTION file (#19). This error message can only be generated from a phantom jump.

Figure 103: Menu jump error message (6 of 6)

```
*** WARNING ***
Background jump requested to option `{option's menu text}' but you do not have access to this option. See your computer representative.
```

This means that the target option requested by XQMM("J") is not in the tree of options to which this user has access (that is, the target option was neither in the user's primary menu tree nor specifically listed as a secondary menu for that user). This error message can only be generated from a phantom jump.



REF: For more information on phantom jumps, see the "Menu Manger: Developer Tools" chapter in the *Kernel Developer's Guide*.

8.7 ^XUTL Global: Structure and Function

The ^XUTL global is an account-specific global. It should exist in each production account on your system. This global is created primarily from information in the OPTION file [^DIC(19)] and is therefore sometimes referred to as "the compiled menu system."

^XUTL is divided into three main sections:

• User Stacks

```
^XUTL("XQ",$J)
^XUTL("XQT",$J) (MENU templates only)
```

Display Nodes

```
^XUTL("XQO",ien)
```

Jump Nodes

```
^XUTL("XQO","P" ien)
```

8.7.1 User Stacks

User stacks are stored in nodes in ^XUTL("XQ",\$J) and ^XUTL("XQT",\$J).

The example illustrated in Figure 104 shows a typical user stack. In this case the \$J is 541065826.

The "XQ" nodes can be divided into meaningful sets according to what is contained in the third subscript. The numeric third subscripts begin with the zero node which is set to the date and time in VA FileMan format by the program 'XUS1 when the user logs on or '%XUCI when the user is changing UCIs.

The other numeric, third subscripts (in this case the numbers 1 to 3) reflect the user's progression through the menu system. Each time a new option is invoked, a new node is created which contains the option number, concatenated with a "P", the number of the option whose compiled menu tree contains the

current option, a caret ("^"), and the zero-node of the OPTION file (#19) for that option. A different format is used for options in a user's secondary menu tree.

A pointer in the node ^XUTL("XQ", \$J, "T") indicates which option in this list of numbered nodes the menu driver is currently using. This pointer is set and reset by the menu driver as the user moves up and down the menu tree. In the example, XUPROGMODE is the option that the menu driver is currently using.

Other "XQ" nodes of the global that have a non-numeric third subscript are used to store various pieces of Kernel information that are set up at signon. ^XUTL("XQ",\$J,"XQM") points to the user's primary menu.

In the following example (Figure 104), the user's primary menu is OPTION file (#19) entry #29.

Figure 104: User Stack example

```
^XUTL("XO",541065826,0) = 2920113.081624
^XUTL("XQ",541065826,1) = 29P29^EVE^Systems Manager
                        Menu^^M^.5^^192^^^^^n^1^^^
^XUTL("XQ",541065826,2) = 31P29^XUPROG^Programmer Options^^M^^
                        XUPROG^^^^^n^^
^XUTL("XQ",541065826,3) = 49P29^XUPROGMODE^Programmer mode^^R
                         ^^XUPROGMODE^^^^^ n^^
^XUTL("XO", 541065826, "DUZ") = 63
^XUTL("XQ", 541065826, "DUZ(0)") = LlPp
^XUTL("XQ", 541065826, "DUZ(2)") = 16000
^XUTL("XQ",541065826,"IO") = _TNA5103:
^XUTL("XQ", 541065826, "IOBS") = $C(8)
^{\text{XUTL}(\text{"XQ"},541065826,\text{"IOF"})} = \#, $C(27,91,50,74,27,91,72)
^XUTL("XQ",541065826,"ION") = LAT DEVICE
^XUTL("XQ", 541065826, "IOS") = 158
^XUTL("XO", 541065826, "IOSL") = 24
^XUTL("XQ",541065826,"IOST") = C-VT100HIGH
^XUTL("XQ", 541065826, "IOST(0)") = 149
^XUTL("XQ",541065826,"IOT") = VTRM
^XUTL("XQ", 541065826, "T") = 3
^XUTL("XQ", 541065826, "XQM") = 29
```

8.7.2 XQT Nodes (MENU Templates)

The "XQT" nodes are used to create a stack of options similar to the "XQ" stack when a MENU template is invoked. These nodes are translated from the ^VA(200,DUZ,19.8) Multiple when a user precedes an option selection with a left square bracket character, "[", much like a PRINT template is invoked in VA FileMan. For example, if the user has defined a MENU template named "DOIT" using the Menu Template options of the User's Tool Box, typing "[DOIT" loads that sequence of options into the "XQT" nodes and begin executing them. When a MENU template is requested by the user, the option tree of that template is loaded into the "XQT" nodes and remains loaded as long as the user is logged on. Further requests for "[DOIT" uses that same stack.

8.7.3 Display Nodes

Display nodes are stored in 'XUTL("XQO", internal number).

The first example below (<u>Figure 105</u>) shows the display nodes for EVE, the System Manager's Menu. The internal number of EVE in this particular OPTION file (#19) is 29. In the first part of the example the option names and menu texts, along with a limited number of fields for that option compiled from the

OPTION file (#19), are concatenated together. It is from this part that XQ2 (the menu display program) gets the information it needs.

In the second part, all the menu texts and synonyms are listed in order in uppercase. It is here that XQ tries to match what the user entered at the terminal with the correct option. The third part of the example, the 0th node of the options, is listed by number and provides the remaining information that the Menu System may need to make the option work. To understand what the various "^" pieces mean, look at a VA FileMan global format data dictionary listing of the OPTION file (#19).

Illustrated in the second example (<u>Figure 106</u>) is the display node for the SECONDARY MENU OPTIONS of a user whose DUZ is equal to 66. Here, the user has only a single secondary menu called "Secondary Menu" (with an internal number of 580 in the OPTION file [#19]). The various parts of this example are identical to those of the Display Nodes for the EVE menu example above.



NOTE: The second subscript, instead of pointing to a menu in the OPTION file (#19), is a "U" concatenated with the user's DUZ which points to the NEW PERSON file (#200) entry. This is because secondary menu options are stored in the SECONDARY MENU OPTIONS field in the NEW PERSON file (#200) entry for each user.

Figure 105: Display Nodes for EVE example

```
^XUTL("XQO",29,0) = 2^55048,38923
^XUTL("XQO",29,0,1) = ^XUCORE^Core Applications ...^NOT
                        AVAILABLE^^^^^XUTIO^Device Handler
                        ...^^^n^^FM^DIUSER^VA FileMan ...^^^n^^XMMGR^
                        Manage Mailman ...^^^^^XUMAINT^Menu Management
                        ...^^^^n^^^XUPROG^Programmer Options ...^XUPROG^^^
^XUTL("XQO",29,0,2) = ^XUSITEMGR^Operations Management ...^^^^^XU-SPL-MGR
                         ^Spool Management ...^^^^^XUSPY^System Security
                        ...^^^^^ZTMMGR^Task Manager ...^^^n^^XUSER^User
                        Edit ...^^^^
^XUTL("XQO",29,"CORE APPLICATIONS") = 40^1
^XUTL("XQO",29,"DEVICE HANDLER") = 32^1
^XUTL("XQO",29,"FM") = 19^0
^XUTL("XQO",29,"MANAGE MAILMAN") = 30^1
^XUTL("XQO",29,"MENU MANAGEMENT") = 9^1
^XUTL("XOO",29,"OPERATIONS MANAGEMENT") = 174^1
^XUTL("XQO",29,"PROGRAMMER OPTIONS") = 31^1
^XUTL("XQO",29,"SPOOL MANAGEMENT") = 415^1
^XUTL("XQO",29,"SYSTEM SECURITY") = 226^1
^XUTL("XQO",29,"TASK MANAGER") = 83^1
^XUTL("XQO",29,"USER EDIT") = 39^1
^XUTL("XQO",29,"VA FILEMAN") = 19^1
^XUTL("XQO",29,"^",9) = ^XUMAINT^Menu Management^^M^^^105^^^n^n^^^^
^XUTL("XQO",29,"^",19) = FM^DIUSER^VA FileMan^^M^^^^n^^^n^1^^
^XUTL("XQO",29,"^",30) = ^XMMGR^Manage Mailman^^M^^^299^^^^54^^1^1^^^
^XUTL("XQO",29,""^",31) = ^XUPROG^Programmer Options^^M^^XUPROG^^^^^n^^
^XUTL("XQO",29,"^",32) = ^XUTIO^Device Handler^^M^^^413^^^n^^20^n^^
^XUTL("XQO",29,"^",39) = ^XUSER^User Edit^^M^^^153^^^^^n^^
^XUTL("XQO",29,"^",40) = ^XUCORE^Core Applications^1^M^^^^^^^^^
^XUTL("XQO",29,"^",83) = ^ZTMMGR^Task Manager^^M^^^^^n^^50^^1^^
^XUTL("XQO",29,"^",174) = ^XUSITEMGR^Operations Management^^M^^^^^^y^^n^^
^XUTL("XQO",29,"^",226) = ^XUSPY^System Security^^M^^^^^119^n^^
^XUTL("XQO",29,"^",415) = ^XU-SPL-MGR^Spool Management^^M^^^419^^^^20^^
```

Figure 106: Display Nodes for a secondary menu

```
^XUTL("XQO","U66",0) = 1^54927,30758

^XUTL("XQO","U66",0,1) = ^ZZTSTSM^Secondary Menu ...^^^n^^

^XUTL("XQO","U66","SECONDARY MENU") = 580^1

^XUTL("XQO","U66","^",580) = ^ZZTSTSM^Secondary Menu^^M^^^^^n^^^1^^1
```

8.7.4 Jump Nodes

Jump nodes are stored in ^XUTL("XQO", "P"_internal number), where there is one "P_..." entry in ^XUTL("XQO") for each primary menu that exists. The jump nodes, for each primary menu, store the pathways to all options that can be jumped to.

The jump nodes are created in the XQ8* series of programs. They are very similar to display nodes, except that:

- They have a "P" concatenated on the front of the primary option's number in the second subscript.
- These nodes describe the entire primary menu tree rather than just the single level tree.

Examples of the jump nodes for a single primary menu are shown in <u>Figure 107</u> and <u>Figure 108</u>. Since these nodes can be very extensive in number, some nodes have been removed from the examples to save space.

In the first example (<u>Figure 107</u>) are the "lookup" nodes, where the jump software tries to match a menu text or synonym with what the user has entered at the terminal. Each node is set to its internal number in the OPTION file (#19) and, in the second "A" piece, a 0 if it is a synonym or a 1 if it is menu text.

In the second example (<u>Figure 108</u>), the "menu pathway" entries below the "P580" node show all of the options that can be jumped to from the primary menu whose internal entry number (IEN) is 580. Each entry contains lists of the series of options that *must* be navigated through in a jump from the primary menu. In the case of the option DILIST (# 17), the list of options that have to be processed is 520,519,518,411,17. If, as in the case of ZZTEST4 (# 318), there is more than one possible pathway, then each is listed along with various other necessary pieces of information (e.g., locks, time restraint, etc.).

Figure 107: Jump Nodes example—Lookup nodes

```
^XUTL("XQO","P580",0) = 55165,28536

^XUTL("XQO","P580","19^") = 394^0

^XUTL("XQO","P580","2ND SECOND LEVEL MENU TEST^") = 575^1

^XUTL("XQO","P580","3^") = 518^0

^XUTL("XQO","P580","ACTN^") = 391^0

^XUTL("XQO","P580","ALL^") = 420^0
```

Figure 108: Jump Nodes example—Menu Pathways

```
^XUTL("XQO","P580","LIST FILE ATTRIBUTES^") = 17^1
^XUTL("XQO","P580","TEST 4^") = 318^1
^XUTL("XQO","P580","TOOL^") = 581^0
^XUTL("XQO","P580","X-TYPE OPTION TEST^") = 576^1
^XUTL("XQO","P580","X^") = 576^0
^XUTL("XQO","P580","ZDAVE^") = 411^1
^XUTL("XQO","P580","^",5) = ^XUEDITOPT^Edit
                                options^^E^581,5,^^106^^^^20^n^^^
^XUTL("XQO", "P580", "^", 17) = ^DILIST^List File Attributes^^A
                               520,519,518,411,17,^^^^n,^y^^n^1^^^
^XUTL("XQO","P580","^",318) = ^ZZTEST4^Test
                                4^^0^520,575,397,318,^^^^n,^^^^^
^XUTL("XQO", "P580", "^", 318, 0) = 2
^XUTL("XQO","P580","^",318,0,1) = 520,575,578,397,318,^^^n,^
^{XUTL}(^{XQO''}, ^{P580''}, ^{^{*}}, ^{318}, 0, 2) = 520, 575, 578, 318, ^{^{n}}, ^{^{n}}
^XUTL("XQO","P580","^",579) = ^ZZLEVEL3B^Phantom
                               Mother^^M^520,575,579,^^^^n,^^^1^1^^1
^XUTL("XQO","P580","^",580) = ^ZZTSTPM^Primary Menu^^M^^^^^n^^^1^1^^1
^XUTL("XQO","P580","^",581) = ^ZZLUKTOOLS^Luke's
                                Tools^^M^581,^^^^^^1^1^^1
```

8.8 Menu Startup Parameter

The XQ MENUMANAGER PROMPT parameter was provided with Kernel patch XU*8.0*614. This parameter is checked during menu startup. It allows sites to change the default **<TEST ACCOUNT>** prompt to another value (e.g., **<LEGACY SYSTEM>**) in menu prompts of *non*-production VistA systems. The text defined by this parameter is inserted in the Menu Manager prompts. If no text is defined, the hard-coded default is "**<TEST ACCOUNT>**". Alternatives could be:

- "<LEGACY SYSTEM>"
- "<CONTINGENCY>"
- "<READ ONLY>"
- Any other value from 3 to 20 characters, depending upon the purpose of the non-production VistA system.

To change the value on a non-production system, use the General Parameter Tools option [XPAR MENU TOOLS] and select "EP Edit Parameter Values." You have to log off and log back into VistA to see the changed menu prompt.



NOTE: The prompt can be set in advance on a production system before it is mirrored to a non-production system, and the prompt only appears on the *non*-production system.

8.9 Menu Manager Variables (Troubleshooting)

There is a group of Menu Manager variables that is always defined. It may be useful for system administrators to know what these variables signify when investigating errors. If an error is reported in VA FileMan's DIP routine, for example, knowing the value of XQY at the time of the error indicates which option was invoking the DIP routine. The option can then be reviewed to discover the name of the routine that was calling DIP.

Table 10: Menu Manger variables (always defined)

Variable	Description
XQABTST	Flag that signals whether alpha-beta testing is in effect.
XQDIC	Internal entry number (IEN) of the option's parent (which <i>must</i> be a menu) in the OPTION file, if an option is executing. If the user is in a menu, XQDIC is set to the IEN of the current menu's parent (unless they are in their primary menu, in which case XQDIC is set to the IEN of the primary menu).
	The value of XQDIC also corresponds to the second subscript in the display nodes portion of the ^XUTL global, ^XUTL("XQO",) for the menu in question.
XQPSM	Like XQDIC, a lookup value into the second subscript of ^XUTL, the compiled menu global. XQPSM points to the tree of the target option in the jump. It resulted from the ability to jump to any option, not just ones on the primary menu tree. It can help identify jumps from a primary, secondary, or Common option.
XQT	Current option's type (e.g., M for menu, A for action).
XQUR	User's response to the menu prompt (replaces A).
XQUSER	User's name in the form SEVEN A. XUUSER.
XQY	Internal entry number (IEN) of the current option or menu (replaces Y).
XQY0	First node (subscript of zero) of the current option (replaces Y(0)).
XQXFLG	Contains several flags, including whether capacity management testing is active.

8.10 Security Keys

8.11 User Interface

Security keys are primarily used to allow access to specially protected options. If a software application exports a menu that has one or two options that require a secured level of access, they can use security keys to lock those special options. When an option is locked, you can only use the locked option if you hold the security key matching the key with which the option was locked.

Entering two question marks ("??") at the menu system's select prompt displays the current options. If any of the options are locked, that fact is listed also, along with the names of any associated security keys. In the following example, the option Programmer Options is locked with a security key named XUPROG:

Figure 109: Sample locked menu options showing required security key—Entering two question marks (??)

```
Select Systems Manager Menu Option: ??

Device Handler ... [XUTIO]


Menu Management ... [XUMAINT]

Programmer Options ... [XUPROG]

**> Locked with XUPROG
```

You can list which security keys you currently hold by using the Display User Characteristics option on the Common menu. It displays a list of all security keys you hold, similar to the following:

Figure 110: Display User Characteristics option—Sample output



The security keys you need to carry out computing activities should be assigned by system administrators when your computer account is first added to the system. Other keys can be allocated at a later time by system administrators or designee (e.g., an application coordinator) with the use of the Secure Menu Delegation menu utilities.

8.12 System Management

8.12.1 Identifying Locked Options

System administrators can list which security keys lock what options by using Menu Management's Diagram Menus option. The following example (Figure 111) shows that the Programmer Options menu is locked with the XUPROG security key. It also shows that one of its options, Programmer mode, is locked with the XUPROGMODE security key:

Figure 111: Diagram Menus option—Sample user dialogue

Security keys are stored in the SECURITY KEY file (#19.1). Security keys given to users are stored in the users' NEW PERSON file (#200) entries, in the KEYS field (Multiple).

Options are locked by a given security key when the name of that key is entered into the LOCK field (#3) of the OPTION file (#19). If an option is locked, users need to be given the security key in order to invoke the option.

8.12.2 Key Management

Keys are defined and allocated to users with options on the Key Management menu.

Figure 112: Key Management menu options

```
SYSTEMS MANAGER MENU ...
                                                                                [EVE]
                                                                            [ TILAMUX]
 Menu Management ...
    Key Management ...
                                                                          [XUKEYMGMT]
      Allocation of Security Keys
                                                                           [XUKEYALL]
       De-allocation of Security Keys
                                                                         [XUKEYDEALL]
       Enter/Edit of Security Keys
                                                                          [XUKEYEDIT]
       All keys a user needs
                                                                            [XOLOCK1]
       Change user's allocated keys to delegated keys
                                                                       [XQKEYALTODEL]
       Keys for a given menu tree
                                                                           [XQLOCK2]
       Delegate keys
                                                                           [XQKEYDEL]
                                                                          [XQSHOKEY]
       List users holding a certain key
       Remove delegated keys
                                                                          [XOKEYRDEL]
       Show the keys of a particular user
                                                                          [XQLISTKEY]
```

8.12.3 Allocating and De-allocating Security Keys

The main option to assign security keys to a user or users is the Allocation of Security Keys option [XUKEYALL]. Allocating a security key to a user lets them invoke options that are locked with the key. For options with reverse locks, allocating the security key locks the user out from the option. In either case, allocating the key to a user does *not* allow the user to give the key to anyone else.

To remove a security key from a user, use the De-allocation of Security Keys option [XUKEYDEALL].

Unless you have been delegated a security key, the only way you can allocate or de-allocate keys is if you hold the XUMGR security key or have a FILE MANAGER ACCESS CODE field (#3) of "@".



REF: For more information on delegating security keys, see the "<u>Delegating Security Keys</u>" section.

All of the security keys that a new user needs to use their assigned options can be determined by using the All Keys a User Needs option on the Key Management menu [XQLOCK1]. This produces a list of the primary and secondary menus for that user, and compiles a list of the keys for that menu tree. This list can then be assigned or delegated. It can also be edited before the keys are given to the user. Similarly, the Keys For a Given Menu Tree option [XQLOCK2] examines a menu and lists all of the security keys associated with all sibling options.

8.12.4 Delegating Security Keys

Delegating keys allows you to give a user the ability to assign specific security keys to other users, as opposed to the XUMGR security key and "@" VA FileMan Access code (i.e., FILE MANAGER ACCESS CODE field [#3]), which allow all keys to be assigned.

One way to delegate security keys is to use the Change user's allocated keys to delegated keys option [XQKEYALTODEL]. This option delegates to a user all of the security keys that are currently allocated to that user. Any entries in their KEYS field (Multiple) are entered in the DELEGATED KEYS field (Multiple) as well. They can now use the Allocation of Security Keys option [XUKEYALL] to give the security keys to others.

Alternatively, system administrators can use the Delegate keys option [XQKEYDEL] to populate the DELEGATED KEYS field (Multiple) one-by-one.

A user who has been delegated a security key can allocate that key to others in two ways:

- Through the Allocation of Security Keys option [XUKEYALL], if it is on their menu.
- By delegating an option locked by the security key in question; the key is allocated along with the option.

The key recipients (excepting holders of the XUMGR security key or a FILE MANAGER ACCESS CODE field [#3] of "@") *cannot* assign the security key to others, however, even if they have access to the Allocation option, because the key does not exist in their DELEGATED KEYS field (Multiple).

One example of key delegation is a system administrator designee, delegated the Provider key, who allocates that key to incoming medical residents.

For security reasons, users who have a key in their DELEGATED KEYS field (Multiple) *cannot* allocate that key to themselves. That key *must* be awarded by another user who has been delegated the key or by a system administrator who holds the XUMGR system security key.

8.12.5 Creating and Editing Security Keys

Keys can be created using the Enter/Edit of Security Keys option [XUKEYEDIT] on the Key Management menu. If a security key has already been defined, its name *cannot* be edited. It also *cannot* be deleted, as discussed below. Other key attributes stored in the SECURITY KEY file (#19.1) can be used for special purposes. Attributes of the Provider key are shown in the following example:

Figure 113: Attributes for the Provider security key—Sample user dialogue

```
No editing.

Name: provider// <enter>
DESCRIPTIVE NAME: provider// <enter>
PERSON LOOKUP: LOOKUP// <enter>
KEEP AT TERMINATE: YES// <enter>
DESCRIPTION:
1>This KEY is given to all entries in the New Person file that need
2>to be looked up as a Provider. Those entries that hold this key
3>are considered to be providers. It was given to all active
4>Providers in file 6 at the time of the Kernel 7 install.
EDIT Option: <enter>
Select SUBORDINATE KEY: <enter>
GRANTING CONDITION: <enter>
```

8.12.5.1 PERSON LOOKUP

As described in the "Security Keys: Developer Tools" chapter in the *Kernel Developer's Guide*, a special AK cross-reference on the NEW PERSON file (#200) is maintained automatically for anyone who is granted a security key that is flagged for Person Lookup. This cross-reference has been introduced to facilitate identification of user groups, like providers.

8.12.5.2 KEEP AT TERMINATE

As described in the "<u>Signon/Security</u>" section concerning user deactivation, security keys that are marked as "KEEP AT TERMINATE" is *not* removed as a user attribute of terminated users. This allows the continued processing of activities that had been previously authorized (e.g., for billing purposes, notes, pending orders, or other actions), because the user held the security key.

For example, the PROVIDER security key KEEP AT TERMINATE field is set to **YES** in case a medical order continues to hold an approved status, even though the authorizing provider had been deactivated. As another example, the AudioCare (COTS) pharmacy software depends on the PROVIDER key remaining. The renewal process (OR*3*336, ORAREN routine) looks at the original order and creates a new order with the same information, sending an alert to the provider to review and sign the order. If the original provider is no longer active, the order still gets created, but the alert gets forwarded to a surrogate or backup reviewer for signature of the order.

8.12.5.3 SUBORDINATE KEY (Exploding Keys)

If a security key has any associated subordinate keys (i.e., entries in the SUBORDINATE KEY Multiple field), the subordinate keys are automatically assigned along with the overall key. A security key with this feature is called an exploding key, since it and its subordinates are assigned all at once.



NOTE: If entries in the SUBORDINATE KEY Field (Multiple) are edited, dynamic updating of the security keys already assigned to users does *not* occur.

Exploding security keys *cannot* be exported with software, although, there may be support for this functionality in the future. They are intended to be created by system administrators as a timesaving method in the key allocation process.

8.12.6 Deleting Security Keys

Keys should not be deleted from the SECURITY KEY file (#19.1). Kernel has made the NAME field (#.01) of the SECURITY KEY file (#19.1) uneditable to prevent deletion of security keys through VA FileMan. System administrators should *not* attempt to edit the key global directly to remove a key, since associated pointing relationships are left to cause errors. The one mechanism Kernel does provide for deletion of security keys is through the Kernel Installation and Distribution System (KIDS).



REF: For more information on KIDS, see the "<u>Kernel Installation and Distribution System</u>" section in this manual and the "KIDS Developer Tools" section in the *Kernel Developer's Guide*.

8.12.7 Reindexing All Users' Security Keys Option

Figure 114: Reindex the users key's option

```
SYSTEMS MANAGER MENU ... [EVE]
User Management ... [XUSER]
Manage User File ... [XUSER FILE MGR]
Reindex the users key's [XUSER KEY RE-INDEX]
```

You can use the Reindex the users key's option [XUSER KEY RE-INDEX] to re-index all users' security keys in the NEW PERSON file (#200). If a user has a security key, but is lacking the corresponding ^XUSEC cross-reference for the key, you can use this option to regenerate the ^XUSEC cross-reference. While the ^XUSEC cross-reference is being rebuilt, there can be an impact on all users with security key lookups failing in ^XUSEC until the index is entirely rebuilt; therefore, this option should be used with caution and is best delayed until users are not signed on.

8.12.8 Using Security Keys with Reverse Locks

If a security key is associated with an option via the REVERSE/NEGATIVE LOCK field, rather than the LOCK field (#3), it functions to lock out users who hold the key. The security key used for a reverse lock is just like any other key, differing only in the way it is associated with an option. Menu Management's Diagram Menus option indicates the existence of any reverse locks, such as the use of the XMNOPRIV security key to prevent access to MailMan's shared mail facility.

The typical use of a security key with the REVERSE/NEGATIVE LOCK field is to restrict access to options otherwise available to all users (e.g., MailMan User and other options on the Common menu).

8.12.9 Security Key Delegation Levels

Starting with Kernel 8.0, security keys are subject to delegation levels just as options are subject to delegation levels. A field in the NEW PERSON file (#200), DELEGATION LEVEL, stores a user's delegation level (for security keys and options). When a security key is delegated, the person to whom it is delegated is assigned a level one number lower than the delegation level of the person doing the delegating. This is to prevent the delegated-to person from removing DELEGATED KEYS from someone with a lower delegation level.



REF: For more information about delegation levels, see the "Secure Menu Delegation" section.

9 Secure Menu Delegation

The job of allocating menu options to users can be a time-consuming activity, so site managers may want to consider delegating this responsibility to application coordinators. Application coordinators are familiar with the menus for their software and can learn how to assign these to new users in their service area.

Secure Menu Delegation allows the Site Manager to delegate the management of certain menu options to another user (e.g., an application coordinator). This user, now a delegate, can then assign these as primary or secondary options (along with their security keys) to users who fall under their administrative jurisdiction.

For example, the Site Manager might delegate the management of the Laboratory software options to the Lab Application Coordinator (LAC), and the LAC could then allocate or remove options from everybody in the Laboratory software. The system is set up in such a way that the LAC could also delegate, with the Site Manager's permission and manager's menu, the management of all the chemistry menus to the head of the Chemistry Section, and so on, creating another level of delegation.

There are two divisions in Secure Menu Delegation:

- The menu to create and manage delegates.
- The menu for the delegates themselves to assign options to end users.

9.1 User Interface: Acting as a Delegate

As a delegate, you have been delegated options (usually by system administrators). If you have been delegated options, you can assign these options to computer users on the computer system.

As a delegate, you can assign the following options to your users:

- Options that have been delegated to you.
- Menus that you have created from options delegated to you.
- Options you have created from VA FileMan templates.

As a delegate, you need to understand the basic structure of the OPTION file (#19), which is a file that points back to itself. That is, a menu is an entry in the OPTION file (#19); but items on menus are themselves pointers to other entries in the OPTION file (#19). You should also understand the difference between types of options, be familiar with menu trees, and be sufficiently reluctant to assign great numbers of secondary menus.

9.1.1 Delegate's Menu

To delegate options to users, you need to be assigned a menu called Delegate's Menu Management [XQSMD USER MENU], which is located under the Secure Menu Management menu. The options on the Delegate's Menu Management menu are as follows:

Figure 115: Delegate's Menu Management options

```
Delegate's Menu Management

Build a New Menu

Edit a User's Options

Copy Everything About an Option to a New Option

Copy One Users Menus and Keys to others

Limited File Manager Options (Build)

[XQSMD EDIT OPTIONS]

[XQCOPYOP]

[XQCOPYOP]

[XQSMD COPY USER]
```

Each of these options on the delegate's menu is discussed in the topics that follow.

9.1.2 Edit a User's Options Option

Using the Edit a User's Options option [XQSMD EDIT OPTIONS] allows you to edit a user's primary and secondary menus. This is the chief method you can use to add (and subtract) options on your users' menus.

Most of your work is in adding and deleting options on your users' secondary menus. You are only able to add or delete options from a user's secondary menu if the option in question has been delegated to you. That means that you do not have access to a user's entire secondary menu; instead, only those options on the secondary menu that are also delegated to you.

If, when you edit a user's secondary menu, you choose an option that is already on a user's secondary menu, you are asked if you want to delete it from their secondary menu. Otherwise, you are asked if you want to add the option to their secondary menu.

If you are assigning an option that is locked with a security key, the delegation process checks whether you have been delegated the key as well. If you have, the key is automatically assigned to the user along with the option. If you have not been delegated the key, you get an error message saying that you have not been delegated the needed security key (the option is assigned to the user, but they do *not* have the key to unlock the option).

If you delete an option that is locked with a security key and that key is delegated to you (and you are at a higher key delegation level than the option holder), the key is deleted along with the option (unless the user holds another option locked by the same security key).

In the following example (<u>Figure 116</u>), the LRZ MAIN menu option is added to the user's secondary menu. LRZ MAIN is locked with a security key and that key is automatically assigned when the option is assigned:

Figure 116: Edit a User's Options—Sample user dialogue

```
Select Delegate's Menu Management Option: EDIT A USER'S OPTIONS

Select NEW PERSON NAME: XUUSER, FIVE
PRIMARY MENU OPTION: XMUSER// <Enter> MailMan Menu .
No keys needed to delete!.
No keys needed to give!

SECONDARY MENU OPTION: LRZ MAIN <Enter> Lab User Menu ...
ZZLRMAIN key also given!

SECONDARY MENU OPTION: <Enter>

Select NEW PERSON NAME:
```

Unlike secondary menus, you are only able to edit a user's PRIMARY MENU OPTION if their current primary menu is an option that has been delegated to you. Otherwise, you are not allowed to change that user's PRIMARY MENU OPTION.



NOTE: You *cannot* add or subtract options on a user's primary menu; you can only replace the user's entire PRIMARY MENU OPTION with another one.

9.1.3 Build a New Menu Option

Using the Build a New Menu option [XQSMD BUILD MENU], located on the Delegate's Menu Management menu [XQSMD USER MENU], you can create new menus with menu items chosen from your delegated options.

First, you need to provide an option name for the new menu you are creating. The menu name prefix, used by the delegate to create local options, can be in one of two forms:

- (Preferred) A system administrator-assigned local namespace beginning with the letter "A" (e.g., A6A).
- (Discouraged) Package namespace (e.g., LR) to which the user *must* add the letter "**Z**" (e.g., LRZ) in order to avoid conflict with national releases.



NOTE: As of Kernel patch XU*8.0* 482, options in the **A*** namespace can be created *without* adding a "**Z**" to the end of the package namespace.

Once you provide a name for the menu, you are asked to provide the following information:

- Text for the menu.
- Description for the menu.
- Items for the menu (choose from your delegated options).

Once you have created a new menu, you can assign it to your users just as if it were an option delegated to you.

9.1.4 Copy Everything About an Option to a New Option Option

Using the Copy Everything About an Option to a New Option option [XQCOPYOP], you can copy any option on the computer system into a new option. First you are asked which existing option you would like to copy; then, you are asked for a name for the copied option. The option name *must* begin with a namespace assigned to you by the system administrators.

9.1.5 Copy One Users Menus and Keys to others Option

Using the Copy One Users Menus and Keys to others option [XQSMD COPY USER], you can copy the menus and security keys of one user to another user. Each menu or security key you copy, however, *must* have been delegated to you; otherwise, they are skipped in the copy process. What gets copied from one user into the other user are:

- PRIMARY MENU OPTION (and all descendant menus).
- SECONDARY MENU OPTIONS.
- KEYS.

The PRIMARY MENU OPTION of the user you're copying from *replaces* the PRIMARY MENU OPTION of the user you are copying to. The SECONDARY MENU OPTIONS and the KEYS of the user you're copying from are *merged* into the SECONDARY MENU OPTIONS and the KEYS of the user you're copying to.

9.1.6 Limited File Manager Options (Build) Option

The Secure Menu Delegation system provides a way for delegates to create options out of VA FileMan templates. Delegates who have enough access to VA FileMan to create INPUT, SORT, or PRINT templates can create menu options for their users that directly call these templates.

9.1.6.1 Characteristics of Intended Users

The Limited File Manager Options (Build) option [XQSMD LIMITED FM OPTIONS] is designed for delegates, such as some application coordinators who have VA FileMan access to a set of files and can create INPUT, SORT, or PRINT templates. These delegates may have the VA FileMan options for editing or printing without the ability to modify data dictionaries. They may also have explicit file access to a specified set of files via the File Access Management system. Typically they would be working without the special FILE MANAGER ACCESS CODE field (#3), DUZ(0).

9.1.6.2 System Administrator Setup to Enable Building Options from Templates

To allow a user to create menu options from VA FileMan templates, system administrators *must* first assign to the user:

- Delegate's Menu Management menu [XQSMD USER MENU].
- XQSMDFM Security Key.
- A namespace beginning with the letter "A" (e.g., A6A) in which to create options. To do this, use the Specify Allowable New Menu Prefix option [XQSMD SET PREFIX] located on the Secure Menu Delegation menu [XQSMD MGR]. System administrators are discouraged from assigning package namespaces (e.g., LR) to which the user *must* add the letter "Z" (e.g., LRZ) to avoid conflict with national releases.

9.1.6.3 Building Options

The tool for building options with VA FileMan templates is called the Limited File Manager Options (Build) option [XQSMD LIMITED FM OPTIONS]. It is part of the Delegate's Menu Management menu under the Secure Menu Management menu and is locked with the XQSMDFM security key.

First, you *must* have created a SORT, PRINT, or INPUT template for a VA FileMan file. Once you have created a template, you can make this template available as an option to your users by turning it into an option.

You can create three types of options:

- Edit-type option (from an EDIT template).
- Print-type option (from PRINT and SORT templates).
- Inquire-type option (from either a PRINT template or a file name).

Once you have turned the template into an option, you can assign that option to your users as you deem necessary. Then, when a user uses the option, they execute the PRINT, SORT, or INPUT template from which the option was created.

Suppose you have created a PRINT template called LRZ REFERRAL PRINT for the Lab's REFERRAL file. To turn this PRINT template into an Inquire option, use the Limited File Manager Options (Build) option, as shown below:

Figure 117: Limited File Manager Options (Build)—Sample user dialogue

```
Select Delegate's Menu Management Option: LIMITED FILE MANAGER OPTIONS (BUILD)
The menu options you build or edit must begin with the namespace:
The option types that may be built are P(rint), E(dit), and I(nquire), and
you must have a template or templates ready to be included in the option.
Or enter D(elete) to DELETE an option
Select Option Type (P/E/I/D): I
     Enter Print Template Name (Optional): LRZ REFERRAL PRINT
     Option Name: LRZ REFERRAL INQUIRE
 Located in the LR (LAB SERVICE) namespace.
 ARE YOU ADDING 'LRZ REFERRAL INQUIRE' AS A NEW OPTION (THE 996TH)? Y <Enter>
   OPTION MENU TEXT: DISPLAY A REFERRAL
MENU TEXT: Display a Referral Replace <Enter>
DESCRIPTION:
  1> Display Lab Referral entries (option created by LAB ADPAC).
  2> <Enter>
EDIT Option: <Enter>
Select Delegate's Menu Management Option:
```

9.2 System Management: Managing Delegates

The options for creating and managing delegates are on the Secure Menu Delegation menu [XQSMD MGR], which is on the Menu Management menu. Typically, system administrators would be the sole holder of this menu. The options on this menu are:

Table 11: Secure Menu Delegation menu options

Option Text	Function
Select Options to be Delegated	Delegate options
List Delegated Options and their Users	Print Report
Print All Delegates and their Options	Print Report
Remove Options Previously Delegated	Undo Delegation
Replicate or Replace a Delegate	Copy a Delegate
Show a Delegate's Options	Print Report
Delegate's Menu Management	Delegate's menu
Specify Allowable New Menu Prefix	Assign namespaces

The main options to create and manage delegates are:

- Select Options to be Delegated
- Replicate or Replace a Delegate

9.2.1 Delegating Options: Select Options to be Delegated Option

To delegate options, use the Select Options to be Delegated option [XQSMD ADD] from the Secure Menu Delegation menu. Using this option is a two-step process:

- 1. Choose the users to whom options are delegated.
- 2. Choose which options to delegate to that group of users.

You can choose to set up one user or many users as delegates. You can choose one option or a group of options to delegate to them.

You also need to assign (*not* delegate!) the Delegate's Menu Management menu [XQSMD USER MENU] to the delegate; this menu gives delegates the means to assign delegated options to users.

Figure 118: Delegating Options: Select Options to be Delegated option—Sample user dialogue

```
Select Secure Menu Delegation Option: SELECT OPTIONS TO BE DELEGATED
Enter the name(s) of your delegate(s), one at a time
Name: XUUSER, THREE
Name: XUUSER, FOUR
Name: <Enter>
Enter options you wish to DELEGATE TO these users
Add option(s): XUINQUIRE
Add option(s): XUUSERACC
Add option(s): <Enter>
For the following user(s):
1. XUUSER, THREE
2. XUUSER, FOUR
You will delegate the following options:
XUINOUIRE
            Inquire
XUUSERACC Diagram Menus
Delegated by XUUSER, FIVE on Jul. 21, 2004 3:55 PM.
Ready to delegate these options to these people? Y// <Enter>
Request to add delegated options has been queued, task # 465,
    named: XUUSER, FIVE adding delegated options.
```

9.2.1.1 Delegating Security Keys

If options that you intend to delegate are locked with security keys, you need to delegate the matching keys to the delegate; otherwise, the delegate is *not* able to assign keys to unlock options they have assigned to their users.

If the option is locked with a security key that you possess, the Select Options to be Delegated option branches you to the Key Management program, and lets you allocate (if you so wish) the appropriate keys to the delegates you are creating.

However, to assign security keys to users, the delegate *must be delegated* the key. To do that, you need to use the Key Management menu option, Delegate keys option [XQKEYDEL]. This option allows you to delegate security keys to delegates by populating the DELEGATED KEYS field (Multiple) in their NEW PERSON file (#200) entry. Security keys entered in a delegate's DELEGATED KEYS Multiple allow them to allocate the entered keys to other users (but not themselves).

When a delegate assigns options to a user, they can assign the matching security keys as part of that process. However, as an enhancement to a delegate's ability to work with keys, system administrators can assign the delegate the following options from the Key Management menu:

- Allocation of Security Keys
- De-allocation of Security Keys
- Show the Security Keys of a Particular User

As long as the delegate does not hold the XUMGR security key, which allows any key to be allocated, the Key Management menu options only allow delegates to allocate and de-allocate security keys they've been delegated. Kernel also follows key delegation levels with the Allocation of Security Keys and De-allocation of Security Keys options.



NOTE: Key management options *must* be separately assigned; they are not a part of the Delegate's Menu Management menu [XQSMD USER MENU].

9.2.1.2 Delegation Level (Options and Keys)

DELEGATION LEVEL is a field in the NEW PERSON file (#200) specifying the number of steps that a person is from the original delegation of options by the Site Manager (whose Delegation Level is 0). Starting with Kernel 8.0, the delegation level is also maintained for DELEGATED KEYS. For instance, if the Site Manager delegates all laboratory options to the Lab ADP Application Coordinator (ADPAC), then the Lab ADPAC would have a Delegation Level of 1. Should the Lab ADPAC further delegate a set of those options to the Chief of Chemistry, the Chief would have a level of 2, and so on.

The use of levels insures that supervision is not compromised such that the lower level user could alter menus or remove security keys of the higher level person. No attempt is made to determine who actually works for whom since that information is not available to the software. Delegation chains should therefore be constructed with some care.

To modify the set of options (and accompanying security keys) delegated to a particular person, you *must* have a Delegation Level equal to, or less than, the person you are trying to modify. If you create a new delegate by delegating some (or all) of the options delegated to you, that person has a Delegation Level equal to your level +1.

It may be necessary to modify Delegation Levels using VA FileMan as the organization's structure changes over time.

9.2.2 Further Delegation

The only way a delegate can delegate, rather than simply assign, options to someone else is if the delegate has access to the Select Options to be Delegated option [XQSMD ADD], or the Replicate or Replace a Delegate option [XQSMD REPLICATE]. These options should only be on the Secure Menu Delegation menu [XQSMD MGR]. You should carefully evaluate whether to give this menu to delegates (which gives them the right to further delegate).

9.2.3 Options too Sensitive to Delegate

Certain options (e.g., Programmer-related options) are considered too sensitive or powerful to be delegated. They are marked as not delegable in the OPTION file (#19), and the Secure MenuMan Delegation software does *not* delegate these options. The traditional methods of assigning these menu options must be employed by the Site Manager.

It should be noted that a higher-level option, such as EVE, would still give the delegate access to lower level options, such as XUMAINT, even though XUMAINT is itself marked in the OPTION file (#19) as non-delegable. The Delegation software does not follow the option trees down to insure that options of options are not delegable.



CAUTION: It is *highly recommended* that the Site Manager, Information Security Officer (ISO), or chief system administrator review the options marked as too sensitive to be delegated and, using VA FileMan, add any locally sensitive options to this list.

It is the responsibility of each site to insure that the security of the system is not violated.

9.2.4 Replicate or Replace a Delegate Option

You can copy the Delegated Options of a delegate to another user. Use the Replicate or Replace a Delegate option [XQSMD REPLICATE] to do this. The options that you transfer to another user do not replace any options the user has been previously delegated. They are added to those options, if any. Like the Select Options to be Delegated option, this option also can branch you to the security key allocation program for the new delegate.

You are also asked if the delegated options should be removed from the original delegate. If you say **NO** ("N"), the original delegate remains a delegate. If you say **YES** ("Y"), all Delegated Options are removed from the original delegate, who are no longer an active delegate. In order to remove the options from a delegate, however, you *must* have a Delegation Level lower than they do.

9.2.5 Remove Options Previously Delegated Option

To simply remove an option from a delegate's list of delegable options, use the Remove Options Previously Delegated option:

- 3. Enter the name or names of the delegates from which you want to remove options.
- 4. Enter the option or options you want to remove from the specified set of delegates.

You're given a chance to review the choices you made; if you say to proceed, a task is queued that removes the options you selected from the delegates you specified.

9.2.6 Specify Allowable New Menu Prefix Option

Use the Specify Allowable New Menu Prefix option to assign allowable menu prefixes to your delegates. Your delegates need to be given allowable new menu prefixes if they:

- Build new menus.
- Copy options.
- Create options from VA FileMan templates.

Typically, if your delegate works with one particular software application, you would assign them that software's namespace as an allowable prefix. Options that the delegate creates *must* then be prefixed with that namespace, appended with a Z.

If you do *not* specify an allowable prefix for a delegate, they are *not* able to use the following options:

- Build a New Menu
- Copy Everything About an Option to a New Option
- Limited File Manager Options (Build)

You can specify multiple new menu prefixes for a given delegate.

9.2.7 Reports

You can use the following options to generate reports about delegates on your system:

- List Delegated Options and their Users (Sort by delegated option.)
- Print All Delegates and their Options (Sort by delegate name.)
- Show a Delegate's Options
 (Display all delegated options for one delegate.)

10 Alerts

10.1 User Interface

When you receive an alert, something on the computer system is requesting your immediate attention. A software application might issue an alert to one or more users when certain conditions are met (e.g., depleted stock levels or abnormal lab test results).

The first time you reach a menu prompt after receiving a particular alert, the alert's message is displayed to you by the menu system. The alert message is displayed along with a standard notice to select the View Alerts "VA" option on the Common menu to process the alert (see Figure 119).

When you receive an alert, you should find out what the alert is asking of you, and attend to it. This is called processing the alert.

Until you process all unprocessed alerts you receive, you'll be reminded that you have pending alerts each time you are at a menu prompt. You do *not*, however, see the alert message; you only see that the first time you receive an alert and reach the menu prompt.

Figure 119: Alert—Sample user message

```
Dr. You need to enter a progress note on 'KRNPATIENT,ONE'.

Enter "VA VIEW ALERTS to review alerts

Select Systems Manager Menu Option:
```

10.1.1 Processing Alerts

To process alerts, choose the View Alerts "VA" option from the Common menu. The View Alerts "VA" option presents a list of all pending alerts, numbered consecutively with the most recent alerts listed first, with the exception of *Critical* alerts (as of Kernel patch XU*8.0*602):

- Critical alerts move to the top of the list and are shown in reverse video.
- Critical alerts are identified by strings of text contained in the ALERT CRITICAL TEXT file (#8992.3).

Information-only alerts are displayed with the letter "I" in front of the alert message. When you process Information-only alerts, all that happens is that they are removed from the pending alerts list. Their only purpose was to send you the one-line alert message.

When you process alerts that are *not* Information-only, processing the alert may send you to a particular option or program. Afterwards, you are returned to the View Alerts screen if more alerts need processing, or back to the menu prompt if no pending alerts remain.

There are various methods for processing alerts from the View Alerts screen. You can enter any of the following alert process codes (listed alphabetically):

Table 12: Alert processing codes

Process Code	Description	
Α	Process all alerts in the order shown.	
D	Delete specific alerts (some alerts <i>cannot</i> be deleted). Only listed if one or more INFORMATION-ONLY alerts have been listed. If unable to delete an alert, users see: "Unable to delete alerts which require action: n,n,n,"	
F	Forward one or more specific alerts. Forwarding may be sent as an alert to specific users or mail groups, a mail message, or sent to a specific printer.	
I	Process all INFORMATION-ONLY alerts. Only listed if one or more INFORMATION-ONLY alerts have been listed.	
М	List pending alerts in a mail message and deliver the message to your VistA MailMan IN basket.	
n	Single number to process a single alert.	
n,n,n-n	Range of numbers to process a range of alerts (e.g., 1,3,5-8).	
Р	Print a copy of the pending alerts to a printer.	
R	Redisplay available alerts.	
S	Add or remove a surrogate to receive alerts for you. An optional start and end date can also be entered.	
^	Exit the alert processing screen by entering a caret ("^").	

The Alert Handler ordinarily deletes alerts once you have processed the alert. If you have processed all pending alerts, and try to select the View Alerts "VA" option, nothing is displayed. View Alerts only offers a listing when there are pending alerts; if no alerts are pending, View Alerts simply returns you to the menu prompt.

Figure 120: View Alerts "VA" option—Sample user dialogue

```
ACCESS CODES: *******
VERIFY CODES: ******
Good evening One You last signed on Jan 9,2004 at 14:39
Dr. You need to enter a progress note on 'KRNPATIENT, ONE'.
          Enter "VA VIEW ALERTS to review alerts
Select Clinic Manager Menu Option: "VA
     Dr. You need to enter a progress note on 'KRNPATIENT, ONE'.
     Alk Phos elevated, schedule fu bone scan
3.I For your information, meeting at 12 noon, room 223
          Select from 1 to 3
          or enter ?, A, I, F, S, P, M, R, or ^ to exit: ?
YOU MAY ENTER:
   One or more numbers in the range 1 to 3 to select specific alert(s)
      for processing. This may be a series of numbers, e.g., 2,3,6-9
   A to process all of the pending alerts in the order shown.
   I to process all of the INFORMATION ONLY alerts, if any, without further ado.
   S to add or remove a surrogate to receive alerts for you
   {\tt F} to forward one or more specific alerts. Forwarding may be as an ALERT
to specific user(s) and/or mail group(s), or as a MAIL MESSAGE, or to a
specific PRINTER.
   D to delete specific alerts (some alerts may not be deleted)
   P to print a copy of the pending alerts on a printer
   M to receive a MailMan message containing a copy of these pending alerts
   R to Redisplay the available alerts
   ^ to exit
   or RETURN to see additional pending ALERTS
          Select from 1 to 3
          or enter ?, A, I, F, S, P, M, R, or ^ to exit
          or RETURN to continue:
```

10.1.2 Deleting Alerts

As of Kernel patch XU*8.0*114, you can delete alerts by using the "D" alert processing code when viewing alerts. The user can, if desired, delete specific alerts without viewing or processing them. This option provides the ability to delete "INFORMATION ONLY" alerts. Alerts that require processing *cannot* currently be deleted. However, if alerts requiring processing are created with the XQACNDEL variable set to 1 they too would be able to be deleted (i.e., the developer of the code that creates the alert can specify if it *must* be processed or can be deleted). Any alerts that were selected for deletion, but could *not* be deleted are noted for the user.

The ability for the user to delete alerts other than INFORMATION ONLY requires that the developers within a software application decide that specific alerts, which would normally invoke processing via an option or routine, can be deleted specifically by the user *without* processing. They would then set the XQACNDEL variable to a value of 1 (one) prior to calling SET^XQALERT to set up the alert. Deletion of an alert by the user (or by system administrators or ADPACs using the existing option) is noted within the ALERT TRACKING file (#8992.1) as deletion by a user (with the user ID) *without* processing of the alert.

10.1.3 Forwarding Alerts

Beginning with Kernel 8.0, you can forward alerts by using the "F" alert processing code when viewing alerts. You can choose one or more alerts and forward them in the following ways:

- Forward as alerts to a specific user on the computer system.
- Forward as alerts to a mail group on the system.
- Copy alerts into mail messages and send to users and mail groups on the system.
- Print to an output device on the system (e.g., a printer).

10.1.4 Surrogates and Alerts

Beginning with Kernel patch XU*8.0*114, you can designate or remove a surrogate for alerts by using the "S" alert processing code when viewing alerts. The user can, if desired, specify a start date/time or an end date/time for the surrogate to be effective. If a start date/time is not specified, the surrogate becomes active immediately. If an end date/time is specified, the surrogate is removed automatically effective with the first alert sent to the user after the end date/time has passed. If an end date/time is *not* specified, the surrogate is active until another surrogate is specified or the user removes the surrogate.

As of Kernel patch XU*8.0*602, entering a start or end date/time in the past is *not* permitted:

- If a date is entered, then a time is also required.
- If a start date or end date is entered *without* the year, and appending the *current* year creates a date in the past, then the next *future* year is appended to the date.

A message is sent to the surrogate to indicate that he has been designated as a surrogate, and a message is sent when the surrogate is removed.

If the user has no alerts and selects the alert option, he is asked if he wants to add or remove a surrogate. The XQALERT SURROGATE SET/REMOVE option is also provided. It can be used by system administrators or ADPACs to add or remove a surrogate for a selected user. This option is located on the Alert Management menu.

10.2 System Management

An alert notifies one or more users of a matter requiring immediate attention. Thus, alerts function as brief notices that are distinct from mail messages or triggered bulletins.

Starting with Kernel 8.0, alerts are stored in the ALERT file (#8992, stored in ^XTV(8992,). Also the ALERT TRACKING file (#8992.1), stored in ^XTV(8992.1,) provides a means to track alerts and users' responses to alerts.

For each user to whom an alert is sent, the ALERT TRACKING file (#8992.1) stores the following data:

- Alert name.
- Date created.
- Software identifier of alert.
- User who generated the alert.
- Message text of the alert.
- Action associated with the alert.
- Data associated with the alert.

For each recipient of the alert, the ALERT TRACKING file (#8992.1) stores the following data:

- First date and time observed (shown in menu cycle).
- First date and time selected for processing.
- Date and time processing completed (if any).
- Date and time alert was deleted.
- Forwarding information—If alert was forwarded, user who forwarded it, and date and time of forwarding.
- Surrogate information—If a surrogate was added for alerts, user who was the surrogate, and date and time of the surrogate.

The PATIENT^XQALERT and USER^XQALERT functions provide access to information in the ALERT TRACKING file (#8992.1).



REF: For a description of the XQALERT and other alert-related APIs, see the "Alerts: Developer Tools" chapter in the *Kernel Developer's Guide*. Kernel and Kernel Toolkit APIs are also available in HTML format at a VA Intranet Website.

10.2.1 Alert Management Menu

The Alert Management menu [XQALERT MGR] contains the following options, described below:

Figure 121: Alert Management menu options

```
SYSTEMS MANAGER MENU ...
                                                                               [EVE]
Operations Management ...
                                                                         [XUSITEMGR]
 Alert Management...
                                                                       [XQALERT MGR]
    SURO Alerts - Set/Remove Surrogate for User
                                                     [XOALERT SURROGATE SET/REMOVE]
         Delete Old (>14 d) Alerts
                                                                [XQALERT DELETE OLD]
                                                                      [XQALERT MAKE]
         Make an Alert on the fly
         Purge Alerts for a User
                                                            [XQALERT BY USER DELETE]
            **> Locked with XQAL-DELETE
         Report Menu for Alerts ...
                                                                 [XQAL REPORTS MENU]
         Set Backup Reviewer for Alerts
                                                          [XQAL SET BACKUP REVIEWER]
                                                    [XQAL SURROGATE FOR WHICH USERS]
         Surrogate for which Users?
```

10.2.1.1 Alerts - Set/Remove Surrogate for Users Option

The Alerts - Set/Remove Surrogate for User option [XQALERT SURROGATE SET/REMOVE] is provided so that system administrators or ADPAC personnel can do the following:

- Set a surrogate to receive alerts for a user.
- Remove a surrogate from receiving alerts for a user.

The option asks for a user to be selected, then is ready to specify a new surrogate for the selected user, or to remove the current surrogate for that user.

This option is *not* needed by the individual users who may select to name or remove a surrogate as one of the options while processing alerts (or if no alerts are present for the user, as his/her only option on selecting alert processing).

10.2.1.2 Delete Old (>14 d) Alerts Option

The Delete Old (>14 d) Alerts option [XQALERT DELETE OLD] performs the following functions:

- Purges unprocessed alerts from the ALERT file (#8992).
- Purges alert tracking information from the ALERT TRACKING file (#8992.1).
- Forwards unprocessed alerts to supervisors or surrogates.

You can use the Delete Old (>14 d) Alerts option to purge all alerts that have been unprocessed for longer than a specified retention period (the default is 14 days.) It is assumed that an alert becomes obsolete within this period and can be purged by system administrators. This option also performs additional functions, which are described below.

This option can be run either directly or as a queued job. You can specify a retention period other than the 14-day default when you queue the option only, by using the TASK PARAMETERS field of the OPTION SCHEDULING file (#19.2). If you put a numeric value in the TASK PARAMETERS field, this value replaces the default alert retention value of 14 days.

The Delete Old (>14 d) Alerts option also purges the ALERT TRACKING file (#8992.1). It purges all entries in the ALERT TRACKING file (#8992.1) that are more than 30 days old. The only exception is if, when an alert is created, the call to create the alert specified a retention period different than 30 days; in this case, the different period is used.

Finally, this option forwards unprocessed alerts to supervisors and surrogates (if this was requested when the alert was created). However, if the period to wait before forwarding exceeds the purging retention period used by this option, the alerts are purged rather than forwarded.

Due to the number of tasks performed by this option, it should be queued through TaskMan on a regular basis. The suggested scheduling frequency is once every day.

10.2.1.3 Make an Alert on the Fly Option

The Make an Alert on the Fly option [XQALERT MAKE] allows you to generate an alert on the fly. It interactively asks you for the alert message, recipients, and alert action, if any (you can specify an alert action type of routine or option). It then generates the alert on the fly.

This option is *recommended* primarily for system administrators and ADPACs; it may or may not be appropriate for other selected users.



NOTE: This option does *not* allow the user to set the CAN DELETE WITHOUT PROCESSING field (#.1) in the ALERT file (#8992)

10.2.1.4 Purge Alerts for a User Option

The Purge Alerts for a User option [XQALERT BY USER DELETE] allows you to delete alerts for a user. The main purpose of this option is to provide a way to delete alerts for a user who has been inactive for a period of time (e.g., on leave), and who has accumulated a number of alerts that should *not* need processing.

This option is locked with the XQAL-DELETE security key, and should only be used by system administrators or ADPACs.

10.2.1.5 Report Menu for Alerts Menu

The Report Menu for Alerts menu [XQAL REPORTS MENU] This menu provides several options for generating reports on alerts for users or patients. It consists of the following submenu items:

Figure 122: Report Menu for Alerts menu options

Select Report Menu for Alerts Option: ??

Critical Alerts Count Report [XQAL CRITICAL ALERT COUNT]
List Alerts for a user from a specified date [XQAL ALERT LIST FROM DATE]
Patient Alert List for specified date [XQAL PATIENT ALERT LIST]
User Alerts Count Report [XQAL USER ALERTS COUNT]
View data for Alert Tracking file entry [XQAL VIEW ALERT TRACKING ENTRY]

10.2.1.5.1 Critical Alerts Count Report Option

The Critical Alerts Count Report option [XQAL CRITICAL ALERT COUNT] is used to generate a report of users who have more than a specified number of alerts containing the word "critical" or the words "abnormal imaging" between the specified start and end dates. The report is presented in descending order for the number of critical/abnormal imaging alerts present.

For each user who has the specified number of critical/abnormal imaging alerts or more, the report includes the following:

- User name.
- Section/Service for the user.
- Number of alerts in the ALERT file (#8992).
- Last signon date.
- Number of Critical alerts or Abnormal Imaging alerts.
- Date of the oldest alert.

10.2.1.5.2 List Alerts for a user from a specified date Option

The List Alerts for a user from a specified date option [XQAL ALERT LIST FROM DATE] is used to obtain an interactive list of alerts from the ALERT TRACKING file (#8992.1) for a specified user starting from a specified date.

The listing includes the following:

- Internal Entry Number (IEN) for the alert in the ALERT TRACKING file (#8992.1).
- Date and time the alert was generated.
- Message text of the alert.
- Information about any option or routine to be executed for processing the alert.

10.2.1.5.3 Patient Alert List for specified date Option

The Patient Alert List for specified date option [XQAL PATIENT ALERT LIST] is used to obtain a list of alerts for a specified patient from the ALERT TRACKING file (#8992.1) for a selected date.

A prompt is provided to obtain a quick scan listing of dates with at least some alerts for the patient on it based on OR and DVB alerts (other patient related alerts need to be identified by looking at each alert's message text and are included in the full list, but not the quick scan).

The listing includes the following:

- Internal Entry Number (IEN) for the alert in the ALERT TRACKING file (#8992.1).
- Date and time the alert was generated.
- Message text of the alert.
- Information about any option or routine to be executed for processing the alert.

10.2.1.5.4 User Alerts Count Report Option

The User Alerts Count Report option [XQAL USER ALERTS COUNT] is used to generate a report on users who have more than a specified number of alerts in the ALERT file (#8992). The report covers a specified range of dates, and can be sorted by any of the following data:

- User name
- Number of alerts
- Service/Section

In addition, the report in each of these formats may be generated by Divisions if desired.

For each user who has the specified number of alerts or more, the report includes the following:

- User name
- Section/Service for the user
- Number of alerts in the ALERT file (#8992)
- Last signon date
- Number of Critical alerts or Abnormal Imaging alerts
- Date of the oldest alert

10.2.1.5.5 View data for Alert Tracking file entry Option

The View data for Alert Tracking file entry option [XQAL VIEW ALERT TRACKING ENTRY] can be used to view data for one or more entries in the ALERT TRACKING file (#8992.1) in captioned format. The internal entry numbers for the entries to be displayed *must* be entered individually.

10.2.1.6 Set Backup Reviewer for Alerts Option

The Set Backup Reviewer for Alerts option [XQAL SET BACKUP REVIEWER] was added with Kernel patch XU*8.0*174.

This option provides a mechanism for a user to set entries into the PARAMETERS file (#8989.5) that assigns an individual as the "Backup Reviewer for Unprocessed Alerts," which is the DISPLAY TEXT Field (#.02) for the "XQAL BACKUP REVIEWER" entry in the NAME field (#.01) in the PARAMETER DEFINITION file (#8989.51), if there is a date specified in the DAYS FOR BACKUP REVIEWER field (#.15) in the ALERT DATE/TIME Multiple field (#.01) in the ALERT file (#8992) for that alert.

If this is the case, an alert that remains unread for the specified number of days is forwarded to the "Backup Reviewer for Unprocessed Alerts" indicated at the lowest level found for processing for the user in the PARAMETERS file (#8989.5). The following is the processing order (listed lowest to highest level):

- 1. User
- 2. OERR Team
- 3. Team
- 4. Service
- 5. Division
- 6. System

10.2.1.7 Surrogate for which Users? Option

The Surrogate for which Users? option [XQAL SURROGATE FOR WHICH USERS] provides a view of which users have specified a selected user as surrogates for themselves.

11 Server Options

11.1 System Management

11.1.1 What is a Server Option?

A server option is a special type of option (stored in the OPTION file [#19]) that can be triggered by mail messages. Addressing a mail message to a server option is termed a "server request." A server request awakens the option and causes it to execute the following:

- Any M code in the server option's ENTRY ACTION field (#20).
- Any M code in the HEADER field (#26).
- The routine indicated in the ROUTINE field (#25).
- Any M code in the EXIT ACTION field (#15).

A server-type option is similar to a run routine-type option. The difference is that a server option is activated by a mail message while a run routine option is activated by a user choosing that option from a menu on a screen. Server options should only be invoked by mail messages (never directly by a user).

The form of the mail message that activates the server option is identical to any other mail message except that it is addressed to S.<option name>. The "S." (like the "G." form for sending to mail groups) routes the message to the server request software.

11.1.2 What Can Server Options Do?

A server request might trigger a bulletin, send a MailMan reply, or initiate an audit of itself. Developers and local system administrators can also customize the bulletins or MailMan replies.

11.1.3 Can Server Requests Be Denied?

Only server-type options can be activated by mail messages. The following *must* be true for a server request to be processed:

- The server option *must* be set to type "s" in the TYPE field (#4) of the OPTION file (#19). If the type is not "s" and a request is received, it results in an error that, by default, is recorded in the AUDIT LOG FOR OPTIONS file (#19.081).
- The server option name *must* be complete and exact when a server request is made or the request is denied.
- The server option *must not* be disabled (it can be disabled for all requests by setting its LOCK (#3) or OUT OF ORDER MESSAGE fields).

As long as the conditions listed above are satisfied, the only mechanism a site has for security for server requests is the setting of the server option's SERVER ACTION field (#221). This field has the following settings:

Table 13: SERVER ACTION field (#221) security values for server requests

Value	Description
R	Run immediately. This code causes the server request to be honored in real time as soon as it is received from MailMan (run immediately), provided it is <i>not</i> prevented by a setting in the TIMES/DAYS PROHIBITED field (#3.91).
Q	Queue server. This code causes the server request to be honored (queued) as soon as permitted by the TIMES/DAYS PROHIBITED field (#3.91).
N	Notify local authorities. This code causes the server request to create a TaskMan entry but does <i>not</i> schedule it to run. A local mail group is notified along with the task number so that it can be approved locally and then scheduled to run using TaskMan's Requeue Tasks option.
I	Ignore any server requests. This code causes the software to ignore all requests for this server option. A bulletin or MailMan message can still be sent, however.

When a server request is received, the server option itself is executed similarly to the way a normal option is executed. That is, if a server request causes a server option to be run or queued, the server option, (along with its associated entry action code, header code, routine, and exit action code), does *not* run until the option as a whole runs as scheduled by TaskMan.

11.1.4 How Can the Number of Instances of a Server Option Be Controlled?

To tie a server option to a device of type RESOURCES, use the SERVER DEVICE field (#227) and set the SERVER ACTION field (#221) to "Q" (Queue server) in the OPTION file (#19). This allows you to control how many instances of the server option can run at any one time. Only as many server option processes can run at any one time as are set up in the associated device's RESOURCE SLOTS field (#35) in the DEVICE file (#3.5). So if 30 mail messages come in at the same time and attempt to fire off 30 server option processes, you can control the maximum number of simultaneous processes that actually run. Additional server options are able to run when resource slots are freed up from the resource device.

11.1.5 Setting Up a Server Option

A server option has many fields in common with other option types and is set up using the Menu Management option Edit options. This option calls the FileMan edit template option [XUEDITOPT], which prompts for data to be entered in the following fields (listed in field number order):

Table 14: OPTION file (#19) field values when setting up a server option

Field Name	Description
NAME (#.01)	This should be a namespaced set of 3 to 30 uppercase letters.
MENU TEXT (#1)	Since there is never a menu prompt for a server option, this field should instead contain an accurate description of what this server option does, as it is used by the server request in error messages, bulletins, and MailMan replies. It should be 3 to 50 characters in length.
OUT OF ORDER MESSAGE (#2)	If this field contains between 1 and 80 characters of text, the server option is placed "out of order" and is <i>not</i> activated by a server request. The message itself is included in bulletins or MailMan replies that report the failure.
LOCK (#3)	Since server options have no online user associated with them, the existence of a lock in this field prevents the execution of a server option, much like an OUT OF ORDER MESSAGE. The user for all server options is the PostMaster. The originator of a server request is recorded, however, in the return address variable.
DESCRIPTION (#3.5)	This word-processing field should contain an extensive description of the server option intended for the local site manager and system administrators. The description should include an exact description of what the server option does and the resources it requires.
PRIORITY (#3.8)	This field determines the priority at which the server option runs.
TIMES/DAYS PROHIBITED (#3.91)	This multiple allows the local system administrators to control the days and times during which the server request is honored. If data is entered that prevents the server option from being honored immediately, the software determines the next available time slice that is not prohibited and queues the request for that time. Server options that are marked "R" for Run Immediately in the SERVER ACTION field are instead queued to run at the next non-prohibited time period.
TYPE (#4)	This field <i>must</i> always contain the code "s" for server-type option or the request is denied and an error results.
EXIT ACTION (#15)	The M code stored in this field is executed just before the server option exits.
ENTRY ACTION (#20)	The M code in this field is executed if the server request is honored. If, as with other options, the variable XQUIT exists after the Entry Action is executed, the request is terminated at that point and an error is generated.
ROUTINE (#25)	If there is a routine name in this field in the forms ROUTINE, ^ROUTINE, or TAG^ROUTINE, the routine is run.

Field Name	Description	
HEADER (#26)	This field of M code is executed, if it exists.	
SERVER BULLETIN (#220)	This field is a pointer to the BULLETIN file (#3.6); it indicates the bulletin to use to notify the local mail group of a server request on their system. If there is no bulletin entered in this field, the default bulletin XQSERVER is used.	
	Unless there are pressing reasons to do otherwise, it is recommended that the default bulletin XQSERVER be used by leaving the SERVER BULLETIN field blank.	
	If the mail groups pointed to by XQSERVER (or the bulletin pointed to in this field) does not contain an active user (i.e., a user possessing a Verify code and no effective TERMINATION DATE) the software turns on auditing (i.e., SERVER AUDIT described below) and sends a MailMan message to the local PostMaster.	
	CAUTION: The most common reason for server options not functioning is that there is no active user associated with the bulletin specified. For security reasons, server options do <i>not</i> run without a locally defined active user associated with the chosen bulletin.	
SERVER ACTION (#221)	This SET OF CODES field allows the local system administrators to decide how a server request is to be treated (see <u>Table 13</u>).	
SERVER MAIL GROUP (#222)	This field is a pointer to another mail group (the first is pointed to by XQSERVER or the bulletin in Field #220) to which server request notifications are to be sent. The software notifies all legitimate users in all mail groups pointed to. It is <i>recommended</i> that this field be left blank and a mail group be assigned the chosen bulletin instead.	
	CAUTION: Server options do <i>not</i> work unless there is a local, active user associated with the specified mail group.	
SERVER AUDIT (#223)	This field causes the server request to be audited in the AUDIT LOG FOR OPTIONS file (#19.081). The default is YES . The information stored for an audited server option includes:	
	Option name	
	User (always PostMaster)	
	Device	
	Job number	
	Date/Time Date/Time	
	• CPU	
	Message number Deturn address of annular	
	Return address of sender Subject of the manager	
	Subject of the message	

Field Name	Description	
	Error message A server option can also be audited using the normal option auditing software. Auditing the PostMaster or the namespace "XQSRV" captures all server requests.	
SUPPRESS BULLETIN (#224)	If set to "Y" (YES), it prevents a bulletin from being sent under normal conditions. If there is an error or a possible security breach, a bulletin is still fired. If the field is <i>not</i> filled in, it takes the default of "N," which means that the sending of bulletins is <i>not</i> suppressed.	
SERVER REPLY (#225)	This SET OF CODES controls the MailMan reply to a server request. The reply is a message returned to the user who has sent the server request and should not be confused with the local user to whom the bulletin is addressed. If a reply is requested, the software uses the return address of the sender as supplied by MailMan to send a local or network reply.	
	REF: For an example of a server-type option return message, see the Figure 124. The possible codes are:	
	N No reply is sent (the default).	
	E A reply is sent to the return address of the sender only in the event of an error.	
	R A reply is always sent.	
SERVER DEVICE (#227)	Optionally, use this field and the SERVER ACTION field (#221) set to "Q" (Queue server) to control the number of server requests for this server option that can be processed at any one time. Enter the name of a device of type RESOURCES (in the DEVICE file [#3.5]). The number of instances of this server option that can run at any one time is limited to the number of resource slots in the selected resource device (i.e., RESOURCE SLOTS field (#35) in the DEVICE file (#3.5)).	

11.1.6 Testing if a Site is Reachable: XQSPING Server Option

You can use the XQSPING server option to invoke the Kernel XTSPING utility at a site. This utility tests to see if the domain to which a message is addressed is reachable. For example, if you want to see if the network link to the Field Office (FO) is working properly, you could address a message to:

```
S.XQSPING@FO-SITE.VA.GOV
```

If the text of the message and the subject are simply the line "Testing", you should get the following message in return:

Figure 123: Sample message received when "pinging" a domain address

The XTSPING utility copies the message addressed to it and returns it to the person who sent it.

11.1.7 Testing a Server Option: XQSCHK

You should list the server option you want to test in the text of the message addressed to XQSCHK. The subject of the message sent to the XQSCHK server option is not important. However, the body of the text *must* contain the name of the server option to be checked. When you specify the server option to be checked, do *not* precede the server option name with an "S.", instead, list the server option's name exactly as it appears in the OPTION file's .01 field.

The XQSCHK server option returns Fields #220 to #225 from the OPTION file (#19) to show how the option has been set up. In addition, several other things about the option are investigated and error or warning messages may be also returned.

For example, if you want diagnostic information about a server option named ZZSERVER, and the option resides on the system at a field office (FO), you should create a message containing the text ZZSERVER and send it to:

```
S.XQSCHK@FO-SITE.VA.GOV
```

The XQSCHK server option unloads the name of the server option (in this example ZZSERVER, see <u>Figure 124</u>). Assuming such a server option exists, you would expect to receive a reply in a MailMan message as shown below:

Figure 124: XQSCHK server option—Sample MailMan return message

```
MailMan message for XUUSER, ONE COMPUTER SPECIALIST
Subj: Server Request Reply from FO-SITE.VA.GOV
From: Postmaster in 'IN' basket
                 Nov. 28, 1992 12:18 PM
   Sender: XUUSER, ONE
   Option name: ZZSERVER
    Subject: TESTING XQSCHK
   Message #: 999
    This is a reply from FO-SITE.VA.GOV
    Checking Server Option ZZSERVER.
    Fields 220 to 225 in the Option File:
           220 - No bulletin selected, will use default XQSERVER.
           221 - The server action code is Run Immediately.
           222 - The mail group ZZGROUP is pointed to.
           223 - Auditing is turned off.
           224 - The server's bulletin is not suppressed.
           225 - Reply mail is sent when an error is trapped.
```

11.1.8 Errors and Warnings from the XQSCHK Server Option

<u>Table 15</u> lists the errors or warnings that might be included in the return message from the XQSCHK server option, along with an explanation of each:

Table 15: XQSCHK server option—Error/Warning messages

Error/Warning Message	Description
Can't unload name of server from message: [message subject].	The name of the server option to be tested could not be unloaded from the text of the message sent to waken the XQSCHK server option. The message should contain just the name of the server option to be tested and nothing more. XQSCHK ignores blank lines (up to 4) and any lines of text that follow the line where it finds the options' name.
The option [option name] is not in the Option File.	There is no option in the remote site's OPTION file (#19) that matches the name of the server option that was unloaded from the text of the message. The string it is using to search the OPTION file (#19) is returned in [option name].
Option [option name] is not shown as a server-type option but a [type].	The option is not marked in the remote OPTION file (#19) as a server-type option, but some other kind of option returned in [type], such as a print-type option.

Error/Warning Message	Description
[Option name] is marked as Out Of Order with the message: [message].	The OUT OF ORDER MESSAGE field for that option has been filled in with the text that is returned in [message].
The expected data in ^DIC(19,[option number], 220) is missing.	There is no information for this option in fields 220 through 225. The 220 node of the OPTION file (#19) is missing or blank.
No bulletin associated with this option default XQSERVER is missing from system.	There is no bulletin pointed to by Field #220 of this option in the OPTION file (#19), and the default XQSERVER bulletin has been removed from the system. Server options are <i>not</i> run without an associated bulletin, even if it is suppressed.
Option [option name] points to a bulletin not in the bulletin file.	WARNING: there is an invalid pointer in Field #220 of the OPTION file (#19) that points to a nonexistent bulletin. The default bulletin XQSERVER is used.
Option [option name] points to a mail group not in the Mail Group File.	WARNING: there is an invalid pointer in Field #222 of the OPTION file (#19) indicating a mail group that should receive the bulletin in addition to the mail group pointed to by the BULLETIN file.
There are no mail groups associated with the bulletin [bulletin name].	The bulletin returned in [bulletin name] does not have a mail group associated with it in the BULLETIN file (#3.6).
There is no active user associated with the bulletin [bulletin name].	When following the pointers from the bulletin to the mail group to the NEW PERSON file (#200), an active user was not found. Each server option <i>must</i> be linked to a user who has an Access and Verify code and is not terminated.
There is no routine in field 25 of the Option File for this option.	This server option has no routine associated with it in the ROUTINE field of the remote site's OPTION file (#19).
The routine [routine name] is not on the system.	The routine that is named in the ROUTINE field of the OPTION file (#19) is not found on the system. It has been removed or is in another UCI.
There is no server action code for this option.	The required server option action code in field 221 of the OPTION file (#19) is blank.

12 Help Processor

12.1 User Interface

Kernel's Help Processor is a utility for displaying help frames. A help frame is a screen of text that explains some part of a software application. Each individual help frame can have keyword links to other help frames. Using these keywords, you can navigate through a series of related help frames to learn more about each help frame section.

Some places where you may encounter help frames are:

- When requesting help on options in the menu system.
- When requesting help on a menu in the menu system.
- As a standalone option describing some part of a software application.

Figure 125: Help frame example

```
USING THE 'Help Processor' OPTION
The Help processor is a frame-oriented display system which allows
users and programmers to access and manage help text.
The system is driven off of the HELP FRAME FILE.
There are several LINKS which will cause the help text to be
displayed to the user. The system is interactive, and the user may
select which section he/she wishes further information on.
The Help Frame Processor Menu contains the following options:
 DISPLAY/EDIT
                 - Displays the text of a help frame, and allows for the
                     edit of the name, header, text, or related frames.
                 - Lists all the help frames for a specified package,
                     showing parent help frames, linked to menu option,
                     and invoking routine.
                  - Lists the help frames in several different formats.
 LIST
 MORE OPTIONS...
Select HELP SYSTEM action or <return>:
```

At the bottom of every displayed help frame is a "Select HELP SYSTEM action..." prompt. You have several choices at this prompt. To back your way out of the help frame system, you can simply press the **<Enter>** key. This backs you up one level, or exits you if you are at the top level of a help frame tree. If you want to exit quickly from help frames, you can enter "^Q" to quit immediately without having to back all of the way out.

You can list other choices at the "Select HELP SYSTEM action..." prompt by entering a question mark ("?"). The full list of choices is:

Table 16: Help system command actions

Response	Action	
Keyword	Jump to help frame associated with Keyword.	
<enter></enter>	Quit to previous help frame (exit if no previous).	
^Q	Quit the help system.	
^R	Refresh the current frame.	
^ T	Table of related frames.	
^0	On/off switch for bracketing/reverse video of keywords.	
^H	How you got to this frame.	
^E	Edit this frame (only if authorized as editor of frame).	

Keywords in a help frame are displayed by the help processor in reverse video. If you enter the first few letters of a keyword and press the **Enter>** key, the help processor jumps to the help frame linked to the entered keyword.

12.1.1 Help Frames in the Menu System

If a menu option has associated help frames, you can display them by entering a question mark ("?") followed by an option's menu text or synonym at a menu prompt (i.e., ?option). For example:

Figure 126: Display a help frame for an option—Entering one question mark (?) and option name

```
Select Office Menu Option: ?MAILMAN
```

Entering three question marks ("???") at the menu prompt indicates which options have associated extended help (help frames).

Figure 127: Display a help frame for an option—Entering three question marks (???)

Select Office Menu Option: ???

If a menu itself has an associated help frame, entering four question marks ("????") at the menus "Select ... action: " prompt displays the help frame associated with that menu if one exists:

Figure 128: Display a help frame for an option—Entering four question marks (????)

Select Help Processor Option: ????

12.2 System Management

Help frames are entries in the HELP FRAME file (#9.2). The Header and Text of help frames can be displayed to users to provide instruction about software or other topics. Help frames can be distributed with software or can be created locally to provide information about local policies and procedures.

The options used to create, edit, and link help frames are on the Help Processor menu [XQHELP-MENU], shown below:

Figure 129: Help Processor menu options

```
SYSTEMS MANAGER MENU ...
                                                                                  [EVE]
Menu Management ...
                                                                             [XUMAINT]
  Help Processor ...
                                                                         [XOHELP-MENU]
     Display/Edit Help Frames
                                                                      [XQHELP-DISPLAY]
     List Help Frames
                                                                         [XQHELP-LIST]
     New/Revised Help Frames
                                                                       [XQHELP-UPDATE]
     Cross Reference Help Frames
                                                                         [XQHELP-XREF]
     Assign Editors
                                                                       [XQHELP-ASSIGN]
     Unassign Editors
                                                                     [XQHELP-DEASSIGN]
     Fix Help Frame File Pointers
                                                                           [XOHELPFIX]
```

Use of the Help Processor options is explained by help frames associated with the options.

12.2.1 Display/Edit Help Frames Option

The help frames can be displayed with the Display/Edit Help Frames option [XQHELP-DISPLAY]. You can use the **?option** syntax at the select prompt, as follows:

Figure 130: Display/Edit Help Frames option—Displaying help using the ?option syntax

```
Select Help Processor Option: PDISPLAY <Enter> /Edit Help Frames
```

12.2.2 List Help Frames Option

The List Help Frames option [XQHELP-LIST] can be used to print a series of frames with a table of contents and page numbering to resemble a hard copy manual.

Figure 131: List Help Frames option—Sample user dialogue

```
Select Help Processor Option: LIST HELP FRAMES
Select primary HELP FRAME from which to list: XUDOC NEW
```

12.2.3 New/Revised Help Frames Option

The New/Revised Help Frames option [XQHELP-UPDATE] produces a VA FileMan-generated print of all help frames that have been updated during a specified time period.

12.2.4 Cross Reference Help Frames Option

The Cross Reference Help Frames option [XQHELP-XREF] lists any of the following cross-references to a specified set of help frames:

- Parents (other help frames that call the specified help frame).
- Options (options whose HELP FRAME field references the specified help frame).
- Routines (if a developer has entered the routine in the specified help frame's INVOKED BY ROUTINE field).

12.2.5 Fix Help Frame File Pointers Option (Deleting Help Frames)

There is no Kernel utility to delete help frames, but the menu system does *not* generate errors if a pointed-to help frame is missing. If a site chooses to delete help frames using VA FileMan, they should use the Fix Help Frame File Pointers option [XQHELPFIX] afterwards to delete dangling pointers from the OPTION file's HELP FRAME field.

12.2.6 Assigning/De-assigning Help Frame Editors

An existing help frame can be edited, through the Help Processor options, by the following people:

- The help frame author.
- Any holder of the XUAUTHOR security key.
- Anyone who has been assigned as an editor to that help frame.

To assign an editor to a given help frame use the Assign Editors option [XQHELP-ASSIGN] or to deassign an editor to a given help frame, use the Unassign Editor option [XQHELP-DEASSIGN].

12.2.7 Disk Space Concerns

Help frames consume disk space. The amount can be considerable if numerous frames are exported with a software application. You can estimate the size of the HELP FRAME file (#9.2) by Kernel's Block Count utility.

Figure 132: Estimating the size of the HELP FRAME file (#9.2) using Kernel's Block Count utility

```
Select Systems Manager Menu Option: PROG <Enter> rammer Options
Select Programmer Options Option: GLOBAL <Enter> Block Count
Block Count for Global ^DIC(9.2)
```

12.2.8 Creating and Editing Help Frames

One way to edit help frames from the HELP FRAME file (#9.2) is to use the Display/Edit Help Frames option to display the help frame in question. Then, at the "Select Help System Action:" prompt, you can enter "^E" to edit the help frame if you have edit access to the help frame. You have edit access if:

- You are the help frame's author.
- You are assigned as an editor for the help frame.
- You are a holder of the XUAUTHOR security key.

Another handy way to edit help frames is within the help frame system as invoked from a software application. For example, if the help frames are tied to a software's options, you can use the software, invoke the help frame for each field or option, and then edit that help frame on the spot. To edit a help

frame in this manner, enter "^E" at the help frame action prompt. To do this, however, you *must* have edit access to the help frame as described above.

12.2.8.1 Namespacing of Help Frames

Like entries in the OPTION (#19) or SECURITY KEY (#19.1) files, entries in the HELP FRAME file (#9.2) *must* be namespaced to avoid overwriting problems.

12.2.8.2 Help Frame Layout Considerations

When entering the text of help frames, you should keep each line to fewer than 80 characters for proper screen display.



NOTE: The text is displayed "as it stands" and is not processed by VA FileMan's text formatter. That is, the text is not wrapped, and word-processing "windows" are not evaluated. Frames are usually 22 lines in length although an end-of-page READ is issued to allow a pause if the frame exceeds 22 lines.

If there are only a few lines of text, the Help Processor displays a table at the bottom of the screen of all related frames (those frames that the current frame has keyword links to). The table shows the choices of other frames so the user need not enter the keywords in the text. You can force the table of related frames out of the display by entering enough blank lines so that the frame's length is 20 lines (assuming the display has a page length of 24 lines).

For the Help Processor to identify and highlight keywords, the keywords are entered in the text of the help frame enclosed in square brackets. By convention, keywords in help frames are usually in all capital letters. A square bracket character can be displayed as part of the frame's text by entering two of the characters (e.g., [[or]]).

If the frames are to be printed using the List Help Frames option, the resulting help manual has an organized outline, if the frames are linked in a top-down tree structure without any circular connections among the branches.

12.2.8.3 Linking a Help Frame as Help for an Option or Menu

Once a help frame (or a series of help frames) has been created, you can associate it (them) with options by entering the name of the top-level help frame in the HELP FRAME field of the OPTION file (#19). You can use Menu Manager's option Edit options to do this. That way, when a user enters a single question mark ("?") in conjunction with the option name, Menu Manager invokes the associated help frame.

Figure 133: Linking help frames to an option—Sample user dialogue

```
Select Systems Manager Menu Option: MENU <Enter> Management
Select Menu Management Option: EDIT OPTIONS
Select OPTION to edit: XQHELP-MENU <Enter> Help Processor
NAME: XQHELP-MENU// HELP FRAME
HELP FRAME: XQHELP
```

13 Error Processing

13.1 User Interface

When an option you are using encounters an error condition, you are usually returned to the menu system. A message is displayed indicating that an error has occurred. You are then presented with the last menu prompt and can continue.

There are certain error conditions, however, that may prohibit or prevent return to the menu system. In these situations, you are halted off the system.

13.2 System Management

The Error Processing menu handles errors for Caché systems. It provides access to options pertaining to the error trap, displaying, printing, and purging errors. Like the error traps provided by the operating systems, the utility allows the investigation of program execution errors or the examination of system errors by capturing a picture of the environment for later reconstruction.

The %ZTER* routines are called from ERR^ZU to trap errors and store them in the ^%ZTER global, a Manager account global that should be translated so that all errors are included on one report. The XTER* routines are used to format the error report.

13.2.1 Error Screens

At times you may not want to trap a certain type of error, but merely to count them because you are already aware of the error and can do nothing to prevent it. At other times you may not even want to count the error because it is inevitable or harmless. An error screen is a string of characters that is compared with the error message of every error trapped. Any trapped error whose message contains the screen is screened out. You decide for each screen whether the error is counted or completely ignored. In either case the error is not recorded in either the Kernel ERROR LOG file (#3.075) or the TaskMan Error Log. In TaskMan, if a running task encounters a screened error, the Submanager still notes the error in the record for that task.

Kernel gives you four options with which to manage your error screens:

- <u>List Error Screens Option</u> [XUTM ERROR SCREEN LIST]
- Add Error Screens Option [XUTM ERROR SCREEN ADD]
- Edit Error Screens Option [XUTM ERROR SCREEN EDIT]
- Remove Error Screens Option [XUTM ERROR SCREEN REMOVE]



NOTE: Even though these four option names are prefixed with "XUTM" and located on TaskMan menus, these error screen options apply to all errors and *not* just TaskMan-specific errors. These four options are located on the Taskman Error Log menu [XUTM ERROR], located under the Taskman Management Utilities menu [XUTM UTIL], located under the Taskman Management menu [XUTM MGR], which are all located under the Systems Manager Menu [EVE].

13.2.1.1 List Error Screens Option

Figure 134: List Error Screens option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Taskman Error Log ... [XUTM ERROR]
List Error Screens [XUTM ERROR SCREEN LIST]
```

The List Error Screens option [XUTM ERROR SCREEN LIST] lists in a simple table the screens you have established and the number of errors that have been screened out by each.

13.2.1.2 Add Error Screens Option

Figure 135: Add Error Screens option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Taskman Error Log ... [XUTM ERROR]
Add Error Screens [XUTM ERROR SCREEN ADD]
```

With the Add Error Screens option [XUTM ERROR SCREEN ADD] you can enter a screen and specify whether the errors should be counted. If there are already similar screens in place (e.g., entering SYN when SYNTAX is already established) you are so informed, shown the similar screens, and prompted for confirmation before being asked about the count. Entering two question marks ("??") at the "Enter Screen To Apply:" prompt displays the list of error screens.

13.2.1.3 Edit Error Screens Option

Figure 136: Edit Error Screens option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Taskman Error Log ... [XUTM ERROR]
Edit Error Screens [XUTM ERROR SCREEN EDIT]
```

Use the Edit Error Screens option [XUTM ERROR SCREEN EDIT] if you want to reset the counter on a screen or change your mind about whether or not the screen counts its errors. You *must* type in the exact screen you wish to edit. Again, entering two questions marks displays the list of error screens currently in place.

13.2.1.4 Remove Error Screens Option

Figure 137: Remove Error Screens option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Taskman Error Log ... [XUTM ERROR]
Remove Error Screens [XUTM ERROR SCREEN REMOVE]
```

When you type in a screen at the prompt for this option, the screen is removed for you. If there are any similar screens, the Remove Error Screens option [XUTM ERROR SCREEN REMOVE] asks whether you wish to remove them also. Again, entering two question marks ("??") displays the list of error screens.

13.2.2 Enhanced Error Processing

Enhanced error processing for Caché sites is supported. Kernel's error trap captures variables in their state at the time errors occur, regardless of how variables may have been NEWed beforehand. Stack levels for the routine call stack are recorded in the error trap in the \$STACK variable.

The descriptions of the Error Processing menu option topics that follow are arranged in the same order as the options appear on the Error Processing menu [XUERRS].

Figure 138: Error processing options

```
SYSTEMS MANAGER MENU ... [EVE]
Programmer Options ... [XUPROG]
Error Processing ... [XUERS]
P1 Print 1 occurrence of each error for T-1 (QUEUE) [XUERTRP PRINT T-1 1 ERR]
P2 Print 2 occurrences of errors on T-1 (QUEUED) [XUERTRP PRINT T-1 2 ERR]
Clean Error Trap [XUERTRP CLEAN]
Error Trap Display [XUERTRAP]
Interactive Print of Error Messages [XUERTRP PRINT ERRS]
```

13.2.3 Print 1 Occurrence of Each Error for T-1 (QUEUE) Option

The Print 1 occurrence of each error for T-1 (QUEUE) option [XUERTRP PRINT T-1 1 ERR] lists the first occurrence of each error recorded on the previous day. T-1 represents "Today-1 = Yesterday". You can queue it to run shortly after midnight. If a device is specified, the output is sent to the specified device. If a device is *not* specified, the output is placed in a mail message and sent to the individual who queued the option to run. It should be set to automatically requeue at a 1 day ("D") interval.

13.2.4 Print 2 Occurrences of Errors on T-1 (QUEUED) Option

The Print 2 occurrences of errors on T-1 (QUEUED) option [XUERTRP PRINT T-1 2 ERR] lists the first two occurrences of each error recorded on the previous day. T-1 represents "Today-1 = Yesterday". It can be queued to run shortly after midnight. If a device is specified, the output is sent to the specified device. If a device is *not* specified, the output is placed in a mail message and sent to the individual who queued the option to run. It should be set to automatically requeue at a 1 day ("D") interval.

13.2.5 Clean Error Trap Option

You can use the Clean Error Trap option [XUERTRP CLEAN] to purge the error log. It is locked with the XUPROGMODE security key. You can use the corresponding direct mode utility, ^XTERPUR, in programmer mode. There is also a queueable version, Error Trap Auto Clean option [XUERTRP AUTO CLEAN].

Purging is a partial clearing of the ERROR LOG file (#3.075) stored in the ^%ZTER(1, global. This global node should not be deleted directly since potentially important recent errors would be purged. Deletion of the entire ^%ZTER global would be a greater mistake since the standard reference data contained in the ERROR MESSAGES file (#3.076) stored in ^%ZTER(2, would be lost.

You are first prompted for the number of days to leave in the error trap. If you enter a number of days to retain errors, all errors older than the specified number of days are immediately purged:

Figure 139: Choosing the number of days to leave errors in the error trap

```
To Remove ALL entries except the last N days, simply enter the number N at the prompt. OTHERWISE, enter return at the first prompt, and a DATE at the second prompt. If no ending date is entered at the third prompt, then only the date specified will be deleted. If an ending date is entered that range of dates INCLUSIVE will be deleted from the error log.

Number of days to leave in error trap: 50

DONE
```

If you just press **<Enter>** instead of entering a number of days to retain, you are then prompted for a start date and end date between which to remove errors. Errors in the period you specify are then purged immediately:

Figure 140: Choosing a start and end date range to delete errors from the error trap

```
Starting Date to DELETE ERRORS from: 1/1 <Enter> (JAN 01, 2004) Ending Date to DELETE ERRORS from: 1/31 <Enter> (JAN 31, 2004)
```

The queueable version of this option, Error Trap Auto Clean, can be scheduled to run in the background. By default, it cleans up errors recorded more than 7 days in the past. You can specify a different interval by placing a numeric value (representing the number of days beyond which to purge) in this option's TASK PARAMETERS field.

13.2.6 Error Trap Display Option

The Error Trap Display option [XUERTRAP] displays errors that have been trapped on the system. The messages for these errors are operating-system dependent. You can use the corresponding direct mode utility, ^XTER, from programmer mode.

The error trap tries to capture a description of the error, the local symbol table, the last global reference, and other signon statistics. For Caché, \$ZC calls are used to record IO counts, CPU time, and page faults.

Figure 141: Error trap display option—Sample user dialogue

```
In response to the DATE prompt you can enter:
     'S' to specify text to be matched in error or routine name.
Which date? > T-1
1 error logged on 2/9/95
  1) <ECODETRAP>PRGMODE+5^%ZOSV:2 07:41:52 KDE, KDE 20801D46
     TNA4523:
No disconnect error
Which error? > 1
Process ID: 2020107A (538972282)
                                           JAN 18, 1992 17:19:21
Username: EXAMPLE
                            Process Name: VISTA User
UCI/VOL: [NXT~NXT~ABC999~NXT:KDAABC999]
$ΖA:
                                     $ZB: \013
Current $IO: _TNA4523: Current $ZIO: LTA_00129420196A
CPU time:
           3.17
                             Page Faults:
                                                1204
                                                  96
Direct I/O: 81
                            Buffered I/O:
$ZE= <ECODETRAP>PRGMODE+5^%ZOSV:2
 D @XQZ G OUT"
Last Global Ref: ^XUSEC(0,"CUR",24,2950209.074142)
Which symbol? >
```

Errors can be reported by searching for a date range or character string. Question marks show a count of errors for the selected range. Two question marks ("??") exclude disconnects and three ("???") include disconnects. A string search could be used to find XQ in all routines or an UNDEF in the definition of all errors. Once an error is identified, the report generator shows the job number, username, IO value, date/time, UCI/Volume Set, error type, last global reference, and the line of code that caused the error. It then prompts for a listing of variables, enter " L " to list all or a letter, such as X, to list those starting with X. The listing can be printed to the screen or to an output device. You can page through the screen listing, one screen at a time, and enter " Q " to quit or enter " A " to exit at the end of each screen.

A restore feature can be invoked by entering "**^R**" provided that the user is working in programmer mode. Programmer mode is required as a protection against restoration of variables from within the menu system. To the extent possible, the environment at the time of the error is restored with the routine and local symbol table intact.

Figure 142: Local symbol table help

```
Which symbol? > ?
Enter:
    ^Q to EXIT
    ^^' to return to the last question
    Leading character(s) of symbol(s) you wish to examine
    $ to get a display of the $ system variables
    ^L to obtain a list of all symbols
    ^R to restore the symbol table and ... and enter direct mode
```

After reviewing the error log, you are given the opportunity to examine the operating system's error log. Now that most VistA applications record their errors in Kernel's error log, however, there is less need to track VistA errors in the operating system error log.

Figure 143: Choosing to examine the operating system's error log—Sample user dialogue

```
Do you want to check the OPERATING SYSTEM ERROR TRAP too? NO//
```

13.2.7 Interactive Print of Error Messages Option

The Interactive Print of Error Messages option [XUERTRP PRINT ERRS] provides for an interactive print of the first "**n**" of occurrences of an error (where "**n**" is user selectable) over a specified date range.

III. Device Handler

14 Device Handler: User Interface


Applications that are designed for the Kernel environment perform output in a consistent manner, using Kernel's Device Handler. This ensures consistency, both for how you are asked to select devices for output, and also for how output is actually performed.

When you respond to the "DEVICE:" prompt, you are using the Device Handler.

14.1 Printing to Devices


At the "DEVICE:" prompt, to send output to your terminal, you can simply press the **<Enter>** key. This tells the Device Handler to display the report on the home device (that is, on your terminal), as shown below:

Figure 144: Choosing the home device




To send output to a printer, enter the name of the printer at the "DEVICE:" prompt, as shown below:

Figure 145: Choosing a printer device



To select the closest printer, if one is defined (unlikely), you can simply enter **P** and press **Enter>**, as shown below:

Figure 146: Choosing the closest printer device



You can enter a question mark ("?") to display help about the syntax of the response.

Figure 147: Device syntax help—One question mark (?)

```
DEVICE: ?
Specify a device with optional parameters in the format
Device Name; Right Margin; Page Length
or
Device Name; Subtype; Right Margin; Page Length
```

You can enter two question marks ("??") to display available printers and other devices connected to the current Volume Set or "reachable from" the current Volume Set. You can also ask for a series of help frames under extended help:

Figure 148: Displaying devices help—Two question marks (??)

```
DEVICE: ??
The following information is available:
    All Printers
    Printers only on 'ROU'
    Complete Device Listing
    Devices only on 'ROU'
    Extended Help

Select one (A,P,C,D, or E):
```

You can list all devices. In addition to printers, this list shows other types of devices you can use to handle output. An example of a partial printer listing is shown below:

Figure 149: Sample printer listing

```
Select one (A,P,C,D, or E): P

GENICOM10P 6th Floor 301

HP LASER DEV-10P

HP LASER DEV-12P
```



REF: Unusual device types (e.g., Resource devices) are discussed in "Special Devices."

14.1.1 Specifying Right Margin and Page Length

Ordinarily, when choosing an output device, you only need to specify the device name. There can be times, however, when you may find it useful to specify the right margin or the page length for your output. The syntax to specify margin and page length uses semicolon delimiters. The format is:

```
DEVICE: Device Name ; Right Margin ; Page Length
```

The following examples show how to use the additional semicolon-delimited pieces at the "DEVICE:" prompt:

Table 17: Sample semicolon-delimited pieces at the "DEVICE:" prompt

Semicolon-delimited Piece	Description	
DEVICE: DVNM5;80;66	Use the DVNM5 device with a right margin of 80 columns and page length of 66 lines.	
DEVICE: ;132	Use the home device, right margin of 132.	
DEVICE: ;;66	Use the home device and format the output with page breaks at 66 lines.	
DEVICE: ;;9999	Scroll output on the home device without needing to press the <enter></enter> key at page breaks.	

14.2 Queuing

At the "DEVICE:" prompt, if you enter a device's name, the output goes directly to that device. If the output you're sending is, for example, a long report, this ties your terminal up until the report finishes printing to that device.

You can print output and yet keep your terminal free for other processing by queuing your jobs rather than running them directly. As described in the " $\underline{TaskMan}$: $\underline{User\ Interface}$ " section, you can queue output by entering \mathbf{Q} at the "Device:" prompt. The device prompt is then presented a second time so that you can specify the output device.

Figure 150: Specifying a device and queuing a print job—Sample user dialogue (1 of 2)

DEVICE: Q
DEVICE: DVNM5
REQUESTED TIME TO PRINT: NOW// <Enter>
REQUEST QUEUED!
Task number: 856103

Alternatively, you can still specify the device first. The Device Handler checks to see if the device is available and, if so, asks you if you want to queue your output. If the device cannot be reached at the current time, Device Handler indicates that the device is busy or unavailable. You can avoid the preliminary availability check by entering \mathbf{Q} at the first prompt (see Figure 150).

Figure 151: Specifying a device and queuing a print job—Sample user dialogue (2 of 2)

```
DEVICE: DVNM5
DO YOU WANT YOUR OUTPUT QUEUED? NO// YES

REQUESTED TIME TO PRINT: NOW// T@18:00 <Enter> (JUL 11, 2004@18:00)
REQUEST QUEUED!
Task number: 856109
```

Whether you request queuing before or after naming a device, Device Handler then asks you to specify a time for the queued job to run. You can accept the default (NOW) or indicate a later time in the usual format. Queuing sends output to TaskMan for scheduling. Meanwhile, you can continue working on the computer system without a delay.

Figure 152: Queuing a print job—Sample user dialogue

```
REQUESTED TIME TO PRINT: NOW// T@18:00 <Enter> (JUL 11, 2004@18:00)
REQUEST QUEUED!
Task number: 856109
```



REF: For more information about queuing output, see the "TaskMan: User Interface" section.

14.3 Specifying a Special Subtype

There is an exception to using numbers in the second semicolon piece to indicate a right margin setting. If, instead of a number, you use a letter and then a hyphen in a device specification (e.g., P-DEC), the second semicolon piece specifies a terminal type entry from the TERMINAL TYPE file (#3.2) to use for the output. A terminal type entry specifies information about what commands to use with specific printers (e.g., escape codes).

Figure 153: Terminal-type device entry—Without pauses

```
If the home device is a video terminal, output would be formatted with page breaks, and it would scroll without waiting for the user to press the <Enter> key after a screen display.
```

One form of the subtype request made possible by VA FileMan's print routines is the use of the word SINGLE along with **P-** or **PK-**. Appending "-SINGLE" indicates that a pause should occur after the display of each page. If using a slaved device to print the screen display, for example, the next page is displayed only after the user has pressed **Enter>**:

Figure 154: Terminal-type device entry—With pauses

DEVICE: ;P-DEC-SINGLE

If the home device is a video terminal, output would be presented one (single) page at a time; the next page being displayed after the user presses the <Enter> key.

If you're not sure which subtype to use, you can enter a partial specification of the subtype in the second piece, and the Device Handler lets you choose from all matching subtypes. For example, if a dozen subtypes begin with "P-LASER...," you can list them by entering only the beginning of the subtype name (e.g., P-LASER):

Figure 155: Partial Device specification—Unknown subtype

DEVICE: LASER; P-LASER

All subtypes beginning with P-LASER are listed; you can then choose a subtype from this list.

When using a subtype as the second semicolon piece of a device specification, you can still specify a right margin and page length to use, but you then do so with the 3rd and 4th semicolon pieces:

Figure 156: Device specification—Four semicolon piece: Sample

DEVICE: LASER; P-LASER-NEW; 132; 100

The syntax for the four semicolon piece form of the device specification is:

Figure 157: Device specification—Four semicolon piece: Syntax

DEVICE: Device Name ; Subtype ; Right Margin ; Page Length

14.3.1 Spool Document Names—An Exception

When you request the spool device at the device prompt, you can use the following formats to specify the spool document name:

Figure 158: Device syntax—Specifying a spool document name: Sample formats (1 of 2)

```
DEVICE: Spooler; Spool Document Name; Right Margin; Page Length
```

Figure 159: Device syntax—Specifying a spool document name: Sample formats (2 of 2)

```
DEVICE: Spooler; Subtype; Spool Document Name
```

Although neither right margin nor page length can be specified when including a subtype as the second piece and spool document name as the third, no functionality is lost. The explanation is simple; the spooler only responds to these two terminal type specifications. In other words, identifying a subtype for the spooler does no more than define a margin and page length.

Spool document entries in the SPOOL DOCUMENT file (#3.51) *cannot* have names beginning with: **P-**, **PK-**, **C-**, etc. (i.e., one or two letters followed by a hyphen, see Section #15.4.1). Because this syntax is the required naming convention for subtypes, you are allowed to specify the document name and the subtype in any order.



REF: For more information about Spool Devices, see the "Spooling" section.

14.4 Alternate Syntax for Device Specification

An alternate syntax is available for specifying right margin and page length when responding to the device prompt. Using the alternate format, you can specify pitch, intensity, and quality. The success of specifying these additional attributes, however, depends on whether the corresponding fields have been defined by system administrators at your site.

The syntax requires the use of a slash ("/") after the last semicolon (see Figure 160).

You can use the following codes to specify special device attributes (in any order), without separating punctuation to delimit the pieces:

Table 18: Alternate device attribute codes

Code	Description
В	Boldface
L	Page length
М	Margin
Р	Pitch
Q	Quality (can be Q, Q1, or Q2)

For example, you could specify:

Figure 160: Specifying a device—Using alternate syntax

DEVICE: LASER; P-LASER-LANDSCAPE; /M132L100P16BQ2

In this example (Figure 160), the following attributes are set:

- Margin ("M") is set to 132 (M132)
- Page length ("L") is set to 100 lines (L100)
- Pitch ("**P**") is set to 16 (**P16**)
- Intensity to boldface ("B")
- Quality ("Q") set to letter quality (Q2).

An absence of the B would indicate normal intensity. The quality settings are: Q, Q1, and Q2.

Your system administrators need to confirm that the appropriate code to set the specified printer attributes is set up for the device that you are using. Then, when the Device Handler closes the device, system administrators need to be sure that appropriate reset code is in the CLOSE EXECUTE field, so that the characteristics do *not* stay in effect. If, for example, someone requests a small pitch, subsequent reports also use the small pitch unless reset in the CLOSE EXECUTE statement for that device (or altered by the OPEN EXECUTE statement of the next device called).

14.5 Summary

The Device Handler is a common interface used by all VistA applications to send output to devices (usually, printers). Once you become familiar with the Device Handler, you can enhance your productivity by making use of some of the Device Handler's special features, including queuing, selecting a specific right margin or page length, and selecting a special subtype.

15 Device Handler: System Management

The Device Handler makes use of two primary Files:

- DEVICE File (#3.5)
- TERMINAL TYPE File (#3.2)

Together, these two files control most of the characteristics of devices in Kernel.

The global locations of the device-related files are:

Table 19: Device-related files global locations

Device-related File Name	Global Location
DEVICE (#3.5)	^%ZIS(1,
TERMINAL TYPE (#3.2)	^%ZIS(2,
DA RETURN CODES (#3.22)	^%ZIS(3.22,

15.1 DEVICE File (#3.5)

Kernel's DEVICE file (#3.5) stores information about devices on the system. All connected volume Sets/CPUs should make use of a single DEVICE file (#3.5). Then all information concerning a particular device is stored in just one place, which facilitates device management.

Sometimes, a CPU has an attachment point to which a device can be connected, for example, physical ports. The \$I field in the DEVICE file (#3.5) entry identifies this attachment point.

Most devices (e.g., printers) are connected to the network and \$I points to the name used by the underlying OS to point to the device. When using such a device, Kernel's Device Handler allows the creation and use of multiple DEVICE file (#3.5) entries for the same physical device. Each DEVICE file (#3.5) entry can contain different specifications (font, margin, page length, etc.) to format output. Each entry in the DEVICE file (#3.5), then, uniquely identifies a set of instructions to send to a particular device on the network.

Each device that Kernel Device Handler needs to communicate with should be set up as an entry in the DEVICE file (#3.5). The DEVICE file (#3.5) supports a variety of devices, including video display terminals (VDTs), commonly called cathode ray tube devices (CRTs); printers; tape drives; and operating system files (e.g., Host File Server [HFS] devices).

The DEVICE file (#3.5) is located in the Manager's account for common reference from all associated accounts. With TaskMan's help, this information is also available to all associated processors (CPUs) in the local area network.

15.1.1 DEVICE File Fields

The most essential fields in the DEVICE file (#3.5) to populate or consider populating for device entries are:

Table 20: DEVICE file fields

Field	Description
NAME (#.01)	This is the name of the device. It is used at the "DEVICE" prompt to
	select this device. It should not be the internal name for the device but a logical one. It must start with one uppercase character and not contain lowercase characters.
\$I (#1)	This field holds the hardware port name that the operating system (OS) can identify when referencing a port on a CPU. On layered systems where opening of host files is supported, this field can hold the host file name.
VOLUME SET(CPU) (#1.9)	(Optional) This field holds the name of the CPU to which this device belongs. It holds the name of the CPU where the physical port resides.
	If entered, the device is assumed to be accessible only from the specified CPU.
	If the field is left blank, this device is assumed to be accessible from all CPUs in the network. In other words, when this device is referenced, the Device Handler operates as if this device is resident on the local CPU. For example, if there is a device that uses the same \$I on each CPU, one entry can be made in the DEVICE file (#3.5) by leaving this field set to null. This shortcut works only if the same \$I has been associated with this device on every CPU. The Device Handler still maintains the CPU cross-reference to support queuing and other activities. The cross-reference format involves use of periods as delimiters. If the VOLUME SET(CPU) value were "BBB," the cross-reference for the device with a \$I of 75 would be "BBB.75". If the VOLUME SET(CPU) value were NULL, then ".75" would be the CPU cross-reference.
	NOTE: In the Caché environment, where cluster mounting is used and most devices are set up on all CPUs, all such devices do not need a value for this field.
SIGN-ON/SYSTEM DEVICE (#1.95)	If set to YES, this field identifies that this entry is the primary device among those device entries that have the same \$I with the same VOLUME SET(CPU). Among those device entries that have a common \$I and CPU, only one of these entries can have this field set to YES. If none of the common device entries is set to YES, the default device is identified by the first device on the CPU cross-reference. The default device is used when the Device Handler is invoked with \$I as the device to be selected.
TYPE (#2)	This field contains the general type of device on the CPU.
	REF: For a list of device types, see Table 21.
SUBTYPE (#3)	Use this field to select a default terminal type for the device. This field points to the TERMINAL TYPE file (#3.2) to retrieve a standard

Field	Description	
	set of characteristics that have been defined for vendor devices (e.g., Laser printers or VT320 CRTs).	
	REF: For a discussion of the TERMINAL TYPE file (#3.2), see the "TERMINAL TYPE File (#3.2)" section.	
QUEUING (#5.5)	You can control the degree of queuing allowed for a device with the QUEUING field.	
	REF: For a list of settings to control queuing for a device, see Table 22.	
PRE-OPEN EXECUTE (#7)	This is the executable M code that is used by %ZIS before opening the device.	
	If you define the %ZISQUIT variable, the device open fails. Setting %ZISQUIT=1 in the PRE-OPEN EXECUTE code signals %ZIS to reject the selected device. With this variable, you can use the PRE-OPEN EXECUTE as a screen on whether the device should be opened or not.	
POST-CLOSE EXECUTE (#8)	This is the executable M code that is used by %ZISC after closing the device.	
OPEN PARAMETERS (#19)	These parameters are used to open a device with specified characteristics/addresses. This field is primarily used with non-terminal devices (e.g., Magtape and Sequential Disk Processor).	
	Magtape (MT), SDP (obsolete), and Host File Server (HFS) device types use the value in this field as the default if the ASK PARAMETERS (#5) flag is set. Users would then be prompted for address/parameters. If the ASK PARAMETERS flag is not set and if there is a value in the OPEN PARAMETERS field (#19), this value is used when opening the device (or file).	
	NOTE: Each operating system has its own way of specifying parameters. For example, under Caché, margins are set with both the OPEN and USE command.	
USE PARAMETERS (#19.5)	This field holds the parameters to be used in an M USE statement.	
	The Device Handler takes information from this field when opening and using such devices as the Magtape (MT) drive.	
	NOTE: Each operating system has its own way of specifying parameters. For example, under Caché, margins are set with both the OPEN and USE command.	

Table 21: Device types in the TYPE Field in the DEVICE file (#3.5)

Туре	Description	
BAR	Identifies the device as a bar code reader.	
CHAN	Network Channels are high speed devices that use network protocols (e.g., TCP/IP).	
HFS	The Host File Server (HFS) type, and the associated functionality, provides the vehicle to READ and WRITE to host level files. Instead of directing reports to a printer, the results could be placed into an OpenVMS or UNIX/Linux file. This would allow non-M-based statistical software or spreadsheet to use data produced by the M-based application by simply extracting data from the host file.	
IMPC	Imaging work station device (reserved for VistA Imaging).	
MT	Magtape (MT) devices.	
ОТН	Other (OTH) devices that do not fit a particular category.	
RES	Resources (RES) is a type used for special sequencing of tasks that do not require a particular device.	
SDP	(Obsolete) Sequential Disk Processor (SDP) is a predefined allocated disk space used for sequential processing; use HFS.	
SPL	Spool (SPL) device is a predefined allocated disk space. It is similar to SDP; however, access to the spool device can be achieved from multiple users simultaneously.	
TRM	Terminal devices (e.g., most CRTs and printers) should be associated with a corresponding device entry with a type of "TRM".	
VTRM	Virtual Terminal Server devices are those that are associated with a dynamically created M port identification (\$I). A generic device entry with a device type of "VTRM" can be established for users who log into the system through terminal servers or other network protocols.	

- NOTE: Device type descriptions can also be obtained by entering two question marks ("??") at the TYPE field while editing a device.
- **REF:** For more information on these device types, see "Special Devices."

Also, for more information on Host File Server (HFS) devices, see "Host Files."

Table 22: Queuing settings

Setting	Queuing	Description
0	ALLOWED	Jobs can be queued or run directly (default).
1	FORCED	Queuing is forced, unless disallowed by application.
2	NOT ALLOWED	Queuing to device is not allowed.

15.1.1.1 OpenVMS-Specific DEVICE Fields



NOTE: These fields are used by VMS and *not* Caché.

The DEVICE file (#3.5) can store operating system-specific information. For example, several fields are included in the DEVICE file (#3.5) to configure terminals and ports on Terminal Servers as part of an OpenVMS start-up command file. These are:

Table 23: Mixed OS Environment fields in the DEVICE file (#3.5)

Field	Description
LAT SERVER NODE (#61)	This is the DECserver/terminal server node name that the device is on. It is used by the XTLATSET routine to build data files for VMS startup.
LAT SERVER PORT (#62)	This is the port on the DECserver/terminal server to which this device is connected. It can be entered in the LC-2-5 form or 31 form. On EQUINOX it is in the PORT_31 form. This field is used by the XTLATSET routine to build VMS data files for startup.
VMS DEVICE TYPE (#63)	This is a flag that is passed into the file LT_PTR.DAT by the XTLATSET routine to select how this port should be set up in VMS by the SYS\$MANAGER:SYSPRINT.COM file when it runs.
LAT PORT SPEED (#64)	This field holds the value that is passed to the TSC_LOAD.COM file for loading the DECserver permanent database.
PRINT SERVER NAME OR ADDRESS (#65)	This field contains the fully qualified domain name (FQDN) or specific TCP/IP address of a remote server (e.g., LPD/LPR printing) or device (e.g., Telnet printer).
TELNET PORT (#66)	This field contains the Telnet port of a remote device (e.g., Telnet printer). The allowable range is a number between 2000 and 65534.
REMOTE PRINTER NAME (#67)	This is the name of the remote printer that is referenced by the PRINT SERVER NAME OR ADDRESS (#65) and TELNET PORT (#66) fields.

Kernel Toolkit software distributes the XTLATSET and NVSTNSET routines that makes use of these fields.

15.1.2 Device Edit Menu

The DEVICE file (#3.5) has many more fields where additional specific information for particular devices can be entered. Kernel provides a number of options to facilitate creating and editing device types on the Device Edit menu [XUDEVEDIT] on the Device Management menu [XUTIO]:

Figure 161: Device Edit options

Device Management	•••	[XUTIO]
Device Edit		[XUDEVEDIT]
ALL	Edit All Device Fields	[XUDEVEDITALL]
CHAN	Network Channel Device Edit	[XUDEVEDITCHAN]
HFS	Host File Server Device Edit	[XUDEVEDITHFS]
LPD	LPD/VMS Device Edit	[XUDEVEDITLPD]
MT	Magtape Device Edit	[XUDEVEDITMT]
RES	Resource Device Edit	[XUDEVEDITRES]
SPL	Spool Device Edit	[XUDEVEDITSPL]
TRM	TRM or VTRM Device Edit	[XUDEVEDITTRM]



AUTHOR'S NOTE: The SDP Device Edit option [XUDEVEDITSDP] is purposely not displayed in this menu list, because it is obsolete.

15.1.3 Sample Device File Entries

Kernel patch XU*8.0*440 also included the addition of the SECONDARY \$I field (#52) in the DEVICE file (#3.5).

15.1.3.1 HFS Devices

Figure 162 and Figure 163 show an HFS device using the Host File Server Device Edit option [XUDEVEDITHFS] to update Field #52:

Figure 162: HFS device—Sample data entry screen

```
EDIT A HOST FILE SERVER DEVICE
   NAME: HFS
                                             LOCATION: Host Disk File
     $I: USER$:[TEMP]MIXED.TXT
ALT $I: /TMP/MIXED.TXT
SUBTYPE: P-OTHER
                                           MARGIN WIDTH:
      ASK PARAMETERS: YES
       ASK HOST FILE: YES
                                             PAGE LENGTH:
ASK HFS I/O OPERATION: NO
                                        VOLUME SET(CPU):
   OPEN PARAMETERS: ("NWS")
  CLOSE PARAMETERS:
 PRE-OPEN EXECUTE:
POST-CLOSE EXECUTE:
           QUEUING: ALLOWED
                                      SUPPRESS FORM FEED: YES
Exit
         Save
                  Refresh
Enter a command or '^' followed by a caption to jump to a specific field.
COMMAND:
                                               Press <PF1>H for help
                                                                         Insert
```

Figure 163: HFS device—Sample DEVICE file entries

```
NAME: HFS

ASK DEVICE: NO

LOCATION OF TERMINAL: Disk

ASK HOST FILE: NO

ASK HFS I/O OPERATION: YES

OPEN COUNT: 5

TYPE: HOST FILE SERVER

OPEN PARAMETERS: ("NWS")
```

<u>Figure 164</u> shows a printer set up as an HFS device with the Terminal Type CLOSE EXECUTE, which submits the file to the OS print queue:

Figure 164: HFS device—Sample data entry screen with the Terminal Type CLOSE EXECUTE

EDIT A HOST FILE SERVER DEVICE NAME: SDD P10 LOCATION: Printer next to One Xuuser \$I: USER\$:[TEMP]SDD_DN2\$PRT.TXT Alt \$I: SUBTYPE: P-HP8000 TCP/S ASK PARAMETERS: NO MARGIN WIDTH: ASK HOST FILE: NO PAGE LENGTH: ASK HFS I/O OPERATION: NO VOLUME SET(CPU): OPEN PARAMETERS: "NWS" CLOSE PARAMETERS: PRE-OPEN EXECUTE: POST-CLOSE EXECUTE: QUEUING: SUPPRESS FORM FEED: YES Exit Save Refresh Enter a command or '^' followed by a caption to jump to a specific field. COMMAND: Press <PF1>H for help Insert

15.1.3.2 **NULL Devices**

<u>Figure 165</u> and <u>Figure 166</u> shows a NULL device entry for a mixed operating system, VMS (Primary) and Linux (Secondary), using the TRM or VTRM Device Edit option [XUDEVEDITTRM] to update the SECONDARY \$I field (#52) in the DEVICE file (#3.5):

Figure 165: Mixed Operating System: VMS (Primary) and Linux (Secondary) NULL device—Sample data entry screen

Edit a TRM or VTRM device NAME: NULL LOCATION: Bit Bucket \$I: _NLA0: ALT \$I: /dev/null TYPE: TERMINAL SUBTYPE: P-OTHER SIGN-ON/SYSTEM DEVICE: NO VOLUME SET(CPU): ASK DEVICE: NO MARGIN WIDTH: ASK PARAMETERS: NO PAGE LENGTH: SUPPRESS FORM FEED: OUEUING: Exit Save Refresh Enter a command or '^' followed by a caption to jump to a specific field. COMMAND: Press <PF1>H for help Insert

Figure 166: Mixed Operating System: VMS (Primary) and Linux (Secondary) NULL device—Sample DEVICE file entries

NAME: NULL

ASK DEVICE: NO

SIGN-ON/SYSTEM DEVICE: NO

SECONDARY \$1: /dev/null

SUBTYPE: P-OTHER

\$1: _NLAO:

ASK PARAMETERS: NO

LOCATION OF TERMINAL: Bit Bucket

OPEN COUNT: 8523

TYPE: TERMINAL



REF: For additional sample NULL device entries, see Section 15.6.4.2, "Null Device."

15.1.3.3 BROWSER Devices

The following example shows DEVICE file (#3.5) entries for a BROWSER device:

Figure 167: BROWSER device—Sample DEVICE file entries

```
$I: USER$:[BROWSER]DDBR.TXT
NAME: BROWSER
 ASK DEVICE: YES
                                       ASK PARAMETERS: NO
 SIGN-ON/SYSTEM DEVICE: NO
                                      OUEUING: NOT ALLOWED
                                      ASK HOST FILE: NO
 LOCATION OF TERMINAL: BROWSER
 ASK HFS I/O OPERATION: NO
                                      SECONDARY $1: /tmp/ddbr.txt
 OPEN COUNT: 1
                                      OPEN PARAMETERS: ("NWS")
 POST-CLOSE EXECUTE: D POST^DDBRZIS I $G(IO("CLOSE"))'="" N % S %=$$DEL1^%ZISH(
IO("CLOSE"))
 PRE-OPEN EXECUTE: N X S X=$$TEST^DDBRT S:X IO=$$UNIQUE^$ZISUTL(IO) I 'X S %ZIS
QUIT=1,X="Browser not selectable from current terminal." W $C(7),!,X
  SUBTYPE: P-BROWSER
                                       TYPE: HOST FILE SERVER
```

15.1.3.4 P-MESSAGE Devices

The following example shows DEVICE file (#3.5) entries for a P-MESSAGE device:

Figure 168: P-MESSAGE device—Sample DEVICE file entries

```
NAME: P-MESSAGE-HFS-ONT $1: USER$:[TEMP]XMHFS.TMP

ASK DEVICE: NO ASK PARAMETERS: NO

SIGN-ON/SYSTEM DEVICE: NO QUEUING: ALLOWED

LOCATION OF TERMINAL: HFS FILE==> MESSAGE

ASK HOST FILE: NO ASK HFS I/O OPERATION: NO

SECONDARY $1: /tmp/xmhfs.tmp OPEN PARAMETERS: ("NWS")

PRE-OPEN EXECUTE: D EN^XMAPHOST Q:$G(POP) S IO=$$UNIQUE^$ZISUTL(IO)

SUBTYPE: P-MESSAGE-HFS-ONT TYPE: HOST FILE SERVER
```

15.1.3.5 TELNET Devices

The following examples show DEVICE file (#3.5) entries for TELNET devices:

Figure 169: TELNET device—Sample DEVICE file entries (1 of 2)

```
NAME: TELNET/LINUX $1: /dev/pts/
ASK DEVICE: YES SIGN-ON/SYSTEM DEVICE: YES
LOCATION OF TERMINAL: Telnet Terminal
OPEN COUNT: 101 SUBTYPE: C-VT320
TYPE: VIRTUAL TERMINAL
```

Figure 170: TELNET device—Sample DEVICE file entries (2 of 2)

```
NAME: TELNET/VMS $1: TNA
ASK DEVICE: YES ASK PARAMETERS: NO
SIGN-ON/SYSTEM DEVICE: YES LOCATION OF TERMINAL: Telnet terminal
OPEN COUNT: 8657 SUBTYPE: C-VT320
TYPE: VIRTUAL TERMINAL
```

15.2 Mixed OS Environment Fields



NOTE: This is for Caché only.

With the advent of remote data centers (RDCs), the VA may use mixed OS environments with a Caché Extended Caché Protocol (ECP) App/Data server configuration. In this environment output devices need different \$IO values depending on where the job is running. Kernel patch XU*8.0*440 added support to allow the Device Handler to work in a mixed operating system (OS) environment. The following fields were added to the KERNEL SYSTEM PARAMETERS file (#8989.3) to provide this support:

Table 24: Mixed OS Environment fields in the KERNEL SYSTEM PARAMETERS file (#8989.3)

Field	Description	
MIXED OS (#.05)	This is used to select which field to use when selecting operating system (OS)-specific data fields in a mixed OS environment. The support is for Caché in an ECP client/server configuration with only two operating systems at a time. In a mixed environment the primary OS is always VMS, and the secondary OS is not VMS (i.e., Linux or NT). Some of the fields that need mixed values are:	
	PRIMARY HFS DIRECTORY field (#320) in the KERNEL SYSTEM PARAMETERS file (#8989.3)	
	SECONDARY HFS DIRECTORY field (#320.2) in the KERNEL SYSTEM PARAMETERS file (#8989.3)	
	SECONDARY \$I field (#52) in the DEVICE file (#3.5)	
SECONDARY HFS DIRECTORY (#320.2)	This field holds the secondary HFS directory path.	
LOGICAL DISK NAME (#504)	This field holds a logical disk name that is stored in the Caché CPF file for client system in an ECP client/server configuration.	
PHYSICAL DISK (#505)	This field holds the physical disk name to which Cache VMS converts the LOGICAL DISK NAME (#504).	
SECONDARY \$I (#52)	This field holds the \$IO value to be used if this is the secondary system in a mixed OS environment. It is not used otherwise. It is only used for output devices.	

15.2.1 Edit Logical/Physical Mapping Option

Kernel patch XU*8.0*440 added the Edit Logical/Physical Mapping option [XU SID EDIT] on the Kernel Management Menu [XUKERNEL]. The XU SID EDIT option lets you edit the fields that support the LOGICAL to PHYSICAL translation for the System ID. This is only valid in a Caché 5.2 client/server configuration.

15.2.2 Enter/Edit Kernel Site Parameters option

Kernel patch XU*8.0*440 updated the Enter/Edit Kernel Site Parameters option [XUSITEPARM], screen 3, shows these added fields:

Figure 171: Enter/Edit Kernel Site Parameters option—ScreenMan form 3: MIXED OS (#.05) and SECONDARY HFS DIRECTORY (#320.2) fields

```
Kernel Site Parameter edit
            DOMAIN: XXX.KERNEL.FO-SITE.MED.VA.GOV
    MAX SPOOL LINES PER USER: 99999
MAX SPOOL DOCUMENTS PER USER: 99
MAX SPOOL DOCUMENT LIFE-SPAN: 60
                MIXED OS: VMS/LINUX
DEFAULT DIRECTORY FOR HFS: USER$:[TEMP]
  SECONDARY HFS DIRECTORY: /VAR/TMP/
DNS IP: 10.9.99.10,10.9.21.999
NEW PERSON IDENTIFIERS:
Exit
        Save Next Page Refresh
Enter a command or '^' followed by a caption to jump to a specific field.
COMMAND:
                                              Press <PF1>H for help
                                                                       Insert
```

15.3 Device Security

To regulate who can use a particular device, you can use the PASSWORD and SECURITY fields.

The SECURITY field, if populated, should contain a string of characters to compare with a user's FILE MANAGER ACCESS CODE field (#3), DUZ(0), when the device is selected. Access is denied to anyone whose DUZ(0) does not contain one of the specified characters. As with other uses of DUZ(0), the at-sign ("@"; programmer access) overrides this restriction.

The PASSWORD field, if populated, forces all users trying to log on to the device to be prompted for the matching password, before entering their Access code.

15.4 TERMINAL TYPE File (#3.2)

The TERMINAL TYPE file (#3.2) holds device vendor-specific code to characterize a terminal type. For example, escape sequences can be entered in the OPEN EXECUTE (#6) and CLOSE EXECUTE (#7) fields to set pitch or font. Every device in the DEVICE file (#3.5) *must* be assigned a terminal type, in the SUBTYPE field (#3).

The most common fields to populate for TERMINAL TYPE file (#3.2) entries are:

Table 25: Common fields in the TERMINAL TYPE file (#3.2)

Field	Description
NAME (#.01)	The name of the terminal type. REF: For a description and list of acceptable terminal type name formats, see the "Terminal Type Naming Conventions" section and Table 26.
SELECTABLE AT SIGN-ON (#.02)	This field is used to screen the choices that can be made at the "DEVICE TYPE" prompt during signon.
RIGHT MARGIN (#1)	This field is the number of characters wide for this device.
FORM FEED (#2)	The argument of an M WRITE statement that sets the top-of-form for the use of tractor-feed paper on a printer, or clears the screen of a video display terminal.
PAGE LENGTH (#3)	This field is the number of usable lines on the output device.
BACK SPACE (#4)	The argument of an M WRITE statement that causes the cursor to back space.
OPEN EXECUTE (#6)	This is the executable M code that is used by %ZIS to OPEN the terminal.
CLOSE EXECUTE (#7)	This is the executable M code that is used by %ZIS to CLOSE the terminal [i.e., X ^%ZIS("C")].

The TERMINAL TYPE file (#3.2) has many more fields where additional specific information for particular terminal types can be entered. Kernel provides the following options to facilitate creating and editing terminal types:

Figure 172: Terminal type edit options

Device Management Terminal Type Edit Change Device's Terminal Type List Terminal Types	[XUTIO] [XUTERM] [XUCHANGE] [XULIST]
--	---

15.4.1 Terminal Type Naming Conventions

The convention for naming terminal types is as follows:

Table 26: Terminal type naming conventions

Terminal Type	Description
C-	Video terminals (e.g., C-VT320).
PK-	Printers with keyboards.
P-	Printers without keyboards (e.g., P-LASER).
M-	Modems.

The general format is limited to two alphabetic character prefix, followed by a hyphen, and followed by alphanumeric characters.

As mentioned previously (see Section #14.3.1), a spool document name *cannot* use this format; this is so that it can be distinguished from a device subtype in a call to the Device Handler. Confusion could arise since either can be used as the second piece of the device specification. The SPOOL DOCUMENT file (#3.51) has an input transform pattern match that guards against creation of document names in the format of device subtypes.

15.4.2 How Shared Device and Terminal Type Attributes are Used

The DEVICE (#3.5) and TERMINAL TYPE (#3.2) files share attribute fields for RIGHT MARGIN and PAGE LENGTH. If a value is entered for RIGHT MARGIN or PAGE LENGTH in the DEVICE file (#3.5), it overrides the value from the TERMINAL TYPE file [#3.2].

When a user selects a device by responding to the device prompt with only the first required piece of information, the device identification, Device Handler retrieves parameters to characterize the device (e.g., RIGHT MARGIN) from the DEVICE file (#3.5). Furthermore, the Device Handler checks the ASK PARAMETERS (#5) flag for the selected device and, if the flag is set, prompts the user for associated parameters, presenting DEVICE file (#3.5) characteristics as the default. For terminals and virtual terminals (types TRM and VTRM, respectively), the user is prompted for the right margin. For magtape (MT), Sequential Disk Processor (SDP; obsolete), and Host File Server (HFS) devices, they can be prompted for address/parameters with the value of the OPEN PARAMETERS field (#19) (in the DEVICE file [#3.5]) as the default.



REF: For more information on Magtape (MT) devices, see "Special Devices."

For more information on Host File Server (HFS) devices, see Chapter 16, "Host Files."

15.4.3 Terminal Type Information Retained by User

User can change some terminal type attributes of their signon device by doing either of the following:

- Changing the terminal type during the session with the Edit User Characteristics option [XUSEREDITSELF].
- Selecting a device for direct output.

Kernel uses the 'XUTL global to hold information about changes made to device characteristics of the home device during a session.



REF: For more information the 'XUTL global, see the "Menu Manager: System Management" section

The terminal type established for users at each signon is stored in their NEW PERSON file (#200) entries so that, if necessary, it can be used as a default for the next signon.

15.5 Devices and Signon

15.5.1 Device Selection at Signon and Virtual Terminal Devices

Every interactive user *must* be associated with a device by the Device Handler when they sign onto the VistA system. The device association is done by matching the incoming user's \$I (#1) field value with the \$I value of an entry in the DEVICE file (#3.5).

Historically, it was practical to set up one device entry with a matching \$I for each physical port. With the move to OpenVMS, however, the \$I of the user was dynamic, with many thousands of \$I values possible. The Virtual Terminal device type (VTRM; see Table 21) was created as a way to have one device entry to be used for signon for multiple incoming \$I values. The Device Handler still checks to see if it can assign a device to an incoming process based on an exact match of \$I values. If there is no direct match, however, Device Handler checks to see if the *first part* of the user's \$I value matches the \$I value of a virtual device entry. This way, a virtual device with a \$I value of "_TNA" can service all incoming processes whose \$I values *start* with the string "TNA".

Virtual devices do *not* need a value in the VOLUME SET(CPU) field (#1.9); they should have the SIGN-ON/SYSTEM DEVICE field (#1.95) set to **YES**, however, to speed up the signon device selection process.

Common device prefixes on VMS systems that could be used for virtual terminal device entries include:

- "TNA"—Telnet devices
- "RTA"—Remote processes using the "SET HOST" command
- "FTA"—Secure Shell devices

Processes on VMS systems that use Telnet usually have \$I values beginning with the prefix "TNA", concatenated with an integer value and a colon (e.g., "TNA8456:"). A single virtual terminal device entry whose \$I value is "TNA" services all such processes.

15.5.2 Terminal Type Selection at Signon

Besides needing a device assigned at signon, users also need a terminal type. As described in the "Signon/Security: System Management" section, Kernel can usually determine the correct subtype without needing to prompt the user by querying the terminal and matching the returned string (if any) with return codes for terminals stored in the DA RETURN CODES file (#3.22).

If the user is prompted to enter a terminal type, they need to choose one. The list of terminal types from which they can choose is screened by the SELECTABLE AT SIGN-ON field (#.02) in the TERMINAL TYPE file (#3.2). Users can only choose from entries with this field set to **YES**. This stops users from choosing inappropriate terminal types. The setting of this field does *not* prevent terminal types from being chosen by the DA return code method, however. Make sure that all terminal types appropriate for signon have SELECTABLE AT SIGN-ON (#.02) set to **YES**.

If the Signon/Security system cannot supply even a default, the Device Handler makes a selection according to the signon device's subtype.

15.5.2.1 Managing Display Attributes (DA) Return Codes

Figure 173: DA Return Code Edit option

```
Device Management ... [XUTIO]
DA Return Code Edit [XU DA EDIT]
```

The DA RETURN CODES file (#3.22) stores entries for the codes returned by different terminals after Kernel prompts for their display attributes at signon. This file then maps Kernel terminal types to the terminal's return codes. This mapping allows sites to set up mappings for new terminals or to map different terminals to a common type. For example, a site could map all codes returned by all DEC VT type terminals to a single C-VT102 type terminal type.

The DA RETURN CODES file (#3.22) is a small static file managed by the DA Return Code Edit option [XU DA EDIT]. You can use the DA Return Code Edit option to automate the population of the DA RETURN CODES file (#3.22). When you select this option, the terminal you are using is queried and you are shown the terminal's DA code response. You are then prompted for the terminal type and description for this return code. Enter the terminal type name for the terminal you are using. The option updates the DA RETURN CODES file (#3.22), and all terminals responding with this code are recognized at signon. You can quickly populate the DA RETURN CODES file (#3.22) by using this option from several different types of terminals.

Kernel pre-populates the DA RETURN CODES file (#3.22) with a set of standard terminal type entries. You may need to add more entries as needed to handle all terminals at your site.

15.6 Troubleshooting

Figure 174: Device management—Troubleshooting options



Kernel provides several options on the Device Management menu [XUTIO] to aid with troubleshooting device problems, which are described in the topics that follow.

15.6.1 Loopback Test of Device Port Option

Use the Loopback Test of Device Port option [XUTLOOPBACK] to test an RS-232 serial data line when using a loopback connection on the line. First, disconnect the data line from the device it is attached to (if any). Then, tie pins 2 and 3 of the RS-232 serial data line together. This is a loopback connection; data sent down pin 2 (transmit) loops back up pin 3 (receive). The Loopback Test of Device Port option sends the letters of the alphabet down the data line one at a time, and attempts to READ them back. If both lines are intact, you should see "ABCDEFGHIJKLMNOPQRSTUVWXYZ" print on the terminal from which you are testing the data line.

15.6.2 Send Test Pattern to Terminal Option

Use the Send Test Pattern to Terminal option [XUTTEST] to send a simple test pattern to a device. This is an easy way to verify whether a device is connected to the system. It lets you choose how many lines of the test pattern to send, and then sends that number of lines to the device. You can confirm on the device end exactly how many lines of the test pattern you receive, which can be useful when troubleshooting printer handshaking problems.

15.6.3 Out of Service Set/Clear Option

You can use the Out of Service Set/Clear option [XUOUT] to set a device out of order. It asks you the date on which to put the device out of order. From that date forward, the Device Handler does *not* allow any jobs to use the device (users get a message that the device is out of order). To clear the out of order status, use this option again and delete the out of order date.

15.6.4 Verify HFS and Null Device Setup (required)

15.6.4.1 HFS Device

Verify you have a Host File Server (HFS) device in the DEVICE file (#3.5) named "HFS". If you have performed KIDS installations on your server before, you probably already have an appropriate HFS device set up. If you do *not* have an entry for this device, you *must* create one.



REF: For information on how to create an HFS device, see "Host Files."

15.6.4.2 Null Device

Verify you have a Null device in the DEVICE file (#3.5) named "NULL" (or whose mnemonic is named "NULL"). You can have other devices with similar names, but one device is needed whose name or mnemonic is "NULL". The subtype should be a "P-" subtype (e.g., P-OTHER), the margin should be a minimum of 80, and the page length should be a minimum of 60. Sample setups:

Figure 175: VMS NULL device—Sample DEVICE file entries

NAME: NULL \$1: NLAO:

ASK DEVICE: NO ASK PARAMETERS: NO

SIGN-ON/SYSTEM DEVICE: NO LOCATION OF TERMINAL: BIT BUCKIT

SUBTYPE: P-OTHER TYPE: TERMINAL

Figure 176: Mixed Operating System: VMS (Primary) and Linux (Secondary) NULL device—Sample DEVICE file entries

NAME: NULL \$1: NLAO:

SECONDARY \$I: /dev/null

ASK DEVICE: NO ASK PARAMETERS: NO

SIGN-ON/SYSTEM DEVICE: NO LOCATION OF TERMINAL: Bit Bucket

SUBTYPE: P-OTHER TYPE: TERMINAL

Figure 177: Linux Null Device Example—Caché null device setup

NAME: NULL \$1: /dev/null

ASK DEVICE: NO ASK PARAMETERS: NO

SIGN-ON/SYSTEM DEVICE: NO LOCATION OF TERMINAL: BIT BUCKIT

SUBTYPE: P-OTHER TYPE: TERMINAL

Figure 178: Windows Null Device Example—Caché null device setup

NAME: NULL \$1: //./nul

ASK DEVICE: NO ASK PARAMETERS: NO

SIGN-ON/SYSTEM DEVICE: NO LOCATION OF TERMINAL: BIT BUCKIT

SUBTYPE: P-OTHER TYPE: TERMINAL

<u>Figure 179</u> is the TERMINAL TYPE file (#3.2) entry that is used by all of the NULL device configurations.

Figure 179: Null Device Example—P-OTHER Terminal Type setup

NAME: P-OTHER RIGHT MARGIN: 132 FORM FEED: # PAGE LENGTH: 64

BACK SPACE: \$C(8) DESCRIPTION: General prntr (132)

15.7 Device Identification and Cross-references

Devices can be selected in several ways from the "DEVICE:" prompt. Besides the NAME field (#.01), three other attributes: MNEMONIC, LOCAL SYNONYM, and \$I can also be used to select devices. When LOCAL SYNONYM is used, the Device Handler searches the local CPU for a match. Thus, the same LOCAL SYNONYM value (e.g., PRINTER) can be used to identify several devices, one per CPU.

When editing devices through VA FileMan, two additional fields can be used for lookup:

- VOLUME SET(CPU) (#1.9)
- SIGN-ON/SYSTEM DEVICE (#1.95)

You can separate these values with a period delimiter, as follows:

Table 27: Sample period-delimited pieces used for device lookup

Period-delimited Piece	Description	
CPU	All devices matching CPU.	
CPU.\$I	All devices matching the CPU and \$I.	
SYS	All SIGN-ON DEVICES.	
SYS.CPU	All SIGN-ON DEVICES matching CPU.	
SYS.\$I	All SIGN-ON DEVICES matching \$I.	
SYS.CPU.\$I	All SIGN-ON devices matching CPU and \$I.	

For example, to display all signon devices on CPU "BBB", you could do:

Figure 180: Displaying signon devices on a specific CPU—Sample user dialogue

```
Select DEVICE NAME: SYS.BBB
```

To display all signon devices whose \$I begins with "_TNA" you could do:

Figure 181: Displaying signon devices with a specific \$I—Sample user dialogue

```
Select DEVICE NAME: SYS.._TNA
```

The ^%ZIS global listing in <u>Figure 182</u> shows the cross-references for a device with a \$I value of 99 and an internal entry number (IEN) of 251. It is a SIGN-ON/SYSTEM DEVICE (#1.95) and has a VOLUME SET(CPU) (#1.9) value of AAA.

Figure 182: Global listing for device cross-references—\$I value = 99 and IEN = 251

```
^%ZIS(1, "G", "SYS.AAA.99", 251) = ""

^%ZIS(1, "CPU", "AAA.99", 251) = ""

^%ZIS(1, "C", "99", 251) = ""
```

If this device is a virtual terminal with a \$I of _TNA and established as a SIGN-ON/SYSTEM DEVICE (#1.95) but not given a VOLUME SET(CPU) (#1.9) value, the cross-reference structure would be as follows:

Figure 183: Global listing for virtual terminal device cross-references—\$I value = _TNA and IEN = 251

16 Host Files

16.1 Host Files: User Interface

Host File Server (HFS) devices allow you to send output to a file maintained by your computer's operating system, rather than to a printer. You can send your output to an HFS device, if such a device type has been established on the system. Depending upon how system administrators define the HFS device, you may be prompted for a host file name and for an input/output operation:

Figure 184: Choosing a Host File Server (HFS) device—Sample user dialogue

```
DEVICE: HFS <Enter> DISK FILE
HOST FILE NAME: TMP.TMP// <Enter> INPUT/OUTPUT OPERATION: ?
Enter one of the following host file input/output operation:

R = READONLY

N = NEWVERSION

RW = READ/WRITE
```

Not all input/output modes are available on all systems. The possible modes for input/output operation work as follows:

Table 28: HFS input/output modes of operation

Input/Output Mode	Description
APPEND	Data from a WRITE operation is appended to the file.
MIXED	Both READs and WRITEs are allowed for the specified file.
NEWVERSION	A new file is created with a higher version number; this file can be used for WRITEs only.
READ	READs are allowed from the specified file; WRITEs are not allowed.
READONLY	READs are allowed from the specified file; WRITEs are not allowed.
READ/WRITE	Both READs and WRITEs are allowed for the specified file; if a WRITE operation is performed, output is appended to the file.
WRITE	WRITEs are allowed; output can be sent to the specified file.

16.2 Host Files: System Management

To provide access to host files through the Device Handler, set up device entries of type HFS.

There are three fields in an HFS device entry that act as flags for what a user *must* enter when they use an HFS device. The fields are:

Table 29: HFS-related fields in the DEVICE file (#3.5)

Field	Description
ASK PARAMETERS (#5)	If this field is set to YES , the user <i>must</i> enter the correct M open parameters to open the device. This field should be set to NO if the device is accessible to <i>non</i> -system administrator users. If it is set to YES , the default value is the current value of the OPEN PARAMETERS field (#19).
ASK HOST FILE (#5.1)	When this field is set to YES , the user can choose what file is opened. If it is set to NO , the default file name built into the device entry is always used. This field should be set to NO if the HFS device is accessible to <i>non</i> - system administrator users. Host files can proliferate if too many users are able to create many files. Also, an HFS device opens up access to the host operating system and the potential for overwriting vital files.
ASK HFS I/O OPERATION (#5.2)	If this field is set to YES , the user can choose in what mode the file should be opened (e.g., READ or WRITE). If it is set to NO , files are opened in WRITE mode. This should be set to NO if the device is accessible to <i>non</i> -system administrator users, assuming that all such users would only need to WRITE host files.

16.2.1 Host File Server Device Edit Option

Figure 185: Host File Server Device Edit option

Device Management	[XUTIO]
Edit Devices by Specific Types	[XUDEVEDIT]
Host File Server Device Edit	[XUDEVEDITHFS]

The Host File Server Device Edit option [XUDEVEDITHFS] lets you to edit Host File Server device attributes using a ScreenMan form.


16.2.2 Caché and GT.M HFS Device Setup

Caché and GT.M require the name of the host file to be part of the device \$I and not part of the parameter list.

Table 30: HFS I/O operation modes for Caché and GT.M

I/O Operation Mode	Description
NEWVERSION	A new file is created (on VMS with a higher version number); this file can be used for WRITEs only.
READONLY	READs are allowed from the specified file; WRITEs are not allowed.
READ/WRITE	Both READs and WRITEs are allowed for the specified file; if a WRITE operation is performed, output is appended to the file.

Figure 186: Host File Server device for Caché and GT.M—Sample settings



17 Spooling

17.1 Spooling: User Interface

Spooling privileges can be granted by system administrators to users who prepare and manage reports. By sending your output to the spooler, rather than to a printer, you can benefit in several ways. Since spooling saves the output online in a holding area, you can easily print multiple copies of the report at a later time. Spooling is also a good way to store the results of a time-consuming calculation (e.g., a complex VA FileMan report). By queuing to the spooler, a report involving intensive processing can be done at night or off hours when the system is relatively free. Output can then be printed during the day when the printer can be attended. Finally, when using the spooler, report processing can run to completion without printer problems interfering.

17.1.1 Sending Output to the Spooler

If you have been given the authority to spool, you can send output to the spooler by responding to the "DEVICE:" prompt with the name of the spool device. Devices used for spooling are commonly named SPOOL or SPOOLER.

If you do not have spooling privileges and you try to use the spool device, the spooler issues a message that authority has not been granted, as shown below:

Figure 187: Unable to send output to a spool device—Sample message

DEVICE: SPOOL

You aren't an authorized SPOOLER user.

To send output to the spooler with a customized right margin of 96 and page length of 66, you can use the following syntax:

Figure 188: Specifying spooled output margin and length

DEVICE: SPOOL:96:66

After requesting the spool device, you are usually prompted for a spool document name, as shown below (<u>Figure 189</u>). The prompt is not issued, however, if the spool device has been set up to generate the spool document name itself.

Figure 189: Spool document name prompt

DEVICE: SPOOL

Select SPOOL DOCUMENT NAME:

To skip the "Select SPOOL DOCUMENT NAME:" prompt, you can specify the spool document name at the "DEVICE:" prompt by entering the name in the second semicolon piece. A name entered here is *not* used if the spooler is set up to generate names itself, however. Because of the format used, the Device Handler knows that a spool document name, rather than a device subtype, is being specified. Subtypes begin with one or two letters followed by a hyphen (e.g., P-DEC), while spool document names cannot (see Section #14.3.1).

Figure 190: Specifying the spool device and document name

DEVICE: SPOOL; MYDOC

DEVICE: SPOOL; P-OTHER80; MYDOC

If the computing environment is composed of several networked processors, you may need to specify where spooling should take place. The spooler on the current CPU should be chosen unless the output is queued.

Figure 191: Spooling output to a spool device on the same CPU

```
DEVICE: SPOOL

1 SPOOL AAA
2 SPOOL BBB
Choose 1-2>
```

If the output is queued, you can choose a spooler on another CPU and a time to schedule the job to run.

Figure 192: Queuing output to a spool device

```
DEVICE: Q
DEVICE: SPOOL BBB
```

Figure 193: Spooler Parameters at the Device prompt (summary)

```
DEVICE: Spooler

DEVICE: Spooler;Right Margin;Page Length

DEVICE: Spooler;Subtype

DEVICE: Spooler;Spool Document Name

DEVICE: Spooler;Subtype;Spool Document Name
```

17.1.2 Retrieving Spooled Documents

After a spool document has been created, you can retrieve the output by using options on the Spooler Menu. This menu is distributed as part of Kernel's Common menu, a menu available to all users. Specifically, the Spooler Menu is in your User's Toolbox menu.

To quickly reach the Toolbox, or any other option on the Common menu, you can enter a quotation mark plus the menu text or synonym, as shown in Figure 194:

Figure 194: Spooler Menu options

```
Select Primary Menu Option: "TBOX

Select User's Toolbox Option: SPOOLER MENU

Select Spooler Menu Option: ?

Allow other users access to spool documents

Browse a Spool Document

Delete A Spool Document

List Spool Documents

Make spool document into a mail message

Print A Spool Document

[XU-SPL-ALLOW]

[XU-SPL-BROWSE]

[XU-SPL-DELETE]

[XU-SPL-LIST]

[XU-SPL-MAIL]

[XU-SPL-MAIL]
```

17.1.2.1 List Spool Documents Option

The List Spool Documents option [XU-SPL-LIST] lists any documents that you have created. Other users *cannot* read or print these documents unless you have authorized them to do so with the Allow other users access to spool documents option [XU-SPL-ALLOW], also on the Spooler menu.

17.1.2.2 Delete A Spool Document option

Use the Delete A Spool Document option [XU-SPL-DELETE] to delete spool documents. Since there is a limit on the amount of spool space that any one user can consume, you may need to delete old spool documents to free up space for new ones. If you attempt to create a new document when the space limits have been exceeded, the spooler issues a message about the need to delete some documents.

Old documents are deleted automatically, on a schedule as determined by system administrators. System administrators set the "life span" of a spool document via the MAX SPOOL DOCUMENT LIFE-SPAN field (#31.3) in the KERNEL SYSTEM PARAMETERS File (#8989.3). System administrators should inform you of the life span of spooled documents, so that you are *not* surprised when old documents are purged.

17.1.3 Browsing a Spool Document

17.1.3.1 Browse a Spool Document Option

With the Browse a Spool Document option [XU-SPL-BROWSE], you can view spool documents with VA FileMan's Browser. The Browser allows you to view spool documents on your terminal screen, letting you scroll backward and forward through the report, and also letting you perform simple searches within the report.



REF: For more information on using the Browser, see the VA FileMan User Manual.

17.1.4 Printing Spool Documents

17.1.4.1 Print A Spool Document Option

Use the Print A Spool Document option [XU-SPL-PRINT] to print spool documents. Before selecting an output device, you are prompted for the number of copies to print. If you have been granted the ability to print to multiple devices, you can send your output to several devices for simultaneous printing. If this privilege has been granted to you, the device prompt is displayed again after you choose the first printer. Entering a **NULL** response to the second device prompt tells the spooler not to use any more additional printers.

To save users the time and trouble of despooling their documents, system administrators can set up a spool device for auto-despooling. If you invoke such a spool device, the spool document is sent to one or more printers when the spooling process has completed. After automatic printing, the spool document remains available for reprinting as necessary (it is not automatically deleted upon despooling).

17.1.5 Making Spool Documents into Mail Messages

17.1.5.1 Make spool document into a mail message Option

If you have been granted the ability to make spool documents into mail messages, the Make spool document into a mail message option [XU-SPL-MAIL] on the Spooler Menu is available. You can use it to make documents into regular mail messages that can then be edited, copied, or forwarded just like other VistA MailMan messages. After the text has been moved into a mail message, the spool document is deleted. The deletion is to allow space for new spool documents.

If you plan to make a document into a message, you should do the original output to the spool device with an appropriate margin and page length for a MailMan message. Since MailMan breaks incoming text lines at about the 75th character, a right margin of 75 may be desirable. Indicating that page breaks should not be inserted during the spooling process may also be desirable. Otherwise, the VA FileMan window command |TOP| is inserted into the text at the beginning of each page. While this automatic formatting is an advantage when printing spool documents, it is a disadvantage when creating a mail message. Page breaks are *not* inserted when indicating a page length of 99999 lines or a number greater than the document's total. Therefore, when you know your spool document is to be a MailMan message, a suitable margin and page length request might be:

Figure 195: Formatting/Sending a document to a spool device to print as a MailMan message— Sample user dialogue

DEVICE: SPOOL;75;99999

To turn the spool document into a MailMan message, once your spool document completes, go to the Spooler Menu and select the appropriate option, as illustrated below:

Figure 196: Make spool document into a mail message option

Select Primary Menu Option: ^SPOOLER MENU
Select Spooler Menu Option: MAKE SPOOL DOCUMENT INTO A MAIL MESSAGE

If the number of lines in the document exceeds 500, you are asked whether the transfer process should be queued. This prompt is provided for your convenience since queuing of a time-consuming process is usually preferred. After using the option, you can find your messages by reviewing recently delivered mail in your MailMan IN basket.

17.2 Spooling: System Management

17.2.1 Spool Document Storage

Spool document identification is stored in the SPOOL DOCUMENT file (#3.51) in the ^XMB global. This file is for internal use by Kernel's spooler and should not be directly manipulated by system administrators. It holds identifying information, such as the name of the spool document and the line count totals. The document's text is stored in the SPOOL DATA file (#3.519) in the ^XMBS global. If the spool document is made into a mail message, the text is moved into the MESSAGE file (#3.9), the ^XMB global, and the corresponding entry in the SPOOL DOCUMENT file (#3.51) is deleted.

When initially creating a spooled document, output is sent to the operating system's spooling area (as defined in the spool device). Kernel's spooler moves the output into the ^XMBS global when the operating system's spooling process is complete. The status of the document (a field in the SPOOL DOCUMENT file [#3.51]) is then changed from Active to Ready and the document can be accessed by the user. Thus, except during spooling, the operating system's spool area should be empty.

17.2.2 Overflowing Spool Document Storage

When the output is moved from the operating system's spool area into the ^XMBS global, the lines are counted. If during the count the user's maximum line limit is reached (as defined in the MAX SPOOL LINES PER USER field [#31.1] in the KERNEL SYSTEM PARAMETERS file [#8989.3]), the transfer process is halted and a notification message is appended to the transferred text. The entry in the SPOOL DOCUMENT file (#3.51) is also marked as incomplete. Thus, the ^XMBS global is protected from growth expansion that could overflow the disk storage area.

The Kernel spooler *cannot*, however, count the lines of output as they are sent to the operating system's spool area. If the user's line limit is not exceeded before initiating the report, Kernel permits sending of an unlimited amount of output to the operating system's spooler. System administrators should consider this when granting spooling privileges. Users who are allowed to spool should be trained accordingly.

Users need to anticipate the results of a process they send to the spooler. If they are not sure what to expect, they should be instructed to test the process by sending it directly to an output device. If unexpected results should occur (e.g., an endless loop or meaningless sort), they can interrupt and cancel the process. Users should also be advised about appropriate use of processing time. Methods of efficient VA FileMan searching and sorting should be used when invoking the spooler (just as when printing directly). For example, as described in the VA FileMan documentation, the first sort-by field should be a cross-referenced field when possible and search criteria should be specified with the most likely conditions first.

17.2.3 Granting Spooling Privileges

Options on the Spool Management menu can be used to grant spooling privileges to users.

Figure 197: Edit User's Spooler Access option

```
SYSTEMS MANAGER MENU ... [EVE]
Spool Management ... [XU-SPL-MGR]
Edit User's Spooler Access [XU-SPL-USER]
```

The following spooler-related fields are user-specific and are stored in the NEW PERSON file (#200):

Table 31: User spooler-related fields in the NEW PERSON file (#200)

Field	Description
ALLOWED TO USE SPOOLER (#41)	If set to YES it gives the user the ability to invoke the spooler at the device prompt.
MULTI-DEVICE DESPOOLING (#41.1)	If set to YES it enable the user to despool a spooled document to more than one device simultaneously.
CAN MAKE INTO A MAIL MESSAGE (#41.2)	If set to YES it permits the conversion of a spool document into a MailMan mail message. The user is able to use all MailMan functions, such as copying and forwarding. As a mail message, the document can no longer be manipulated with the spooler since its flag in the SPOOL DOCUMENT file (#3.51) has been deleted.

As mentioned earlier, the user-oriented spooler options are distributed as part of the Common menu, a menu available to all users. If system administrators have chosen to lock the Spooler Menu or removed it from the Common menu, access to the options needs to be re-established for users who are allowed to spool via the Edit User's Spooler Access option [XU-SPL-USER], as shown below:

Figure 198: Edit User's Spooler Access—Sample user dialogue

```
Select Spool Management Option: EDIT USER'S SPOOLER ACCESS

Select NEW PERSON NAME: XUUSER, SIX
ALLOWED TO USE SPOOLER: YES// <Enter>
MULTI-DEVICE DESPOOLING: YES// <Enter>
CAN MAKE INTO A MAIL MESSAGE: YES// <Enter>
```

17.2.4 Managing Spool Documents

The remaining options on the Spool Management menu [XU-SPL-MGR] are also found on the user-oriented Spooler Menu. They are provided on the Spool Management menu simply for convenience to system administrators to access any spool document on the system. Users *must* hold the XUMGR security key in order to access all spool documents. Together, these options along with the XUMGR security key permit system administrators to view, print, or delete anyone's spooled documents.

Figure 199: Spool Management menu options

SYSTEMS MANAGER MENU Spool Management [XU-SPL Delete A Spool Document [XU-SPL-DE] List Spool Documents [XU-SPL-P] Print A Spool Document [XU-SPL-P]
--

17.2.5 Spooler Site Parameters Edit Option

Figure 200: Spooler Site Parameters option

```
SYSTEMS MANAGER MENU ... [EVE]
Spool Management ... [XU-SPL-MGR]
Spooler Site Parameters Edit [XU-SPL-SITE]
```

The Spool Management menu [XU-SPL-MGR] also has the Spooler Site Parameters Edit option [XU-SPL-SITE] for setting the spooler site parameters (system-wide defaults for the spooler). The initial settings are defined when installing Kernel but can be edited afterwards.

The spooler site parameters control the total number of documents a user can create and the total number of lines for all documents. When the limits are reached, the user *cannot* create new spooled documents.

The effects of the three spooler site parameter fields are as follows:

Table 32: Spooler site parameter fields in the KERNEL SYSTEM PARAMETERS file (#8989.3)

Spooler Site Parameter Field	Description
MAX SPOOL LINES PER USER (#31.1)	This field holds the MAX number of lines of spooled output a user is allowed. If the user has more than this number, then they are <i>not</i> permitted to spool any more until some of their spool documents are deleted. This only controls allowing the creation of new spool documents and does not terminate a job that is running that has gone over the limit. Recommended value 9999.
MAX SPOOL DOCUMENTS PER USER (#31.2)	This field limits the number of spool documents that any user can have on the system. Recommended value 10-100.
MAX SPOOL DOCUMENT LIFE-SPAN (#31.3)	This field controls the number of days that a spooled document is allowed to remain in the spooler before deletion by the XU-SPL-PURGE option that needs to be setup to run in the background.

17.2.6 Purge old Spool documents Option

Figure 201: Purge old spool documents option

PARENT OF QUEUABLE OPTIONS	[ZTMQUEUABLE OPTIONS]
Purge old spool documents	[XU-SPL-PURGE]

A spool document is automatically deleted when its life span (in days) is reached. The purge is carried out by the Purge old spool documents option [XU-SPL-PURGE]. This option is listed on the PARENT OF QUEUABLE OPTIONS menu [ZTMQUEUABLE OPTIONS] along with others that should not be invoked interactively but should be scheduled to run through TaskMan.

17.2.7 Defining Spool Device Types

The DEVICE file (#3.5) entries for spooler device types make use of information about the underlying operating system's spooling mechanism. Examples for several operating systems are provided in the topics that follow.

17.2.7.1 Caché and GT.M

Caché and GT.M use an OpenVMS directory for spooling. As indicated in the VistA Cookbook for VAX sites, the directory should be established with full privileges for System, Owner, Group, and World. The directory specifications are used as the \$I value.

Figure 202: Spool Device for Caché and GT.M

```
Name: SPOOL

$I: VA1$:[SPOOLER]

Type: SPOOL

Subtype: P-OTHER
```

17.2.8 Spool Device Edit Option

The Spool Device Edit option [XUDEVEDITSPL] lets you edit spool device attributes using a ScreenMan form.

Figure 203: Spool Device Edit option

```
Device Management... [XUTIO]
Edit Devices by Specific Types... [XUDEVEDIT]
Spool Device Edit [XUDEVEDITSPL]
```

- NOTE: The type of data entered in the \$I (#1) and OPEN PARAMETERS (#19) fields depends on the type of M system you are using and the mode of access.
- **REF:** For further details, see your M system manuals.

REF: Examples are provided in the "Defining Spool Device Types" section.

17.2.9 Auto-despooling

For convenience, spool devices can be defined to ensure that despooling takes place automatically, without user interaction. If the AUTO DESPOOL (#31) field in the DEVICE file (#3.5) is set to **YES**, one copy of the spooled output is sent to each device named in the DESPOOL DEVICES field (#32, Multiple). Having the output automatically despooled saves users the time and trouble of logging on and printing a spool document that may have been created the previous evening. Documents are *not* deleted upon despooling; they remain available to the user for subsequent printing.

Figure 204: Device Edit option—Sample user dialogue

```
Select Device Handler Option: DEVICE EDIT

Select DEVICE NAME: SPOOL

NAME: SPOOL// ^AUTO D <Enter> ESPOOL

AUTO DESPOOL: 1 <Enter> YES
Select DESPOOL DEVICES:
```

17.2.10 Generating Spool Document Names

Spool devices can be set up to automatically generate the name that identifies the spool document. If the GENERATE SPL DOC NAME field (#33) in the DEVICE file (#3.5) is set to **YES**, users of that device are *not* prompted to enter the spool document name. Also, if the flag is set, any user- or developer-defined name [in IO("DOC")] is ignored. The generated name consists of the first 15 characters of the spool device's name, followed by an underscore ("_"), and followed by the internal entry number (IEN) of the spool document in the SPOOL DOCUMENT file (#3.51).

Figure 205: Generating spool document name—Sample user dialogue

GENERATE SPL DOC NAME: YES

18 Special Devices

This chapter discusses the following special devices and device issues:

- Browser Device
- Form Feeds
- Magtape (MT)
- Network Channel Devices
- Resources
- <u>Sequential Disk Processors (Obsolete)</u>
- Slaved Printers

18.1 Browser Device

18.1.1 User Interface

VA FileMan's Browser allows you to view reports on your terminal screen, letting you scroll backward and forward through the report, and also letting you perform simple searches within the report.

If the Browser has been installed at your site and set up as a device, you can use the Browser to view any report that asks you for an output device.

To send a report to the BROWSER device, at any device prompt, enter BROWSER as the device. You may not want to send huge reports to the BROWSER, however, since the report *must* complete before you can view its output in the Browser.



REF: For information on using the Browser and on Browser commands, see the *VA FileMan User Manual*.

Figure 206: Print File Entries option—Sample user dialogue when sending a report to the Browser device

```
Select VA FileMan Option: PRINT FILE ENTRIES

OUTPUT FROM WHAT FILE: NEW PERSON// DOMAIN <Enter>
SORT BY: NAME// <Enter>
START WITH NAME: FIRST// <Enter>
FIRST PRINT FIELD: NAME
THEN PRINT FIELD: <Enter>
HEADING (S/C): DOMAIN LIST// <Enter>
DEVICE: BROWSER <Enter> BROWSER
BROWSER TITLE (optional): VA FileMan Browser// <Enter>
...one moment...
```

Figure 207: Print File Entries option—Sample Domain List report, as displayed in the Browser device

DOMAIN LIST	VA FileMan	JUL 28,2009	12:44	PAGE 1
NAME		001 20,2009	12.11	11102 1
ALBANY.MED.VA.GOV				
ALBUOUEROUE.MED.VA.GOV				
ALEXANDRIA.MED.VA.GOV				
ALTOONA.MED.VA.GOV				
AMARILLO.MED.VA.GOV				
ANCHORAGE.MED.VA.GOV				
ANN-ARBOR.MED.VA.GOV				
ASHEVILLE.MED.VA.GOV				
ATLANTA.MED.VA.GOV				
AUGUSTA.MED.VA.GOV				
B43.FO-SITE.MED.VA.GOV				
BALTIMORE.MED.VA.GOV				
BATAVIA.MED.VA.GOV				
BATH.MED.VA.GOV				
BATTLE-CREEK.MED.VA.GOV				
BAY-PINES.MED.VA.GOV				
BDC.MED.VA.GOV				
BECKLEY.MED.VA.GOV				
Col> 1 <pf1>H=Help <pf1>E=</pf1></pf1>	Exit Line>	22 of 320 S	creen>	1 of 15

18.1.2 System Management

You can set up VA FileMan's Browser as a device to which users can send their output.

When a user sends output to a Browser device, the Browser device performs the following steps:

- 1. Output is sent to a host file.
- 2. When the output completes, the host file is closed.
- 3. The contents of the host file are read back into a scratch global.
- 4. The host file is deleted.
- 5. The Browser is called, which displays the data in the global to the user, through the Browser interface.
- 6. When the user exits the Browser, the scratch global is deleted.

This provides a quick way to generate a report and view the report through the scrollable Browser, potentially saving paper and wear and tear on printers.

To support the Browser device, you need to set up a special terminal type (P-BROWSER) and a special device type (BROWSER).



REF: For sample entries of the special Browser terminal type and device entries for the Caché and GT.M operating systems, see <u>Figure 208</u> and <u>Figure 209</u>.

The Browser device tests the current terminal to see whether it supports:

- A scrolling region.
- Reverse indexing.

If the terminal does not support these features, the Browser device issues a message saying that it is not selectable from the current terminal. Also, in order for the check (\$\$TEST^DDBRT) to work properly, the user *must* already be in the Kernel menu system or *must* have set up developer variables through the ^XUP entry point. Otherwise, the test always fails.

18.1.2.1 Storing Host Files in a Specific Directory

By default, the temporary host files created by the Browser device are stored in the current default directory. You can optionally specify a path to a specific directory to store the temporary host files. Make sure the directory you specify exists on all nodes/CPUs where users can sign on. On DOS systems, do not specify the root directory, since there is a limit on the number of files a DOS root directory can hold. Finally, make sure you change both the OPEN PARAMETERS (#19) and POST-CLOSE EXECUTE (#19.8) fields in the Browser DEVICE file (#3.5) entry to specify the directory (replace DD with, for example, D:\BROW\DD).

Figure 208: Caché and GT.M Browser Device—TERMINAL TYPE file (#3.2) entry

NAME: P-BROWSER

RIGHT MARGIN: 80

PAGE LENGTH: 99999

OPEN EXECUTE: D OPEN^DDBRZIS

CLOSE EXECUTE: D CLOSE^DDBRZIS

DESCRIPTION: Browser Device

Figure 209: Caché and GT.M Browser Device—DEVICE file (#3.5) Entry

```
NAME: BROWSER
                                        $I: DDBR.TXT
 ASK DEVICE: YES
                                       ASK PARAMETERS: NO
 SIGN-ON/SYSTEM DEVICE: NO
                                       QUEUING: NOT ALLOWED
 LOCATION OF TERMINAL: HFS/CRT
                                       ASK HOST FILE: NO
 ASK HFS I/O OPERATION: NO
                                       MARGIN WIDTH: 80
 FORM FEED: #
                                       PAGE LENGTH: 99999
                                       OPEN PARAMETERS: NEW:DELETE
 BACK SPACE: $C(8)
 POST-CLOSE EXECUTE: D POST^DDBRZIS
 SUBTYPE: P-BROWSER
                                       TYPE: HOST FILE SERVER
 PRE-OPEN EXECUTE: I `$$TEST^DDBRT S %ZISQUIT=1 W $C(7),!, "Browser not selectable
from current terminal.",!
```

18.2 Form Feeds

18.2.1 User Interface

Most users would prefer to see their printouts without any extra blank pages before or after the content. Most prefer to see their reports printed on a fresh page instead of starting in the middle of the previous printout. The printing of labels should also be accomplished without unnecessary form feeds. If a printer is generating extra pages, you should contact the system administrators to remedy the problem.

18.2.2 System Management

If a particular device does *not* need a form feed between reports, system administrators should set the SUPPRESS FORM FEED AT CLOSE field (#11.2) to **YES** in the device's DEVICE file (#3.5) entry. Label printers, for example, should have this flag set. This procedure prevents the Device Handler from issuing a form feed:

Figure 210: Device Edit option—Sample user dialogue

```
Select Systems Manager Menu Option: DEVICE HANDLER
Select Device Handler Option: DEVICE EDIT

Select DEVICE NAME: LABEL PRINTER
NAME: LABEL PRINTER// *SUP <Enter> PRESS FORM FEED AT CLOSE
SUPPRESS FORM FEED AT CLOSE: YES
```

The Device Handler also checks the TERMINAL TYPE file (#3.2) to see if form feeds have been suppressed for that terminal type. It checks for the existence of the IONOFF variable. Thus, for certain terminal types (e.g., laser printers), system administrators can set this "no form feed" variable in the corresponding terminal type's CLOSE EXECUTE field (#7).



NOTE: The IONOFF variable can also be set by the calling application to suppress form feeds.

Figure 211: Terminal Type Edit option—Sample user dialogue

```
Select Systems Manager Menu Option: DEVICE HANDLER
Select Device Handler Option: TERMINAL TYPE EDIT
Select TERMINAL TYPE NAME: P-DEC-LABEL
NAME: P-ZPK80// CLOSE EXECUTE
CLOSE EXECUTE: S IONOFF=""
```

18.3 Magtape

18.3.1 System Management

Figure 212: Edit Devices by Specific Types option

```
Device Management... [XUTIO]

Edit Devices by Specific Types... [XUDEVEDIT]

Magtape Device Edit [XUDEVEDITMT]
```

The Edit Devices by Specific Types option [XUDEVEDIT] lets you edit specific types of devices using ScreenMan.

Values entered in a Magtape (MT) device for the following fields may not be relevant to a given application:

Table 33: Fields in the DEVICE (#3.5) and TERMINAL TYPE (#3.2) files that may not be relevant for certain devices

File	Field	Description
DEVICE (#3.5)	SUBTYPE (#3)	Use this field to select a default terminal type for the device. This field points to the TERMINAL TYPE file (#3.2) to retrieve a standard set of characteristics that have been defined for vendor devices (e.g., Laser printers or VT320 CRTs). REF: For a discussion of the TERMINAL TYPE file (#3.2), see the "TERMINAL TYPE File (#3.2)" section.
	MARGIN WIDTH (#9)	Data in this field overrides the RIGHT MARGIN field value from the TERMINAL TYPE file (#3.2). Leave this field blank unless you are sure that you need to have a different RIGHT MARGIN than what is in the TERMINAL TYPE file (#3.2).
TERMINAL TYPE (#3.2)	FORM FEED (#2)	The argument of an M WRITE statement that sets the top-of-form for the use of tractor-feed paper on a printer, or clears the screen of a video display terminal.
	PAGE LENGTH (#3)	This field is the number of usable lines on the output device.
	BACK SPACE (#4)	The argument of an M WRITE statement that causes the cursor to back space.

The data values entered in these fields may be arbitrary for Magtape devices. However, if the application plans to copy the output to a printer, the characteristics may need to be similar to that of the printer.

If an application intends to use these fields, be cautious about the type of data that is entered. When sent to the tape unit, some control codes initiate tape movement or cause tape markers to be written to the mounted tape.

Data entered in the \$I and OPEN PARAMETERS fields depends on the type of M system you are running, the type of tape unit, and the desired format.



REF: For examples of the type of data required in these fields, see the "<u>Device Handler: System Management</u>" section.



REF: For further details on Magtape devices, see your specific M implementation manuals.

18.4 Network Channel Devices

18.4.1 System Management

Network channel devices are typically high speed channel devices (e.g., TCP/IP). Currently, this network channel device support exists under the Caché and GT.M operating system. In most cases, these devices are used for specialized purposes rather than for general output. For example, network mail could use such devices to move enormous amounts of email through high speed communication channels.

The use of network channel devices requires at least two processes on each end of the communication channel, a server and a client, which can then exchange information:

- Server Process—One process *must* be available at all times. It can be actively running or triggered to run at a given moment. This process is commonly known as a server. The server waits until another process makes a request to exchange information.
- Client Process—The other process is known as the client.

The two processes can be hosted by two CPUs using network protocols.

18.4.1.1 Network Channel Device Edit

Figure 213: Network Channel Device Edit option

```
Device Management... [XUTIO]

Edit Devices by Specific Types... [XUDEVEDIT]

Network Channel Device Edit [XUDEVEDITCHAN]
```

The Network Channel Device Edit option [XUDEVEDITCHAN] allows you to edit network channel device attributes.

When editing Network Channel devices, the contents of the fields listed in <u>Table 33</u> are not necessarily relevant for using network Channel devices. However, these fields are provided in case the application calling the Device Handler is not able to distinguish between a printer and a Network Channel device when sending output.

The timeout on the M OPEN command may not be applicable with Network Channel devices. Therefore, it may be necessary to answer **NO** to the USE TIMEOUT ON OPENS field (#2009.5) in the DEVICE file (#3.5).



REF: For more information regarding device timeout applicability, see the appropriate Caché manual.

For Network Channel devices that use TCP/IP, data is required for the OPEN PARAMETERS field (#19) in the DEVICE file (#3.5). For the client device setup, this field stores the remote Internet address to which the host connects.

Figure 214: Network Channel Device Edit option—Sample output

```
EDIT A NETWORK CHANNEL DEVICE
NAME: SDD-DIRECT
                                                                   PAGE 1 OF 1
NAME: SDD-DIRECT
                                   LOCATION OF TERMINAL: HP-8000 near Raul
 $I: |TCP|9100
                                        VOLUME SET(CPU):
TYPE: NETWORK CHANNEL
                                  SIGN-ON/SYSTEM DEVICE: NO
SUBTYPE: P-HP8000 TCP/S
                                           MARGIN WIDTH:
                                            PAGE LENGTH:
                          USE TIMEOUT ON OPENS:
          ASK DEVICE: NO
      ASK PARAMETERS: NO
                                          OPEN TIMEOUT:
      OPEN PARAMETERS: ("10.6.21.138":9100:"M")
            USE LOCK:
```

The GLOBAL LOCK field (#36) in the DEVICE file (#3.5) stores a **YES/NO** Set of Codes. This is important, especially if the application expects that only one client at a given time is able to open the device. If this field is set to **YES** an M lock on ^%ZIS("lock",IO) is obtained before the device is opened. It remains until a call to ^%ZISC to close the device. It can be used with any type of device.

18.5 Resources

18.5.1 System Management

A Resource device is a type of device that can only be used by tasks. They *cannot* be used for input or output (I/O). As such, they are not available for user selection at the device prompt. The purpose of a resource is to provide a mechanism of limiting the number of concurrent jobs that can run at any one time.

When creating a task, a task can request the resource as an input variable for the ^%ZTLOAD call. The resource itself, as defined in the DEVICE file (#3.5), has a field called RESOURCE SLOTS (#35) that determines how many jobs can simultaneously own it as a resource.

The Device Handler and TaskMan work together to provide resource device functionality. The RESOURCE file (#3.54), stored in the translated ^%ZISL global, regulates processing and is for internal use only. The NAME field (#.01) holds the \$I of the resource device. Other fields hold information on jobs currently using the resource, information that is cleared when the resource is closed.

The RESOURCE file (#3.54) supports processing by maintaining a count of the number of available "slots." The ability to open and close resources is accomplished by decrementing and incrementing this count.

18.5.1.1 Limiting Simultaneous Running of a Particular Task

Resources make it possible for you to control the number of a particular kind of non-I/O task that runs at any one time. If you have a particular job and you want no more than three running versions of it at any one time, you can queue the job (through the ^%ZTLOAD interface) to a resource that had a RESOURCE SLOTS (#35) setting of 3.

18.5.1.2 Running Sequences of Tasks

Resources also make it possible to run non-I/O tasks in sequential order. Non-I/O tasks ordinarily can run simultaneously because they do not compete for the ownership of I/O devices. If you instead queue such tasks to the same resource, and the resource has a RESOURCE SLOTS (#35) setting of 1, TaskMan runs the tasks one at a time and in the order queued. In this way, the results of one process can be used by another. This sequential processing might be appropriate, for example, for the processing of physician orders or other nested tasks involving code execution.

An additional enhancement to resource devices, called SYNC FLAGs, allows TaskMan to run the next task waiting for a resource only if the previous task using that resource has completed successfully. You can use SYNC FLAGs to ensure that subsequent jobs run only if previous jobs have completed successfully.

18.5.1.3 Creating Resource Devices

Figure 215: Resource Device Edit option

```
SYSTEMS MANAGER MENU ... [EVE]
Device Management ... [XUTIO]
Resource Device Edit [XUDEVEDITRES]
```

The Resource Device Edit option [XUDEVEDITRES] provides a facility for editing resource devices. Software that uses a resource should include in its installation instructions the way the new resource should be defined in the DEVICE file (#3.5). System administrators can then create one or more resource-type (RES) entries.

Figure 216: Resource device—Sample output

```
NAME: ZZRES $1: ZZRES
LOCATION OF TERMINAL: NA RESOURCE SLOTS: 1
TYPE: RESOURCE
```

The installation instructions should indicate the number of resource slots. Sequential processing should use a value of 1. The NAME and \$I should probably use the same value and be namespaced according to VistA conventions.

18.6 Sequential Disk Processors (Obsolete)

Though the Sequential Disk Processors (SDP) entry is still found in the DEVICE file (#3.5), it is obsolete and users should now use Host File Server (HFS) devices.



REF: For more information on HFS devices, see "Host Files."

18.7 Slaved Printers

18.7.1 User Interface

If your terminal has an auxiliary printer port with a printer directly attached, you can send output normally destined for the CRT terminal directly to a printer. Output for the terminal is redirected from the host computer through the terminal's auxiliary port to the printer. Such printers are commonly called slaved printers or slaved devices.

If slaved printing is available from your terminal, you can send a printed report to your slaved printer, by entering the device name that corresponds to your slaved printer like this:

Figure 217: Slaved Printer—Sample user dialogue

DEVICE: SLAVELA50



NOTE: Consult your local system administrators to find out if slaved printing devices are available.

18.7.2 System Management

There are two modes of slaved printing:

- Auto Print Mode (a.k.a. Copy Print Mode)—When Auto Print Mode is toggled on, output is displayed on the terminal as well as printed on the printer. Special escape sequences and control characters, such as those that are normally used to adjust fonts/pitches, are *not* passed to the printer; however, those used for actions like carriage return, line feed, and form feed are passed on to the printer.
- Printer Controller Mode (a.k.a. Transparent Print Mode)—When Printer Controller Mode is toggled on, output is only printed on the printer; nothing is displayed on the terminal. All escape sequences and control characters are passed to the printer. This mode is preferable to Auto Print Mode, especially when compressed mode printing is desired.

The following are the escape sequences used to toggle the slaved printing modes for DEC VT220/VT320 terminals:

Table 34: Escape sequences used to toggle the slaved printing modes for DEC VT220/VT320 terminals

Mode	Escape Sequence
Auto print mode on.	ESC [?5i
Auto print mode off.	ESC [?4i
Printer controller mode on.	ESC [5i
Printer controller mode off.	ESC [4i

18.7.2.1 Device and Terminal Type File Entries

To use a slaved printer through the Device Handler, two DEVICE file (#3.5) entries along with corresponding TERMINAL TYPE file (#3.2) entries *must* be made for the following:

- Home Device
- Slaved Printer

One pair of DEVICE/TERMINAL TYPE entries is needed to describe the home (i.e., CRT) terminal attributes including the codes to open and close the printer port. The OPEN PRINTER PORT (#110) and CLOSE PRINTER PORT (#111) fields of the TERMINAL TYPE file (#3.2) can be used to store the appropriate codes.

Another pair of DEVICE/TERMINAL TYPE entries is needed to describe the attributes of the slaved printer including escape codes to adjust fonts/pitches. The OPEN EXECUTE (#6) and CLOSE EXECUTE (#7) fields of the TERMINAL TYPE file (#3.2) can be used to hold such codes. Additionally, the device entry for the slaved printer *must* have a value of 0 (zero) entered into the \$I field. This \$I value identifies the DEVICE file (#3.5) entry as one for a slaved device.

The following examples show the setup for a home device, and the setup for slaved printers

Figure 218: Home Device example (VT320)—DEVICE file (#3.5) entry

```
NAME: TELNET DEVICE $1: _TNA

ASK DEVICE: YES ASK PARAMETERS: NO

VOLUME SET(CPU): KDE SIGN-ON/SYSTEM DEVICE: YES

LOCATION OF TERMINAL: Network MARGIN WIDTH: 80

FORM FEED: #,$C(27,91,50,74,27,91,72) PAGE LENGTH: 24

BACK SPACE: $C(8) SUBTYPE: C-VT320

TYPE: VIRTUAL TERMINAL

TIMED READ (# OF SECONDS): 400
```

Figure 219: Home Device example (VT320)—TERMINAL TYPE file (#3.2) entry

```
NAME: C-VT320

FORM FEED: #,$C(27,91,50,74,27,91,72) RIGHT MARGIN: 80

PAGE LENGTH: 24

DESCRIPTION: Digital Equipment Corporation VT-320 video

OPEN PRINTER PORT: W *27," [5i"

CLOSE PRINTER PORT: W *27," [4i"
```

Figure 220: Slaved Printer example: DEC LA50—DEVICE file (#3.5) entry

```
NAME: SLAVELA50 $1: 0
ASK DEVICE: YES ASK PARAMETERS: YES
SLAVED FROM DEVICE: TRM
LOCATION OF TERMINAL: SLAVE DEVICE FOR LA50
MARGIN WIDTH: 132 FORM FEED: #
PAGE LENGTH: 64 SUBTYPE: P-LA50
TYPE: TERMINAL
```

Figure 221: Slaved Printer example: DEC LA50—TERMINAL TYPE file (#3.2) entry

NAME: P-LA50 RIGHT MARGIN: 132

FORM FEED: # PAGE LENGTH: 64

OPEN EXECUTE: W *27,"[4w" CLOSE EXECUTE: W *27,"[0w"

DESCRIPTION: LA50 132 COL/16.5 CPI

Figure 222: Slaved Printer example: Epson LQ870—DEVICE file (#3.5) entry

NAME: SLAVELQ870 \$1: 0
ASK DEVICE: YES ASK PARAMETERS: YES
SLAVED FROM DEVICE: TRM
LOCATION OF TERMINAL: SLAVE DEVICE FOR LQ870
MARGIN WIDTH: 132 FORM FEED: #
PAGE LENGTH: 64 SUBTYPE: P-LQ870
TYPE: TERMINAL

Figure 223: Slaved Printer example: Epson LQ870—TERMINAL TYPE file (#3.2) entry

NAME: P-LQ870 RIGHT MARGIN: 132
FORM FEED: # PAGE LENGTH: 64
OPEN EXECUTE: W *15 CLOSE EXECUTE: W *18
DESCRIPTION: EPSON LQ870 PRINTER--CONDENSED

18.7.2.2 Use of Slaved Printer: Processing Steps

The Device Handler manages output to slaved printers using the following steps:

- 1. Execute the OPEN PRINTER PORT (#110) code of the home device's terminal type.
- 2. Execute the OPEN EXECUTE (#6) code of the slaved printer's terminal type.
- 3. When the application closes the device, execute the CLOSE EXECUTE (#7) code of the slaved printer's terminal type.
- 4. Execute the CLOSE PRINTER PORT (#111) code of the home device's terminal type.

18.7.2.3 Queuing to Slaved Printers

If queuing to a slaved device is desired, then the SLAVE FROM DEVICE field of the DEVICE file (#3.5) *must* be used. This field is a pointer to the DEVICE file (#3.5). Data *must* be entered in this field for the entry for the slaved printer. This data should point to the home device entry unless the slaved printer is attached to a terminal on a Terminal Server (i.e., a virtual terminal).

If queuing to a slaved device is being performed from a virtual terminal, then a third device entry *must* be established that fully describes the home device with a type of TRM. This device should be entered into the SLAVE FROM DEVICE field.



NOTE: When queuing to a slaved device from a terminal on a Terminal Server, the user *must* be fully logged off the computer system and logged off the port by the time the queued task is scheduled to run.

IV. TaskMan

19 TaskMan: User Interface

The Kernel TaskMan (TM) software allows you to run tasks (e.g., VA FileMan prints and sorts) in the background and lets you continue working without interruption.

19.1 Creating Tasks

VistA runs in a multiprocessing environment, which means the computer can work on more than one job at a time. Each job the computer works on consumes a part of the computer's resources. Initially, you have only one job, your interactive terminal session, with which to do your work. TaskMan, however, allows you to claim more of the computer's resources by allowing you to schedule additional jobs to run in the background.


19.1.1 Background Jobs

You can queue additional tasks to run through TaskMan. Once started, these additional tasks (called background tasks) can run at the same time as the foreground jobs and without further dialogue with the people who started them. Appropriate use of background tasks can cut your frustration by reducing the amount of time you *must* wait for the computer to do lengthy, repetitious work that does not need human intervention. Every task queued to run in the background reduces time spent waiting and also uses the computer's resources more efficiently.

19.1.2 Queuing Output

Most users use TaskMan by queuing reports, labels, and other kinds of output. Because output involves no dialogue once it has begun and because it requires you to wait while it prints, it makes an ideal candidate for queuing. You can queue most output when the computer asks you to select a device to which the output should be sent. The series of prompts and responses to queue a job to a device usually looks something like this:

Figure 224: Queuing output—Sample user dialogue



After you answer this series of prompts, the output is queued for TaskMan to start at the requested time, and you can continue with other work while TaskMan prints the output. When many tasks need the same device at the same time, TaskMan runs them in order based on the time they were requested.

19.1.3 Other Sources of Tasks

An application can create other kinds of tasks without your interaction. The application might offer to queue other kinds of work like large filing or complex data analysis jobs. Sometimes applications queue tasks without asking. For example, the delivery of MailMan messages is performed by a job running as a task. If that task is not running when someone uses the MailMan options, MailMan automatically uses

their foreground job to queue the task without asking them. Although people may knowingly or unknowingly queue these other kinds of tasks, output remains the most common kind of work to queue.

19.2 Working with Tasks

Figure 225: TaskMan User option



TaskMan also allows you to examine or modify your own tasks. You can do this by using the TaskMan User option [XUTM USER], located in the User's Toolbox menu on your Common menu. This option lets you monitor or manipulate one task at a time.

19.2.1 Selecting Tasks

When you choose the TaskMan User option, it first asks you to select a task with which to work. TaskMan displays the "Select TASK:" prompt. If you enter a single question mark ("?"), you get some general help about the option; if you enter two question marks ("??"), you can get a list of every task that you have queued to run. Typically, you would enter two question marks at this prompt so that you can get a listing of your individual tasks, listed by task number. You then choose a task from the list of tasks to work with. Using the TaskMan User option looks like the following:

Figure 226: TaskMan User option—Sample user dialogue

```
Select User's Toolbox Option: TASKMAN USER
Select TASK: ??
Please wait while I find your tasks...searching...finished!
1: (Task #161325) ZTSK2^XMA02, Queued print for XUUSER, TWELVE. Device VER$LW.
  KRN, KDE. From TODAY at 14:22, By you. Scheduled for TODAY at 20:00
2: (Task #161776) ZTSK^DIP4, DEVICE LIST. Device VER$LW. KRN,KDE.
  From TODAY at 14:22, By you. Scheduled for TODAY at 22:00
End of listing. Press RETURN to continue: <Enter>
Select TASK: 161776 <Enter> DEVICE LIST
               Taskman User Option
                    Display status.
                    Stop task.
                    Edit task.
                    Print task.
                   List own tasks.
                    Select another task.
               Select Action (Task # 161776):
```

You can select tasks either by task number or list number. In the list of tasks, the list number is at the left hand side of the each task listing, and is followed by the task number for each task (in parentheses). The rest of the information helps identify where the task came from and what it does.

19.2.2 Tasks in the Task List

You can only select tasks that are still in TaskMan's task list. When a task finishes running, it usually removes itself from the task list. Thus, you should not get a listing of every task you have run in the last year! Tasks that do not clean up their entries usually get cleaned out by TaskMan several days after they complete. You should only have to select tasks that are still actively waiting to start, currently running, or encountered some kind of problem while running.

19.2.3 Display Status of Tasks

Once you've selected a task to work with, you can ask to see the status of that task, using the Display status option ("D"). TaskMan uses a task's status to try to explain how soon the task runs and why. The possible normal statuses for a task include:

- Scheduled for <date and time>.
- Being inspected by TaskMan.
- Waiting for a partition.
- Being prepared.
- Currently running.
- Completed <date and time>.



NOTE: Please keep in mind that TaskMan can only "guess" whether a task is currently running.

One of the following messages may show up if the task needs some system resource not currently available:

- Waiting for device < name of device >.
- Waiting for the link to <name of CPU> to be restored.

When you display the status of a task waiting for a device, TaskMan shows you how many tasks are in line for that device ahead of your task. Additional statuses exist for tasks that have encountered some kind of problem. For each situation it lists a different explanation of the problem. For example, if you use the Stop task option to stop a task, its status shows up as "Stopped by you."

19.2.4 Stopping Tasks

Under certain conditions, you may want to stop a task. The TaskMan User option allows you to do this through the Stop task option ("ST"). Your ability to stop a task depends on the task's status, however. If the task has already been stopped, is finished, or it encountered a problem while running and you try to stop it, the Stop task option tells you that the task has already stopped. If the task has not yet started running, on the other hand, you can always stop it. If the task has started running, the Stop task option succeeds in stopping it only if the developer who wrote the task has designed the task to be stopped by a user. At any rate, it does not cause any problems if you try to stop a running task.

To stop a task, use the Stop task option. Once you stop a task, it remains in the TASKS file (#14.4) until you edit it to run again or until TaskMan purges it from the Task list.

19.2.5 Editing Tasks

The Edit task option ("E") lets you edit a task's output device, description, and run time.

The task *must* be unscheduled before it can be edited. The Edit task option asks if it's OK to unschedule the task. To edit the task, answer **YES**. But once the task is unscheduled, it does *not* run unless you reschedule it by finishing each step of editing the task.



NOTE: You *cannot* edit a task that is already running.

Once the task is unscheduled, you can update the following task settings:

- When the task should start.
- Which device it should use (and whether a device is needed).
- What the description of the task should be.

Once you've had a chance to modify these three settings, you're asked whether the task should be rescheduled as shown (see Figure 227). If you answer **YES**, the task is updated to reflect the changes you specified. If you answer **NO**, however, no settings are changed, but the task remains unscheduled (and does *not* run until you use Edit Task to reschedule it).

Figure 227: Edit Task option—Sample user dialogue

```
Before you edit the task I'll make sure it's not scheduled, okay? YES// <Enter>
Task ready for editing.

Currently, this task requests output device VER$LW.
Do you want to change the output device for this task? NO// Y
Select Task's Output Device (^ for none): P236

When should this task run?: AUG 16, 2004@22:00// <Enter>
Task's purpose: DEVICE LIST// <Enter>
161776: DEVICE LIST. P236. Next run time: AUG 16, 2004@22:00.

Shall I reschedule this task as shown? YES// <Enter>
Task rescheduled.
```

19.2.6 Listing and Printing Tasks

You can use the List own tasks option ("L") to review your tasks. This option displays the same list as that given when you enter two question marks ("??") at the "Select Task:" prompt.

The Print task option lets you print out the description of the task that you have currently selected.

19.2.7 Selecting Another Task

Once in the TaskMan User option, you can choose to work with a different task by using the Select another task option ("SE"). Enter another task number to work with a different task. If you're not sure what task you want to work with, you can get a list of all of your tasks by entering two question marks ("??").

19.3 Summary

Most output in VistA is performed by creating tasks that run in the background. Once you become familiar with TaskMan's queuing system, you can increase productivity by using some of TaskMan's special features, including listing your future tasks, displaying a task's status, stopping a running task, and editing a future task's run time and output device.

20 TaskMan: System Management—Overview

Kernel's TaskMan module provides a standardized system for initiating and managing background processing. Since TaskMan handles all background processes, system managers have a unified set of controls that apply to all background processes on their systems.

Most of TaskMan's processing does not involve interaction with users, rendering its operation virtually invisible. The explanations that follow provide information about the operation of TaskMan.

20.1 TaskMan's Division of Labor

TaskMan uses a three-step system to start and manage background processing:

1. Queuers

Foreground jobs *cannot* directly start any background jobs. Instead, they call the TaskMan Application Program Interface (API) to file requests in the TASKS (#14.4) and SCHEDULE files. The program code calling the TaskMan API is called a Queuer. The TASKS file (#14.4) is VA FileMan-compatible. The SCHEDULE file is *not* VA FileMan compatible.



REF: For a description of the TASKS (#14.4) and SCHEDULE file structure, see the "Troubleshooting" section in "TaskMan: System Management—Operation."

2. Manager

A TaskMan program called the Manager runs at all times in the background. The Manager monitors the SCHEDULE file. As needed, it initiates background jobs (called Submanagers) to perform the work requested by the foreground jobs.

3. Submanagers

Each background job request is picked up by a TaskMan process called the Submanager. The Submanager is the job that actually runs each task. Submanagers handle contention for partitions and I/O devices by running the waiting tasks in order, first the oldest tasks and then the more recent ones.

20.1.1 Queuers

Tasks run by TaskMan begin with code in a software application that decides to perform some work in the background. This code is a queuer. Most applications in VistA respond to a user's request to queue some output, but other decisions may be involved. Two commonly used queuers are programs that create report output (by using the TaskMan API) and options that are scheduled through the OPTION SCHEDULING file (#19.2).

20.1.1.1 Programs that Use the TaskMan API

One commonly used queuer is an application's call to the TaskMan API to queue tasks. In this process the queuer defines the task and its environment. Applications are not allowed to do direct manipulation of the ^%ZTSCH and ^%ZTSK globals.

The TaskMan API consists of entry points that allow developers to create, manipulate, and inquire about tasks. The most widely used entry point, ^%ZTLOAD, lets developers queue tasks, which involves creating and scheduling them. First, an application sets the variables that ^%ZTLOAD needs to define the desired task. In turn, ^%ZTLOAD uses that information to create an entry in the TASKS file (#14.4). ^%ZTLOAD then sets up a simple cross-reference to the new task in the SCHEDULE file, thereby finishing the queuing process.

After queuing the task, ^%ZTLOAD quits, returning control back to the queuer and leaving the next step in the process to the Manager routines.

20.1.1.2 Option Scheduling through the OPTION SCHEDULING File (#19.2)

Another commonly used queuer is the OPTION SCHEDULING file (#19.2). Menu Manager and TaskMan work together to allow certain options to be run as TaskMan tasks. These special options can be scheduled to run just once, or they can be set up to run over and over based on a rescheduling cycle. Such cycles can even include running the task whenever the computer system boots up.

20.1.2 Manager

For tasks to run, at least one CPU in a configuration needs to run a Manager. Only one Manager process needs to run per CPU; the site determines how many CPUs should be configured to run a Manager. The Manager's job is to route the tasks created by queuers. It normally runs at all times in the manager UCIs. It repeats the same loop of code all day long; every 2 seconds it looks for overdue tasks, every 15 seconds it checks the environment and performs some cleanup.

The environment check allows the system manager to control the Manager even at its busiest. All of the commands to which the Manager responds (described later) take effect here, between every task processed.

The Manager looks for overdue tasks in the schedule list, comparing the current time to the start time of the tasks listed. If an overdue task is found, the Manager removes it from the schedule list and inspects it. If the task is defined with a complete task record, the Manager places it in a list of tasks ready to run. The Manager places a task on one of several different lists depending on whether the task needs ownership of a currently unavailable I/O device. As its final step in processing each overdue task, the Manager checks the number of Submanagers available to process tasks and starts up new submanagers, if needed. The Manager uses the JOB command (or %SPAWN if the Manager is running in a DCL context on a Caché system).

The only variation on this scheme happens when the Manager finds a task bound for a different Volume Set. Depending on the system configuration, such tasks may need to be run by the Manager running on that other Volume Set. In this case, the current Volume Set's Manager copies the task over to the Volume Set on which the task should run and marks it as moved in the current TASKS file (#14.4). In this process, the task is assigned a new task number, and the Manager on that other Volume Set handles the task from there. If during this process the Manager discovers that the link between the two Volume Sets has dropped, it saves the task in a list of tasks waiting for that Volume Set and checks periodically to see whether it has been restored. When the link recovers, the Manager sends, in sequence, all the waiting tasks to the other Volume Set.

The Manager never actually runs the task but merely places it in a list as a task now available to be run by a Submanager.

20.1.3 Submanagers

Submanagers are the processes that actually run tasks. A Manager starts Submanagers whenever more are needed to handle the current workload of tasks, and they only last as long as they are needed. Submanagers loop back and forth between finding new tasks to run and running them.

To run each task, the Submanager first removes the task from the list of waiting tasks on which it reside (e.g., the Job or the I/O list). Then it looks up the task's entry in the TASKS file (#14.4), unloading all of the information about the task. If the task needs a device, the Submanager calls the Device Handler to get ownership of it and issues a USE command for it. Then the Submanager sets up the partition for the task and does the following:

- Sets the priority.
- Cleans out unwanted variables.
- Sets up requested variables.
- Prints a page header on the device if one was requested, etc.

Next, the Submanager starts the task running at the task's entry point. The Submanager uses a DO command and runs the task's entry point in its own partition. When the task finishes, the Submanager cleans up after the task:

- Closes the output device.
- Performs any commands left for it by the task, etc.

Running completely without user interaction, each task performs the work it was created to do and then quits, returning control to the Submanager that started it. The task may leave instructions for its Submanager, such as to requeue the task so that it runs again later or to delete the task's entry from the TASKS file (#14.4), but the task itself finishes before the Submanager continues.

After Submanagers have run all available tasks, they wait an interval before quitting. This period, called Submanager retention time, allows the Submanager to keep its partition open for new tasks for a while so that the Manager need not start a new Submanager. Every time a new task shows up during the retention time, the Submanager starts its main loop over again, returning to retention again only after all new tasks have been run. When the Submanagers eventually reach the end of their retention time, they quit.





Figure 228: TaskMan Manager and Submanager process flow diagram



20.2 TaskMan's Files

The two central files that facilitate task processing are:

- TASKS file (#14.4)
- SCHEDULE file (*not* VA FileMan-compatible)

TaskMan is configured by three configuration Files:

- VOLUME SET (#14.5)
- UCI ASSOCIATION (#14.6)
- TASKMAN SITE PARAMETERS (#14.7)

These files and the TaskMan routines fall within TaskMan's namespace (ZTM), and numberspace. TaskMan user interface routines have been moved to the XUTM namespace beginning with Kernel 8.0 (they were previously in the ZTM namespace).

TaskMan also relies upon software components outside of its direct control. As an integral part of Kernel, TaskMan accesses several files controlled by other Kernel modules and calls many software entry points as a whole. TaskMan's main external relation, however, is with VistA software applications through the queuers and the tasks they use.

20.2.1 TaskMan Globals: ^%ZTSCH and ^%ZTSK

^%ZTSCH holds the SCHEDULE file, and ^%ZTSK the TASKS file (#14.4). Every environment controlled by a single Manager needs each of these globals in its library UCI. % globals are used to make these files accessible to all the UCIs in that environment so a single Manager's influence spans all of those UCIs. When the environment spans Volume Sets, ^%ZTSCH and ^%ZTSK are translated across the Volume Sets included. They are never replicated because TaskMan updates them so frequently.

The ^%ZTSK global is mostly defined by VA FileMan (beginning with Kernel 8.0), but the ^%ZTSCH is not. Historically these globals were not VA FileMan-compatible. Now, the inquire, search, and print capabilities of VA FileMan can be used to study the TASKS file (#14.4). At present, all edit access to these globals is restricted to the TaskMan options that edit the tasks in various ways.



REF: For a description of the structure of ^%ZTSCH and ^%ZTSK, see the "<u>Troubleshooting</u>" section in "TaskMan: System Management—Operation."

20.2.2 SCHEDULE File

The SCHEDULE file holds all of the lists and nodes that TaskMan uses to manage itself and to schedule tasks. Some of these lists are:

- Schedule List (or Time Queue)
- Waiting List (or IO Queue)
- Job List
- Compute Server Job List (or C List)
- Link List
- Status List
- Run Node
- TaskMan Error Log
- Error Screens

The SCHEDULE file's function is split between identifying the status of active tasks and of TaskMan itself.



REF: For more information on these lists, see the "<u>TaskMan: System Management—Operation</u>" section.

Most of the lists in the SCHEDULE file describe tasks, as follows:

- Schedule List—Sorts all scheduled tasks by time, according to when they are supposed to begin running.
- Waiting List—Stores each task whose running was delayed because its I/O device was busy.
- Job List—Holds those tasks that can begin running immediately.
- Link List—Stores tasks whose running is delayed because of a dropped link to another Volume Set.
- Task List—Describes all actively running tasks.
- Compute Server Job List—Describes all tasks waiting to start on a Compute Server (cross-CPU queuing).

The role of tracking the status of TaskMan itself is split between lists of information and individual nodes and flags. The Status List is where the Manager keeps track of its current condition; it is a list because system administrators may choose to run more than one Manager in the same TaskMan environment. The RUN Node is a place where TaskMan stamps the current time; this node reveals when TaskMan stops running. The TaskMan Error Log is a simple list in which TaskMan stores each error that occurs either within TaskMan itself or within the tasks that it runs. The Error Screens are screens that can be established by system administrators to prevent the recording of certain errors.

These lists and nodes, as well as others not described here, are the primary data structures that TaskMan uses to schedule and run tasks.

20.2.3 TASKS File (#14.4)

The TASKS file (#14.4), unlike the SCHEDULE file, contains the tasks themselves.

Every task run by TaskMan is described by an entry in the TASKS file (#14.4). Each entry is subscripted by a unique internal number, and ^%ZTSK(-1) always equals the number of the most recently created task. The lists and nodes in ^%ZTSCH store the tasks' numbers that are scheduled to run. Each task's entry consists of a ^%ZTSK(task #, 0) node that contains most of the essential information about the task, several decimal nodes (.1, .2, .25, and .26) that store the remainder of the critical information, and a number of storage nodes under ^%ZTSK(task#,.3) that store the names and values of parameters that TaskMan creates for the task. Left unchecked, this file tends to grow.



REF: For a description of the various means of controlling this growth, see the "<u>TaskMan:</u> <u>System Management—Operation</u>" section.

20.2.4 Other Files

The TASKS (#14.4) and SCHEDULE files, taken together, describe all the information about tasks on the system. A few more files are needed, however, to describe everything about how tasks are managed on the system.

The following three files are stored in ^%ZIS:

- The VOLUME SET file (#14.5)—Describes the computer system's Volume Sets and how they are configured into TaskMan environments.
- The UCI ASSOCIATION file (#14.6)—Lists all the UCIs on the system and which Volume Sets they belong to. In more complicated systems, it is also used to describe how the UCIs in different environments correspond with one another.
- The TASKMAN SITE PARAMETERS file (#14.7)—Lets the system manager divide up the environments by both CPU and Volume Set. This allows a fine degree of control over such parameters as priority, partition size, and retention time.

Taken together, these files give system administrators precise and powerful control over TaskMan's behavior.

Other minor pieces of information are scattered throughout other Kernel files, especially the DEVICE (#3.5) and OPTION SCHEDULING (#19.2) files.

20.3 System Configuration Terminology

TaskMan operates close to the level of the system architecture. It must be capable of starting tasks in all the environments within a computer system. This means it *must* know about those environments; consequently, the options, routines, files, and documentation somehow *must* refer to that architecture.

One problem presented by system configuration is terminology. Such system architecture features as UCIs, directories, Volume Sets, and namespaces are not part of the ANSI M standard, so different vendors use different terminology. Although it would be ideal for Kernel to use a universal terminology, none exists. For historical reasons, Kernel has settled on a terminology based on that of **DSM-11** that includes the following terms:

Term Definition UCI User Class Identifier. This is roughly equivalent to a "directory" or an "account". A UCI refers to the environment limited to a particular set of routines and globals. In Caché terms, this is a "namespace." Manager UCI Roughly equivalent to a "system UCI" or a "library UCI." This is where the vendor's system management routines are kept, and where all %namespaced routines and globals reside. Currently, all Kernel % routines and globals are mapped back to the production account. **Volume Set** On current systems, we just set this to the string "ROU". This is the critical definition, since this is what affects how TaskMan starts background jobs. **CPU** Also known as a "node" or "computer", this designates a source of computing power and partitions. It is used both for controlling TaskMan's behavior with parameters and for sending tasks to specific CPUs. **Mounted Volume Set**

Table 35: TaskMan system configuration terminology



NOTE: The TaskMan chapters in this section make use of this terminology.

Obsolete; no longer used.

20.4 TaskMan Security Key

The TaskMan module comes with one security key, ZTMQ. The ZTMQ security key does not completely lock any options. Instead, it affects the behavior of the following three options:

- Dequeue Tasks [XUTM DQ]
- Requeue Tasks [XUTM REQ]
- Delete Tasks [XUTM DEL]

Those who use these options without holding this security key can manipulate only their own tasks. Only the holder of the ZTMQ security key can use these options to manipulate any task on the system.

21 TaskMan: System Management—Configuration

This chapter discusses the many issues surrounding the configuration of TaskMan.

21.1 Defining TaskMan Environments

The part of configuring TaskMan for a system that requires the most creativity is deciding how to divide the system's UCIs, Volume Sets, and CPUs into TaskMan environments. A TaskMan environment is the collection of UCIs from which entries can be made directly into a given Manager's TASKS (#14.4) and SCHEDULE files and that are within that Manager's reach. This requires looking at the system in terms of queuing and starting tasks. There are a number of options available. Many different configurations are possible.

One type of configuration has CPUs sharing the same Volume Set. Since this type of environment shares a single Volume Set among multiple CPUs, they also share a single TASKS (#14.4) and SCHEDULE file. However, the reach of Managers *cannot* span CPUs. Therefore, you *must* decide which CPUs in that environment run Managers, or whether some of them should rely on the other CPUs to run their tasks for them. Alpha clusters in VA are typically configured with Managers on only one or a few CPUs.

A different configuration allows you to limit the number of places TaskMan runs. In this scenario, you pick certain CPUs to run TaskMan and give them Managers and files to do the job. To have background processing support, the remaining Volume Sets need to be able to queue to one of the Managers on the system. This entails translating the TASKS (#14.4) and SCHEDULE files of that Manager so they are visible to the unsupported Volume Set. To tell TaskMan that the one Volume Set runs no tasks but is instead supported by the other, you *must* configure the VOLUME SET file (#14.5) as described later in this section.

Another possible configuration is to allow tasks to run everywhere, which requires that you place Managers within reach of every UCI and that you define your TaskMan environments accordingly. Under this configuration every CPU needs its own Manager, and its own TASKS (#14.4) and SCHEDULE files.

One other configuration to keep in mind, of course, is to have a standalone environment disconnected from the rest of the computer system. Such environments make excellent test areas for developers. They are configured the same regardless of the configuration of the main system.

21.2 Configuring TaskMan

TaskMan's three configuration files *must* be setup to properly reflect your system's layout. The three files are:

- TASKMAN SITE PARAMETERS (#14.7)
- VOLUME SET (#14.5)
- UCI ASSOCIATION (#14.6)

There are three options on the Edit TaskMan Parameters menu, one to edit each of the three configuration files.

Because the TASKMAN SITE PARAMETERS (#14.7) allows you to define parameters (e.g., TaskMan Job Limit) separately for each CPU on your system; you are able to optimize TaskMan's behavior individually for each CPU.

You no longer need to stop and then restart TaskMan in order to change the TASKMAN JOB LIMIT on a CPU. Cross-references on the relevant fields locate every TaskMan on your system and inform them that they need to update their TaskMan parameter information. Thus, within a minute or so of making the changes, TaskMan on that CPU should be operating with the new value.

21.2.1 TaskMan's Reach

The key issue that defines TaskMan's configuration is its "reach," those places where TaskMan can start background jobs. TaskMan's reach extends to:

- All UCIs a Submanager can access directly after using Kernel's UCI switching facilities.
- All other Managers TASKS (#14.4) and SCHEDULE files to which a given Manager can WRITE using extended global reference.
- All UCIs on Print Servers with link access to the current Volume Set.

TaskMan's reach does *not* include other sites on a wide area network, because they *cannot* be accessed through either UCI switching or through extended global reference. There are ways to simulate such a reach through the use of server options, however. For purposes of TaskMan configuration, we generally think in terms of the reach of a single Manager, which can only run tasks in the UCIs it can reach.

21.2.2 TASKMAN SITE PARAMETERS File (#14.7)

Figure 229: Site Parameters Edit option

```
SYSTEMS MANAGER MENU ... [EVE]
Task Manager ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Edit Taskman Parameters ... [XUTM PARAMETER EDIT]
Site Parameters Edit [XUTM BVPAIR]
```

System managers *must* enter one set of site parameters into the TASKMAN SITE PARAMETERS file (#14.7) for each Manager that runs in a different Volume Set/CPU. This set of parameters tells each Manager how it should process tasks. The parameters are organized both by Volume Set and by CPU. This allows two CPUs that share a Volume Set to be treated differently if one is more powerful than the other.

Table 36: TASKMAN SITE PARAMETERS File (#14.7)—Field entries

	• • •
Field	Description
BOX-VOLUME PAIR (#.01)	The BOX-VOLUME PAIR field identifies a Volume Set and the CPU on which it is available. It contains the name of a Volume Set concatenated to the CPU ("box") name: first the Volume Set name and then the CPU name. For example, if the Volume Set name is "KRN" and the name of the CPU (e.g., box) is "ABC999," then the BOX-VOLUME PAIR would be "KRN:ABC999."
	For systems on which each CPU tends to have a unique Volume Set, and vice versa, you can enter just the Volume Set name (e.g., "PSA" or "AAA"). This field's value for the current process can be found by doing GETENV^%ZOSV and checking the fourth *-piece of Y. Since the Volume Set and CPU are identified, the TaskMan site parameters can be tuned for each specific Volume Set and CPU affected. Systems running Managers on more than one CPU need one entry for each CPU where a manager is running.
LOG TASKS? (#2)	Set the LOG TASKS? field to YES to make tasks log in and out through the signon log the way interactive users do. How to set this is up to the individual site; it does consume

Field	Description
	space and resources.
TASK PARTITION SIZE (#4)	The TASK PARTITION SIZE field is used to assign partition sizes for tasks. The value from this field is plugged directly into the JOB command used to create new Submanagers. If this field is left blank, all tasks receive the operating system's current default value. This field should only be used by system managers who thoroughly understand how their vendor's version of M handles partition sizes with the JOB command.
SUBMANAGER RETENTION TIME (#5)	The SUBMANAGER RETENTION TIME number determines how many seconds Submanagers should wait while looking for new tasks. The purpose of this field is to reduce the number of JOB commands needed to process a site's tasks. By keeping old Submanagers around to run new tasks, new process creation is significantly reduced.
TASKMAN JOB LIMIT (#6)	If there are more active processes on the system than the number stored in the TASKMAN JOB LIMIT field, TaskMan does <i>not</i> create new Submanagers to handle tasks. Task processing is left to existing Submanagers until the number of processes falls back below this number. This number should be slightly lower than the MAX SIGNON ALLOWED field (#41,2) of the VOLUME SET field (#41, Multiple) in the KERNEL SYSTEM PARAMETERS file (#8989.3) so that the system manager still has room to sign on when TaskMan is using its greatest number of partitions.
TASKMAN HANG BETWEEN NEW JOBS (#7)	The TASKMAN HANG BETWEEN NEW JOBS field sets a delay between the creation of new Submanagers, in seconds. It is useful as a throttle. For systems, this delay spaces out the use of the JOB command to avoid slowing users' response time when the Manager needs to JOB off many new processes in rapid succession.
	For systems that create new processes cheaply, this delay is unnecessary. This delay also becomes less important when a high Submanager retention time is used since higher retention times reduce the likelihood that TaskMan needs to create new processes.
	Be sure not to combine a high TASKMAN HANG BETWEEN NEW JOBS value with a low SUBMANAGER RETENTION TIME value, since that increases the number of jobs per day TaskMan has to start and can cause busy systems to fall behind. The number should be the lowest value that prevents the problem and can be left blank for systems with efficient JOB commands.
MODE OF TASKMAN (#8)	The MODE OF TASKMAN field determines how each CPU (BOX-VOLUME pair entry) should process tasks. You can set it to one of four values:
	General Processor ("G"): The G type should be selected when the TASKS (#14.4) and Scheduling files are seen by only one Volume Set. For example, VA's Alpha clusters have several CPUs, but each of them

Field	Description
	runs on the same Volume Set. The Manager on a G type runs tasks created on the same Volume Set, and tasks from any other Volume Set that explicitly requests the G type's Volume Set. The G type sends tasks from another Volume Set that did not explicitly request its Volume Set back to the originating Volume Set, however.
	To transfer tasks to a G type, TaskMan uses extended global references to copy the task to the destination TASKS (#14.4) and Scheduling files and then removes the task from its own side. Submanagers started on a G-type processor process tasks in the Partition Waiting List and the Busy Device Waiting List.
	Print Server ("P"): The P type should be selected when multiple Volume Sets map to the same TASKS (#14.4) and Scheduling files, and you want to run the Manager on the Volume Set/CPU in question.
	Like the G type, the Manager on a P type runs tasks created on the same Volume Set and tasks from any other Volume Set/CPU that explicitly request the P type's Volume Set/CPU. Unlike the G type, however, the P type also runs tasks from other Volume Sets that did not make an explicit Volume Set request. Tasks are transferred to a P type in the same way as to a G type, and Submanagers behave the same.
	Compute Server ("C"): The C type should be selected when multiple Volume Sets map to the same TASKS (#14.4) and Scheduling files (as with the P type), but when the Volume Set/CPU in question runs users (not tasks). The Manager does not start on a C type. Tasks that explicitly request to run on a C type are transferred to it by being placed in the Link Waiting List; a Submanager is then jobbed across to the C type Volume Set/CPU. Submanagers started on a C type only process tasks in the Link Waiting List for their Volume Set.
	Other Non-TaskMan ("O"): Neither the Manager nor the Submanager runs on O types. Tasks sent from or to an O type are rejected.
	Because of the field's crucial role in guiding TaskMan's behavior, the field is required.
VAX ENVIRONMENT FOR DCL (#9)	The VAX ENVIRONMENT FOR DCL field only has meaning to DSM for OpenVMS and Caché systems. It is set to the OpenVMS username of the DSM environment manager account. Setting it to this username causes the Manager to use %SPAWN to SUBMIT Submanagers to run. This method requires that certain DCL command files exist, along with a TASKMAN OpenVMS user account and directory.

Field	Description
	REF: For descriptions of the needed setups, see the "Running TaskMan with a DCL Context" section. If the field is empty, the Manager starts Submanagers with the JOB command instead.
LOAD BALANCE ROUTINE (#21)	If you are running multiple Managers (one per node), use the LOAD BALANCE ROUTINE field to set up load balancing between the Managers on each node. It should be set to the name of an extrinsic function that returns a load rating for the node.
	REF: For more information on load balancing, see the "Multiple TaskMan Managers and Load Balancing" section.

21.2.3 **VOLUME SET File (#14.5)**

Figure 230: Volume Set Edit option

```
SYSTEMS MANAGER MENU ... [EVE]
Task Manager ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Edit Taskman Parameters ... [XUTM PARAMETER EDIT]
Volume Set Edit [XUTM VOLUME]
```

TaskMan knows about a system's configuration from the values entered into the VOLUME SET file (#14.5) using the Volume Set Edit option [XUTM VOLUME]. The information stored in this file strongly affects TaskMan's behavior. If you inaccurately describe your system, you usually notice very quickly as TaskMan begins processing tasks in a consistently incorrect way.

You need to make one entry in this file for each Volume Set that tasks can be queued to or from. These entries are only used when:

- A Manager is running on the Volume Set and *must* look up information about its own environment.
- The Volume Set is a required volume, in which case every Manager *must* check access to it when they start up.
- A task needs to run on the Volume Set, in which case the Manager *must* look up how to get the task there.

The following is what we have set up for FORUM:

Figure 231: Sample Volume Set setup on FORUM

VOLUME SET (14.5)

VOLUME SET: ROU INHIBIT LOGONS?: NO
LINK ACCESS?: NO TASKMAN FILES UCI: VAH
DAYS TO KEEP OLD TASKS: 1 TYPE: GENERAL PURPOSE VOLUME SET

SIGNON/PRODUCTION VOLUME SET: Yes

UCI ASSOCIATION (14.6)

Empty

TASKMAN SITE PARAMETERS (14.7)

BOX-VOLUME PAIR: ROU:FORFORUM1 LOG TASKS?: NO
SUBMANAGER RETENTION TIME: 60 TASKMAN JOB LIMIT: 400
TASKMAN HANG BETWEEN NEW JOBS: 1 MODE OF TASKMAN: GENERAL PROCESSOR
OUT OF SERVICE: NO MIN SUBMANAGER CNT: 10
LOAD BALANCE ROUTINE: \$\$CACHE1() Auto Delete Tasks: Yes
Manager Startup Delay: 30

The value of ^%ZOSF("VOL") is "FOR".

Table 37: VOLUME SET File (#14.5)—Field entries

Field	Description
VOLUME SET (#.01)	The VOLUME SET field should be set to the name of a Volume Set. It is used in extended global references to reach this Volume Set and can be used in UCI-switching software to move Submanagers between UCIs. If you are unsure how your Volume Sets are named, you can look at the value of ^%ZOSF("VOL") in the Volume Set in question.
TYPE (#.1)	The TYPE field is used to help resolve where tasks should run; it should properly identify the type of the Volume Set. Typically it should be set to the same value as the MODE OF TASKMAN field (#8) for all BOX-VOLUME PAIRs associated with this Volume Set, in the TASKMAN SITE PARAMETERS file (#14.7). This field must be filled in for all Volume Sets. This field can have the following values: • G—GENERAL PURPOSE VOLUME SET • P—PRINT SERVER • C—COMPUTE SERVER • O—OTHER NON-TASKMAN VOLUME SET These values have the same meanings as the equivalent values for the MODE OF TASKMAN field (#8) in the TASKMAN SITE PARAMETERS file (#14.7), as described previously in the "TASKMAN SITE PARAMETERS File (#14.7)" section. GENERAL PURPOSE VOLUME SET for Volume Sets is the rough equivalent of the MODE OF TASKMAN value GENERAL PROCESSOR for BOX-VOLUME PAIRs.

Field	Description
	NOTE: The FILE SERVER value has been removed; Volume Sets for File Servers should be set to a TYPE of OTHER NON-TASKMAN VOLUME SET.
INHIBIT LOGONS? (#1)	Setting the INHIBIT LOGONS? field to YES causes TaskMan to notify Signon that logons are now prohibited and to enter a PAUSE state (stopping processing of tasks) until logons are allowed again. Under ordinary circumstances, system managers should leave this field as NULL or NO .
LINK ACCESS (#2)	The LINK ACCESS field should always be set to NULL or YES for the usual kinds of configurations used in VistA. Answer NO to tell TaskMan that this Volume Set cannot be accessed by other Volume Sets using the local network links. Tasks that request a Volume Set without link access are rejected by TaskMan. Such Volume Sets are usually PC workstations linked into the larger network. They can access the core computers, but <i>cannot</i> be accessed themselves.
	Some system managers may wish to have a completely isolated computer for testing. They can cut it off from the rest of the world by making entries for all the other Volume Sets and setting this field to NO for each of them. This explicitly tells TaskMan it cannot reach the other Volume Sets.
OUT OF SERVICE? (#3, Obsolete, see TYPE field)	The OUT OF SERVICE? field is obsolete and should only be set to NULL ; use the TYPE field (#.1).
REQUIRED VOLUME SET? (#4, Obsolete)	The REQUIRED VOLUME SET? field is obsolete and should only be set to NULL .
TASKMAN FILES UCI (#5)	The TASKMAN FILES UCI field should be set to the name of the UCI that holds the ^%ZTSCH and ^%ZTSK globals (usually the manager UCI). The answer should not contain a comma and Volume Set name (e.g., "VAH,PSA"), just the UCI name (e.g., "VAH"). This field is required.
TASKMAN FILES VOLUME SET (#6)	The TASKMAN FILES VOLUME SET field should be set to the name of the Volume Set that holds ^%ZTSCH and ^%ZTSK.
	A NULL value means this Volume Set holds its own TaskMan files, which is usually the case.
REPLACEMENT VOLUME SET (#7)	The REPLACEMENT VOLUME SET field should be set to the name of a Volume Set to which tasks can be sent if this Volume Set is unavailable. A REPLACEMENT VOLUME SET should be essentially equivalent in features to the current one, since tasks that would normally run on the current one are running on the REPLACEMENT VOLUME SET instead. For many Volume Sets, no other Volume Set is equivalent, and tasks should wait for the link to be restored rather than run elsewhere. If tasks that need this Volume Set should wait, leave the field blank.

Field	Description
DAYS TO KEEP OLD TASKS (#8)	The number stored in the DAYS TO KEEP OLD TASKS field is used by the XUTM QCLEAN option to decide which tasks to delete. The decision only affects inactive tasks, as explained in the discussion of the XUTM QCLEAN option. Values in this field <i>cannot</i> inadvertently cause TaskMan to delete scheduled or running tasks. If the field contains no value, XUTM QCLEAN keeps the last seven days' tasks. A value of 0 here keeps your file very clean.

21.2.4 UCI ASSOCIATION File (#14.6)

Figure 232: UCI Association Table Edit option

```
SYSTEMS MANAGER MENU ... [EVE]
Task Manager ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Edit Taskman Parameters ... [XUTM PARAMETER EDIT]
UCI Association Table Edit [XUTM UCI]
```

There are two different kinds of entries made into the UCI ASSOCIATION file (#14.6) using the UCI Association Table Edit option [XUTM UCI]:

- Partial File Entries
- Complete File Entries

21.2.4.1 Partial File Entries

File entries with the following first two fields filled in identify the valid UCIs on the system for TaskMan:

- FROM UCI (Table 38)
- FROM VOLUME SET (Table 38)

Every VistA site needs one entry of this type for each UCI to which tasks can be queued or from which tasks are created.



NOTE: Caché sites only need to fill in these first two fields.



REF: For a sample configuration, see the "<u>Sample Configuration: Standardized VA Caché and GT.M Configuration</u>" section.

21.2.4.2 Complete File Entries

File entries with all four fields (<u>Table 38</u>) completed collectively build a UCI ASSOCIATION TABLE.

A complete UCI ASSOCIATION TABLE tells TaskMan which UCI to use for tasks that *must* switch Volume Sets in order to reach an I/O device. This situation arises when an I/O device is located in a different Volume Set than the Volume Set where the task was created. In such situations, the Manager knows exactly where the task originated and knows to which Volume Set it *must* be moved, but it does not know in which UCI on that Volume Set it should run the task. A UCI ASSOCIATION TABLE entry supplies the missing information by linking equivalent UCIs together. When building a full UCI ASSOCIATION TABLE, you can omit entries where the UCIs on both Volume Sets have the same name because TaskMan assumes that same-named UCIs are equivalent if no entry is present.

Table 38: UCI ASSOCIATION file (#14.6)—Partial and complete field entries

Field	Description
FROM UCI (#.01)	The FROM UCI field should be set to the name of a UCI on your system. Enter only the UCI name (e.g., "VAH"). Do <i>not</i> include the Volume Set name (e.g., "VAH,ROU").
	• For entries requiring only two fields, this catalogues all the UCIs on your system (and there should be an entry for each).
	 For four-field entries, this represents a UCI from which tasks are being transferred in order to reach their I/O device.
FROM VOLUME SET (#1)	The FROM VOLUME SET field should be set to the name of the Volume Set that holds the UCI identified in the entry's FROM UCI field (#.01). Every Volume Set listed in this field should be described in the VOLUME SET file (#14.5).
	For four-field entries, this represents the Volume Set from which tasks are being transferred in order to reach their I/O device.
TO VOLUME SET (#2)	The TO VOLUME SET field is only used for entries that build a UCI Association Table. For such entries, it should be the name of the Volume Set to which tasks are being transferred in order to reach their I/O devices.
TO UC (#3)I	As with TO VOLUME SET(#2), the TO UCI field is only used for entries that build a UCI Association Table. For such entries, it should be the name of the UCI to which tasks are transferred whenever they <i>must</i> be moved from the UCI on the first Volume Set to the second Volume Set in order to reach their I/O devices. As with the From UCI field, the Volume Set name should not be included.

21.2.5 Sample Configuration: Standardized VA Caché and GT.M Configuration

Sites that run Managers on their satellites should make the appropriate TASKMAN SITE PARAMETERS file (#14.7) entries for each satellite and adjust their TaskMan Job Limit to reflect each satellite's individual capacity.

Figure 233: VOLUME SET file (#14.5) standardized VA Caché and GT.M configuration

VOLUME SET TYPE INHIBIT LOGONS? LINK ACCESS? OUT OF SERVICE? REQUIRED VOLUME SET?	You need one entry, for ROU GENERAL PURPOSE VOLUME SET Blank or NO
TASKMAN FILES UCI TASKMAN FILES VOLUME SET REPLACEMENT VOLUME SET DAYS TO KEEP OLD TASKS SIGNON/PRODUCTION VOLUME SET	VAH Leave this blank Leave this blank Up to you; can leave blank Yes

Figure 234: UCI ASSOCIATION file (#14.6)—Standardized VA Caché and GT.M configuration

FROM UCI FROM VOLUME SET TO VOLUME SET TO UCI	1 entries: VAH ROU Blank Blank



NOTE: You can leave this empty.

Figure 235: TASKMAN SITE PARAMETERS file (#14.7) standardized VA Caché and GT.M configuration

	<u> </u>
BOX-VOLUME PAIR	ROU:FORFORUM1 Your answer should be the volume set name concatenated with the ":" concatenated with
	the name of the Cache Configuration.
LOG TASKS?	Blank or NO (unless TaskMan is running in a
	DCL context, in which case set to YES)
DEFAULT TASK PRIORITY	Blank
TASK PARTITION SIZE	Blank
SUBMANAGER RETENTION TIME	60
TASKMAN JOB LIMIT	400 (2-5 lower than Max Signons)
TASKMAN HANG BETWEEN NEW JOBS	1
MODE OF TASKMAN	GENERAL PROCESSOR
ENVIRONMENT FOR DCL	Blank
OUT OF SERVICE	Blank
MIN SUBMANAGER CNT	2
LOAD BALANCE ROUTINE	Blank
Auto Delete Tasks	Yes
Manager Startup Delay	30

21.3 Manager Startup

You may want to configure your system so that, on CPUs where the Manager should run, a Manager starts up every time the CPU starts up. Otherwise, you need to manually start up the Manager each time you start up those nodes that should run the Manager.

For most sites, only one Manager is needed to cover each environment. Therefore, this section focuses on starting up only a single Manager.

Neither the Manager nor the Submanagers starts up on a BOX-VOLUME PAIR pair of the wrong type, so pay attention to how you fill in the MODE OF TASKMAN field of the TASKMAN SITE PARAMETERS file (#14.7). If you want the Manager to start, you *must* make sure this field is set to either a Print Server or a General Processor.

Getting the Manager to start up when the system does is accomplished in the VA by the ZSTU routine in the "%SYS" namespace. This routine is provided by Enterprise Product Support (EPS).

21.4 Multiple TaskMan Managers and Load Balancing

TaskMan supports the running of multiple Manager processes; however, only one Manager process should run per CPU. Running multiple Managers is probably useful only at large sites; at a large site, doing this can enable tasks to be processed more quickly than if only one CPU runs a Manager. An added bonus with multiple Managers is that if one CPU running a Manager becomes unavailable, Managers still run on the other CPUs, with no further re-configuration required.

21.4.1 Configuration for Multiple Managers

Each node that runs a TaskMan Manager *must* have its own entry (BOX-VOLUME PAIR) in the TASKMAN SITE PARAMETERS file (#14.7).

Each CPU *must* share access to a common ^%ZTSK and ^%ZTSCH global, and have access to the same devices. Because of this, all CPUs *must* run the same M implementation.

21.4.2 Starting Up, Pausing, and Stopping Multiple Managers

You need to start a Manager on each CPU where a Manager should run. Whatever steps you follow to start a single Manager, you need to repeat for any additional nodes on which you want to run additional Managers.

The options that place TaskMan in a WAIT state and stop TaskMan are *not* CPU-specific; they affect all running Managers across the system.

21.4.3 Load Balancing

The LOAD BALANCE ROUTINE field in the TASKMAN SITE PARAMETERS file (#14.7) holds the name of a function that returns a CPU's load rating. This field is only useful if you are running multiple TaskMan Managers.

To use load balancing, enter a routine name in the LOAD BALANCE ROUTINE field for each participating CPU's BOX-VOLUME PAIR entry. Kernel patch XU*8.0*355 added the following routine for TaskMan load balancing in Caché:

\$\$CACHE2(@com-file,logical-name) in ^ZTM6

If the com-file value is set, that com-file runs each time TaskMan gets the balance value. The logical-name defaults to "VISTA\$METRIC" or uses the value entered. The normal way would be to have \$\$CACHE2() in the field and use the following two scripts:

- GET_METRIC.COM—This script sets the logical "VISTA\$METRIC." It can be run by TaskMan or from the TM\$<node> batch queue with the METRIC_SCHEDULE.COM script.
- METRIC_SCHEDULE.COM—This script takes a parameter of the number of seconds to reschedule itself. It defaults to 15 seconds and runs under the "SYSTEM" user.



NOTE: These scripts are located in the same directory as the TaskMan in DCL files.

Use of TaskMan in DCL is optional.

It is all right to run multiple TaskMan Managers without using load balancing; it is also all right if load balancing is set up and only one Manager is running (that Manager automatically takes all jobs itself). If one Manager's CPU has the LOAD BALANCE ROUTINE field filled in, and another running Manager's CPU does not, the Managers acts as if no load balancing is taking place. In short, the only ramification from various combinations of Managers with the LOAD BALANCE ROUTINE field filled in or not is that load balancing might not take place.

The load balancing routine *must* be an extrinsic function that returns a positive value. The CPU with the highest value is the one that runs new tasks.

Cache Algorithms:

- \$\$Cache2()—Returns the TCPIP metric.
- \$\$Cache1()—Returns the Available jobs.

Each CPU performing load balancing compares its current CPU capacity with that of the other nodes running Managers. If the current CPU has a lower rating than the other CPUs, it puts itself in a BALANCE state and waits to let the other CPUs take up the load before running more jobs itself.

Submanagers try and wait until there node is running before testing if they should exit.

21.4.4 Monitor Taskman Option

On a system where multiple managers are running, the Monitor Taskman option [XUTM ZTMON] shows a combined view of the operation of multiple managers.

If the current node (the one where you are running the Monitor Taskman option) has a lower rating than other nodes, Monitor TaskMan shows that the current node is in a BALANCE state.

21.5 Device Handler's Influence on TaskMan

Certain DEVICE file (#3.5) fields strongly affect TaskMan's behavior. System managers should keep these effects in mind as they configure their systems' devices.

Table 39: DEVICE file (#3.5)—TaskMan-related field entries

Field	Description
VOLUME SET(CPU) (#1.9)	If the VOLUME SET(CPU) field is not filled in, TaskMan considers this device to be available from all Volume Sets. If it is filled in, TaskMan makes sure all tasks that need this device start on the designated Volume Set.
TYPE (#2)	Any tasks that <i>must</i> wait for HFS- or SPL-type devices are rescheduled for ten minutes in the future, instead of being placed in a list of waiting tasks. This is because these lists are checked through repeated opens, which may contaminate the output of these two special types of devices.
PRIORITY AT RUN TIME (#25)	The PRIORITY AT RUN TIME field overrides the default priority that system managers can establish for tasks using the Site Parameters Edit option on the Edit TaskMan Parameters menu.
TASKMAN PRINT A HEADER PAGE? (#26)	If the TASKMAN PRINT A HEADER PAGE? field is set to YES for the device being opened by the Submanager, a header page is printed. The header page distributed with TaskMan is very simple, and system managers can substitute their own locally written header pages. To do this, you <i>must</i> rename your header page routine as ^%ZTMSH, the name of the one distributed with TaskMan.
	Whenever you install new versions of Kernel, it overwrites ^%ZTMSH with the default copy, so you should maintain your local version by doing the following:
	 Keep your local header page routine saved somewhere under a local name.
	After each Kernel install, re-save the locally named copy as ^%ZTMSH.

The following example shows an alternative to the default header page distributed with Kernel:

Figure 236: Customized Header Page routine

```
%ZZTMSH
             ;SEA/RDS-Local: Sample Header Page ;3/9/92 11:17 ;
             ;;1.0;Local;;
LOCAL
             ;Print The Local Header Page
R
            ;build text lines
            S X1=$P($G(^VA(200,DUZ,0)),U) I X1="" S X1="name unknown"
            S X2=$P($G(^VA(200,DUZ,5)),U,2) I X2="" S X2="unlisted mail stop"
            S X3=$P($G(^VA(200,DUZ,.13)),U,2) I X3="" S X3="unlisted phone number"
            S ZZLINE1=$$FORMAT(" "_X1_" ("_X2_") "_X3_"",IOM)
S ZZLINE2=$$FORMAT(" "_ZTDESC_" ",IOM)
            S ZZLINE3=$$FORMAT(" "_ION_" "_$$HTE^XLFDT($H)_"",IOM)
D
            ;display each line three times
            F X=1:1:3 W !,ZZLINE1
            W ! F X=1:1:3 W !,ZZLINE2
            W ! F X=1:1:3 W !,ZZLINE3
FORMAT(ZZTEXT,ZZIOM) ;local extrinsic function
            ;input: text to be formatted, and margin width
             ;output: text filled out to margin width -3 with *characters
            N ZZ1,ZZFILLED
            S ZZ1=ZZIOM-3-$L(ZZTEXT) \ 2
            S $P(ZZFILLED, "*", ZZ1*2+1) = ""
            S $P(ZZFILLED,"*",ZZ1+1)=ZZTEXT
            I $L(ZZFILLED)+3-ZZIOM S ZZFILLED=ZZFILLED_"*"
            Q ZZFILLED
```

Figure 237: Customized Header Page

21.6 Running TaskMan with a DCL Context

When run from a DCL context, TaskMan runs as an OpenVMS user. The Manager runs as a job that originates from a node-specific OpenVMS batch queue and, by default, submits new Submanagers to the same queue as needed.

One advantage to running TaskMan from a DCL context is that it allows jobs to be queued to specific CPUs. When a program calls ^%ZTLOAD, it can request that the job run on a specific CPU/node in your cluster (via the ZTCPU input variable). Unless you are running TaskMan in a DCL context (on Caché systems only), this request will probably fail (and possibly cause the task *not* to run). When TaskMan runs with a DCL context, however, the Manager can submit the job as a new Submanager to a given CPU's TaskMan batch queue.

Depending on the %ZTSK and %ZTSCH mapping, multiple Cache environments on the same CPU can each run TaskMan in a DCL context. Although TaskMan in each Cache environment shares the same account, directory, DCL command files, and batch queue, jobs run in the environment specified in each environment's VAX ENVIRONMENT FOR DCL site parameter.



NOTE: Kernel patch XU*8.0*355 added the \$\$CACHE2 routine for TaskMan load balancing and provides support for DCL context in Caché.

21.6.1 Setup for Running TaskMan in a DCL Context in a Cache/VMS Environment

The following steps show you how to set up TaskMan to run in a DCL context in Cache/VMS (see Kernel patch XU*8.0*355).



NOTE: The following is just an example and has to be modified for your site. You need to adjust the UIC [100,20] to match your system and indicate the location of the TaskMan directory.

1. Create TASKMAN that runs the TaskMan jobs:

Figure 238: Create TASKMAN

```
ADD TASKMAN/OWNER="SYSTEM MANAGER" -

/ACCOUNT=CACHE -

/PRIV=(NETMBX,TMPMBX) -

/DEFPRIV=(NETMBX,TMPMBX) -

/DEVICE=USER$/DIR=[TASKMAN]/LGICMD=LOGIN.COM -

/FLAGS=(DisCtlY,DisWelcome,DisReport,DisForce_Pwd_Change,DisPwdDic,DisPwdHis) -

/PASS=TASK$MAN/UIC=[100,20]
```

2. Create the TASKMAN directory:

Figure 239: Create the TASKMAN directory

Define/SYSTEM DHCP\$TASKMAN USER\$:[TASKMAN]

3. Create the system logical name for the directory with the COM files.



NOTE: Be sure to also add to the STARTUP\$LOGICALS.COM file.

Figure 240: Create system logical name for the directory with the COM files

Define/SYSTEM DHCP\$TASKMAN USER\$:[TASKMAN]

4. Create the queues, as explained in this manual.



NOTE: Be sure to also add to the STARTUP\$DEFINE_QUEUES.COM file.

TaskMan submits jobs to the queue TM\$<node>. Because we use "run loginout" to detach the execution, we do not need a large JOB limit here.

Figure 241: Create system logical name for the directory with the COM files

INIT/QUEUE/BATCH/OWNER=[TASKMAN] /prot=(S:M,O:D,G:R,W:S)/JOB=5/AUTOSTART_ON=isfva2:: TM\$isfva2

- 5. Load the following DCL command files into the [TASKMAN] directory:
 - GET_METRIC.COM
 - LOGIN.COM
 - METRIC_SCHEDULE.COM
 - ZTM2WDCL.COM
 - ZTMS2WDCL.COM

These command files are located in the cache-taskman sub-directory in the Anonymous FTP site.



NOTE: Get the files in ASCII mode.

Figure 242: Sample user dialogue to retrieve DCL command files


```
ABC999$ SET DEF USER$: [TASKMAN]
ABC999$FTP FTP.FO-SITE.MED.VA.GOV
220 ABC999.ISC-SITE.MED.VA.GOV FTP Server (Version 5.3) Ready.
Connected to FTP.FO-SITE.MED.VA.GOV.
Name (FTP.FO-SITE.MED.VA.GOV:fort): ANONYMOUS
331 Guest login OK, send ident as password.
Password: XXXXXXXXXX
230 Guest login OK, access restrictions apply.
FTP> CD CACHE-TASKMAN
FTP> LS
150 Opening data connection for USR$:[ANONYMOUS.CACHE-TASKMAN]*.*;*
GET_METRIC.COM
LOGIN.COM
METRIC_SCHEDULE.COM
ZTM2WDCL.COM
ZTMS2WDCL.COM
FTP> ASCII
200 TYPE set to ASCII.
FTP> GET GET METRIC.COM
FTP> GET LOGIN.COM
FTP> GET METRIC_SCHEDULE.COM
FTP> GET ZTM2WDCL.COM
FTP> GET ZTMS2WDCL.COM
FTP> BYE
221 Goodbye.
```



NOTE: Repeat for each node in the TASKMAN SITE PARAMETERS file (#14.7).

6. Edit TaskMan Parameters:

Figure 243: Sample user dialogue to edit TaskMan parameters



21.6.2 How to Restart TaskMan when Running in a DCL Context

To manually restart TaskMan when TaskMan is running in a DCL context, you can either:

- Sign in as OpenVMS user TASKMAN and DO RESTART^ZTMB.
- Sign in from an OpenVMS account that has the OPER and SYSPRV privileges and DO RESTART^ZTMB. This submits the Manager to run under the username TASKMAN.

In either case, however, do *not* use the Restart TaskMan option in the Kernel menus; it is not compatible with TaskMan in a DCL context.

Figure 244: ZTM2WDCL.COM Command File

```
$! ZTM2WDCL.COM - Cache Run Taskman in a DCL Context
$! * KERNEL 8 *
$!
$! P1 is the Cache config that taskman should start in.
$! P2 is the namespace that taskman should start in.
$! P3 = null to START and 1 to RESTART
$! This file is submitted to the queue to run and it
$! builds and runs the TMP_pid.* files
$!
$! Build the file to run, can't pass arguments with RUN
$ pid = F$GETJPI("","PID")
$ infile="TMP_" + pid + ".ZTM"
$ outfile = "TMP_" + pid + ".log"
$ SAY = "write output"
$!
$ entry="START"
$ if p3 .eq. 1 then entry="RESTART"
$! open and build the input file
$ OPEN/write output 'infile'
$ SAY "$! Taskman temp file to run the Manager"
$ SAY "$! Delete this file if it is not open."
$ SAY "$ set verify"
$ SAY "$ csession ""'\p1'"" ""-U"" ""\p2'"" ""\entry'^%ZTM0"""
$ SAY "$ exit"
$ Close output
$! If a log file is needed change _NLAO: to 'outfile
$ name = "ZTMS " + pid
$ run sys$system:loginout.exe -
      /input='infile -
       /output=_NLA0: -
       /detach /process='name
Ś!
$!
       Wait for loginout to run it then delete the file.
$ wait 00:01
$!
$ del TMP_*.ZTM;1
$ exit
```

Figure 245: ZTMS2WDCL.COM Command File

```
$! ZTMS2WDCL.COM - Cache Start Submanager with a DCL Context
$! * KERNEL 8 *
$! pl is the Cache config name
$! p2 is the namespace to start.
$! p3 is NOT used. (VOL for DSM)
$!
$! This file is submitted to the queue to run and it
$! builds and runs the TMP_pid file
$! Build the file to run, can't pass arguments with RUN
$ pid = F$GETJPI("","PID")
$ infile = "TMP_" + pid + ".ZTMS"
$ outfile = "TMP_" + pid + ".log"
$ SAY = "write output"
$! open and build the input file
$ OPEN/write output 'infile'
$ SAY "$! Taskman temp file to run a submanager"
$ SAY "$! Delete this file if it is not open."
$ SAY "$ set verify"
$ SAY "$! '`P1' and '`P2'"
$ SAY "$ csession ""'\p1'"" ""-U"" ""\p2'"" ""START^%ZTMS"""
$ SAY "$ exit"
$ Close output
$!
$! If a log file is needed change _NLAO: to 'outfile
$ name = "ZTMS_" + pid
$ run sys$system:loginout.exe -
      /input='infile -
      /output= NLA0: -
       /detach /process='name
$!
       Wait for loginout to run it then delete the file.
$!
$ wait 00:01
$!
$ del TMP_*.ZTMS;1
$ exit
```

Figure 246: Example of OpenVMS User TASKMAN on ALPHA AXP Systems

Username: TASKMAN Owner: [50,20] ([DEV,TASKMAN]) Account: UIC: CT.T: DCL Tables: DCLTABLES Default: USER\$:[TASKMAN] LGICMD: LOGIN Flags: DisCtlY Restricted DisWelcome DisReport Primary days: Mon Tue Wed Thu Fri Secondary days: Sat Sun No access restrictions Expiration: (none) Pwdminimum: 6 Login Fails: Pwdlifetime: 180 00:00 Pwdchange: 19-NOV-1992 14:12 Last Login: 20-NOV-1992 10:34 (interactive), 20-NOV-1992 10:44 (noninteractive) interactive)

Maxjobs: 0 Fillm: 300 Bytlm: 64000

Maxacctjobs: 0 Shrfillm: 0 Pbytlm: 0

Maxdetach: 0 BIOlm: 300 JTquota: 4096

Prclm: 14 DIOlm: 900 WSdef: 2048

Prio: 4 ASTlm: 600 WSquo: 4096

Queprio: 0 TQElm: 10 WSextent: 16384

CPU: (none) Enqlm: 4096 Pgflquo: 100000 Authorized Privileges: CMKRNL TMPMBX OPER NETMBX Default Privileges: CMKRNL TMPMBX OPER NETMBX

Figure 247: Example of OpenVMS TASKMAN Queue

ABC999\$ SH QUE/FULL TM\$ABC999

Batch queue TM\$ABC999, available, on ABC999:

/BASE_PRIORITY=4 /JOB_LIMIT=50 /OWNER=[DEV,TASKMAN]

/PROTECTION=(S:E,O:D,G:R,W:W)

ABC999\$

22 TaskMan: System Management—Operation

This chapter describes how to operate TaskMan. This chapter discusses the following:

- TaskMan Management Menu
- Taskman Management Utilities
- Scheduling Options
- Taskman Error Log Menu
- Troubleshooting

22.1 TaskMan Management Menu

The Taskman Management menu [XUTM MGR] is the main point of entry into the TaskMan options. It contains the following options:

- Schedule/Unschedule Options
- One-time Option Queue
- Taskman Management Utilities ...
- List Tasks
- Dequeue Tasks
- Requeue Tasks
- Delete Tasks
- Print Options that are Scheduled to run
- Cleanup Task List
- Print Options Recommended for Queueing

The TaskMan Management Utilities submenu and the scheduling-related options are discussed later in this chapter. The options for listing, dequeuing, requeuing, deleting, and cleaning up tasks are discussed first.

22.1.1 List Tasks Option

Figure 248: List Tasks Option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
List Tasks [XUTM INQ]
```

Beginning with Kernel 8.0, the TASKS file (#14.4) (in ^%ZTSK) is VA FileMan compatible (i.e., you can use VA FileMan to print out information about a task). However, the List Tasks option [XUTM INQ] also provides a way to examine tasks in the TASKS file (#14.4). The List Tasks option allows you to choose between several useful ways of selecting tasks. When you choose this option, it presents you with the following menu:

Figure 249: List Tasks option submenu options

```
List Tasks Option

All your tasks.
Your future tasks.
Every task.
List of tasks.
Unsuccessful tasks.
Future tasks.
Tasks waiting for a device.
Running tasks.
Select Type Of Listing:
```

Several choices only appear on the list when there are tasks in those collections to be displayed. Remember, the TASKS file (#14.4) can be Volume Set/CPU-specific. This means that the option can only display tasks from the TASKS file (#14.4) on the current Volume Set/CPU.

Holders of the ZTMQ security key see a slightly different list of selections. Instead of "All your tasks" and "Your future tasks" they see "All of one user's tasks" and "One user's future tasks." These two selections are generic versions of those available to normal users. They allow the holder to see any user's tasks and start by prompting the holder for the user whose tasks should be shown. Other than that, they are identical to the selections used by normal users.

Although each submenu option choice shows a different set of tasks, the format for the output is the same. Here is a sample display from the All your tasks suboption:

Figure 250: All your tasks sub option—Sample of TaskMan tasks running

```
All tasks that you created...

2572: ALIVE^XINDEX, XINDEX of 1 routine. Device QMS-17P. VAH,KXX.

From TODAY at 10:55, By you. Scheduled for TODAY at 12:05

End of listing. Press RETURN to continue:
```

In the upper left-hand corner of each entry is the task number. What follows the task number is either an option name (e.g., XUTM QCLEAN) or a routine entry point (e.g., ERROR^ZTMZT) depending on whether the task was a queued routine or a queued option. This is generally followed by a description of the task. The device to which the task was queued (if any), along with the account in which the task was/is scheduled to run, complete the first line. The next line contains the time the task was created followed by an identification of the creator. In the case of tasks that requeue themselves, this date and time represents when the task was last requeued.

When the creator's DUZ number is not listed in the NEW PERSON file (#200), the phrase "USER #" followed by the DUZ is substituted. Finally, the status of the task is shown.



REF: For a list and description of the status messages, see the "Troubleshooting" section.

Each of these submenu options are described in the topics that follow.

22.1.1.1 All your tasks Option

The All your tasks option (see <u>Figure 250</u>) displays every task in the TASKS file (#14.4) on the current Volume Set/CPU that you created. If you have no tasks scheduled, the option gives you the message "You have no tasks in this Volume Set's TASKS file."

22.1.1.2 Your future tasks Option

The Your future tasks option displays those tasks you created that are currently scheduled to run. If there are none, the option tells you.

"Every task" lists every task in the TASKS file (#14.4).

22.1.1.3 List of tasks Option

The List of tasks option allows you to list one or more tasks by task number. You can specify individual tasks separated by commas along with ranges of tasks using a hyphen.

22.1.1.4 Unsuccessful tasks Option

The Unsuccessful tasks option lists three kinds of tasks:

- Rejected by the Manager's validation process.
- Encountered an error while they were running.
- Unscheduled through the Dequeue Tasks option.

22.1.1.5 Future tasks Option

The Future tasks option shows all tasks that are in the Schedule List or the Waiting List. It does not show the tasks that are in the Job List. In other words, it shows all tasks that are scheduled to run but not those that are currently being run or those that are ready to be run. "Future Tasks" is not offered by the List Tasks option if the Schedule List and Waiting List are empty (an unlikely occurrence at most sites).

22.1.1.6 Tasks waiting for a device Option

The Tasks waiting for a device option shows just the Waiting List, which can be a useful way of isolating problem printers. If there are no tasks currently waiting for output devices to become available, the List Tasks option does *not* show this choice.

22.1.1.7 Running tasks Option

The Running tasks option shows tasks that are currently running.



REF: For a discussion of how TaskMan knows a task is running, see the "<u>Troubleshooting</u>" section.

22.1.2 Dequeue Tasks Option

Figure 251: Dequeue Tasks option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Dequeue Tasks [XUTM DQ]
```

The Dequeue Tasks option [XUTM DQ] allows you to unschedule a task so that the task still exists in the TASKS file (#14.4) but is no longer in the Schedule, Waiting, or Job List. The process of unscheduling a task is called "dequeuing". This option allows you to dequeue any one task or range of tasks. A task that you dequeue has a status of NOT QUEUED in a List Tasks display.

The option first prompts you for the task number. Entering one question mark ("?") gets you a short explanatory message, but entering two question marks ("??") puts you in the List Tasks option to find the task you are interested in dequeuing. When you leave the List Tasks option, you automatically return to the task number prompt.

If you enter the number of a nonexistent task, List Tasks tells you and then prompts you for another task number. If you enter the number of a task that does exist, the option displays the task and asks you if you are sure. Answering **NO** returns you to the task number prompt, whereas a **YES** dequeues the task and then returns you to the task number prompt.

You can also enter a list of tasks to be dequeued. The list can include single tasks separated by commas and ranges of tasks consisting of two numbers separated by a hyphen. After you enter the list, you are asked if you want to know the actual number of tasks in the list. You are then asked if you want a display of the actual tasks that are about to be dequeued.

Only holders of the ZTMQ security key can dequeue any task. Others can only dequeue their own tasks as identified by their DUZ.

22.1.3 Requeue Tasks Option

Figure 252: Requeue Tasks option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Requeue Tasks [XUTM REQ]
```

A benefit of the Dequeue Tasks option is that it is completely non-destructive. If you dequeue a task and subsequently change your mind, you can use the Requeue Tasks option [XUTM REQ] to requeue the task exactly the way that it was. You can also use this option to change some of the details of a task that is already queued.

As with XUTM DQ, you are first prompted for a Task Number with the same help available. Here, you can only enter a single task, *not* a range. The task is then displayed, and you are asked for a new run time with the default being either the original or current run time (whichever applies). The next question is "Do you wish to requeue this task to a device?", with the default depending on whether the task originally requested an output device. If you answer **YES**, the option asks you to specify an output device using the original output device (if there was one) as a default. The option also allows you to adjust the task's priority.

The task is requeued according to your specifications. Requeuing involves completely dequeuing the task so that your task does *not* run twice, making the changes you requested, and placing the task back on the Schedule List. Notice that the task is not dequeued until after you specify the changes you want to make. If you want to modify a task that may start running soon, it is usually a good idea to dequeue it first.

The ZTMQ security key affects this option in two ways

- Users who do not hold the security key are limited to requeuing only their own tasks.
- Users are not prompted to change the priority.

22.1.4 Delete Tasks Option

Figure 253: Delete Tasks option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Delete Tasks [XUTM DEL]
```

The Delete Tasks option [XUTM DEL] has the same structure as the Dequeue Tasks option. The only difference is that where dequeuing a task just removes it from the lists (unschedules it); the Delete Tasks option also deletes the task from the TASKS file (#14.4). When you have deleted a task, there is no reference to that task anywhere in TaskMan's files.

Only holders of the ZTMQ security key can delete any task. Others can only delete their own tasks as identified by their DUZ.

22.1.5 Cleanup Task List Option

Figure 254: Cleanup Task List option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Cleanup Task List [XUTM TL CLEAN]
```

You can use the Cleanup Task List option [XUTM TL CLEAN] to remove a task entry from a task list for a job that is no longer running. This might happen when a process is forcibly exited, but TaskMan still believes the task is running. You can use this option to tell TaskMan which tasks you forcibly exited. TaskMan then removes those tasks from its list of running tasks.

22.2 Taskman Management Utilities

A submenu on the Taskman Management menu, called TaskMan Management Utilities menu [XUTM UTIL], provides several options to set up, monitor, and modify the TaskMan environment.

The Taskman Management Utilities menu contains the following options:

- Monitor Taskman
- Check Taskman's Environment
- Edit Taskman Parameters ...
- Restart Task Manager
- Place Taskman in a WAIT State
- Remove Taskman from WAIT State
- Stop Task Manager
- Taskman Error Log ...
- Clean Task File
- SYNC flag file control

These options are discussed in the topics that follow.

22.2.1 Monitor Taskman Option

Figure 255: Monitor Taskman option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Monitor Taskman [XUTM ZTMON]
```

The Monitor Taskman option [XUTM ZTMON] gives you a screen of information about the current state of TaskMan and offers you several ways to get more information. The monitor focuses on the current state of the Manager itself and on the contents of the SCHEDULE file.

As you use this option, you acquire an intuitive understanding of how these lists should look and behave when your system is healthy. Spending the time using this option to get that intuition saves you troubleshooting time by helping you to notice problems sooner.

22.2.1.1 RUN Node

The first section of the Monitor TaskMan screen reports whether the Manager is currently running on your machine, and if so, whether or not it is being delayed. This is accomplished by comparing TaskMan's RUN Node to the M \$HOROLOG variable. Under normal circumstances they should be within 15 seconds of each other, though certain conditions can cause a difference of up to two minutes. Any difference greater than that, however, is a sign that the Manager is being delayed, typically by a problematic device or a recurring error. Of course, the Manager is also likely to fall behind if the system is saturated to the point where all of the jobs on the system are slow. The last line of the first section evaluates the difference and guesses at the Manager's current condition. The \$HOROLOG values are translated into an external format for your convenience in understanding the values.

Figure 256: Sample Monitor TaskMan screen

```
Checking TaskMan. Current $H=54180,45147 (MAY 04, 1989 @12:32:27)
                    RUN NODE=54180,45145 (MAY 04, 1989 @12:32:25)
 TaskMan is current.
  Checking the Status List:
      TaskMan job 4 status 54180,45145^RUN^Main Loop.
      There are 3 idle submanagers
  Checking the Schedule List:
      TaskMan has 29 tasks in the Schedule List.
      None of them are overdue.
  Checking the IO Lists: Last TM scan: 54180,45146^_TNA9995:
  Device: _TNA9995: is not available, and there are 7 tasks waiting.
  Checking the Job List:
      There are no tasks waiting for partitions.
       For KDE: ISC6V2 there are 2 tasks. Not responding
  Checking the Task List:
      There are 5 tasks currently running.
  Enter monitor action: UPDATE//
```

22.2.1.2 Status List

The Status List is where each Manager periodically reports its current status. The job number of the Manager is reported both for ease of location on a system status report and also to distinguish between multiple Managers (if there are more than one). Under normal circumstances, the Manager removes its entry from the Status List when it shuts down, but if a Manager stops abnormally (e.g., RJD or FORCEX) its entry is usually left on the list. The list is updated and cleaned out whenever a new Manager is started or restarted.

The status of a Manager consists of three parts:

- Date and time—This date and time should equal the RUN node's date and time, and like that node, it should be close to the current \$HOROLOG.
- Manager's state.
- Description of special circumstances.

The Manager can be in one of five states at any given time:

- BALANCE
- ERROR
- PAUSE
- RUN
- WAIT

RUN is the normal state, with a description of "Main Loop."

The Manager's status is the most important piece of information the monitor gives, and it should always be the first thing checked when troubleshooting problems.



REF: For a detailed list and description of the possible state messages, see the "<u>Troubleshooting</u>" section.

22.2.1.3 Schedule List

The Schedule List always shows the number of tasks currently scheduled to run and checks the times for which they are scheduled to determine whether any of them should already have started. When many tasks are queued to run at the same time, it is not unusual for the Manager to be a little late in sending off the last few.

When most of the tasks on the Schedule List are overdue, however, the Manager is probably having problems keeping up. This is *not* a normal condition. If the problem is not a recurring error or a difficult output device, the most likely culprit is your default setup in the TASKMAN SITE PARAMETERS file (#14.7). Another possible problem is that TaskMan is trapping many errors or trying to access a very slow link between Volume Sets. If the problem is error trapping, the Status List should regularly show the Manager in an Error state. Also, remember that if the machine is saturated, all of the jobs on the system, including the Manager, runs slowly.

22.2.1.4 IO List

The IO List first shows the last time (\$H) a Submanager checked the list and the last device checked. The check generally shows how many tasks are waiting for each device in the IO List. The occasional remark "Allocated" means that a Submanager has already noticed that the device is available and has allocated the device to a task using the Device Allocation List. Devices should only be allocated for a short time before the Submanager opens the device, making it unavailable.

Understanding how the IO List works can make this particular check very useful. Submanagers handle the Device IO Lists. Unusual behavior in these lists usually points to device or Submanager problems.

There are three fundamental things to look for with this check:

- When a device becomes available—The Submanagers should notice and start a task running on that device. If the Submanagers do not do this, it is probably time to start looking for problems with the Submanagers.
- When a device is allocated—A Submanager should quickly make it unavailable. If this fails to occur, the Submanagers may be having problems. There can be extenuating circumstances (e.g., the system being very slow) that explain these occurrences.
- When many tasks are backed up waiting for the same device—Sometimes it is just because that device is busy. However, sometimes the device is off-line or out of paper.

22.2.1.5 Job List

The Job List is where tasks wait for partitions, so if many tasks are backed up here you know the Submanagers are not picking them up. This can be caused by any of the following:

- A slow system.
- TaskMan reaching its job limit.
- TaskMan assigning tasks a priority that is too low for them to run.

Systems that are too busy backs up in this list, *not* the Schedule List. The Compute Server Job List is checked here and lets you know about tasks waiting to run on other CPUs and if the Submanagers are not starting.

22.2.1.6 Task List

The Task List is where TaskMan keeps track of the tasks it has started running. Entries are set into this list when the Submanagers start their tasks and are cleared when the tasks quit or cause errors to be trapped. KILLing a task by forcing its process to exit in the middle of execution (using such vendor-specific tools as RJD, RESJOB, FORCEX, KILLJOB, etc.) does not give the Submanager a chance to clear the task from the Task list, so the Task List can become inaccurate. If you frequently KILL jobs but want to keep your Task List accurate, you need to manually remove the obsolete entries. The exit action of the KILL off a users' job option [XURESJOB] helps you identify and remove from the list of running tasks those you have forcibly exited.

22.2.1.7 Monitor Action Prompt

After summarizing the status of the Manager and the principal lists of the SCHEDULE file, the monitor offers you a choice of actions. They are displayed if you enter a single question mark ("?") at the "Enter monitor action:" prompt:

Figure 257: TaskMan monitor actions

```
Enter <RET> to update the monitor screen.
Enter ^ to exit the monitor.
Enter E to inspect the TaskMan Error File.
Enter S to see a system status listing.
Enter ? to see this message.
Enter ?? to inspect the tasks in the monitor's lists.
```

These actions (see Figure 257) attempt to bring together those utilities used most often in response to seeing a monitor screen. Updating is the most commonly used choice since you often want to watch how the lists change over time. The TASKMAN ERROR file needs to be easily accessible, not only in case the Manager enters an Error state, but also if a task that should take a long time to run leaves the Job List but never shows up in the Task List. This usually means the task hit an error and quit, which can be confirmed or disproved by a quick glance at the TaskMan Error Log. The System Status Report can be used to verify that tasks, Submanagers, and the Manager are indeed running as the monitor suggests.

Some actions at the Monitor Action prompt are not accessible when monitoring TaskMan from the manager's account (using the direct-mode utility D ^ZTMON).

22.2.1.8 Inspecting the Tasks in the Monitor's Lists

If you are in a non-library account, you can directly inspect the contents of the various lists. Do this by entering two question marks ("??") at the "Enter monitor action:" prompt. You get the following list of choices:

Figure 258: Options for inspecting tasks in the TaskMan Monitor's Lists

```
Help For Monitor Taskman Option

Schedule List.
Waiting Lists.
One Waiting List.
Job List.
Task List.
Link Lists.

Select Type Of Listing:
```

These listings use the same format as that of the List Tasks option, and show you the contents of the lists at the time you look at them. The One Waiting List listing prompts you to select a device, and the help for that prompt lets you see those devices that have tasks waiting. Many of these lists change very quickly. Thus, it is not unusual to enter the help with the intention of seeing the task that was shown by the main screen to be in the Job List, only to be informed by the help software that the Job List is now empty. These kinds of experiences are simply part of troubleshooting TaskMan.

While these monitor actions are useful, there are still times when you *must* leave the monitor to follow up on information you saw there. For example, you may want to check the list of unsuccessful tasks or to list a specific task; both these actions require using the List Tasks option.

Taken as a whole, the checks that make up the monitor can save you a lot of time in trying to evaluate TaskMan's status. The example shown in <u>Figure 256</u> is of a healthy, and not very busy, Manager. Monitors at sites usually show considerably more activity, especially in the Waiting Lists.

22.2.2 Check Taskman's Environment Option

Figure 259: Check Taskman's Environment option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Check Taskman's Environment [XUTM CHECK ENV]
```

The Check Taskman's Environment option [XUTM CHECK ENV] presents two screens of information about TaskMan's environment on the current CPU. The first screen (see <u>Figure 260</u>) performs all of the checks that the Manager does whenever it starts, restarts, or encounters an error. The second screen (see <u>Figure 261</u>) shows what values the Manager is using for its definition variables. This information can be very useful in pinpointing startup problems, in verifying that the Manager is using the information you want it to use and in getting a general feel for how you have defined your system's task management.

Figure 260: Check TaskMan's Environment option—First screen

This first screen (see <u>Figure 260</u>) goes through each step that the Manager goes through when it starts or restarts and reports the results. If your Manager is failing to start, this screen should identify any problem with the environment.

Figure 261: Check TaskMan's Environment option—Second screen

```
Here is the information that TaskMan has:
Operating System: OpenM-NT
Volume Set: ROU
Cpu-volume Pair: ROU:KDAABC999
TaskMan Files UCI and Volume Set: VAH,ROU
```

This group identifies the current TaskMan operating environment.

```
Log Tasks? N
Submanager Retention Time: 30
Min Submanager Count: 10
Taskman Hang Between New Jobs: 1
TaskMan running as a type: GENERAL
TaskMan is using VAX DSM environment: ABC999
TaskMan is using '$$CACHE@() for load balancing
Balance Interval: 10
```

This group reports the values of some Kernel site parameters that are important to TaskMan.

```
Logons Inhibited?: N
Taskman Job Limit: 35
Max sign-ons: 40
Current number of active jobs: 25
```

This group shows if logons are being inhibited and how many partitions are available.

End of listing. Press RETURN to continue:

The second screen (see <u>Figure 261</u>) reports more information about the current TaskMan environment. The first group of four items identifies the current TaskMan operating environment. The next group of items reports the values of some Kernel site parameters that are important to TaskMan.



REF: These parameters, as well as all the other parameters that TaskMan uses, are described in detail in the "<u>TASKMAN SITE PARAMETERS File (#14.7)</u>" section in "<u>TaskMan: System Management—Configuration.</u>"

The last four items show if logons are being inhibited and how many partitions TaskMan currently has to work with. These values show how busy your system is, as well as how busy it can become. Their importance is also described in the discussion of parameters.

22.2.3 Restart Task Manager Option

Figure 262: Restart Task Manager option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Restart Task Manager [XUTM RESTART]
```

The Manager generally starts automatically when your system comes up. If the Manager crashes or is stopped, you can use the Restart Task Manager option [XUTM RESTART] to restart it. The option first checks the RUN node and calculates whether it thinks the Manager is currently running. If this option believes the Manager is running, it asks you if you are sure you want to restart another TaskMan; you *must* answer **YES** to start the Manager. If XUTM RESTART thinks the Manager has stopped, it asks you for confirmation before jobbing out a new Manager. If XUTM RESTART believes the Manager to be active when you know for sure that it has failed, you can invoke XUTM STOP to prove to XUTM RESTART that the Manager really has stopped. Then you are able to restart it.

22.2.4 Place Taskman in a WAIT State Option

Figure 263: Place Taskman in a WAIT State option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Place Taskman in a WAIT State [XUTM WAIT]
```

The WAIT state (as described in the "Troubleshooting" section) is a condition in which the Manager does nothing but wait for you to release it. Putting a stop to the Manager's activities without actually shutting down the Manager can often be very useful. For example, with the Manager in a WAIT state, you can look at the tasks after they are queued but before the Manager has a chance to validate them. This can help you isolate problems caused by the queuing process from those caused by the validation process. Another time you may want to create a WAIT state is before restarting a manager that has stopped. This prevents the Manager from processing any tasks when it first starts up; the Manager checks out its environment and then WAIT for your command to continue. The Place Taskman in a WAIT State option [XUTM WAIT] gives you a way to switch the Manager's activities on and off without having to completely shut down and restart the Manager.

When you select the XUTM WAIT option, you are also prompted with the question "Should active submanagers shut down after finishing their current tasks?". If you answer **YES**, the Submanagers on the current Volume Set/CPU quits when they finish a task instead of recycling. If you answer **NO**, the Manager enters a WAIT state and the Submanagers continue with their business. If you also want to keep the Submanagers from searching the Waiting List and the Job List for tasks, you need to explicitly say so at this prompt. This inhibition of the Submanagers' recycling remains in effect either until you remove the WAIT state or until a new Manager starts or restarts, whichever comes first.

22.2.5 Remove Taskman from WAIT State Option

Figure 264: Remove Taskman from WAIT State option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Remove Taskman from WAIT State [XUTM RUN]
```

The Remove Taskman from WAIT State option [XUTM RUN] simply undoes the effects of XUTM WAIT, allowing the Manager to process tasks and allowing the Submanagers to recycle (if recycling had been inhibited).

22.2.6 Stop Task Manager Option

Figure 265: Stop Task Manager option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Stop Task Manager [XUTM STOP]
```

The Stop Task Manager option [XUTM STOP] gives you a clean way to stop the Manager from within the menu system. This option also asks if you want the Submanagers to shut down when they finish what they are doing.



NOTE: The WAIT state takes precedence. While the Manager is in a WAIT state, not even XUTM STOP affects it until after you invoke XUTM RUN to release it from the WAIT state; after it is released, it shuts down.

This option should always be used to shut down TaskMan, rather than simply KILLing the TaskMan process, which can leave the TaskMan globals in an improper state and even lose tasks.

22.2.7 SYNC flag file control Option

Figure 266: SYNC flag file control option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
SYNC flag file control [XUTM SYNC]
```

With the SYNC flag file control option [XUTM SYNC], for any SYNC FLAG entry, you can remove it from the file and delete all waiting tasks with the same SYNC FLAG. You can also choose START NEXT, which resumes running the series of tasks associated with that SYNC FLAG. This is useful when one task in a series of tasks that is synchronized with SYNC FLAG fails.

22.2.8 Clean Task File Option

The TASKS file (#14.4) grows every time a new task is queued. While the SAC requires applications to delete their tasks' entries when they complete, it is possible that older applications may not do this. Other tasks abort with errors; still others are rejected. The result is that ^%ZTSK is always growing. Options are available that clean up the ^%ZTSK global.

Figure 267: Clean Task File option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Clean Task File [XUTM CLEAN]
```

In unusual circumstances, you may need to clean the ^%ZTSK global manually. Kernel provides the called Queuable Task Log Clean Up option to regularly clean up the TASKS file (#14.4) in the background.

Only rarely are you *not* able to rely on the queued cleanup to perform this function. However, when necessary, you can use the interactive Clean Task File option [XUTM CLEAN]. First, XUTM CLEAN asks you if you are sure you want to clean out the old entries from the TASKS file (#14.4). If you respond that you are, the option asks you how far back you want to keep old entries. The default is to keep old entries going back a week and to delete the older ones. After you provide this value, the option queues a task to do the cleanup. XUTM CLEAN *cannot* be queued.

22.2.9 Queuable Task Log Clean Up Option

The Queuable Task Log Clean Up option [XUTM QCLEAN], resides on the ZTMQUEUABLE OPTIONS menu. This option allows you to purge all of the entries for tasks that are no longer queued (for whatever reason) and to purge the TaskMan Error Log. It is very useful to be able to queue the cleanup to run automatically each night; XUTM QCLEAN has been distributed to provide this feature. XUTM QCLEAN should not be run interactively; indeed, it is not available from any of TaskMan's menus. To queue this option, use Schedule/Unschedule Options to queue it to run.

The date XUTM QCLEAN starts purging the TASKS file (#14.4) is controlled by the DAYS TO KEEP OLD TASKS parameter in the VOLUME SET file (#14.5). A value of seven days is recommended. XUTM QCLEAN does not need an output device; therefore, you can leave that field blank. Once set up, the task automatically runs periodically, cleaning out inactive task entries that are older than the time period specified in the DAYS TO KEEP OLD TASKS parameter. If you want to run this on all of your machines, create an entry in the OPTION SCHEDULING file (#19.2) for each machine on which you want to run it.

22.3 Scheduling Options

TaskMan lets you, the site manager, schedule options that run regularly as tasks. Menu Manager and TaskMan work together to give you this ability. All you have to do is tell TaskMan which option you want to queue and how you want to queue it.

22.3.1 Which Options to Queue

The first requirement for queuing regards the option type. Only the run, print, and action types of options can be queued. The second requirement is that the option (if a run or action type) *must* not involve user input! There is nothing to prevent you from queuing an option of the wrong type or from queuing one that prompts the user for input, but doing so results in a failed task. You *must* be conscious of the nature of the task when you consider creating one that performs an option. If the option itself does *not* run in the background, then queuing it is pointless. Even options that themselves queue tasks probably cannot be queued, because most of these ask the user for an output device or a run time.

Software applications can make recommendations for scheduling of options. This is a great help to site managers.



REF: Recommendations for scheduling Kernel options can be found in the *Kernel Installation Guide* and the *Kernel Technical Manual*.

22.3.1.1 PARENT OF QUEUABLE OPTIONS Menu

Some options that are intended to be queued are not intended to be run interactively, so placing such options on a user menu could cause problems. The PARENT OF QUEUABLE OPTIONS menu [ZTMQUEUABLE OPTIONS], a menu-type option, has no parent in the menu tree and is intended to be used as the parent of all such options.

22.3.1.2 Printing Options Recommended to Run and Scheduled to Run

Figure 268: Print Options Recommended for Queueing and Print Options that are Scheduled to run options

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Print Options Recommended for Queueing [XUTM BACKGROUND RECOMMENDED]
Print Options that are Scheduled to run [XUTM BACKGROUND PRINT]
```

The Print Options Recommended for Queueing option [XUTM BACKGROUND RECOMMENDED] displays all options in the OPTION SCHEDULING file (#19.2) that are recommended for scheduling by the option's developer.

The Print Options that are Scheduled to run option [XUTM BACKGROUND PRINT] lists all currently scheduled options on your system. By comparing these two reports, you can see if any options recommended for scheduling are not scheduled on your system (and vice-versa).

22.3.1.3 Schedule/Unschedule Options

Figure 269: Schedule/Unschedule Options option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Schedule/Unschedule Options [XUTM SCHEDULE]
```

The Schedule/Unschedule Options option [XUTM SCHEDULE] is a straightforward VA ScreenMan edit option, and allows you to schedule and unschedule options. After you select the option to schedule, you are prompted for information about the task you want to set up. You can edit the following fields in the OPTION SCHEDULING file (#19.2):

- QUEUED TO RUN AT WHAT TIME (#2) (see Section 22.3.1.4)
- DEVICE FOR QUEUED JOB OUTPUT (#3) (see Section <u>22.3.1.7</u>)
- QUEUED TO RUN ON VOLUME SET (#5) (see Section 22.3.1.8)
- RESCHEDULE FREQUENCY (#6) (see Section 22.3.1.9)
- SPECIAL QUEUEING (#9) (see Section 22.3.1.11)
- TASK PARAMETERS (#15) (see Section 22.3.1.10)

The cross-references on these fields make calls to TaskMan's API to update the TASKS file (#14.4) and ^%ZTSCH.



NOTE: In order to queue a task, its SCHEDULING RECOMMENDED field (#209) in the OPTION file (#19) *must* be set to **YES**.

22.3.1.4 Queued to Run At What Time

To queue an option, select the option and enter a time at least two minutes in the future into the QUEUED TO RUN AT WHAT TIME field (#2) in the OPTION SCHEDULING file (#19.2). When you enter a time (and date) for the task to run, the task is immediately put on the Schedule List for that time.

22.3.1.5 How to Delete a Regularly Scheduled Task

Deleting a scheduled task is as simple as entering the at-sign ("@") at the QUEUED TO RUN AT WHAT TIME field (#2). TaskMan then searches the current TASKS file (#14.4) for the task that corresponds to the entry in the OPTION SCHEDULING file (#19.2) and deletes it.

If your system has multiple copies of the TaskMan globals, you *must* use Schedule/Unschedule Options on the same Volume Set/CPU where your task originated, when you delete the task. Otherwise, the future task in the TASKS file (#14.4) is *not* found (and deleted) when you enter an at-sign ("@") in the QUEUED TO RUN AT WHAT TIME field (#2).

22.3.1.6 How to Requeue a Regularly Scheduled Task

Requeuing merely involves placing a new value in the QUEUED TO RUN AT WHAT TIME field (#2). When you do this, the currently scheduled task is deleted (exactly as described above when deleting a scheduled task). Then, a new task is created at the new time to replace the previously scheduled task.

If your system has multiple copies of the TaskMan globals, you *must* use Schedule/Unschedule Options on the same Volume Set/CPU where your task originated, when you requeue the a task. Otherwise, the

existing future task in the TASKS file (#14.4) is *not* found (and deleted) when you enter a new time in the QUEUED TO RUN AT WHAT TIME field (#2).

22.3.1.7 Device For Queued Job Output

The DEVICE FOR QUEUED JOB OUTPUT field (#3) in the OPTION SCHEDULING file (#19.2) is where you can give the task an output device. For print (Report) type options this is obviously mandatory; for run or action types you need to consider if the option needs an output device. Modifying this value for an already-scheduled task merely causes a direct change to the currently scheduled task.

Tasks with an output device are assigned a process name of "Task ####" where "####" is the task number; tasks with no output device are assigned a process name of "BTask ####" (with B meaning background).

22.3.1.8 Queued To Run On Volume Set

Use the QUEUED TO RUN ON VOLUME SET field (#5) in the OPTION SCHEDULING file (#19.2) to designate a Volume Set or CPU for the task other than your current one. This field is only useful for options that do not have a device selected because most devices are tied to a CPU, and thus, the task *must* run on the CPU that has that device.

Modifying this value for an already-scheduled task merely causes a direct change to the currently scheduled task.

Running a task on each CPU for a given option may at times be useful (e.g., XQBUILDTREEQUE option). In such cases, make multiple entries in the OPTION SCHEDULING file (#19.2), and use the QUEUED TO RUN ON VOLUME SET field (#5) to specify the Volume Set/CPU where each scheduled task should run.

If you leave the DEVICE FOR QUEUED JOB OUTPUT field (#3) blank, the task that performs the option runs without a device (or tries to). If you also leave the QUEUED TO RUN ON VOLUME SET field (#5) blank, the task runs on the current CPU without a device. If you fill in both fields, TaskMan uses the value of the QUEUED TO RUN ON VOLUME SET field (#5), unless overridden by the VOLUME SET(CPU) field (#1.9) in the DEVICE file (#3.5) entry of the selected device.

22.3.1.9 Reschedule Frequency

Whenever a task starts running an option, it looks to see what is in the RESCHEDULE FREQUENCY field (#6) in the OPTION SCHEDULING file (#19.2). If the field is blank, the option does not reschedule itself. If you have filled in this field, the task uses the value you placed in the field to figure out when you want it to run next. Then it updates the QUEUED TO RUN AT WHAT TIME field (#2) to reflect the new scheduled time. When this field is updated, the next task in the sequence is scheduled.

If you change the existing value in the RESCHEDULE FREQUENCY field (#6), the new increment is used beginning after the next time the option runs.

There are several formats you can use in this field:

- Every "n" seconds.
- Hours.
- Days.
- Months (incremental).
- A particular day of the month.
- A list of times every "**n**" months.



REF: For a list of the code formats for the RESCHEDULE FREQUENCY field (#6), see the "Special Queueing" section.

For the incremental scheduling frequencies (every n seconds, hours, days, or months), the increment is added to the scheduled date and time in the QUEUED TO RUN AT WHAT TIME field (#2) to determine when the task should run next. As of Kernel 8.0, if the incremented time is in the past, however, TaskMan keeps adding the increment until a future time is reached, only then does it reschedule the task.

22.3.1.10 Task Parameters

Use the TASK PARAMETERS field (#15) in the OPTION SCHEDULING file (#19.2) to pass data to a scheduled option. TASK PARAMETERS holds a string that is passed to scheduled jobs through the ZTQPARAM variable. Ideally, the developer of an option that uses the TASK PARAMETERS string should describe the format and meaning of the string in the option's DESCRIPTION field.

22.3.1.11 Special Queueing

Use the SPECIAL QUEUEING field (#9) in the OPTION SCHEDULING file (#19.2) to designate which option is scheduled to be run by TaskMan.



NOTE: In order to queue a task, its SCHEDULING RECOMMENDED field (#209) in the OPTION file (#19) *must* be set to **YES**.

Valid values are:

Table 40: Special Queueing field settings

Value	Option Description
S	STARTUP—TaskMan queues the job to run whenever the TaskMan/computer is started (i.e., at System Boot). If you want to the run the startup option on multiple CPUs, make multiple entries in the OPTION SCHEDULING file (#19.2), and use the QUEUED TO RUN ON VOLUME SET field (#5) to specify on what Volume Set/CPU each should run.
SP	STARTUP/PERSISTENT —TaskMan queues the job as it does for "STARTUP. It marks it as a "PERSISTENT" task to be restarted if it stops unexpectedly.
Р	PERSISTENT —TaskMan runs it on its normal schedule, marking it as Persistent. TaskMan restarts the task if it stops unexpectedly.
	If the task completes in a normal fashion it is treated like any other regularly scheduled task and it is rescheduled based on the value in the RESCHEDULING FREQUENCY field (#6) in the OPTION SCHEDULING file (#19.2).

Table 41: Option Scheduling frequency code formats

Code	Frequency	
nS	Every <i>n</i> seconds.	
nH	Every <i>n</i> hours.	
nD	Every <i>n</i> days.	
nM	Every <i>n</i> months.	
day[@time]	Day of week (for Day	codes, see <u>Table 42</u>).
D[@time]	Every weekday.	
E[@time]	Every weekend day	(Sat,Sun).
nM(entry[,entry[,]])		ach entry in the parameter list; the entries in the ery <i>n</i> months only) can be:
	Entry Format	Frequency
	dd[@time]	Day of month (e.g., 15).
	n <u>day</u> [@time]	Nth day of week in month (e.g., 1W,3W).
	L[@time]	Last day of month.
	L <u>day</u> [@time]	Last specific DAY in month, (e.g., LM,LT,LW).

Table 42: Day codes used in Option Scheduling frequency code formats

Day Code	Description
M	Monday
Т	Tuesday
W	Wednesday
R	Thursday
F	Friday
S	Saturday
U	Sunday

Table 43: Examples of Option Scheduling frequency code formats

Code	Frequency
12H	Every 12 hours.
14D	Every 14 days.
1M(1,15)	First and 15th of the month.
1M(L@23:45)	Last day of the month at 11:45 pm.
1M(LS)	The last Saturday of the month.
3M(15@12:00,L@12:00)	Noon (on the 15th and last days), every 3 months.
W@4pm	Each Wednesday at 4 pm.
D	Each weekday.

22.3.1.12 Problems With Scheduled Options

Once an option has been put on a schedule, it stays on that schedule unless one of the following happens:

- You delete the task.
- The running task aborts while setting up the next task in the sequence; the schedule sequence is broken.
- You dequeue the task that is scheduled to run the option. You *must* either requeue the task or use the Schedule/Unschedule Options option to start the cycle over.
- You change the value in the RESCHEDULING FREQUENCY field (#6) in the OPTION SCHEDULING file (#19.2). The new increment is used beginning after the next time the option runs.
- You change the value in the QUEUED TO RUN AT WHAT TIME (#2). The currently scheduled task is unscheduled and a new one is scheduled for the time you specify.

Another peculiarity in this process involves using a monthly scheduling frequency. What should happen if on January 31st you queue an option and give it a monthly scheduling frequency? Other months lack a 31st day. In this situation, the task pretends there is a 31st day in every month. To avoid this, you can use the RESCHEDULING FREQUENCY field (#6) in the OPTION SCHEDULING file (#19.2) code 1M(L@time).

22.3.1.13 One-time Option Queue Option

Figure 270: One-time Option Queue option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
One-time Option Queue [XU OPTION QUEUE]
```

To run the One-time Option Queue option [XU OPTION QUEUE] at a special time one day without affecting its established schedule, use the One-time Option Queue option. It queues a task to run once, without affecting the option's normal schedule in any way. This lets you handle the condition where you have an option queued to run periodically and you would like to queue it once to run at an irregular time without affecting its normal periodic schedule.

22.4 Taskman Error Log Menu

The Manager and Submanagers keep track of all errors caused by their own software or by the tasks they start. They log their own errors in two places:

- ERROR LOG file (#3.075)
- TaskMan Error Log

Those errors caused by tasks are also recorded in the entries of the tasks themselves and can be seen with any of the various task listing options (List Tasks, TaskMan User, etc.). Just as there are options to display and purge the ERROR LOG file (#3.075), there are options to do the same for the TaskMan Error Log.

When the XUTM QCLEAN option cleans tasks from the TASKS file (#14.4), it also cleans any corresponding entries in the TaskMan Error Log since it is hard to make sense of an error log entry without the task data.

Kernel strongly recommends that you report new errors to your OIFOs and follow up to ensure expeditious patching. If you do this, over time the number of errors occurring on your system diminishes. This also improves the value of the various error logging systems as indicators of significant events deserving investigation.

Allocation and store errors are often not logged in Kernel's ERROR LOG file (#3.075) because the process of logging errors is complicated and usually requires the use of local variables. Local variables take up space and there is no excess space when these errors occur. However, TaskMan makes its simple entries in the TaskMan Error Log prior to calling the Kernel error logging utility. Thus, these errors are often recorded in the TaskMan Error Log, but not Kernel's. You are encouraged to carefully monitor both places.

22.4.1 Show Error Log Option

Figure 271: Show Error Log option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Taskman Error Log ... [XUTM ERROR]
Show Error Log [XUTM ERROR]
```

The Show Error Log option [XUTM ERROR SHOW] displays the errors currently stored in the TaskMan Error Log, showing the date and time that the error occurred in a readable format and showing the error message. After the listing, the option gives the number of errors in the error log.

Errors stored in the TaskMan Error Log historically are also cross-referenced to the TASKS file (#14.4), linking tasks to the errors they cause.

22.4.2 Clean Error Log Over Range Of Dates Option

Figure 272: Clean Error Log Over Range Of Dates

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Taskman Error Log ... [XUTM ERROR]
Clean Error Log Over Range Of Dates [XUTM ERROR LOG CLEAN RANGE]
```

After prompting for a "First date to purge:" and a "Final date to purge:", the Clean Error Log Over Range Of Dates option [XUTM ERROR LOG CLEAN RANGE] removes the entries for all errors that occurred on and between the two dates. It prints the number of entries removed. If the first date is not earlier than the final date, no entries are removed.

Use this option to delete all but recent errors that deserve your attention. It is better to resolve specific kinds of errors as you encounter them. However, if there is a period during which you *cannot* resolve them fast enough to keep the log clean, this option helps you focus on the recent ones.

22.4.3 Purge Error Log Of Type Of Error Option

Figure 273: Purge Error Log Of Type Of Error option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Taskman Error Log ... [XUTM ERROR]
Purge Error Log Of Type Of Error [XUTM ERROR PURGE TYPE]
```

With the Purge Error Log Of Type Of Error option [XUTM ERROR PURGE TYPE] you can delete from the TaskMan Error Log all entries for an error of a specific type. In fact, this option uses the M contains operator ("["); therefore, it removes every error whose message contains your input as a substring. For example, you can remove every error that occurred in a certain routine or even every error whose message contains a "Q." After performing the purge, the option shows you how many entries were removed.

This option is the best way to keep the log clean. As you resolve certain kinds of errors and prevent them from happening again, you can remove all errors of that kind from the log. This leaves behind only those errors you have not resolved, helping you focus on the problems that remain.

22.4.4 Delete Error Log Option

Figure 274: Delete Error Log option

```
SYSTEMS MANAGER MENU ... [EVE]
Taskman Management ... [XUTM MGR]
Taskman Management Utilities ... [XUTM UTIL]
Taskman Error Log ... [XUTM ERROR]
Delete Error Log [XUTM ERROR DELETE]
```

The Delete Error Log option [XUTM ERROR DELETE] completely deletes all errors in the TaskMan Error Log. If the error log is cleaned and purged as described above, you rarely need to use this option.

22.5 Troubleshooting

The information given in this section *cannot* be used by application developers in their code. It is provided to help site managers troubleshoot problems with tasks and TaskMan. Consider this section a reference to TaskMan's global structure and messages.

22.5.1 SCHEDULE File

^%ZTSCH holds the non-VA FileMan-compatible SCHEDULE file, which consists of independent lists and nodes. This is where TaskMan processes tasks. This structure is not supported for use by application software. All task manipulation *must* be done through approved options and entry points. These structures *must* be free to change from version to version to easily adapt and meet the changing needs of VistA. On the following pages is an example of a global that contains one of each type of node used by TaskMan:

The initial node was used to create ^%ZTSCH before TaskMan was active, so that the global type and protection could be assigned.

Table 44: ^%ZTSCH (SCHEDULE File) nodes

^%ZTSCH Node	Description
^%ZTSCH(next run time, task #)	This node stores the Schedule List. The task # corresponds to an entry in the TASKS file (#14.4), and the next run time is computed from the value in the sixth ^-piece of the entry's 0 node (and is the total number of seconds contained in the next run time's \$H translation). If the Schedule List entry equals a device name, the entry was not created through the Program Interface.
^%ZTSCH("C")	This node stores the Compute Server Job List (C list). This list holds tasks that are ready to be run by Submanagers on specific Compute Servers. A Submanager cross-Volume Set jobbed to a Compute Server only runs tasks under this list for the Compute Server on which it is running, and does not process the Device Waiting List or the Job List. The Volume Set, next run time, task #, and device \$IO are stored here.
^%ZTSCH("DEV")	This node stores the Device Allocation List. This list is used by TaskMan to coordinate its allocation of devices to tasks. The presence of a node indicates that TaskMan has already allocated this device to a specific task that has not yet gained ownership of it. It tells TaskMan not to give the device to another task. When the task for whom the allocation node was established gains ownership of the device or fails due to possession by some interactive job, the node is KILLed off. The \$H value is used in case the task fails to remove its own node for some reason; after two minutes TaskMan KILLs the node on its next idle loop.
^%ZTSCH("ER")	This node stores the TaskMan Error Log.
^%ZTSCH("ES")	This node stores the Error Screens.
^%ZTSCH("IDLE")	This node is used to ensure that the Manager's idle loop activities are spaced out correctly in case multiple Managers are being run in the same environment.

^%ZTSCH Node	Description
^%ZTSCH("IO")	This node stores the Device Waiting List. The device \$IO value is the value for the task's device and should not be the \$IO of a spool or host file device. The run time subscript (the total number of seconds contained in the run time's \$H translation) prioritizes the tasks that should have started the longest time ago. The Submanagers use the top node to space out access to the list, and the last device so that only one Submanager at a time is checking the list, and so that checks that find all devices still busy are followed by a short waiting period before the list is checked again.
^%ZTSCH("JOB")	This node stores the Job List. This list holds tasks that are ready to be run by Submanagers. The run time is the total number of seconds contained in the run time's \$H translation, and task # and device \$IO are what you would expect.
^%ZTSCH("LINK")	This node stores the Link Lists. The LINK node itself is only present when a link is down. It is used to time the checks that occur every fifteen minutes. The second level nodes should always be present with the current information on each of the CPUs and Volume Sets.
^%ZTSCH("LOAD", load rating)	This node is used to balance the CPU load among the various Managers that work out of the current TASKS and Schedule files. It identifies the CPU that most recently checked its rating and decided to run. Managers more loaded (a lower rating) than this one wait to allow this Manager to pick up more of its share of the load.
^%ZTSCH("LOADA")	This node stores the Load List. This list records the ratings for all the CPUs with Managers processing this TASKS file. The first ^-piece, which flags the Managers that decide to wait to balance the load, is used to tell the Submanagers on those CPUs that they, too, should wait.
^%ZTSCH("LOGRSRC")	This node flags whether Submanagers should log resources for the capacity management software. This node is set for every Volume Set whenever the LOG RESOURCE USAGE? field of the KERNEL SYSTEM PARAMETERS file (#8989.3) is edited. A cross-reference keeps the ^%ZTSCH("LOGRSRC") node in synchronization with the LOG RESOURCE USAGE? field.
^%ZTSCH("NO-OPTION")	if set, this node stops the Submanagers from running any scheduled options. This is for the KIDS install process.
^%ZTSCH("RUN")	This node is where the Manager periodically stamps the current time, leaving a way to determine whether it is currently active. Invoking the XUTM STOP option removes this node (see Figure 275).

periodically updated entries for each Manager active on your machine and reflects each Manager's own perception of its current state. ^%ZTSCH("STOP") This node prevents Submanagers from running. While it is present, Managers do not start new Submanagers, Submanagers waiting for tasks quit immediately, and those currently running tasks quit as soon as the tasks finish. ^%ZTSCH("SUB") This node counts the number of Submanagers waiting for new tasks. It is updated regularly by Submanagers as they run tasks. The Manager uses this value to decide whether to JOB out new Submanagers and adjusts its value during the idle loop whenever it believes it to be inaccurate. ^%ZTSCH("TASK", task #) This node holds the tasks TaskMan believes are currently running. Since entries are cleaned up when tasks quit or encounter errors, those that are forcibly exited by the system manager are left on the list even though they are not running. The Manager clears the list whenever the system starts up, and the system manager can manually remove inaccurate entries by using the exit action of the KILL off a users' job option [XURESJOB]. The task data stored at each node allows TaskMan to list the tasks even when they clean out their TASKS file (#14.4) records when they start instead of when they quit.	^%ZTSCH Node	Description
periodically updated entries for each Manager active on your machine and reflects each Manager's own perception of its current state. **A**ZTSCH("STOP") This node prevents Submanagers from running. While it is present, Managers do not start new Submanagers, Submanagers waiting for tasks quit immediately, and those currently running tasks quit as soon as the tasks finish. **A**ZTSCH("SUB") This node counts the number of Submanagers waiting for new tasks. It is updated regularly by Submanagers as they run tasks. The Manager uses this value to decide whether to JOB out new Submanagers and adjusts its value during the idle loop whenever it believes it to be inaccurate. **A**ZTSCH("TASK", task #) This node holds the tasks TaskMan believes are currently running. Since entries are cleaned up when tasks quit or encounter errors, those that are forcibly exited by the system manager are left on the list even though they are not running. The Manager clears the list whenever the system starts up, and the system manager can manually remove inaccurate entries by using the exit action of the KILL off a users' job option [XURESJOB]. The task data stored at each node allows TaskMan to list the tasks even when they clean out their TASKS file (#14.4) records when they start instead of when they quit. **A**ZTSCH("UPDATE", \$J of Manager) This node, records when the Manager last updated its local information about the site parameters. This node is KILLed whenever the Manager should update (e.g., site parameters are changed).	^%ZTSCH("STARTUP", UCI, option #)	internal number of all options that are specially queued to run every time the Manager starts up. The \$HOROLOG value reflects when the option was placed
is present, Managers do not start new Submanagers, Submanagers waiting for tasks quit immediately, and those currently running tasks quit as soon as the tasks finish. **A**ZTSCH("SUB") This node counts the number of Submanagers waiting for new tasks. It is updated regularly by Submanagers as they run tasks. The Manager uses this value to decide whether to JOB out new Submanagers and adjusts its value during the idle loop whenever it believes it to be inaccurate. **A**ZTSCH("TASK", task #) This node holds the tasks TaskMan believes are currently running. Since entries are cleaned up when tasks quit or encounter errors, those that are forcibly exited by the system manager are left on the list even though they are not running. The Manager clears the list whenever the system starts up, and the system manager can manually remove inaccurate entries by using the exit action of the KILL off a users' job option [XURESJOB]. The task data stored at each node allows TaskMan to list the tasks even when they clean out their TASKS file (#14.4) records when they start instead of when they quit. **A**ZTSCH("UPDATE", \$J of Manager) This node, records when the Manager last updated its local information about the site parameters. This node is KILLed whenever the Manager should update (e.g., site parameters are changed).	^%ZTSCH("STATUS", \$J of Manager)	periodically updated entries for each Manager active on your machine and reflects each Manager's own
for new tasks. It is updated regularly by Submanagers as they run tasks. The Manager uses this value to decide whether to JOB out new Submanagers and adjusts its value during the idle loop whenever it believes it to be inaccurate. **AZTSCH("TASK", task #) This node holds the tasks TaskMan believes are currently running. Since entries are cleaned up when tasks quit or encounter errors, those that are forcibly exited by the system manager are left on the list even though they are not running. The Manager clears the list whenever the system starts up, and the system manager can manually remove inaccurate entries by using the exit action of the KILL off a users' job option [XURESJOB]. The task data stored at each node allows TaskMan to list the tasks even when they clean out their TASKS file (#14.4) records when they start instead of when they quit. **AZTSCH("UPDATE", \$J of Manager) This node, records when the Manager last updated its local information about the site parameters. This node is KILLed whenever the Manager should update (e.g., site parameters are changed).	^%ZTSCH("STOP")	is present, Managers do <i>not</i> start new Submanagers, Submanagers waiting for tasks quit immediately, and those currently running tasks quit as soon as the tasks
currently running. Since entries are cleaned up when tasks quit or encounter errors, those that are forcibly exited by the system manager are left on the list even though they are not running. The Manager clears the list whenever the system starts up, and the system manager can manually remove inaccurate entries by using the exit action of the KILL off a users' job option [XURESJOB]. The task data stored at each node allows TaskMan to list the tasks even when they clean out their TASKS file (#14.4) records when they start instead of when they quit. ^%ZTSCH("UPDATE", \$J of Manager) This node, records when the Manager last updated its local information about the site parameters. This node is KILLed whenever the Manager should update (e.g., site parameters are changed).	^%ZTSCH("SUB")	for new tasks. It is updated regularly by Submanagers as they run tasks. The Manager uses this value to decide whether to JOB out new Submanagers and adjusts its value during the idle loop whenever it
local information about the site parameters. This node is KILLed whenever the Manager should update (e.g., site parameters are changed).	^%ZTSCH("TASK", task #)	currently running. Since entries are cleaned up when tasks quit or encounter errors, those that are forcibly exited by the system manager are left on the list even though they are not running. The Manager clears the list whenever the system starts up, and the system manager can manually remove inaccurate entries by using the exit action of the KILL off a users' job option [XURESJOB]. The task data stored at each node allows TaskMan to list the tasks even when they clean out their TASKS file (#14.4) records when they start instead of
^%ZTSCH("WAIT") This node, puts the Manager into a WAIT state.	^%ZTSCH("UPDATE", \$J of Manager)	local information about the site parameters. This node is KILLed whenever the Manager should update (e.g., site
· · · · · · · · · · · · · · · · · · ·	^%ZTSCH("WAIT")	This node, puts the Manager into a WAIT state.

Figure 275: ^%ZTSCH Global Structure

```
^%ZTSCH= ""
^%ZTSCH(next run time, task #)= ""
^%ZTSCH(next run time, task #)= (D1) device IOP value
^%ZTSCH("C", volume set)= count
^%ZTSCH("C", volume set, next run time, task #) = device $10
^%ZTSCH("DEV", device $IO)= $H when device was allocated for a specific
                                         ==>task
^%ZTSCH("ER")= "A1" or ""
^%ZTSCH("ER", $H when error happened)= error message
^%ZTSCH("ER", $H when error happened, 0) = context of error
^%ZTSCH("ES", error screen, 0)= ""
^%ZTSCH("ES", error screen, 1)= screened errors count
^%ZTSCH("IDLE")= $H when the Manager's idle loop checks were last performed
^%ZTSCH("IO")= $H when device waiting list was last checked without finding
               ==> an available device^ $IO of last device tried
^%ZTSCH("IO", device $IO)=device type
^%ZTSCH("IO", device $IO, run time, task #)= ""
^%ZTSCH("JOB", run time, task #) = device $IO
^%ZTSCH("LINK") = "" or $H when dropped link was last checked
^%ZTSCH("LINK", volume set)= 1 if link has dropped
^%ZTSCH("LINK", volume set, next run time, task #)= ""
^%ZTSCH("LOAD", load rating) = cpu ^ $H when rating was checked
^%ZTSCH("LOADA", cpu) = whether TM should wait ^ load rating ^ $H
                                   ==>when rating was checked ^ $J of Manager
^%ZTSCH("LOGRSRC") = ""
^%ZTSCH("NO-OPTION")= ""
^%ZTSCH("RUN")= $H when Manager last checked in
^%ZTSCH("STARTUP", UCI, option #)= $H when option was first queued for
                                ==>startup
^%ZTSCH("STATUS", $J of Manager)= $H when Manager last checked in [1] ^
                               ==>status [2] ^ description of status [3]
^%ZTSCH("STOP")= ""
^%ZTSCH("SUB") = count of Submanagers waiting for tasks
^%ZTSCH("TASK", task #)= (A2) entry point [1] ^ (A3) routine [2] ^ (A4)
                     ==>option # [3] ^ (A5) option name [4] ^ (C6)
                      ==>description [5] ^ device name [6] ^ (E1) UCI [7] ^
                      ==>(C3) creation time [8] ^ (C1) creator DUZ or (C2)
                      ==>creator name [9] ^ $J of running task [10] ^ $H
                      ==>when task actually started running [11]
^%ZTSCH("UPDATE", $J of Manager)= $H when the Manager last updated its
                               ==>parameters
^%ZTSCH("WAIT")= ""
```

22.5.2 TASKS File (#14.4)

^%ZTSK holds this partially-VA FileMan-compatible file of tasks. It is structured with a descriptor node followed by sequential entries. The data dictionary for this file is 14.4, TASKS. It is a read-only file. The TASKS file (#14.4) has no cross-references, not even a top-level B cross-reference, and its descriptor node is updated by the purge option (XUTM QCLEAN).

Each entry itself contains a zero node and several decimal nodes followed by a number of storage nodes. Like the SCHEDULE file, the TASKS file (#14,4) is *not* available for direct manipulation or examination by application software. Site managers, however, can print out information on entries in the TASKS file (#14,4) using VA FileMan.

The following diagram (<u>Figure 276</u>) describes the nodes 0 through .26 for each entry in the TASKS file (#14.4):

Figure 276: TASKS File (#14.4) nodes (1 of 2)

```
^%ZTSK(task #, 0)= (#.01) Entry Point [1F] ^ (#2) Routine Name [2F] ^ (#3) User
          ==>[3P:200] ^ (#4) Requested UCI [4F] ^ (#5) Creation Time ($H)
          ==>[5F] ^ (#6) Scheduled Run Time ($H) [6F] ^ (#7) Type of Task
          ==>[7F] ^{\circ} (#8) Option Number [8N] ^{\circ} (#9) Option Name [9F] ^{\circ} (#10)
          ==>Creator Name [10F] ^
          ==> (#11) Creation UCI [11F] ^ (#12) Creation Volume Set [12F] ^
          ==>(#13) RESERVED [13F] ^ (#14) Requested Volume Set [14F] ^ (#15)
          ==>Priority [15N] ^ (#16) Original Create date ($H) [16F]
^%ZTSK(task #, .01)= (#21) Original Destination UCI [1F] ^ (#22) Original
          ==>Destination Volume [2F] ^
^%ZTSK(task #, .02)= (#31) Current Destination UCI [1F] ^ (#32) Current
          ==>Destination Volume Set [2F] ^ (#33) Hop Count [3N] ^
^%ZTSK(task #,.03)= (#41) Task Description [E1,240F]^%ZTSK(D0,.04)= (#42) Schedule
Time Seconds [1N] ^
==>Status Notes [3F] ^ (#54) Job [4N] ^ ^
                                                     ^ (#59.8) Remember
          ==>Until [8F] ^ ^ (#59.1) Stop Flag [10F]^
^%ZTSK(task #, .12, (#71) Error Count [1N] ^ (#72) Error $H [2F] ^ (#73) Error
          ==>Message [3F] ^
^%ZTSK(task #, .2)= (#81) Device IOP value [1F] ^ (#82) $IO value [2F] ^ (#83)
          ==>Device Type [3F] ^ (#84) Device Sub-Type [4F] ^ (#85) Device
          ==>%IS modifier [5F] ^ (#86) Host File Address [6F] ^ (#87) Sync Flag
[7F] ^ (#88) IO
           ==>Reschedule Count [8N] ^
^%ZTSK(task #, .21)= (D8) device file entry # [1] ^
^%ZTSK(task #, .25)= (D7) device parameters [1] ^
```

The remaining nodes of each entry are used to pass variables to the task. If the task has been manipulated only using TaskMan's Program Interface, then the entries look like this:

Figure 277: TASKS File (#14.4) nodes (2 of 2)

```
^%ZTSK(task #, .3, "name")= (F2) value of saved variable
^%ZTSK(task #, .3, "array(", node #)= (F2) value of saved variable
^%ZTSK(task #, .3, "array", node #)= (F2) value of saved variable
```

The distinguishing characteristic here is the fact that the variables to be passed are all subscripted under the .3-node.

22.5.3 Task Status Codes

This section lists the various codes that may be found in the first ^-piece of the .1 node, the text displayed for that code by the List Tasks option, and the meaning of that code. These codes are set into the tasks at every point in processing where the status changes, along with a time stamp and an explanation where necessary.

Several of the codes correspond to the status of the SCHEDULE file entry for the task. If all applications used the Program Interface, the status code would always agree with the task's real status. In fact, many applications still directly manipulate ^%ZTSCH and ^%ZTSK, and they often neglect to update the status codes. Whenever the SCHEDULE file disagrees with the status code, the SCHEDULE file is correct. This is the reason many of the codes listed in Table 45 have multiple meanings.

Status codes 1 through 6 represent one of two common paths a task takes through TaskMan. The other common path replaces code 3 with A, where the task's device is not immediately available.

Table 45: TaskMan Task Status Codes

Status Code	Description
0	Incomplete or still being created.
1	Scheduled for <date and="" time="">. TaskMan uses this status in every option and entry point that schedules a task. If the task fails or errors out and TaskMan <i>cannot</i> trap the error, this status has a different meaning: "Stopped irregularly while scheduled."</date>
2	Being inspected by TaskMan. The Manager sets this status when the time comes for a task to run. As it removes the task from the SCHEDULE file, it sets this code into the task.
3	Waiting for a partition. When the Manager places a task in the Job list of the SCHEDULE file, it gives the task this code. If the task fails or errors out, and TaskMan <i>cannot</i> trap the error, this status has a different meaning: "Stopped irregularly while waiting for a partition."
4	Being prepared. The Submanager gives a task this code when it removes the task from the Job list or Busy Device Waiting list in order to run it.
5	Currently running. The Submanager gives a task this status just before it starts the task at its entry point. If the task fails or errors out, and TaskMan <i>cannot</i> trap the error, this status has a different meaning: "Started running <date &="" time=""> and stopped irregularly."</date>
6	Completed <date and="" time="">. The Submanager gives a task this status after the task quits.</date>
A	Waiting for device <device \$i="" name="" or="">. The Manager or the Submanager gives a task this status when it places the task in the Busy Device Waiting list. If the task fails or errors out and TaskMan <i>cannot</i> trap the error, this status has a different meaning: "Stopped irregularly while waiting for a device."</device>

Status Code	Description
В	Rejected. <rejection message="">.</rejection>
_	The Manager or the Submanager gives a task this status if it fails one of the basic validation tests. (The rejection messages are contained in the " <u>Task Rejection Messages</u> " section.)
С	Error <date and="" time="">. <error message="">.</error></date>
	The Submanager gives a task this status if it traps an error after starting the task. The error message records the vendor-specific \$ZE text.
D	Stopped by user.
	The Manager or the Submanager gives a task this status if, when TaskMan removes the task from the SCHEDULE file for processing, it finds that the user has asked the task to stop. The Submanager also assigns this status if, just before starting the task, it finds the stop request has been made. Finally, the Submanager gives a task this status if the task uses the ZTSTOP output variable to report that it stopped in response to a user's request.
	REF: For an explanation of ZTSTOP, see the description of \$\$S^%ZTLOAD API in the "TaskMan: Developer Tools" chapter in the Kernel Developer's Guide. Kernel and Kernel Toolkit APIs are also available in HTML format at a VA Intranet Website.
E	Interrupted while running.
	At startup, the Manager gives this status to any task listed in the Task list of the SCHEDULE file as still running.
F	Unscheduled by <user "you"="" name="" or="">.</user>
	The Dequeue Tasks [XUTM DQ] and TaskMan User [XUTM USER] options and the DQ^%ZTLOAD entry point use this status for tasks they unschedule.
G	Waiting for the link to <volume name="" set=""> to be restored.</volume>
	The Manager uses this status for tasks that would have been transferred to a different TaskMan environment and deleted from this one, if the local area network link to the remote environment were functioning properly.
	If the task fails or errors out, and TaskMan <i>cannot</i> trap the error, this status has a different meaning: "Stopped irregularly while waiting for a link."
н	Edited without being scheduled. The Requeue Tasks [XUTM REQ] and TaskMan User [XUTM USER] options and the REQ^%ZTLOAD entry point use this status when edited tasks are not subsequently rescheduled.
I	Discarded by TaskMan because its record was incomplete.
	The Manager or the Submanager uses this status for tasks listed in the SCHEDULE file that lack critical information in the corresponding TASKS file (#14.4) entries.
J	Currently being edited.
	This status has been set aside for possible use in future versions of TaskMan.
K	Created without being scheduled.
	The ^%ZTLOAD entry point uses this status for tasks when the application passes ZTDTH="@". Kernel Toolkit utility ^%ZTMOVE uses this value for the tasks it creates to transfer routines between Volume Sets manually.

Status Code	Description
L	Preparing this task caused the Submanager an error <date and="" time="">. <error msg="">.</error></date>
	The Submanager uses this status when it traps an error after claiming a task but before starting it.
	The Manager does not yet record a corresponding status for the analogous situation. Tasks that never start, that are left with a status of 2, have usually caused the Manager an error while it tried to examine them.
М	Waiting for a partition on a Compute Server.
	The Manager gives a task this code when it places the task in the Compute Server Job List.
	If the task fails or errors out, and TaskMan <i>cannot</i> trap the error, this status has a different meaning: "Stopped irregularly while waiting for a partition on a Compute Server."

22.5.4 Task Rejection Messages

Under certain conditions TaskMan can avoid trapping obvious errors by checking the tasks themselves for internal consistency. Whenever it finds tasks with bad data, it rejects them. This involves unscheduling them, setting their status codes to "B", and adding a brief explanatory message. These messages can help identify bugs in application queuing software, in the local system configuration, or in TaskMan itself.

Table 46: TaskMan rejection messages

TaskMan Rejection Message	Description
BAD DESTINATION UCI	The Manager rejects a task for this reason under three different conditions:
	 If the task is bound for the Manager's own Volume Set, whatever value has been passed for the destination UCI must be a valid UCI on the current Volume Set. If ^%ZOSF("UCICHECK") rejects the UCI, TaskMan rejects the task.
	If the task is bound for a different Volume Set and the destination UCI is not listed in the UCI ASSOCIATION file (#14.6) under that Volume Set, the UCI must be accepted as a valid UCI on the current Volume Set so TaskMan can use File #14.6 to determine where the task should run. If ^%ZOSF("UCICHECK") rejects the UCI, TaskMan rejects the task.
	If the task is bound for a different Volume Set and that Volume Set's link is down and its REPLACEMENT VOLUME SET is the current Volume Set, TaskMan rejects the task.
BAD DESTINATION VOLUME SET	Every task's destination Volume Set <i>must</i> be listed in the VOLUME SET file (#14.5).
BAD IO DEVICE <\$I>	If a port goes bad while many tasks wait for it in the Busy Device Waiting list, TaskMan traps an error whenever the port is tested for availability. When the Submanager traps such an error, it rejects every task waiting for that device.

TaskMan Rejection Message	Description
INVALID OUTPUT DEVICE	The Manager performs a lookup on the devices that tasks request. If the ^%ZIS call indicates that the device does not exist, TaskMan rejects the task.
INVALID ROUTINE NAME	If a task's entry point is in a %-routine, the Manager tests for that routine's existence in the library UCI. If the routine does not exist there, TaskMan rejects the task.
NO DESTINATION UCI	When older applications bypassed the Program Interface, they sometimes scheduled tasks without specifying the destination UCI. The Manager rejects all such tasks.
NO LINK ACCESS TO VOLUME SET	If the VOLUME SET file (#14.5) entry for a task's destination Volume Set indicates there is no link access to that Volume Set, the task is rejected.
NO ROUTINE AT DESTINATION	If a task's entry point is in a non-%-routine, then the check for the routine's existence is done by the Submanager prior to starting the task.

22.5.5 TaskMan State Messages

When the Manager does not run, all background processing grinds to a halt. For this reason, the Manager's condition is of vital importance to system managers. When problems are detected with background processing at a site, checking the Manager's condition should be the first step. The Manager periodically records its state in the Status List. The Monitor TaskMan option [XUTM ZTMON] displays this list near the top of the screen. The various states and their meanings are described in the topics that follow.

22.5.5.1 BALANCE State

The Manager lists itself in this state if other Managers (that are processing the same files) appear to have more CPU capacity available than the current Manager. While in the BALANCE state, the Manager does not process any tasks or start any new Submanagers. The Manager removes itself from the BALANCE state when it appears to have at least as much CPU capacity as the active Manager. In general, when many Managers are working out of the same TASKS (#14.4) and SCHEDULE files, most of them are in the BALANCE state at any given time, with only the one or two least loaded Managers actually processing tasks.



REF: For more information about TaskMan load balancing, see the "<u>Multiple TaskMan</u> <u>Managers and Load Balancing</u>" section in "<u>TaskMan: System Management—Configuration</u>."

22.5.5.2 ERROR State

The Manager lists itself in this state after trapping errors. On some systems the process of recording an error is slow, so the presence of a distinct state helps identify the source of delay to the system manager. A troubleshooter who sees this state for TaskMan should immediately check the TaskMan Error list to see what kind of error is being recorded. Because TaskMan's code is structured as a series of nested loops, it can very easily generate thousands of errors a day under certain conditions.

22.5.5.3 PAUSE State

The PAUSE state means that some external condition is preventing the Manager from processing tasks. The description always indicates the cause. While in the PAUSE state, the Manager waits until the problem is resolved, checking once every 60 seconds. The pause states are as follows:

Table 47: TaskMan PAUSE states

PAUSE State	Description
The following required ^%ZOSF nodes are undefined, <list nodes="" of=""></list>	When the Manager starts, restarts, or recovers from a trapped error, its first order of business is to drop through some setup code that checks TaskMan's environment. If any critical ^%ZOSF nodes are missing, it enters a PAUSE state and waits until the system manager restores the nodes.
Required link to <volume name="" set=""> is down</volume>	The other key check in the setup code is to ensure that all Volume Sets listed in the VOLUME SET file (#14.5) as required can actually be reached. The Manager tests each required link and enters the PAUSE state if any tests cause an error. The Manager remains in the PAUSE state, periodically testing the links, until they are restored.
Logons Inhibited	When the system manager sets the INHIBIT LOGONS? field of the VOLUME SET file (#14.5), TaskMan enters a PAUSE state and waits until the flag is cleared.
No Signons Allowed	The system manager can use the software switch to stop logons, which places TaskMan in the PAUSE state.

22.5.5.4 RUN State

The RUN state indicates that the Manager is going about its business in a relatively normal manner, managing background tasks on your system.

Table 48: TaskMan RUN states

RUN State	Description
Start	The Manager sets this value before and after executing the setup code at system startup.
Setup	The Manager identifies when it executes the setup code to test its environment.
Restart	The Manager sets this value after executing the setup code during a restart.
Main Loop	This should be the Manager's usual state. This indicates the Manager is executing the main loop that checks the environment, processes the Schedule list, and performs idle loop activities when appropriate.
TaskMan Job Limit Reached	When the total number of processes on the Manager's CPU exceeds the TaskMan Job Limit given in the VOLUME SET file (#14.5), the Manager can continue to process the Schedule list but <i>cannot</i> start any new Submanagers.

22.5.5.5 WAIT State

While in the WAIT state, the Manager does not react to changes in its environment. It does not process tasks, enter PAUSE states, or even stop after the Stop TaskMan option has been used.

You have two options (described above) that let you create or undo the WAIT state. TaskMan *cannot* enter this state on its own; it can only be initiated manually. This is essentially a tool for you to tightly control the processing of tasks on your machines. The description for this state always reads "TaskMan Waiting".

V. Kernel Installation and Distribution System

23 KIDS: System Management—Installations

Kernel Installation and Distribution System (KIDS) was introduced with Kernel 8.0. Previously, software was exported using a utility called DIFROM, and installed by running INIT routines that the DIFROM utility created. KIDS is the replacement for DIFROM; it introduces significant revisions to the software distribution and installation processes. This chapter introduces KIDS, and describes some of the changes to the software export process.

The following definitions apply throughout the KIDS documentation:

Table 49: KIDS-related terms and definitions

Term	Definition
Transport Global	An exported software application, stored in a global. KIDS exports software (i.e., package) based on its definition in a build entry. The transport global also contains the build entry and the PACKAGE file (#9.4) entry (if any) for a given software application.
Build Entry	An entry in the BUILD file (#9.6) that defines the parts of a software application to export. Also known as a build.
Component	An element of one of the following types: template (PRINT, SORT, and INPUT); form; function; bulletin; help frame; routine; option; security key; and protocol.
Distribution	A Host File Server (HFS) file containing transport globals. If a distribution contains multiple transport globals, KIDS treats them as a single installation when installing from the distribution.
Package	A cohesive set of files, data, and components that together form a set of computing activities related to a functional area (i.e., software).

23.1 KIDS Options

To get to the KIDS: Kernel Installation & Distribution System menu [XPD MAIN] (locked with the XUPROG security key) choose the Programmer Options menu option [XUPROG] on the Kernel Systems Manager Menu [EVE], as shown below:

Figure 278: KIDS menu options

```
Select Systems Manager Menu Option: PROGRAMMER OPTIONS
KIDS
       Kernel Installation & Distribution System ...
                                                                           [XPD MAIN]
             **> Locked with XUPROG
   PG
          Programmer mode
                                                                         [XUPROGMODE]
             **> Locked with XUPROGMODE
                                                                [XQ UNREF'D OPTIONS]
          Delete Unreferenced Options
          Error Processing ...
                                                                             [XUERRS]
          General Parameter Tools ...
                                                                    [XPAR MENU TOOLS]
                                                                    [XU BLOCK COUNT]
          Global Block Count
          List Global
                                                                             [XUPRGL]
             **> Locked with XUPROGMODE
                                                                 [XUPR-ROUTINE-TOOLS]
          Routine Tools ...
                                                                    [XT-OPTION TEST]
          Test an option not in your menu
             **> Locked with XUMGR
Select Programmer Options Option: KIDS <Enter> Kernel Installation & Distribution
    System
          Edits and Distribution ...
                                                             [XPD DISTRIBUTION MENU]
                                                                        [XPD UTILITY]
          Utilities ...
          Installation ...
                                                             [XPD INSTALLATION MENU]
             **> Locked with XUPROGMODE
          Patch Monitor Main Menu ...
                                                      [XTPM PATCH MONITOR MAIN MENU]
                                                       [XPD AUTOMATIC PATCHING MENU]
          Patchman ...
```

As indicated by its name (i.e., KIDS = Kernel Installation and Distribution System), KIDS supports two major functions:

- Distributions
- Installations



REF: In addition, KIDS also provides other utilities. For more information on KIDS utilities, see the "KIDS: System Management—Utilities" chapter.

23.1.1 Distributions

The distribution related options are located on the Edits and Distribution menu [XPD DISTRIBUTION MENU] (see Figure 279). The distribution portion of KIDS allows developers to:

- Define the contents of a software application in a build entry.
- Create transport globals from build entries.
- Export transport globals by creating distributions.

Figure 279: Edits and Distribution menu options

Select Kernel Installation & Distribution System Option: **EDITS AND DISTRIBUTION**

Create a Build Using Namespace Copy Build to Build Edit a Build Transport a Distribution Old Checksum Update from Build Old Checksum Edit Routine Summary List Version Number Update

Select Edits and Distribution Option:



REF: For a description on how application developers use the KIDS build and distribution options, see the "KIDS: Developer Tools" chapter in the *Kernel Developer's Guide*.

23.1.2 Installations

The installation related options are located on the Installation menu [XPD INSTALLATION MENU] (see Figure 280). The installation portion of KIDS allows sites to:

- Load transport globals from KIDS distributions.
- Load transport globals from KIDS PackMan messages.
- Print out the contents of loaded transport globals before installing them.
- Compare the contents of loaded transport globals to the current system before installing them.
- Install loaded transport globals.

Figure 280: Installation menu options

KIDS introduced two files into Kernel:

- BUILD file (#9.6)
- INSTALL file (#9.7)

KIDS also makes use of the existing PACKAGE file (#9.4), but its role in exporting and installing software is diminished.

23.2 Build Entries and the BUILD File (#9.6)


Build entries, stored in the BUILD file (#9.6), are where developers define a software application. This build entry defines the set of files, data, components, installation questions, national software information, pre- and post-install routines, and other settings that comprise the exported software.

Software components are no longer tied to namespace, as they were previously with DIFROM and the PACKAGE file (#9.4). Developers can select any components available on the current system and include them in their build entries as software components.

The format of the NAME field (#.01) of a build entry *must* be the software name concatenated with a space, and then a version number. This means that there is a separate entry for every version of a software application that a developer exports.

Also, a software application's build entry is sent to installing sites as part of the software; after an installation, the site can examine the build entry to see the software definition.

Figure 281: KIDS file diagram



23.3 INSTALL File (#9.7)

The INSTALL file (#9.7) stores a record of each installation a site performs. The INSTALL file (#9.7) allows KIDS to store a separate installation entry for each installation. A new version of software no longer overwrites the installation information of a previous version, and developers' installation history no longer overwrites the sites' installation history. The national PACKAGE file (#9.4) is now static at its top level.

The three main items recorded in the INSTALL file (#9.7) for each installation are the installing site's answers to installation questions, any installation output, and the installation's timing information.

23.4 Changes in the Role of the PACKAGE File (#9.4)

The PACKAGE file (#9.4) still plays a role in installations with KIDS, albeit a diminished one. KIDS provides a link from the build entry of a package to the PACKAGE file, so that developers can link a package to a PACKAGE file (#9.4) entry.

The top level of a PACKAGE file (#9.4) entry for a package now stores static package information. The only part of the PACKAGE file (#9.4) entry that installations update automatically now is the VERSION field (Multiple). A patch sent with KIDS does *not* transport the entire PACKAGE file (#9.4) entry. It only sends the information that is needed to update the PACKAGE file (#9.4). Patch installations updates the PATCH APPLICATION HISTORY field (Multiple), which is within the VERSION field (Multiple). KIDS saves patch names along with their sequence numbers in this multiple. Most other fields have been designated for removal at the top level of the PACKAGE file (#9.4). The PACKAGE file (#9.4) now stores mainly static software information that is not version specific, as well as the patch history of the software.

23.5 Transport Mechanism: Distributions

Distributions are the mechanism KIDS uses to export software. They are more flexible than the previous mechanism (INIT routines).

Distributions are usually in the form of an HFS file. The developer creates transport globals from build entries. KIDS stores transport globals in a global. KIDS can WRITE the global (in a format readable only by KIDS) to an HFS file; the HFS file is the distribution. The HFS file can then be distributed by a variety of methods, including FTP (file transfer protocol), diskette, and tape. For example, if your system is a PC, you can also move the Transport Global to a new medium (i.e., to multiple floppy disks so you can install on other PCs):

- Select the Load a Distribution option (*Do not* run the Environment Check routine).
- Under the Utilities Menu, select the Convert Loaded Package for Redistribution option.
- Under the Edits and Distribution Menu, select the Transport a Distribution option.
- At the "Enter a Host File:" prompt, enter the floppy drive and file name. For example:

```
Enter a Host File: A:\KRN8.KID)
```

One advantage to using distributions over INIT routines is that there is no limit to the size of a software application you can export. Another advantage is that during installations, you no longer have to overwrite a software application's existing routines with the new routines before running the installation.

Alternatively, a KIDS distribution can be sent via a PackMan message in MailMan. But transporting software as host files, especially large ones, avoids slowing down MailMan.

23.5.1 Two Kinds of Distributions

KIDS supports two kinds of distributions:

- **Standard Distribution**—This type of distribution contains transport globals for what are traditionally thought of as software applications, including files, data, and all components. A standard distribution can contain one or more transport globals. If there is more than one transport global, KIDS treats each one as a single installation unit.
- **Global Distribution**—This type of distribution contains one transport global only, and that transport global can export M globals only.

The transport globals in both types of distributions also contain the corresponding build entry, and (if linked to a PACKAGE file [#9.4] entry) the corresponding PACKAGE file (#9.4) entry. However, a patch sent with KIDS does *not* transport the entire PACKAGE file (#9.4) entry. It only sends the information that is needed to update the PACKAGE file (#9.4).

23.6 What Happens to DIFROM?

Developers should no longer use the DIFROM entry point to export software. Developers should use KIDS. The DIFROM method is still supported, but only for the support of sites that use standalone VA FileMan (VA FileMan without Kernel).



REF: For more information on using DIFROM, see the VA FileMan Programmer Manual.

23.7 Installing Standard Distributions

As noted previously, KIDS supports two types of distributions:

- Standard
- Global

This section describes how KIDS installations work when installing standard distributions.

23.7.1 Installation Sequence

KIDS installs standard distributions in three phases:

- 1. Loading transport globals from the distribution.
- 2. Answering installation questions for each transport global.
- 3. Installing each transport global in the distribution.

23.7.1.1 Phase 1: Loading Transport Globals from a Distribution or PackMan Message

- 1. Using the Load a Distribution option, the installer chooses the HFS file from which to load distributions. If loading from a PackMan message, choose the message and invoke the INSTALL/CHECK MESSAGE PackMan option.
- 2. For each transport global, KIDS makes an entry in the INSTALL file (#9.7) for the transport global.
- 3. KIDS loads transport globals from distribution into ^XTMP.
- 4. KIDS prompts the user to see if they want to run the environment check for each transport global (if unsuccessful, the process quits here; the developer may or may not KILL INSTALL file (#9.7) entries and transport globals from ^XTMP.)
- 5. The installer can print the contents of the transport global, compare the contents to the current system, and verify checksums of the transport global.

23.7.1.2 Phase 2: Answering Installation Questions for Transport Globals in a Distribution

- 1. Using the Install Package(s) option, the installer selects a distribution to install by choosing an entry from the INSTALL file (#9.7).
- 2. KIDS runs the environment check for the first transport global; the environment check can allow KIDS to install the transport global, cancel installation of the transport global, or cancel installation of all transport globals in the distribution.
- 3. The installer answers pre-installation questions for the first transport global.
- 4. The installer answers standard KIDS questions for the first transport global.
- 5. The installer answers post-installation questions for the first transport global.
- 6. The installer repeats Steps #2-5 for the remaining transport globals, if there are any more transport globals to process.
- 7. The installer chooses a device for the installation to run on. The installer can queue the installation or run it directly; entering a caret ("^") aborts the installation.

23.7.1.3 Phase 3: KIDS Installation of Software

- 1. KIDS disables any options and protocols the site has asked to be disabled for this install. However, KIDS does *not* disable options and protocols which have an Action of USE AS LINK FOR MENU ITEMS.
- 2. KIDS waits for the time period (from 0 to 60 minutes) the site specifies, if they chose to disable options and protocols.
- 3. KIDS suspends the running of queued options by TaskMan for this install, if the site chooses to do so.
- 4. The pre-install routine is run for the first transport global.
- 5. All components are installed for the first transport global.
- 6. The post-install routine is run for the first transport global.
- 7. KIDS repeats Steps 4-6 for any remaining transport globals to install in the distribution.
- 8. Options and protocols that were disabled for this install (if any) are re-enabled.
- 9. Queued options are removed from suspense (if the site chose to suspend queued options).

23.7.2 Installation Menu

The KIDS Installation Menu [XPD INSTALLATION MENU] contains the following options:

Figure 282: KIDS Installation menu options

```
Select Kernel Installation & Distribution System Option: INSTALLATION
           **> Locked with XUPROGMODE
  1
         Load a Distribution
                                                            [XPD LOAD DISTRIBUTION]
         Verify Checksums in Transport Global
                                                               [XPD PRINT CHECKSUM]
  3
         Print Transport Global
                                                                [XPD PRINT INSTALL]
                                                            [XPD COMPARE TO SYSTEM]
         Compare Transport Global to Current System
  5
         Backup a Transport Global
                                                                       [XPD BACKUP]
         Install Package(s)
                                                                 [XPD INSTALL BUILD]
         Restart Install of Package(s)
                                                               [XPD RESTART INSTALL]
         Unload a Distribution
                                                           [XPD UNLOAD DISTRIBUTION]
```

The number next to the options indicates the order of the option entries you should follow when performing a KIDS installation.

23.7.3 Loading a Standard Distribution

The first step in installing a standard distribution is to load the transport globals from the Distribution. The Load a Distribution option [XPD LOAD DISTRIBUTION] does the following:

- Lists what transport globals are contained in the distribution and asks you if you want to continue.
- Creates entries in the INSTALL file (#9.7) for each transport global in the distribution that passed its environment check.
- Loads transport globals from the distribution (HFS file) into the ^XTMP global (if you answer **YES** to continue).
- Prompts the user to see if they want to run the environment check for each transport global. If a
 transport global does not pass its environment check, KIDS may purge it from ^XTMP;
 otherwise, the transport global stays in ^XTMP. KIDS tells you the result of each environment
 check.
- Checks the version number of the incoming software against any existing software of the same name at the site. If the incoming version number is not greater than the existing version, KIDS aborts the installation for the transport global in question.
- Echoes the name of the first transport global to pass environment check (i.e., "Use transport global name to install this Distribution"). The name of the first transport global to pass its environment check is the name you use to install the distribution, in the next phase.

Loading a distribution is the first of three phases to install VistA software. The second phase is answering installation questions, including scheduling the installation; the third and final phase is the actual running of the installation.

When loading from a PackMan message, load the distribution using the INSTALL/CHECK MESSAGE PackMan option in MailMan. For KIDS PackMan messages, this option through MailMan is equivalent to the Load a Distribution option [XPD LOAD DISTRIBUTION].

Figure 283: Load a Distribution option—Sample user dialogue

```
Select Installation Option: LOAD A DISTRIBUTION
Enter a Host File: ZXG_EXPT.DAT

Distribution saved on Oct 13, 2004@09:29:08
Comment: TEST PKGS

This Distribution contains Transport Globals for the following Package(s):
    TEST 2.1

Want to Continue with Load? YES// <Enter>
Loading Distribution...

Want to RUN the Environment Check Routine? YES// <Enter>
    TEST 2.1

Use INSTALL NAME: TEST 2.1 to install this Distribution.

Select Installation Option:
```


23.7.3.1 When the Distribution is Split across Diskettes

Distributions can come in a single host file (see <u>Figure 283</u>); alternatively, they can come on diskettes, with the host file split up among the diskettes. If you are installing from a distribution that is spread

across diskettes, the Load a Distribution option [XPD LOAD DISTRIBUTION] asks you for subsequent diskettes (e.g., "Insert the next diskette, #2, and Press the return key", etc.). Insert the appropriate disk and press the **<Enter>** key, and continue until the distribution is loaded.

23.7.4 Loading Transport Globals from a Distribution

Figure 284: Loading transport globals from a distribution—Flowchart



23.7.5 Verifying Checksums in a Transport Global

You can verify the checksums for a loaded transport global in advance of installing from it, using the Verify Checksums in Transport Global option [XPD PRINT CHECKSUM]. This option verifies all checksums of routines in the transport global, reporting any discrepancies. In the future, the ability to verify checksums will be extended to other KIDS components besides routines.

As of Kernel patch XU*8.0*369, the integrity checking CHECK1^XTSUMBLD routine supports the Compare local/national checksums report option [XU CHECKSUM REPORT].

As of Kernel patch XU*8.0*393, KIDS was modified to send a message to a server on FORUM when a KIDS build is sent to a Host File Server (HFS) device. This message contains the checksums for the routines in the patch. The server on FORUM matches the message with a patch if the sending domain is authorized on FORUM. There is no longer a need for developers to manually include routine checksums (either CHECK^XTSUMBLD or CHECK1^XTSUMBLD routines) in the patch description. The patch module includes the before and after CHECK1^XTSUMBLD values in the Routine Information section at the end of the patch document.

With changes in the National Patch Module (NPM) on FORUM, when the patch is released the checksums for the routines are moved to the ROUTINE file (#9.8) on FORUM. The checksum "before" values come from the FORUM ROUTINE file (#9.8) and are considered the GOLD standard for released checksums. The local site's Compare local/national checksums report option [XU CHECKSUM REPORT] uses the FORUM ROUTINE file (#9.8) as its source to create reports showing any routines that do *not* match.

This patch also modified the KIDS BUILD file (#9.6) by adding the TRANSPORT BUILD NUMBER field (#63) used to store a build number that is incremented each time a build is made. This build number is added to the second line of each routine in the 7th ";" piece. This makes it easy to tell if a site is running the current release during testing and afterword. The leading "B" found in the checksum tells the code what checksum routine to use.

23.7.6 Printing Loaded Transport Globals

Once you have loaded transport globals from a standard distribution onto your system, you can print out the definitions of the transport globals, using the Print Transport Global option [XPD PRINT INSTALL]. This way, you can see every component exported in each transport global, before you install them.

Figure 285: Print Transport Global option—Sample printed transport global

```
PACKAGE: ZXG DEMO 1.0
______
NATIONAL PACKAGE:
DESCRIPTION:
ENVIRONMENT CHECK : ZXGENV
PRE-INIT ROUTINE : ZXGPRE
POST-INIT ROUTINE: ZXGPOS
______
ROUTINE:
                                          SEND TO SITE
  7XGC00
  ZXGC01
                                          SEND TO SITE
  7XGC02
                                          SEND TO SITE
  ZXGCMOVE
                                          SEND TO SITE
  ZXGCTEST
                                          SEND TO SITE
  ZXGCTW1
                                          SEND TO SITE
  ZXGCWE
                                          SEND TO SITE
  ZXGCXMP1
                                          SEND TO SITE
  ZXGCXMPL
                                          SEND TO SITE
  ZXGDEMO
                                          SEND TO SITE
  ZXGKC
                                          SEND TO SITE
  ZXGLMSG
                                          SEND TO SITE
  ZXGLOAD
                                          SEND TO SITE
  ZXGTMP
                                          SEND TO SITE
INSTALL QUESTIONS:
    SUBSCRIPT: PRE1
DIR(0)=YA^{^}
DIR("A")=Do you want to run the pre-install conversion?
DIR("B")=YES
DIR("?")=Answer YES to run the pre-install conversion, NO to skip it...
```

23.7.7 Comparing Loaded Transport Globals to the Current System

When you have loaded transport globals from a standard distribution onto your system, you can also compare a transport global to the matching software already installed on your system (if any), using the Compare Transport Global to Current System option [XPD COMPARE TO SYSTEM]. This way, you can compare the software you are about to install with the current version of the software on your system.

When this option finds differences, it notes the change by displaying the differences between the current software and the transport global on two lines, one line labeled * OLD * and the other * NEW *.



NOTE: Pointers are converted to FREE TEXT when exporting VA FileMan entries, so these converted free pointers show up as differences when using the compare feature.

Figure 286: Compare Transport Global to Current System option—Sample comparison output

This option was updated with Kernel patch XU*8.0*393 to add a side-by-side comparison in columnar format, which only works if Kernel Toolkit patch XT*7.3*93 has also been installed, as shown below:

Figure 287: Compare Transport Global to Current System option—Sample comparison output in columnar format

```
Select Kernel Installation & Distribution System Option:
        Load a Distribution
        Verify Checksums in Transport Global
        Print Transport Global
        Compare Transport Global to Current System
        Backup a Transport Global
         Install Package(s)
         Restart Install of Package(s)
         Unload a Distribution
Select Installation Option: 4 <Enter> Compare Transport Global to Current System
Select INSTALL NAME: XU*8.0*381 <Enter> Loaded from Distribution
Loaded from Distribution 9/14/06@12:39:52
    => DEMO COMPARE ;Created on Sep 14, 2006@12:39:17
This Distribution was loaded on Sep 14, 2006@12:39:52 with header of
  DEMO COMPARE ;Created on Sep 14, 2006@12:39:17
  It consisted of the following Install(s): XU*8.0*381
    Select one of the following:
                  Full Comparison
                  Second line of Routines only
                  Routines only
                 Columnar Routine compare
Type of Compare: 4 < Enter > Columnar Routine compare
DEVICE: HOME// <Enter> Telnet terminal
Compare XU*8.0*381 to current site Routines Only
Compare of routines from KIDS XU*8.0*381, and disk
Routine XU8P381 not on disk
Routine XUTMTP
  KIDS
______
1{XUTMTP ;SEA/RDS - TaskMan: ToolKit} 1{XUTMTP ;SEA/RDS - TaskMan: ToolKit}
{, Print, Part 1 :04/18/2006 16:19} {, Print, Part 1 :04/24/2003 11:06}
2{ ;;8.0;KERNEL;**20,86,169,242,381*}2{ ;;8.0;KERNEL;**20,86,169,242**;Ju}
```

23.7.8 Backing Up Transport Globals

The Backup a Transport Global option [XPD BACKUP] creates a MailMan message that backs up all current routines on your system that would be replaced by a KIDS patch. This option is under the Installation menu of the KIDS menu. It works on a patch that has been loaded on your system, but not installed.

23.7.9 Running Installations

Once you have loaded the transport globals from a standard distribution, you can install them. Do this using the Install Package(s) option [XPD INSTALL BUILD].

When you load a distribution, KIDS tells you which transport global name to use to install the distribution (e.g., "Use PACKAGE 1.0 to install this Distribution"). This is always the first transport global to successfully load from the distribution. When you use the Install Package(s) option [XPD INSTALL BUILD], select the transport global name reported when you loaded the original distribution. Once you've done that, you can answer the installation questions for each transport global in the distribution.

23.7.9.1 Processing Each Transport Global

When you select a distribution to install, the Install Package(s) option processes the installation questions for each transport global in the distribution. For each transport global, you're asked:

- Pre-Install questions.
- Standard KIDS Questions.
- Post-Install Questions.
- Whether to disable any options or protocols. By typing three question marks ("???") at this prompt KIDS lists all of the options and protocols it will disable. If you answer YES, all incoming options and protocols are disabled. You are also prompted to add to or delete from the list of options and protocols to disable. However, KIDS does not disable options and protocols which have an Action of USE AS LINK FOR MENU ITEMS. All scheduled options on the system are also disabled. Finally, you are asked a time period for installation:

```
Delay Install(Minutes): (0-60): 0//"
```

You can delay before starting the installation after disabling options and protocols from 0 to 60 minutes. This is to allow users already in (disabled) options time to exit the options before the installation starts.

23.7.9.2 Scheduling Installations

The final question you are asked when using the Install Package(s) option to load software is upon what device to run the installation. Your choices at the "DEVICE: " prompt are:

- Run the installation directly by selecting a device without queueing. The installation runs immediately, on the device you specify.
- Queue the installation.
- Abort the installation of the distribution by entering a caret ("^").

23.7.10 When the Installation is Queued

If you queued the installation, you can look up the installation task in TaskMan. A KIDS installation task looks like:

Figure 288: Queued KIDS installation—Sample installation task

```
3: (Task #1179950) EN^XPDIJ, KIDS install. Device VER$LW. KRN,KDE.
From TODAY at 16:24, By you. Scheduled for TODAY at 22:00
```

You can cancel a queued installation (before it has started) by deleting the task. KIDS also allows you to restart an install if the install is queued and you get an error during the installation.

23.7.11 Re-answering Installation Questions

If you queued an installation, you can re-answer installation questions, if you so choose, using the Install Package(s) option. To be able to re-answer the questions, however, you need to locate the task that was queued for the installation and delete it first. Once you delete the installation's queued task, you can re-answer the install questions. When you re-answer questions, your answers from the previous time come up as default responses.

Also, if you abort an installation after answering its installation questions (i.e., by entering a caret ["^"]), your responses are again used as the defaults the next time you try to install.

23.7.12 Information Stored in the INSTALL File (#9.7)

KIDS exports the definition of a software application in the BUILD file (#9.6). KIDS records installations of software in the INSTALL file (#9.7). The installation records in the INSTALL file (#9.7) provide a record of the start time, timing for each checkpoint, and completion time (if any) for an installation.

When an installation aborts, the contents of the INSTALL file (#9.7) determine where the install starts up again when you use the Restart Install of Package(s) option (checkpoint information is stored in the INSTALL file [#9.7]).


As well as being sent to the installation's principal device, all output from the installation is also stored in the INSTALL file (#9.7), in the MESSAGES word-processing-type field.

The installation questions (and your answers to them) are stored in the INSTALL ANSWERS field (Multiple) of the INSTALL file (#9.7).

You can print entries from the INSTALL file (#9.7) with the Install File Print option.

23.7.13 **Answering Installation Questions for a Distribution**

Figure 289: Answering installation questions for a distribution—Flowchart




23.7.14 Installation Progress

If the device selected for output is a VT100-compatible (or higher) terminal, KIDS displays the installation output in a virtual window on the terminal. Below the virtual window, a progress bar graphically illustrates the percentage complete that the current part of the installation has reached. KIDS is able to report progress for the installation of files and for all components (PRINT templates, forms, help frames, routines, options, etc.) KIDS lists those compiled cross-references, INPUT templates, and PRINT templates that were created during the install process. KIDS does not show progress for installing data, nor for pre- and post-install tasks.

On all other devices, progress is reported using dots.

Figure 290: Installation progress—Sample output



23.7.15 Once the Installation Finishes

When the installation runs, its output is sent to the device you specified when you answered the installation questions. If, for example, you queued the installation to a printer, the output is sent to the printer.

You can find out whether an installation finished by looking up the entry in the INSTALL file (#9.7) for that installation (use the Install File Print option). You should check whether an installation completed successfully or not. If the install completed successfully, the STATUS field in the INSTALL file (#9.7) entry is set to "Install Completed." If the install errored out, the STATUS field in the INSTALL file (#9.7) entry is still set to "Install Started." If it errored out, you need to find out what went wrong, and restart the installation.



REF: For information on restarting an installation, see the "<u>Restarting Aborted Installation</u>" section.

If you disabled scheduled options, options, and protocols, KIDS should have re-enabled those (unless the install errored out).

You should refer to the instructions that came with the software you installed to see what post-installation tasks, if any, you should perform.

23.7.16 Restarting Aborted Installations

A feature of KIDS is the ability to restart an aborted installation. KIDS uses a checkpoint system to keep track of how many phases of an installation it completed. When an installation aborts for some reason, you can restart the installation (using the Restart Install of Package(s) option [XPD RESTART INSTALL]). KIDS does *not* automatically re-run the entire installation from the beginning; instead, it reruns the installation only from the last completed checkpoint.

As well as some standard checkpoints built into KIDS (e.g., completion of pre-install, completion of each component type, and completion of post-install), KIDS lets developers create checkpoints for use within their pre- and post-install routines. So depending on how the developer has designed a pre- or post-install, it is possible that, when re-started, the pre- or post-install does not have to be re-run in its entirety either (if the error occurred there). Instead, KIDS only re-runs the pre- or post-install from the last completed developer checkpoint (if any) within the pre- or post-install.

Before restarting an installation, you should try to determine what caused the installation to abort. If an error occurred, any error messages are in the INSTALL file (#9.7) entry, in the MESSAGES word-processing-type field. Once you've fixed the problem, you can use the Restart Install Of Package(s) option [XPD RESTART INSTALL] to continue with the installation. KIDS also allows you to restart an install if the install is queued and you get an error during the installation.

23.7.17 Recovering from an Aborted Distribution Load

If you encounter an error while loading a distribution (using the KIDS option to load a distribution from the export medium into the ^XTMP global), you are unable to re-load the distribution until you clear out what was stored during the aborted load attempt.

To clear out the previously loaded distribution, use the Unload a Distribution option [XPD UNLOAD DISTRIBUTION]. To unload a distribution, enter the name of the *first* transport global that was loaded when you loaded the distribution. The entries in the INSTALL file (#9.7) for all transport globals in the distribution are removed, and the transport globals themselves are purged from the ^XTMP global.

Once you delete entries in the INSTALL file (#9.7) and entries in the ^XTMP global with the Unload a Distribution option [XPD UNLOAD DISTRIBUTION], you should be able to reload the distribution in question. If the install was already started and you choose to unload the distribution, you first *must* edit the INSTALL file (#9.7) and set the STATUS field to Load From Distribution (i.e., 0) prior to using the Unload a Distribution option [XPD UNLOAD DISTRIBUTION].

23.8 Installing Global Distributions

The second type of distribution supported by KIDS is called a global distribution. This type of distribution, unlike standard distributions, is used to only export globals.

You still use the Load a Distribution option to install global distributions. Unlike loading a standard distribution, however, KIDS installs global distributions immediately from the Load a Distribution option. Also, there is no queueing of the installation.

A global distribution can only contain one transport global, and the transport global can only export globals. You know that the distribution you're installing is a global distribution rather than a standard distribution, because when you load it with the Load a Distribution option, KIDS indicates the following:

Figure 291: KIDS Global distribution—Sample message

```
This is a Global Distribution. It contains Global(s) that will update your system at this time. The following Global(s) will be installed:
```

The Load a Distribution option lists each global that will be installed from the distribution. Each global in the list is marked OVERWRITE or REPLACE:

- OVERWRITE—Load the global without purging the site's version of the global beforehand.
- REPLACE—Purge the site's version of the global first, and then load the global.

You are given two chances to abort the installation of the global distribution. If you answer **YES** to both questions, the globals in the global distribution are installed immediately.

23.9 Purging the BUILD and INSTALL Files

Each KIDS installation adds one entry to the BUILD (#9.6) and INSTALL (#9.7) files for every transport global installed from the distribution.



REF: For information about purging these files, see the discussion of the Purge Build or Install Files option in the "<u>Purge Build or Install Files</u>" section in "<u>KIDS: System Management—</u> Utilities."

Figure 292: Installation of a global distribution—Load a Distribution option

```
Select Installation Option: LOAD A DISTRIBUTION
Enter a Host File: [DMANAGER]XGGLOBAL.DAT
KIDS Distribution save on Jan 26, 2004@12:58:25
Comment: GLOBAL PACKAGE
This Distribution contains the following Transport global(s):
    GLOBAL PACKAGE 1.0
This is a Global Distribution. It contains Global(s) that will
update your system at this time. The following Global(s) will be installed:
^XGRON(1) Overwrite
^XGRON("PX") Replace
^XGRON("TX") Overwrite
If you continue with the Load, the Global(s) will be
Installed at this time.
Want to Continue with Load? YES// <Enter>
Loading Distribution...
Globals will now be installed, OK? YES// <Enter>
Installing Globals...
              Jan 26, 2004@13:04:16
GLOBAL PACKAGE 1.0 Installed.
              Jan 26, 2004@13:04:17
Select Installation Option:
```

23.10 Alpha/Beta Tracking

Kernel provides a mechanism for tracking and monitoring installation and option usage during the alpha and beta testing phases of VistA software applications. This tool is primarily intended for application developers to use in monitoring the testing process at local test sites.



NOTE: In VA terminology "Alpha" and "Beta" testing are defined as follows:

- Alpha Testing—VistA test software application is running in a site's Test account.
- Beta Testing—VistA test software application is running in a site's Production account.

Alpha/Beta Tracking provides the following services to both developers and system administrators:

- Notification when a new alpha or beta software version is installed at a site.
- Periodic option usage reports for alpha or beta options being tracked.
- Periodic listings of errors in the software's namespace that are currently in alpha or beta test at the site.

The following options are provided on the Alpha/Beta Test Option Usage Menu [XQAB MENU], which is located on the Operations Management menu [XUSITEMGR]. These options allow developers and system administrators to monitor Alpha/Beta Tracking at a site:

- Errors Logged in Alpha/Beta Test (QUEUED) option [XQAB ERROR LOG XMIT]
- Actual Usage of Alpha/Beta Test Options option [XQAB ACTUAL OPTION USAGE]
- Low Usage of Alpha/Beta Test Options option [XQAB LIST LOW USAGE OPTS]
- Print Alpha/Beta Errors (Date/Site/Num/Rou/Err) option [XQAB ERR DATE/SITE/NUM/ROU/ERR]
- Send Alpha/Beta Usage to Programmers option [XQAB AUTO SEND]



REF: For more detailed information about and description of the Alpha/Beta Tracking functionality (e.g., starting, stopping, and monitoring options), see the "Alpha/Beta Tracking" section in the "KIDS: Developer Tools" section in the *Kernel Developer's Guide*.

24 KIDS: System Management—Utilities

KIDS provides the following utility options:

Figure 293: KIDS Utilities menu options

```
Kernel Installation and Distribution System...
                                                                          [XPD MAIN]
 Utilities...
                                                                       [XPD UTILITY]
   Build File Print
                                                                   [XPD PRINT BUILD]
   Install File Print
                                                            [XPD PRINT INSTALL FILE]
   Edit Install Status
                                                                  [XPD EDIT INSTALL]
   Convert Loaded Package for Redistribution
                                                               [XPD CONVERT PACKAGE]
   Display Patches for a Package
                                                         [XPD PRINT PACKAGE PATCHES]
   Purge Build or Install Files
                                                                    [XPD PURGE FILE]
   Rollup Patches into a Build
                                                                [XPD ROLLUP PATCHES]
   Update Routine File
                                                                [XPD ROUTINE UPDATE]
   Verify a Build
                                                                  [XPD VERIFY BUILD]
   Verify Package Integrity
                                                              [XPD VERIFY INTEGRITY]
```

These utilities can be used both by developers and by sites who install software created by KIDS.

24.1 Build File Print Option

The Build File Print option [XPD PRINT BUILD] prints out the build entry for a software application. It lists the complete definition of the software, including all files, components, install questions, and the environment, pre-install, and post-install routines.

Figure 294: Build File Print option—Sample output

PACKAGE: ZXG DEMO 1.0					PAGE 1
NATIONAL P. DESCRIPTIO		G* func	tions.		
PRE-INIT R	T CHECK : ZXGENV OUTINE : ZXGPRE ROUTINE: ZXGPOS				
FILE #	NAME	UP DATE DD	SEC.	DATA COMES SITE W/FILE DATA	
662105	ZXG DEMO	YES	YES	NO	
PRINT TEMP ZXG PRI	LATE: NT FILE #662105		SE	ND TO SITE	
ROUTINE: ZXGC00 ZXGC01 ZXGC02 ZXGC03 ZXGC04 ZXGC05 ZXGC06 ZXGC07 ZXGC08			SE SE SE SE SE	ND TO SITE	
OPTION: ZXG TES INSTALL QU			SE	ND TO SITE	

24.2 Install File Print Option

The Install File Print option [XPD PRINT INSTALL FILE] prints out the results of an installation, as stored in the INSTALL file (#9.7). Use this option to check on the status of an installation in progress or to print out the results of a completed installation.

Figure 295: Install File Print option—Sample output

Figure 295: Install File Print option—Sample output		
PACKAGE: ZXG DEMO 1.0	COMPLETED	PAGE 1 ELAPSED
	DATE LOADED: FEB 07,	2004@07:51:59
INSTALL STARTED: FEB 07, 2004@07:52:14	07:52:23	0:00:09
ROUTINES:	07:52:15	0:00:01
PRE-INIT CHECK POINTS: XPD PREINSTALL STARTED XPD PREINSTALL COMPLETED	07:52:15 07:52:15	
FILES: ZXG DEMO	07:52:16	0:00:01
PRINT TEMPLATE OPTION	07:52:17 07:52:21	0:00:03 0:00:02
POST-INIT CHECK POINTS: XPD POSTINSTALL STARTED XPD POSTINSTALL COMPLETED	07:52:21 07:52:21	
INSTALL QUESTION PROMPT		ANSWER
XPZ1 Want to DISABLE Scheduled Options, MESSAGES:	Options and Protocol	s NO
<pre>Install Started for ZXG DEMO 1.0 : Feb 07, 2004@07:52:14</pre>		
Installing Routines: Feb 07, 2004@07:52:15		
Running Pre-Install Routine: ^ZXGPRE		
Installing Data Dictionaries: Feb 07, 2004@07:52:16		
Installing PACKAGE COMPONENTS:		
Installing PRINT TEMPLATE		
Installing OPTION Feb 07, 2004@07:52:21		
Running Post-Install Routine: ^ZXGPOS		
Updating Routine file		
Updating KIDS files		
ZXG DEMO 1.0 Installed.		

24.3 Edit Install Status Option

The Edit Install Status option [XPD EDIT INSTALL], released with Kernel patch XU*8.0*539, lets you edit the STATUS (#.02) and the INSTALL COMPLETE TIME (#17) fields in the INSTALL file (#9.7). Use this option to change the status of a patch that was de-installed.

Figure 296: Edit Install Status option—Sample user dialogue

```
Select Utilities Option: EDIT INSTALL <Enter> Status
Select INSTALL NAME: USER TEST
    1 USER TEST 1.0 Install Completed
                                                5/14/08@11:21:04
    => TEST ;Created on May 14, 2008@11:03:58
    2 USER TEST 1.0 Loaded from Distribution
                                                      7/8/09@10:33:16
    => TEST ;Created on Jul 08, 2009@10:31:50
CHOOSE 1-2: 1 <Enter> USER TEST 1.0 Install Completed
                                                          5/14/08@11:21:04
    => TEST ; Created on May 14, 2008@11:03:58
STATUS: Install Completed// ???
       This is the status of this package at this site.
    Choose from:
      Ο
            Loaded from Distribution
              Oueued for Install
      1
              Start of Install
               Install Completed
               De-Installed
STATUS: Install Completed// <Enter>
INSTALL COMPLETE TIME: MAY 14,2008@11:21:04//
```

24.4 Convert Loaded Package for Redistribution Option

Use the Convert Loaded Package for Redistribution option [XPD CONVERT PACKAGE] to add software to an existing distribution.

A KIDS distribution can transport one or more software applications. What if you want to add additional software to an existing distribution? For example, suppose you have a distribution for a software application. Further suppose that patches are transported as individual KIDS software, and you want to add all existing patches to the software's distribution? The Convert Loaded Package for Redistribution option [XPD CONVERT PACKAGE] lets you do this.

In <u>Figure 297</u> and <u>Figure 298</u>, distributions for a software application (i.e., ZXG 1.0) and a patch (i.e., ZXG*1.0*1) are both loaded. The Convert Loaded Package for Redistribution option is used to build a new distribution combining both original distributions.

Follow these steps to create a new distribution from existing distributions:

- Load the original distributions (there is no need to install them, however).
 In this example, we would load the distributions for ZXG 1.0 and ZXG*1.0*1 (but we would not install them).
- 2. Use the Convert Loaded Package for Redistribution option. It lets you choose loaded transport globals, and transfers them into a format ready for export. Also, it creates build entries for each software application contained in the distributions. This allows you to create a new distribution containing the transport globals from the existing distributions. Kernel patch XU*8.0*44 added

the "Want to make the Transport Globals Permanent? NO//" prompt, answering **YES** to this prompt flags the global so that it is not deleted after the transportation. This provides a "Gold" account or library of software and patches that are included in a Transport Global.

In this example, we would first convert the loaded distribution ZXG 1.0 into a form ready to redistribute:

Figure 297: Convert Loaded Package for Redistribution—Sample user dialogue (1 of 2)

```
Select Utilities Option: CONVERT LOADED PACKAGE FOR REDISTRIBUTION
Select INSTALL NAME: ZXG 1.0 <Enter> Loaded from Distribution

This distribution was loaded on Feb 28,2004@08:15:05 with header of

It consisted of the following Install(s):

ZXG 1.0

Want to make the Transport Globals Permanent? NO// YES
Want to continue with the conversion of the package(s)? NO// YES

** DONE **

Select Utilities Option:
```

Then we would convert the patch distribution, ZXG*1.0*1, into a form ready to re-distribute:

Figure 298: Convert Loaded Package for Redistribution—Sample user dialogue (2 of 2)

```
Select Utilities Option: CONVERT LOADED PACKAGE FOR REDISTRIBUTION
Select INSTALL NAME: ZXG*1.0*1 <Enter> Loaded from Distribution

This distribution was loaded on Feb 28,2004@08:15:35 with header of

It consisted of the following Install(s):

ZXG*1.0*1

Want to make the Transport Globals Permanent? NO// YES
Want to continue with the conversion of the package(s)? NO// YES

** DONE **
```

3. Create the new distribution with the Transport a Distribution option. Select each build from the original distributions that you want to be part of the new distribution. For each build that you select, you should be told that the transport global already exists and be asked if you want to use this transport global. Answer **YES** in each case to use the current transport global.

Once you have selected all of the builds for the new distribution, go ahead and create the new distribution.

In this example, we create a new distribution containing both ZXG 1.0 (the original software application) and ZXG*1.0*1 (an added software application):

Figure 299: Transport a Distribution—Sample user dialogue

```
Select Edits and Distribution Option: TRANSPORT A DISTRIBUTION
Enter the Package Names to be transported. The order in which they are
entered will be the order in which they are installed.
First Package Name: ZXG 1.0 <Enter> **Transport Global exists**
   Use this Transport Global? YES
Another Package Name: ZXG*1.0*1 <Enter> **Transport Global exists**
   Use this Transport Global? YES
Another Package Name: <Enter>
Order
      ZXG 1.0 **will use current Transport Global**
      ZXG*1.0*1 **will use current Transport Global**
OK to continue? NO//YES
Enter a Host File: ZXG1.KID
Header Comment: PATCHED DISTRIBUTION ZXG 1.0
     ZXG 1.0...
    ZXG*1.0*1...
Package Transported Successfully
```



NOTE: Changing a distribution's build entries before redistributing is *not* recommended.

24.5 Display Patches for a Package Option

The Display Patches for a Package option [XPD PRINT PACKAGE PATCHES] prints all patches installed for a software application. It displays the Date Installed and who installed the patches. It optionally prints the description of the patch. All the displayed information comes from the PACKAGE file (#9.4).

Figure 300: Display Patches for a Package option—Sample user dialogue

```
Select Utilities Option: DISPLAY PATCHES FOR A PACKAGE
Select PACKAGE NAME: KERNEL
Select VERSION: 8.0// <Enter>
                                                        07-29-95
Do you want to see the Descriptions? NO// <Enter>
DEVICE: HOME// <Enter> SYSTEM
PACKAGE: KERNEL Oct 09, 2004 1:32 pm
                                                                                                PAGE 1
                           INSTALLED
                                                                       INSTALLED BY
PATCH #
VERSION: 8.0 JUL 29, 2004
                                                                        XUUSER, TEN
   28 APR 25, 2004
20 SEQ #23 FEB 09, 2004
32 SEQ #24 MAY 15, 2004
23 SEQ #25 MAY 17, 2004
39 SEQ #26 JUL 19, 2004
26 SEQ #27 JUN 01, 2004
27 SEQ #28 JUN 13, 2004
24 SEQ #29 JUN 30, 2004
40 SEQ #30 AUG 28, 2004
41 SEQ #31 AUG 29, 2004
29 SEQ #32 AUG 30, 2004
                                                                        XUUSER, NINE
                                                                        XUUSER, NINE
                                                                   XUUSER,NINE
XUUSER,NINE
XUUSER,TEN
XUUSER,ELEVEN
XUUSER,TEN
                                                                      XUUSER, TEN
                                                                      XUUSER, NINE
                                                                      XUUSER, TEN
                                                                      XUUSER, ELEVEN
                                                                        XUUSER, TEN
                                                                        XUUSER, NINE
```

24.6 Purge Build or Install Files Option

Each KIDS installation adds one entry to the BUILD (#9.6) and INSTALL (#9.7) files for every transport global installed from the distribution. You can use the Purge Build or Install Files option [XPD PURGE FILE] to purge entries in these files.

The first question the option asks is which file to purge, the BUILD (#9.6) or INSTALL file (#9.7). Choose one of these files.

The next question asked is the number of versions to retain.

24.6.1 Versions to Retain

When you choose to retain some number entries for a software application, the option *must* decide which entries are most recent. The Purge Install or Build Files option uses numeric order based on software version number to decide which entries are the most recent. When there are multiple entries for the same version number (e.g., alpha or beta installs took place), the following order of precedence is used:

- 1. Released Version is the most recent (version number contains no letters, such as 8.0)
- 2. Beta Test Version (version number contains V, such as 8.0V10)
- 3. Alpha Test Version (version number contains T, such as 8.0T10)

24.6.2 Selecting Software Names for Purging

After versions to retain, the next prompt is "Package Name." You can enter a partial or full software application name. You continue to be prompted for additional software names until you simply press the **Enter>** key without making any further entries at the "Package Name" prompt.

- Packages (Software)—To select software entries for purging, at the "Package Name" prompt, enter a partial or full software application name. You can optionally enter partial or full version numbers. The list of candidates for purging contains all entries (excluding patch entries) whose first characters match all characters in the software name that you specify. If you enter "ALL", all software (but *not* patches) are selected for purging.
- **Patches**—Patches are a special case. To select patch entries for purging, you *must* enter the full namespace of the patch, the full version number, and an asterisk. You can optionally add a partial or full patch number after the asterisk. The list of candidates for purging contain all entries whose first characters match all characters in the string you specify.

Figure 301: Purge or Install Files option—Sample user dialogue

```
Select Utilities Option: PURGE OR INSTALL FILES
      Select one of the following:
                    Build
                    Install
          Т
Purge from what file: B
Versions to Retain: (0-100): 1// 0
Package Name: ALL// ZXG
Another Package Name: <Enter> ...
Package(s) in Build file, Don't retain any versions
                                                      Page 1
ZXG 1.0
ZXG 2.0
ZXG 3.0
OK to DELETE these entries? NO// YES
Select Utilities Option:
```

24.6.3 Purging Selected Entries

Based on the software name you enter and the number of entries you ask to retain, the option lists the software it finds to purge. If you answer **YES** to the "OK to DELETE these entries? NO//" prompt, the option purges the listed entries.

24.6.4 Reasons to Retain BUILD and INSTALL File Entries

- **BUILD file**—Entries in the BUILD file (#9.6) are created by the software developers and identify every component in the software. BUILD file (#9.6) entries also contain the checksums for a software application's components. You may want to retain the build entry for the most recent versions of installed software, so that you can verify the checksums of the loaded software against its original checksums.
- **INSTALL file**—Each entry in the INSTALL file (#9.7) contains a record of the installation for a given software application. This information is useful as a record of each installation.

24.7 Rollup Patches into a Build Option

The Rollup Patches into a Build option [XPD ROLLUP PATCHES] finds all the patches for a software application and add their individual BUILD file (#9.6) definitions to the software's BUILD file (#9.6) definition. This enables you to create a single BUILD file (#9.6) entry that contains the definition for the patched software.

KIDS checks the BUILD file (#9.6) and lists all KIDS patches with a matching software name and version number. The list of patches is not necessarily displayed in patch sequence number.

This list only includes KIDS patches. Also, it does *not* include any pre- or post-install routines. You can use the Edit a Build option to further modify the build and add any additional patches.

Figure 302: Rollup Patches into a Build option—Sample user dialogue

24.8 Update Routine File Option

The Update Routine File option [XPD ROUTINE UPDATE] updates the ROUTINE file (#9.8) to match the routine set stored on the current system.

Ideally, the ROUTINE file (#9.8) would contain an entry for every routine on the current system. However, the ROUTINE file (#9.8) does *not* get updated automatically when routines are added to or deleted from the system. But KIDS needs the ROUTINE file (#9.8) so that it can store the list of routines in a software application as pointers to the ROUTINE file (#9.8) (rather than relying on namespace alone).

Developers should use this option to update the ROUTINE file (#9.8) before editing the routine component in a build entry, to ensure that all the routines they want to include in a software application can be selected by the routines' matching entries in the ROUTINE file (#9.8).

If you answer **YES** to the question "Want me to clean up the Routine file before updating?", the option goes through the ROUTINE file (#9.8) and deletes any entries across all namespaces that have no matches with an actual routine on the current system. As of Kernel patch XU*8.0*393, however, any routine that has been marked in the CHECKSUM REPORT field (#6) in the ROUTINE file (#9.8) as "National" is *not* deleted during the clean up the Routine File phase of the update.

Then, the Update Routine File option re-populates the ROUTINE file (#9.8) with all routines currently on the system for the namespaces you enter (you can exclude parts of a namespace if you want, as well).

Figure 303: Update Routine File option—Sample user dialogue

24.9 Verify a Build Option

The Verify a Build option [XPD VERIFY BUILD] checks whether a build entry's listed components actually exist on the current system. This is useful for developers who are preparing to create a transport global. They can check that there are actual components on the system matching the components requested in the build entry, in advance of trying to create a transport global. Therefore, developers should use the Verify a Build option *before* creating transport globals from build entries.

For any component in the build entry that does not actually exist on the system, the option outputs a one-line message identifying the missing component, with the appellation **NOT FOUND**. The developer is also prompted with "Do you want to remove the missing Files? NO//". This allows you to verify if the missing component should in fact be removed from the build. If the missing component is required, the developer should create the missing component for the build entry before creating a transport global.

Figure 304: Verify a Build option—Sample user dialogue

```
Select Utilities Option: VERIFY A BUILD
Select BUILD NAME: XU*8.0*11 <Enter> KERNEL
File #8995 ** NOT FOUND **
Do you want to remove the missing Files? NO// <Enter>
** DONE **
Select Utilities Option:
```

24.10 Verify Package Integrity Option

You can use the Verify Package Integrity option [XPD VERIFY INTEGRITY] to compare checksums of software components on the system against the checksums of the components when they were originally transported. Any discrepancies are reported. Currently, routines are the only components that are checked, but checksums are extended to other software components in the future.

The checksums of components for the currently installed software are verified against checksums stored in the BUILD file (#9.6) entry for the software. If the most recent version of the BUILD file (#9.6) entry for a software application has been purged, the Verify Package Integrity option is no longer able to verify checksums for the loaded software. Because of this, in most cases you should *not* purge the most recent build entry for a software application.

As of Kernel patch XU*8.0*369, the integrity checking CHECK1^XTSUMBLD routine supports the Compare local/national checksums report option [XU CHECKSUM REPORT].

As of Kernel patch XU*8.0*393, KIDS was modified to send a message to a server on FORUM when a KIDS build is sent to a Host File Server (HFS) device. This message contains the checksums for the routines in the patch. The server on FORUM matches the message with a patch if the sending domain is authorized on FORUM. There is no longer a need for developers to manually include routine checksums (either CHECK^XTSUMBLD or CHECK1^XTSUMBLD routines) in the patch description. The patch module includes the before and after CHECK1^XTSUMBLD values in the Routine Information section at the end of the patch document.

With changes in the National Patch Module (NPM) on FORUM, when the patch is released the checksums for the routines are moved to the ROUTINE file (#9.8) on FORUM. The checksum "before" values come from the FORUM ROUTINE file (#9.8) and are considered the GOLD standard for released checksums. The local site's Compare local/national checksums report option [XU CHECKSUM REPORT] uses the FORUM ROUTINE file (#9.8) as its source to create reports showing any routines that do *not* match.

This patch also modified the KIDS BUILD file (#9.6) by adding the TRANSPORT BUILD NUMBER field (#63) used to store a build number that is incremented each time a build is made. This build number is added to the second line of each routine in the 7th ";" piece. This makes it easy to tell if a site is running the current release during testing and afterword. The leading "B" found in the checksum tells the code what checksum API to use.

VI. Toolkit

This section provides descriptive information about the set of software utilities furnished by Kernel Version 8.0 and Kernel Toolkit Version 7.3 (a.k.a. "Toolkit"), describing how these tools can be used for the management and definition of development projects.

The major areas of the Kernel Toolkit described in this section are listed below:

• Multi-Term Look-Up (MTLU):

Multi-Term Look-Up (MTLU) utilities provide a method of enhancing the lookup capabilities of associated VA FileMan files. Multi-Term Look-Up (MTLU) is an adaptation of a tool developed by the Indian Health Service (IHS) which was originally made generic by the Albany Office of Information Field Office (OIFO). MTLU does the following:

- Tests ICD diagnosis and procedure codes, CPT codes, and other commonly used references that have been entered in the LOCAL LOOKUP file (#8984.4). Optionally, terms or phrases can be entered into the LOCAL KEYWORD (#8984.1), LOCAL SHORTCUT (#8984.2), or LOCAL SYNONYM (#8984.3) files.
- o Prints a list of shortcuts, keywords, or synonyms from a specified reference file in the LOCAL LOOKUP file (#8984.4).
- o Adds or deletes a reference file from a site's LOCAL LOOKUP file (#8984.4).
- Enters new or edit existing shortcuts, keywords, or synonyms to the LOCAL LOOKUP file (#8984.4).

Routine Tools:

Routine Tools provide a set of generic tools to aid the VistA development community and system administrators in analysis, writing, and testing of code. These tools are used by VistA developers to support distinct tasks. Routine Tools do the following:

- o Promote standard program interfaces.
- Check adherence to programming standards and correct syntax with the XINDEX utility.
- o Provide standard error trapping, storing, and reporting.
- o Customize and tunes site parameters for local requirements.
- Provide M function libraries.
- o Provide a portable routine and global editor.
- o Provide a Kermit file transfer utility.
- o Provide a Multi-Term Look-Up (MTLU) utility for enhanced VA FileMan lookups.
- o Provide software project management utilities.

• Verification Tools:

Verification Tools are a set of generic tools to aid the VistA development community and system administrators in reviewing M code. These tools are used by VistA developers to support distinct tasks. Verification Tools provide the following:

- o Tools used for comparison of routines and data dictionaries.
- o A tool used to record routine text indicated in the file used to maintain changes in routines.

Where applicable, each major area of Kernel Toolkit is described first in terms of its user interface then in terms of system management implications, showing the menu that can be used to accomplish the task at hand.



REF: Kernel and Kernel Toolkit Application Program Interfaces (APIs) are documented in the "Toolkit: Developer Tools" chapter in the *Kernel Developer's Guide*. Kernel and Kernel Toolkit APIs are also available in HTML format at a VA Intranet Website.



NOTE: The *Parameter Tools Supplement to Patch Description (Patch XT*7.3*26)* explains the functions available with the use of the Parameter Tools, provides information on the Kernel PARAMETERS file (#8989.5), and describes the associated Application Program Interfaces (APIs).



REF: This documentation can be downloaded from the VA Software Document Library (VDL) at: http://www.va.gov/vdl/application.asp?appID=12

The following Kernel Toolkit chapters were removed from the "Toolkit" section of this manual because they are superseded by subsequent software and documentation:

• Duplicate Record Merge:

The Kernel Toolkit "Duplicate Record Merge" documentation is superseded by the *Duplicate Record Merge: Patient Merge* software/documentation (i.e., Kernel Toolkit patch XT*7.3*23).

The Duplicate Record Merge functionality provides a developer Merge Shell with options that allow users to check data files for duplicate entries and merge those entries if any are found. These options provide functionality to combine duplicate records based on conditions established in customized applications . The Merge Shell was originally developed by Indian Health Service (IHS) to support their Multi-Facility Integration Project.



REF: For instructions on how to build a merge capability for a file, see the "Developing a File Merge Capability" section in the *Kernel Developer's Guide* available on the VA Software Document Library (VDL) at: http://www.va.gov/vdl/application.asp?appid=10



REF: The *Duplicate Record Merge: Patient Merge* documentation is available on the VDL at: http://www.va.gov/vdl/application.asp?appid=2

• Capacity Management:

The Kernel Toolkit "Capacity Management" documentation is superseded by the following software/documentation:

- o Capacity Management (CM) Tools 3.0
- o Resource Usage Monitor (RUM) 2.0
- o Statistical Analysis of Global Growth (SAGG) 2.0

0

REF: The Capacity Management-related documentation is available on the VDL at:

- Capacity Management (CM) Tools: http://www.va.gov/vdl/application.asp?appid=129
- Resource Usage Monitor (RUM): http://www.va.gov/vdl/application.asp?appid=130
- Statistical Analysis of Global Growth (SAGG): http://www.va.gov/vdl/application.asp?appid=115

Kernel Toolkit patch XT*7.3*102 removed all options, routines, and files associated with the following menus and options:

- VPM VAX/ALPHA Capacity Management ...
- Move Host File to Mailman
- Response Time Log Options ...

The following namespace options and routines are also removed:

- XUCM*
- XUCS*
- XURTL*
- XTCM DISK2MAIL(option)
- XTCMXTCMFILN (routine)

Data dictionaries and data have been deleted for the following VA FileMan compatible files:

- Global ^XUCM:
 - o CM DAILY STATISTICS (#8986.6)
 - o CM DISK DRIVE RAW DATA (#8986.5)
 - o CM METRICS (#8986.4)
 - o CM NODENAME RAW DATA (#8986.51)
 - o CM SITE DISKDRIVES (#8986.35)
 - o CM SITE NODENAMES (#8986.3)
 - o CM SITE PARAMETERS (#8986.095)
 - o VPM RESPONSE TIME DATA (#8986.098)
- Global ^%ZRTL:
 - o RESPONSE TIME (#3.091)
 - o RT DATE_UCI,VOL (#3.092)
 - o RT RAWDATA (#3.094)

Data has been deleted for the following non-VA FileMan compatible global:

- ^%ZRTL(3)
- ^%ZRTL("RTH")



NOTE to System Managers: The ^XUCM and %ZRTL globals can be removed from your database after installation of this patch; however, please make sure no local routines access these globals before doing so.

25 Multi-Term Look-Up (MTLU)

25.1 Overview

This chapter contains an introduction and functional description, site implementation instructions for Multi-Term Look-Up (MTLU), and the option documentation.

25.2 Introduction to Multi-Term Look-Up (MTLU)

Many medical information systems depend on the standardized encoding of diagnoses and procedures for reports, searches, and statistics. The ICD DIAGNOSIS (#80), ICD OPERATION/PROCEDURE (#80.1), and CPT (#81) files are among some of the more critical files. The Multi-Term Look-Up utility increases the accessibility of the information in these files by associating user-supplied words or phrases with terms found in a more descriptive, free-text field.

Multi-Term Look-Up allows:

- Local setup of virtually any reference file.
- Modification of the behavior of the "special" lookup by defining shortcuts, synonyms, or keywords.

MTLU integrates with any software that uses a reference file that has been entered into a site's LOCAL LOOKUP file (#8984.4).

25.3 Functional Description

The Multi-Term Look-Up (MTLU) utility provides a method of enhancing the lookup capabilities of associated software applications. This utility is comprised of the following options:

- The Multi-Term Lookup (MTLU) option [XTLKLKUP] is used to test ICD diagnosis and procedure codes, CPT codes, and other commonly used references that have been entered in the LOCAL LOOKUP file (#8984.4). Optionally, terms or phrases may be entered into the LOCAL KEYWORD (#8984.1), LOCAL SHORTCUT (#8984.2), or LOCAL SYNONYM (#8984.3), files.
- The Print Utility option [XTLKPRTUTL] is used to print a list of shortcuts, keywords, or synonyms from a specified reference file in the LOCAL LOOKUP file (#8984.4). This list can be sorted alphabetically by name or numerically by code.
- The Delete Entries from Look-Up option [XTLKMODPARK]is used to delete a reference file from a site's LOCAL LOOKUP file (#8984.4). This option should be used as a system administrator/developer utility and can only be accessed by holders of the XTLKZMGR security key.
- The Add Entries To Look-Up File option [XTLKMODPARS]is used to add reference files to a site's LOCAL LOOKUP file (#8984.4). This option should be used as a system administrator/developer utility and can only be accessed by holders of the XTLKZMGR security key. In order to add entries with this option, DUZ(0) *must* be set to an at-sign ("@"; programmer access).

- The Add/Modify Utility option [XTLKMODUTL] is used to enter new or edit existing shortcuts, keywords, or synonyms to the LOCAL LOOKUP file (#8984.4) as described below:
 - o The Shortcuts option [XTLKMODSH] is used to enter new or edit existing shortcuts to the LOCAL LOOKUP file (#8984.4).
 - o The Keywords option [XTLKMODKY] is used to enter new or edit existing keywords to the LOCAL LOOKUP file (#8984.4).
 - The Synonyms option [XTLKMODSY] is used to enter new or edit existing synonyms to the LOCAL LOOKUP file (#8984.4).

25.4 Usage Considerations

MTLU provides users and developers with the ability to perform specialized lookups on database files using standard VA FileMan calls. These files typically comprise a number or "term" in the .01 field and a longer description or definition in some other field.

In the simplest application of MTLU, a special lookup routine (XTLKDICL) is defined in the file's data dictionary (DD), then a MUMPS cross-reference is applied to the description/definition field. Options are available to fully configure a file for use with MTLU. FileMan is used to create/build the cross-reference. To set the cross-reference, text from the selected field is passed to a tokenizing routine (XTLKTOKN). Trivial words are filtered by an expanded Key Word In Context (KWIC), then each remaining token is added to the cross-reference.

To request a lookup, users and developers can pass in words or phrases. Their input is similarly tokenized. However, only terms associated with *all* tokens entered are found. Input can be generalized using partial words or fewer words as well as lexical variants. For example, using the FileMan Inquire to File Entries option on the ICD DIAGNOSIS file (#80) one could first enter "MALIG". MTLU informs the user which terms apply to the search, "MALIG/MALIGNANT", and that 447 matches are found. To be more specific, the user might enter "MALIG LIP" to request all malignancies associated with the lip. In this case, only 12 matches are found. The user can further screen searches by using the Not-Sign (') before a word or phrase. To request all malignancies of the lip *except* those of the lower lip, one could enter "MALIG LIP 'LOWER" and obtain 10 matches. Though the term "malignancies" may not exist in the lookup file, MTLU might still produce a match. When a term contains a suffix that does not produce a match, MTLU removes the suffix and continues the search.



REF: For more information on the Inquire to File Entries option, see the "Print" chapter in the VA FileMan User Manual.

Three additional files are supplied that can dramatically alter the predictable behavior described above. They are checked in the following order against the user's entry:

- 1. LOCAL SHORTCUT file (#8984.2): Shortcuts are used to point to a single term. They can be a word or phrase. MTLU checks the user's entry against this file first for an exact match. If found, the lookup displays only the associated entry. A single shortcut *cannot* point to multiple terms.
- 2. LOCAL SYNONYM file (#8984.3): Synonyms can be associated with many terms in a file because they can be associated with multiple "tokens" rather than a specific term. For example, CANCER can be defined as a synonym of "MALIG", "TUMOR", and "LEUKEMIA". When the user enters CANCER, the lookup finds *all* terms associated with the three tokens as if each had been entered separately. Compared with the example above, CANCER returns 534 matches. CANCER LIP returns the same 12 matches as MALIG LIP.
- 3. LOCAL KEYWORD file (#8984.1): A keyword or phrase can be associated with a single term, much like a shortcut; however, it can also be associated with multiple terms, and multiple keywords can be associated with the same term.

The term SMOKER can be used as a synonym or keyword. As a keyword, one can associate it with a few *specific* diseases. As a synonym, properly selected tokens might result in a display of all smoking-related diseases.

Recall that MALIG results in 447 matches. If this were used as a shortcut to a single entry, MTLU would display only that entry and the remaining 446 would never be displayed.

These files add some control over the behavior of certain lookups. However, developers should use extreme caution when placing entries in these files to ensure that results are predictable and appropriate for both users and other VistA software developers.

The decision to populate them for a given lookup file depends on whether or not a commonly used word or phrase results in any matches during a lookup. If not, it is a candidate. The LOCAL KEYWORD (#8984.1), LOCAL SHORTCUT (#8984.2), and LOCAL SYNONYM (#8984.3) files should only be populated with common words or phrases.

In the event that a search produces no matches, MTLU continues with a standard FileMan search.

25.5 User Interface

25.5.1 Multi-Term Look-Up Menu Options

The following is a description of the Multi-Term Lookup Main Menu [XTLKUSER2] which can be selected from the Application Utilities menu [XTMENU]. The options are described in the same order as they appear on the screen:

Figure 305: Multi-Term Lookup Main Menu options

```
Application Utilities ...
                                                                             [XTMENU]
   Multi-Term Lookup Main Menu ...
                                                                          [XTLKUSER2]
     Multi-Term Lookup (MTLU)
                                                                           [XTLKLKUP]
     Print Utility
                                                                         [XTLKPRTUTL]
     Utilities for MTLU ... <Locked with XTLKZMGR>
                                                                      [XTLKUTILITIES]
     Delete Entries From Look-up <Locked with XTLKZMGR>
                                                                        [XTLKMODPARK]
     ST Add Entries To Look-Up File <Locked with XTLKZMGR>
                                                                        [XTLKMODPARS]
     Add/Modify Utility...
                                                                         [XTLKMODUTL]
```

Most MTLU options are described using the following methods:

- Introduction—A detailed description of the option is given. The introduction usually contains any necessary special instructions.
- Process Chart—The step-by-step flow of the option is illustrated, showing the various choices allowed at each prompt.
- Examples—In most cases, there is an example of what might appear on the screen when using the particular option. If the option produces a hardcopy output, an example of the output is usually given.

The phrase "You will be prompted for a device at this step" appears in the process chart when a device is asked for. A Standard Device Chart is shown on the next page. It provides assistance in answering prompts related to device selection.

The MTLU Process Charts do *not* contain documentation of the system's response to erroneous input. In certain instances, in order to preserve the integrity of previously entered data, the system does *not* allow the entry of a caret (^, sometimes referred to as an up-arrow). This might not be documented.

The following chart provides assistance in answering prompts related to device selection:

25.5.1.1 Standard Device Chart

Figure 306: Standard Device Chart

IF USER ANSWERS WITH Device name/number from your DEVICE file (#3.5) for report to print on 'Q'UEUE to have report queued to print at a Later date/time <enter> for report to Print on your screen Up-arrow <^> Device name/number from your DEVICE file (#3.5) for report to Print on your screen Up-arrow <^> RIGHT MARGIN: 132// *<enter> to accept default, different RIGHT MARGIN Value, or up-arrow <^> *The next step depends on what you entered in Step Device name/number "Q" <enter> (The report appears on y screen) WANT TO FREE UP THIS TERMINAL? NO// *Enter> to accept default 'Y'ES to free up terminal during report processing and to exit from the system Up-arrow <^> Device name/number 'Y'ES to free up terminal during report processing and to exit from the system Up-arrow <^> Up-arrow <^> Up-arrow <^> View of the report appears on y screen Up-arrow <^> Up-arrow <^> Up-arrow <^> Up-arrow <^> VIEUE Device name/number from your DEVICE file (#3.5) for report to print on (#3.5) for print on (*4.5) for print on (*5.5) for print on (*5</enter></enter></enter>	
from your DEVICE file (#3.5) for report to print on	THEN STEP
your DEVICE file (#3.5) for report to print on	2
different RIGHT MARGIN Value, or up-arrow <^>	
Device name/number	6
TERMINAL? NO// <enter> to accept default 'Y'ES to free up terminal during report processing and to exit from the system</enter>	4 5 our
	5
REQUESTED TIME TO PRINT: * <enter> to accept default *Later date/time for report process to begin Up-arrow <^></enter>	6
*If <enter> or later date/time is entered, the following message appears: "REQUEST QUEUED!"</enter>	
Return to the menu.	

25.5.2 Using the Multi-Term Lookup (MTLU) Option

The Multi-Term Lookup (MTLU) option [XTLKLKUP] is used to test the ICD diagnosis and procedure codes, CPT codes, and other commonly used references that have been entered in the LOCAL LOOKUP file (#8984.4) and have been associated with a shortcut, synonym, or keyword.

The system searches for entries in the following order: shortcut, synonym, then keyword. If you are entering a multi-term narrative (phrase), you can enter double spaces between each term to avoid a search of the LOCAL SHORTCUT file (#8984.2). When searching for a keyword phrase, the system searches for each word in the phrase and then displays all common entries. For example, if the keyword is FRACTURE FEMUR, the system searches for FRACTURE and then FEMUR and displays only those codes with a diagnosis containing both keywords or synonyms of those words.

The following process chart shows the prompts and steps involved in using the Multi-Term Lookup (MTLU) option:

Figure 307: Multi-Term Lookup (MTLU) option process chart

STEP	AT THIS PROMPT	IF USER ANSWERS WITH	THEN STEP
1	Lookup on which file?:	Name of entry in LOCAL LOOKUP file (#8984.4)	1
2	NARRATIVE:	Existing shortcut, synonym, or keyword	3
	If a word, phrase, or symbol identify, the following appear	is entered that the system cannot ars:	
	"Narrative contained no usable words.		
	The following word(s) was not used in this search: {word(s)}		
	Search was unsuccessful."		
	in the following order: short one entry is found, they are	tion is displayed. The system searc tcut, synonym, then keyword. If mor displayed, and you are prompted to y is found, the following appears:	e than
3	OK? Y//	<enter> to accept default 'N'O</enter>	
4	Return to the menu.		

The following is an example of what might appear on your screen when using the Multi-Term Lookup (MTLU) option:

Figure 308: Multi-Term Lookup (MTLU) option—Sample user entries

```
Lookup on which file?: ICD DIAGNOSIS

NARRATIVE: DIABETES MELLITUS
( DIABETES DIABETIC MELLITUS )
....

The following 3 matches were found:

1: 250.00 (250.00)
    DIABETES UNCOMPL ADULT/NIDDM
2: 250.40 (250.40)
    DIAB RENAL MANIF ADULT/NIDDM
3: 775.0 (775.0)
    INFANT DIABET MOTHER SYN

Select 1-3: 2
```

25.5.3 Using the Print Utility Option

The Print Utility option [XTLKPRTUTL] is used to print a list of shortcuts, keywords, or synonyms from a specified reference file in the LOCAL LOOKUP file (#8984.4). Both the shortcut and keyword lists can be sorted alphabetically by name or numerically by code. The synonym list, however, only prints alphabetically.

Since these lists can be long and the generation time consuming, it is suggested you queue the report to a device during off hours.


The following process chart shows the prompts and steps involved in using the Print Utility option:

Figure 309: Print Utility option process chart

CITIED	ATT THE DROWN	IF USER	THEN
STEP	AT THIS PROMPT	ANSWERS WITH	STEP
1	Select one of the following:		
	SH Shortcuts KE Keyword SY Synonyms		
	Print which file?:	SH for Shortcuts KE for Keywords SY for Synonym	2
2	Select one of the following:		
	A Alphabetic C Code		
	Sort By?:	`A'lphabetic `C'ode	3
3	Print {Shortcuts, Keywords, o Synonyms} for which file?:	Name of entry in LOCAL LOOKUP file (#8984.4)	3
4	You will be prompted for a de	vice at this step	1
5	Return to the menu.		

The following is an example of what might appear on your screen when using the Print Utility option (an example of the output generated by this option is provided following the computer dialogue):

Figure 310: Print Utility option—Sample user entries and sample output



25.5.4 Using the Utilities for MTLU Option

The following is a list of the options and their descriptions that comprise the Utilities for MTLU menu [XTLKUTILITIES]. This option can only be accessed by holders of the XTLKZMGR security key:

- The Delete Entries From Look-Up option [XTLKMODPARK] deletes entries from the LOCAL LOOKUP file (#8984.4). In order to do this, there *cannot* be any shortcuts, synonyms, or keywords associated with the file to be deleted. This option should be used as a system administrator/developer utility and can only be accessed by holders of the XTLKZMGR security key.
- The Add Entries To Look-Up File option [XTLKMODPARS] sets entries in the LOCAL LOOKUP file (#8984.4). This option should be used as a system administrator/developer utility and can only be accessed by holders of the XTLKZMGR security key. In order to add entries with this option, DUZ(0) *must* be set to an at-sign ("@"; programmer access).
- The Add/Modify Utility option [XTLKMODUTL] is used to make or edit entries in the LOCAL KEYWORD (#8984.1), LOCAL SHORTCUT (#8984.2), and LOCAL SYNONYM (#8984.3) files.

25.5.4.1 Delete Entries from Look-Up Option

The Delete Entries From Look-Up option [XTLKMODPARK] is used to delete a reference file from a site's LOCAL LOOKUP file (#8984.4).

All shortcuts, synonyms, and keywords associated with the reference file you wish to delete *must* be canceled before you attempt to delete the file.

It should be noted that when a reference file is "killed" through this option, all variable pointers from the LOCAL KEYWORD (#8984.1) and LOCAL SHORTCUT (#8984.2) files are deleted. The special lookup routine for the file is also deleted.

Only holders of the XTLKZMGR security key, can access this option.



NOTE: Due to the brevity of this option, no process chart has been provided.

The following is an example of what might appear on your screen when using the Delete Entries From Look-Up option:

Figure 311: Delete Entries From Look-Up option—Sample user entries

```
Select LOCAL LOOKUP NAME: PROCEDURE MODIFIERS

Are you sure you want to delete PROCEDURE MODIFIERS? YES

Deleting from Local Lookup file....

Deleting variable pointers from Local Keyword and Shortcut files.

Deleting special lookup routine from PROCEDURE MODIFIERS DD.
```

25.5.4.2 Add Entries To Look-Up File Option

The Add Entries To Look-Up File option [XTLKMODPARS] is used to add/edit reference files to a site's LOCAL LOOKUP file (#8984.4). Examples of files that a site might wish to enter in their LOCAL LOOKUP file (#8984.4) include: ICD DIAGNOSIS (#80), ICD OPERATION/PROCEDURE (#80.1), and CPT (#81).

Only holders of the XTLKZMGR security key, can access this option. In order to add entries with this option, DUZ(0) *must* be set to an at-sign ("@"; programmer access).

The process chart below shows the prompts and steps involved in using the Add Entries To Look-Up File option:

Figure 312: Add Entries To Look-Up File option process chart (1 of 2)

STEP	AT THIS PROMPT	IF USER ANSWERS WITH	THEN STEP
1	Select LOCAL LOOKUP NAME:	Name of new reference file you wish to enter in LOCAL LOOKUP file (#8984.4 for file list	1
2	ARE YOU ADDING {reference file name} AS A NEW LOCAL LOOKUP (THE nTH)?	`Y'ES	
3	LOCAL LOOKUP NAME: {reference file name}//	<pre><enter> to accept default Other file name</enter></pre>	
4	LOCAL LOOKUP DISPLAY PROTOCOL:	Entry point for routine to determine the display format	
	If the entry made at this step cross reference in the descrip the software still functions, keywords entered in the LOCAL	tion field of the file, but it only uses the	_

^{*}Required field

Figure 313: Add Entries To Look-Up File option process chart (2 of 2)

STEP	AT THIS PROMPT	IF USER THEN ANSWERS WITH STEP
* 5	INDEX:	Cross reference to be used to create new key-words6
	NOTE: The following message i	
	"Ok, will now setup terms for $\{ reference \ fi \}$	KEYWORD and SHORTCUT file DD's to allow le name} entries"
* 6	PREFIX: M//:	Letter(s) to be used to identify a variable pointer7
7	The following reminder message	e is displayed:
		set the lookup routine, XTLKDICL, in1
	The selected file is displayed	ı.
8	OK? YES//	<pre><enter> to accept default9 `N'O1</enter></pre>
9	LOCAL LOOKUP NAME: {reference file name}//	<pre><enter> to accept default10 Correct file name</enter></pre>
10	LOCAL LOOKUP DISPLAY PROTOCOL: {protocol}//	<enter> to accept default</enter>
11	INDEX: {index}//	<pre><enter> to accept default12 correct cross reference to be used to create new Keywords12</enter></pre>
12	Return to the menu.	

^{*}Required field

The following is an example of what might appear on your screen when using the Add Entries To Look-Up File option:

Figure 314: Add Entries To Look-Up File option—Sample user entries

25.5.4.3 Add/Modify Utility Option

The Add/Modify Utility option [XTLKMODUTL] is used to enter new or edit existing shortcuts, keywords, or synonyms to the LOCAL LOOKUP file (#8984.4).

A shortcut is a word or phrase which recognizes one specific code or procedure. If you are adding a shortcut whose text duplicates the first part of an existing entry, you *must* enclose the new shortcut word or phrase in double quotes to prevent the system from matching it to existing terms.

A keyword is a word or phrase which corresponds to several related codes or procedures. Keywords are typically terms commonly used to describe a clinical entity. Entering a series of keywords separated by single spaces results in all of the keywords being added to the specified code.

A synonym is a word entered to expand the lookup capability of an existing term or terms in the LOCAL LOOKUP file (#8984.4). Synonyms would be used in cases where several words within the text of codes or procedures have the same diagnostic meaning (e.g., CANCER and MALIGNANCY). A synonym can be entered for an existing keyword or for a word in the diagnostic description or procedure (e.g., the term CANCER might be matched to the synonyms MALIGNANCY, LEUKEMIA, and CARCINOMA). When CANCER is referenced in the Multi-Term Lookup (MTLU) option, it recognizes all the codes and descriptions associated with MALIGNANCY, LEUKEMIA, and CARCINOMA.



NOTE: A synonym replaces the original word in the lookup process; therefore, to retain the original word in the search, it *must* be matched to itself as well as to other synonyms.

Words used as a shortcut should never be repeated as synonyms or keywords. Since the system searches for shortcuts first and stops when one is found, it cannot find duplicated words in the LOCAL SYNONYM (#8984.3) or LOCAL KEYWORD (#8984.1) files. Since searching all files for each word is time consuming, the search is done in this order so as to speed up the search process.

Since the add/modify functions for Shortcuts, Keywords, and Synonyms are considered separate options, a process chart for each is provided. The charts on the following pages show the prompts and steps involved in using the following options:

Figure 315: Add/Modify Utility menu options

```
Select Add/Modify Utility Option: ??

SH Shortcuts

KE Keywords

SY Synonyms

[XTLKMODSH]

[XTLKMODSY]
```

The Shortcuts option [XTLKMODSH], one of the three selections within the Add/Modify Utility option, is described below.

The following process chart shows the prompts and steps involved in using the Add/Modify Utility option when adding or editing a shortcut:

Figure 316: Add/Modify Utility option—Shortcuts process chart (1 of 2)

		IF USER THEN
STEP	AT THIS PROMPT	ANSWERS WITH STEP
1	SH Shortcuts KE Keywords SY Synonyms	
	Select Add/Modify Utility Option:	SH for Shortcuts
2	Additions/Modifications to Shortcuts in which file?	Name of entry in local reference file
3	Select LOCAL SHORTCUT FREQUENTLY USED NARRATIVE:	New text you wish to use as a shortcut
4	ARE YOU ADDING { 'text'} AS A NEW LOCAL SHORTCUT? An at-sign (@) entered at this	'Y'ES
5	LOCAL SHORTCUT FREQUENTLY	
	USED NARRATIVE: {shortcut}//	<pre><enter> to accept default6 Other text6</enter></pre>
6	LOCAL SHORTCUT ENTRY:	Name or number of entry in LOCAL LOOKUP file (#8984.4) you wish your shortcut to reference

Figure 317: Add/Modify Utility option—Shortcuts process chart (2 of 2)

STEP	AT THIS PROMPT	IF USER ANSWERS WITH	THEN STEP
7	If the selected number/name corresponds to more than one entry, they are shown and you are prompted to choose one. If there is only one corresponding entry, it is displayed and the following appears:		they one
	"OK? YES//	<enter> to accept default</enter>	
8	LOCAL SHORTCUT FREQUENTLY USED NARRATIVE: {shortcut}//	<pre><enter> to accept default Correct shortcut term</enter></pre>	
9	LOCAL SHORTCUT ENTRY: {code}//	<enter> to accept default Correct code</enter>	
	The selected code is displayed	1.	
10	OK? YES//	<pre><enter> to accept default 'N'0</enter></pre>	
11	Return to the menu.		

The Keywords option [XTLKMODKY], one of the three selections within the Add/Modify Utility option, is described below.

The following process chart shows the prompts and steps involved in using the Add/Modify Utility option when adding or editing a keyword:

Figure 318: Add/Modify Utility option—Keywords process chart

STEP	AT TUIC DDOMDT	IF USER	THEN
<u>SIEP</u> 1	AT THIS PROMPT SH Shortcuts KE Keywords SY Synonyms	ANSWERS WITH	<u>STEP</u>
	Select Add/Modify Utility Option:	KE for Keywords <pre><enter> or up-arrow <^></enter></pre>	
2	Additions/Modifications to Keywords in which file?	Name of entry in local reference file	2
3	Which code in the {file name} file?	Code for which you wish to enter a keyword	4
4	Select LOCAL KEYWORD NAME:	New text you wish to use as a keyword	6
5	ARE YOU ADDING {\text'} AS A NEW LOCAL KEYWORD?	'Y'ES' 'N'O or <enter></enter>	
	An at-sign (@) entered at this	step deletes the entire entry.	
6	LOCAL KEYWORD NAME: {keyword}//	<pre><enter> to accept default Correct keyword term</enter></pre>	
7	Return to the menu.		

The Synonyms option [XTLKMODSY], one of the three selections within the Add/Modify Utility option, is described below.

The following process chart shows the prompts and steps involved in using the Add/Modify Utility option when adding or editing a synonym:

Figure 319: Add/Modify Utility option—Adding or editing a synonym process chart (1 of 2)

		IF USER	THEN
STEP	AT THIS PROMPT	ANSWERS WITH	STEP
1	SH Shortcuts KE Keywords SY Synonyms		
	Select Add/Modify Utility Option:	SY for Synonyms< Enter> or up-arrow <^>	
2	Additions/Modifications to Synonyms in which file?	Name of entry in local reference file	2
	The entry made at this step mu letters.	st be in all upper case	
3	Select LOCAL SYNONYM TERM:	New text you wish to use as a synonym	7
4	ARE YOU ADDING {\text'} AS A NEW LOCAL SYNONYM?	`Y'ES	
	An at-sign (@) entered at this	step deletes the entire entry.	
5	LOCAL SYNONYM TERM: {synonym}//	<enter> to accept default Other text</enter>	
6	LOCAL SYNONYM Select SYNONYM:	Existing term in LOCAL LOOKUP file (#8984.4) for which you are entering a synonym	2

Figure 320: Add/Modify Utility option—Adding or editing a synonym process chart (2 of 2)

STEP	AT THIS PROMPT	IF USER ANSWERS	WITH	THEN STEP
7	TERM: {term entered at Step 3}//		to accept defaultsynonym term	
	The entry made at this step mu letters.	st be in	all upper case	
8	Select SYNONYM: {term synonym was entered for}//		to accept defaultterm	
9	Return to the menu.			

25.5.5 Examples

The following are examples of what might appear on your screen when using the Add/Modify Utility option. The first example is for a new shortcut entry, the second example shows a new keyword entry, and the third shows the editing of an existing synonym entry.

25.5.5.1 Example 1

Illustration of a new Shortcut entry.

Figure 321: Shortcut option—Sample user entries

```
SH Shortcuts
KE Keywords
SY Synonyms

Select Add/Modify Utility Option: SH <Enter> Shortcuts

Additions/Modifications to Shortcuts in which file? CPT

Select LOCAL SHORTCUT FREQUENTLY USED NARRATIVE: COUGH
ARE YOU ADDING 'COUGH' AS A NEW LOCAL SHORTCUT? Y <Enter>
LOCAL SHORTCUT FREQUENTLY USED NARRATIVE: COUGH// <Enter>
LOCAL SHORTCUT ENTRY: 31659

Searching for a CPT 31659 BRONCHOSCOPIC PROCEDURES
...OK? YES// <Enter> (YES)
```

25.5.5.2 Example 2

Illustration of a new Keyword entry.

Figure 322: Keyword option—Sample user entries

```
SH Shortcuts
KE Keywords
SY Synonyms

Select Add/Modify Utility Option: KE <Enter> Keywords

Additions/Modifications to Keywords in which file?: CPT

Which code in the CPT file?: 11044 <Enter> CLEANSING TISSUE/MUSCLE/BONE
Select LOCAL KEYWORD NAME: TISSUE SKIN
ARE YOU ADDING 'TISSUE SKIN' AS A NEW LOCAL KEYWORD? Y <Enter> (YES)
LOCAL KEYWORD NAME: TISSUE SKIN// <Enter>
```

25.5.5.3 Example 3

Illustration of editing an existing Synonym entry.

Figure 323: Synonym option—Sample user entries

```
SH Shortcuts
KE Keywords
SY Synonyms

Select Add/Modify Utility Option: SY <Enter> Synonyms

Additions/Modifications to Synonyms in which file?: CPT

Select LOCAL SYNONYM TERM: SLEEP
TERM: SLEEP// <Enter>
Select SYNONYM: DREAM// NIGHT
```

25.6 Systems Management

25.6.1 Implementation of Multi-Term Look-Up (MTLU)

This is how a user would configure a new file to be used with MTLU. The file you select would typically contain a free text field that more completely describes the record entry. Users would then use a cross-reference on this text field to perform lookups. MTLU is distinguished from FileMan in that users can enter a narrative or phrase, rather than a single term. The cross-reference can be either a VA FileMan Key Word In Context (KWIC) cross-reference, or you can create a custom MUMPS cross-reference that calls the routine, ^XTLKWIC (shown below). The ICD DIAGNOSIS file (#80) is used as an example.



REF: Multi-Term Look-Up (MTLU) Application Programming Interfaces (APIs) are documented in the "Toolkit: Developer Tools" chapter in the *Kernel Developer's Guide*. Kernel and Kernel Toolkit APIs are also available in HTML format at a VA Intranet Website.

Once you are in VA FileMan, do the following:

Figure 324: VA FileMan Utility Functions option—Sample user entries

```
Select OPTION: UTILITY FUNCTIONS
Select UTILITY OPTION: CROSS-REFERENCE A FIELD
MODIFY WHAT FILE: ICD DIAGNOSIS// <Enter> ICD DIAGNOSIS
                                                 (12535 entries)
Select FIELD: DESCRIPTION
CURRENT CROSS-REFERENCE IS MUMPS 'D' INDEX OF FILE
CHOOSE E (EDIT)/D (DELETE)/C (CREATE): C
WANT TO CREATE A NEW CROSS-REFERENCE FOR THIS FIELD? NO// Y <Enter> (YES)
CROSS-REFERENCE NUMBER: 2// <Enter>
Select TYPE OF INDEXING: REGULAR// MUMPS
WANT CROSS-REFERENCE TO BE USED FOR LOOKUP AS WELL AS FOR SORTING? YES// N <Enter>
SET STATEMENT: S %="\(^ICD9(\)"AIHS"\,,I,DA)" D S\(^XTLKWIC\)
KILL STATEMENT: S %=\(^ICD9(\)"AIHS"\,,I,DA)" D K\(^XTLKWIC\)
INDEX: AC// AIHS
NO-DELETION MESSAGE: <Enter>
DESCRIPTION: <Enter>
  Edit? NO// <Enter>
DO YOU WANT TO CROSS-REFERENCE EXISTING DATA NOW? YES// Y <Enter> (YES)
...EXCUSE ME, THIS MAY TAKE A FEW MOMENTS...
```

Figure 325: Add Entries To Look-Up File—Sample user entries

```
>D ^XUP
Setting up programmer environment
Terminal Type set to: C-VT100
Select OPTION NAME: APP <Enter> LICATION UTILITIES XTMENU
                                                              Application
Utilities
          Multi-Term Lookup Main Menu ...
Select Application Utilities Option: MULTI <Enter> -Term Lookup Main Menu
          Multi-Term Lookup (MTLU)
          Print Utility
          Utilities for MTLU ...
Select Multi-Term Lookup Main Menu Option: UTIL <Enter> ities for MTLU
   KL
          Delete Entries From Look-up
          Add Entries To Look-Up File
   ST
          Add/Modify Utility ...
Select Utilities for MTLU Option: ST <Enter> Add Entries To Look-Up File
Select LOCAL LOOKUP NAME: ICD DIAGNOSIS
  ARE YOU ADDING 'ICD DIAGNOSIS' AS A NEW LOCAL LOOKUP (THE 3RD)? Y <Enter> (YES)
  LOCAL LOOKUP NAME: ICD DIAGNOSIS// <Enter>
 LOCAL LOOKUP DISPLAY PROTOCOL: DSPLYD'XTLKKWLD
INDEX: AIHS
...Ok, \overline{\text{will}} now setup KEYWORD and SHORTCUT file DD's
   to allow terms for 'ICD DIAGNOSIS' entries...
PREFIX: M// ?
     Answer must be a unique prefix, 1-10 characters in length
  Enter the "Variable Pointer" prefix.
PREFIX: M// D
  <REMINDER> Using `Edit File', set the lookup routine, XTLKDICL, in ICD
DIAGNOSIS DD
Select LOCAL LOOKUP NAME: <Enter>
```

If *all* references to a file (by all packages) are to behave as MTLU lookups, add the special lookup routine, 'XTLKDICL, to the file's DD using the FileMan Edit File option.



REF: For more information on the Edit File option, see the "File Utilities" chapter in the VA FileMan Advanced User Manual.

Figure 326: VA FileMan Edit File option—Sample user entries

```
VAH, MTL>D Q'DI
VA FileMan 20.0
Select OPTION: UT <Enter> ILITY FUNCTIONS
Select UTILITY OPTION: ED <Enter> IT FILE
MODIFY WHAT FILE: ICD DIAGNOSIS// <Enter>
NAME: ICD DIAGNOSIS// <Enter>
DESCRIPTION: <Enter>
  1>Contains all valid ICD diagnosis codes.
EDIT Option: <Enter>
Select APPLICATION GROUP: <Enter>
PROGRAMMER: <Enter>
VERSION: 9// <Enter>
DATA DICTIONARY ACCESS: <Enter>
READ ACCESS: <Enter>
WRITE ACCESS: <Enter>
DELETE ACCESS: <Enter>
LAYGO ACCESS: <Enter>
AUDIT ACCESS: <Enter>
DD AUDIT? NO// <Enter>
ASK 'OK' WHEN LOOKING UP AN ENTRY? YES// <Enter> (YES)
POST-SELECTION ACTION: <Enter>
LOOK-UP PROGRAM: XTLKDICL
CROSS-REFERENCE ROUTINE: <Enter>
Select UTILITY OPTION: <Enter>
```

- NOTE: The developer might elect to use MTLU only in selected instances. This is accomplished by *not* adding the special lookup routine to the file's DD. After the file has been added to the LOCAL LOOKUP file (#8984.4), you can make a developer call to LKUP^XTLKMGR.
- **REF:** Multi-Term Look-Up (MTLU) Application Programming Interfaces (APIs) are documented in the "Toolkit: Developer Tools" chapter in the *Kernel Developer's Guide*. Kernel and Kernel Toolkit APIs are also available in HTML format at a VA Intranet Website.

Glossary

Term	Definition
ALPHA TESTING	In VA terminology, Alpha testing is when a VistA test software application is running in a site's account.
AUTO MENU	An indication to Menu Manager that the current user's menu items should be displayed automatically. When AUTO MENU is not in effect, the user <i>must</i> enter a question mark at the menu's select prompt to see the list of menu items.
BETA TESTING	In VA terminology, Beta testing is when a VistA test software application is running in a Production account.
CAPACITY MANAGEMENT	The process of assessing a system's capacity and evaluating its efficiency relative to workload in an attempt to optimize system performance. Kernel provides several utilities.
CHECKSUM	A numeric value that is the result of a mathematical computation involving the characters of a routine or file.
CIPHER	A system that arbitrarily represents each character as one or more other characters. (See also: ENCRYPTION.)
COMMON MENU	Options that are available to all users. Entering two question marks ("??") at the menu's select prompt displays any SECONDARY MENU OPTIONS available to the signed-on user along with the common options available to all users.
COMPILED MENU SYSTEM (^XUTL GLOBAL)	Job-specific information that is kept on each CPU so that it is readily available during the user's session. It is stored in the ^XUTL global, which is maintained by the menu system to hold commonly referenced information. The user's place within the menu trees is stored, for example, to enable navigation via menu jumping.
COMPUTED FIELD	This field takes data from other fields and performs a predetermined mathematical function (e.g., adding two columns together). You do <i>not</i> , however, see the results of the mathematical function on the screen. Only when you are printing or displaying information on the screen do you see the results for this type of field.
DEA	Drug Enforcement Administration.
DEVICE HANDLER	The Kernel module that provides a mechanism for accessing peripherals and using them in controlled ways (e.g., user access to printers or other output devices).
DIFROM	VA FileMan utility that gathers all software components and changes them into routines (namespacel* routines) so that they can be exported and installed in another VA FileMan environment.
DOUBLE QUOTE (")	A symbol used in front of a Common option's menu text or synonym to select it from the Common menu. For example, the five character string "TBOX selects the User's Toolbox Common option.

Term	Definition
DR STRING	The set of characters used to define the DR variable when calling VA FileMan. Since a series of parameters may be included within quotes as a literal string, the variable's definition is often called the DR string. To define the fields within an edit sequence, for example, the developer may specify the fields using a DR string rather than an INPUT template.
DUZ(0)	A local variable that holds the FILE MANAGER ACCESS CODE field (#3) of the signed-on user.
ENCRYPTION	Scrambling data or messages with a cipher or code so that they are unreadable without a secret key. In some cases encryption algorithms are one directional, that is, they only encode and the resulting data <i>cannot</i> be unscrambled (e.g., Access and Verify codes).
ePCS	Drug Enforcement Administration (DEA) Electronic-Prescribing of Controlled Substances (ePCS).
FILE ACCESS SECURITY SYSTEM	Formerly known as Part 3 of the Kernel Inits. If the File Access Security conversion has been run, file-level security for VA FileMan files is controlled by Kernel's File Access Security system, not by VA FileMan Access codes (i.e., FILE MANAGER ACCESS CODE field [#3] in the NEW PERSON file [#200]).
FORCED QUEUING	A device attribute indicating that the device can only accept queued tasks. If a job is sent for foreground processing, the device rejects it and prompt the user to queue the task instead.
GO-HOME JUMP	A menu jump that returns the user to the primary menu presented at signon. It is specified by entering two carets ("^^") at the menu's select prompt. It resembles the "Rubber-band Jump" but <i>without</i> an option specification/name following the carets.
HELP PROCESSOR	A Kernel module that provides a system for creating and displaying online documentation. It is integrated within the menu system so that help frames associated with options can be displayed with a standard query at the menu's select prompt.
HOST FILE SERVER (HFS)	A procedure available on layered systems whereby a file on the host system can be identified to receive output. It is implemented by the Device Handler's HFS device type.
INIT	Initialization of an software application. INIT* routines are built by VA FileMan's DIFROM and, when run, recreate a set of files and other software components.
JUMP	In VistA applications, the Jump command allows you to go from a particular field within an option to another field within that same option. You can also Jump from one menu option to another menu option without having to respond to all the prompts in between. To jump, type a caret ("^") and then type the name of the field or option to which you wish to jump. (See also GO-HOME JUMP, PHANTOM JUMP, RUBBER-BAND JUMP, or UP-ARROW JUMP.)

Term	Definition
JUMP START	A logon procedure whereby the user enters the "Access code; Verify code; option" to go immediately to the target option, indicated by its menu text or synonym. The jump syntax can be used to reach an option within the menu trees by entering "accesscode; verify code; option".
KERMIT	A standard file transfer protocol. It is supported by Kernel and can be set up as an alternate editor.
MANAGER ACCOUNT	A UCI that holds vendor shared routines.
MENU CYCLE	The process of first visiting a menu option by picking it from a menu's list of choices and then returning to the menu's select prompt. Menu Manager keeps track of information (e.g., the user's place in the menu trees) according to the completion of a cycle through the menu system.
MENU MANAGER	The Kernel module that controls the presentation of user activities (e.g., menu choices or options). Information about each user's menu choices is stored in the Compiled Menu System, the ^XUTL global, for easy and efficient access.
MENU SYSTEM	The overall Menu Manager logic as it functions within the Kernel framework.
MENU TEMPLATE	An association of options as pathway specifications to reach one or more final destination options. The final options <i>must</i> be executable activities and not merely menus for the template to function. Any user can define user-specific MENU templates via the corresponding Common option.
MENU TREES	The menu system's hierarchical tree-like structures that can be traversed or navigated, like pathways, to give users easy access to various options.
PAC	P rogrammer A ccess C ode. An optional user attribute that can function as a second level password into programmer mode.
PART 3 OF THE KERNEL INIT	See FILE ACCESS SECURITY SYSTEM.
PATTERN MATCH	A preset formula used to test strings of data. Refer to your system's M Language Manuals for information on Pattern Match operations.
PHANTOM JUMP	Menu jumping in the background. Used by the menu system to check menu pathway restrictions.
PRIMARY MENUS	The list of options presented at signon. Each user <i>must</i> have a PRIMARY MENU OPTION in order to sign on and reach Menu Manager. Users are given primary menus by system administrators. This menu should include most of the computing activities the user needs.
PROGRAMMER ACCESS	Privilege to become a developer on the system and work outside many of the security controls of Kernel. Accessing programmer mode from Kernel's menus requires having the at-sign security code ("@"), which sets the variable $DUZ(\emptyset)=@$.
PROTOCOL	An entry in the PROTOCOL file (#101). Used by the Order Entry/Results Reporting (OE/RR) software to support the ordering of medical tests and other activities. Kernel includes several protocol-type options for enhanced menu displays within the OE/RR software.

Term	Definition
QUEUING	Requesting that a job be processed in the background rather than in the foreground within the current session. Kernel's TaskMan module handles the queuing of tasks.
QUEUING REQUIRED	An option attribute that specifies that the option <i>must</i> be processed by TaskMan (the option can only be queued). The option can be invoked and the job prepared for processing, but the output can only be generated during the specified time periods.
RESOURCE	A method that enables sequential processing of tasks. The processing is accomplished with a RES device type designed by the application developer and implemented by system administrators. The process is controlled via the RESOURCE file (#3.54).
RUBBER-BAND JUMP	A menu jump used to go out to an option and then return, in a bouncing motion. The syntax of the jump is two carets ("^^", uppercase-6 on most keyboards) followed by an option's menu text or synonym (e.g., ^Print Option File). If the two carets are not followed by an option specification, the user is returned to the primary menu. (See also: GO-HOME JUMP.)
SCHEDULING OPTIONS	A way of ordering TaskMan to run an option at a designated time with a specified rescheduling frequency (e.g., once per week).
SCROLL/NO SCROLL	The Scroll/No Scroll button (also called Hold Screen) allows the user to "stop" (No Scroll) the terminal screen when large amounts of data are displayed too fast to read and "restart" (Scroll) when the user wishes to continue.
SECONDARY MENU OPTIONS	Options assigned to individual users to tailor their menu choices. If a user needs a few options in addition to those available on the primary menu, the options can be assigned as secondary options. To facilitate menu jumping, secondary menus should be specific activities, not elaborate and deep menu trees.
SECURE MENU DELEGATION (SMD)	A controlled system whereby menus and security keys can be allocated by people other than system administrators (e.g., application coordinators) who have been so authorized. SMD is a part of Menu Manager.
SERVER OPTION	An entry in the OPTION file (#19). An automated mail protocol that is activated by sending a message to the server with the "S.server" syntax. A server option's activity is specified in the OPTION file (#19) and can be the running of a routine or the placement of data into a file.
SIGNON/SECURITY	The Kernel module that regulates access to the menu system. It performs a number of checks to determine whether access can be permitted at a particular time. A log of signons is maintained.
SPECIAL QUEUEING	An option attribute indicating that TaskMan should automatically run the option whenever the system reboots.

Term	Definition
SPOOLER	An entry in the DEVICE file (#3.5). It uses the associated operating system's spool facility, whether it's a global, device, or host file. Kernel manages spooling so that the underlying OS mechanism is transparent. In any environment, the same method can be used to send output to the spooler. Kernel subsequently transfers the text to a global for subsequent despooling (printing).
SYNONYM	A field in the OPTION file (#19). Options can be selected by their menu text or synonym. (See also: MENU TEXT.)
TASKMAN	The Kernel module that schedules and processes background tasks (also called Task Manager).
TIMED READ	The amount of time Kernel waits for a user response to an interactive READ command before starting to halt the process.
UP-ARROW JUMP	In the menu system, entering a caret ("A"; sometimes referred to as an up-arrow) followed by an option specification/name accomplishes a jump to the target option without needing to take the usual steps through the menu pathway.
XINDEX	A Kernel utility used to verify routines and other M code associated with a software application. Checking is done according to current ANSI MUMPS standards and VistA programming standards. This tool can be invoked through an option or from direct mode (>D ^XINDEX).
Z EDITOR (^%Z)	A Kernel tool used to edit routines or globals. It can be invoked with an option, or from direct mode after loading a routine with >X ^%Z.
ZOSF GLOBAL (^%ZOSF)	The Operating System File—a manager account global distributed with Kernel to provide an interface between VistA software and the underlying operating system. This global is built during Kernel installation when running the manager setup routine (ZTMGRSET). The nodes of the global are filled-in with operating system-specific code to enable interaction with the operating system. Nodes in the ^%ZOSF global can be referenced by VistA application developers so that separate versions of the software need not be written for each operating system.



REF: For a list of commonly used terms and definitions, see the OI&T Master Glossary VA Intranet Website.

For a list of commonly used acronyms, see the VA Acronym Lookup Intranet Website.

Index

	Acronyms
\$	Intranet Website, 367
•	Acting as a Delegate
\$\$Cache2() Algorithm, 260	User Interface, 149
\$\$TEST^DDBRT API, 227	Action Prompt
\$HOROLOG Variable, 276, 295	Monitor Taskman, 278
\$I Field	Actions
DEVICE File (#3.5), 194, 197, 208, 211, 212,	USE AS LINK FOR MENU ITEMS, 311,
215, 223, 230, 231, 232, 234, 298, 300	319
\$I Field (#1)	Actual Usage of Alpha/Beta Test Options
DEVICE File (#3.5), 195, 208, 223	Option, 326
\$STACK Variable, 183	Add a New User Option, 23
\$ZC Calls, 185	Add a New User to the System Option, 22, 23
	Add DEA ePCS Utility Users, 78
٨	Add Entries To Look-Up File Option, 349, 350
-	Example, 353
^%ZIS("14.5","LOGON","volume set") Node,	Multi-Term Look-Up (MTLU), 341
22	Add Error Screens Option, 182
^XTER Direct Mode Utility, 184	Add/Modify Utility Option, 349, 353
^XTERPUR Direct Mode Utility, 184	Multi-Term Lookup (MTLU), 342
^XTLKDICL Routine, 342, 362	Multi-Term Look-Up (MTLU)
^XTLKWIC Routine, 359	Examples, 358
^ZTMON Direct Mode Utility, 278	Adding Explicit File Access for System
,	Administrators, 61
	Adding New Users, 22
2	Add a New User to the System Option, 22
2-Factor Authentication, 21	Grant Access by Profile, 23
2-1 actor rathemication, 21	Grant Access by Profile Option, 23
	NEW PERSON IDENTIFIERS, 23
A	Primary Menu, 22
Abnormal Signoff and Erman Handling O	Security Forms, 23, 24
Abnormal Signoff and Error Handling, 9	SSN Field (#9)
Abort KIDS Installations, 222	NEW PERSON File (#200), 22, 23
KIDS Installations, 323	XUMGR Security Key, 22, 23
Recovering From KIDS Installations, 323	XUSPF200 Security Key, 23
Restarting Aborted KIDS Installations, 323 ACADEMIC AFFILIATION WAIVER Field	Additional Attributes Editable by Users, 38
	After the File Access Security Conversion, 65
(#13), 42 Academic Afiliation Waiver, 42	AGENCY CODE Field (#9), 19, 57
•	AGENCY Field, 19
ACCESS CODE Field, 32 ACCESS CODE Field (#2), 32	AGENCY File (#4.11), 19
` /'	AK Cross-reference, 146
Access Codes, 1, 4, 5, 6, 7, 8, 9, 15, 16, 19, 24,	ALERT CRITICAL TEXT File (#8992.3), 158
31, 32, 40, 41, 42, 47, 48, 56, 63, 175, 205 Assigning, 22	ALERT DATE/TIME Multiple Field (#.01), 166
	ALERT File (#8992), 162, 163, 164, 165, 166
Log, 48	Alert Management Menu, 161, 163
Old, 48	ALERT TRACKING File (#8992.1), 160, 162,
Purging, 48	163, 165, 166
ACCESSIBLE FILE Multiple Field (#32), 49,	Alerts, 9, 158
50, 55, 60, 61, 63, 64	Critical, 158
	,

Deleting, 160	GETENV^%ZOSV API, 250
Forwarding, 161	LKUP^XTLKMGR, 362
Make an Alert on the Fly Option, 164	PATIENT^XQALERT, 162
Processing, 158	REQ^%ZTLOAD, 299
Purging, 163, 164	TaskMan, 241
Reports, 164, 165, 166, 167	USER^XQALERT, 162
Surrogates, 161, 163	APPLICATION PROXY, 43
System Management, 162	Application Utilities Menu, 343
User Interface, 158	ASK DEVICE TYPE AT SIGN-ON Field, 9,
Alerts - Set/Remove Surrogate for User Option,	18, 19
163	ASK DEVICE TYPE AT SIGN-ON Field
Algorithms	(3200.05), 11, 35
\$\$Cache2(), 260	ASK HFS I/O OPERATION Field (#5.2)
Parsing, 31	DEVICE File (#3.5), 214
All Keys a User Needs Option, 145	ASK HOST FILE Field (#5.1)
All your tasks Option, 272	DEVICE File (#3.5), 214
Allocate/De-Allocate of PSDRPH Key Option,	ASK PARAMETERS Field
89, 109	DEVICE File (#3.5), 214
Allocating	ASK PARAMETERS Field (#5)
Security Keys, 144	DEVICE File (#3.5), 196, 207
Allocation of Security Keys Option, 78, 144,	Assign Editors Option, 179
145, 155	Assign the XU EPCS EDIT DATA Option, 80
Allow other users access to spool documents	Assign the XUEPCSEDIT Security Key, 78
Option, 218	Assign the XUSSPKI UPN SET Option, 83
ALLOWED TO USE SPOOLER Field (#41),	Assigning
35, 221	Access Codes, 19, 22
Alpha/Beta Test Option Usage Menu, 127, 326	Display Order, 126
Alpha/Beta Tracking	File Number Ranges, 35
Sending a Summary Message, 326	Help Frame Editors, 179
Alpha/Beta Tracking (KIDS), 326	Options, 150
Altering Exported Menus, 131	Secondary Menus, 130
ALTERNATE EDITOR File (#1.2), 34	Assumptions, xliii
Alternate Syntax for Device Specification, 192	Attributes
ALWAYS SHOW SECONDARIES Field, 130	Editable by Users, 38
ALWAYS SHOW SECONDARIES Field	Users, 15, 22, 23, 31
(#200.11), 35	AUDIT Access, 49, 51, 52, 54, 55
Answerback Message, 18	Audit Features Menu, 127
Answering Installation Questions for Transport	AUDIT File (#1.1), 55
Globals in a Distribution (KIDS), 310	AUDIT LOG FOR OPTIONS File (#19.081),
AOLD Cross-reference, 48	127, 168, 171
APIs	Audited Options Purge Option, 127
\$\$TEST^DDBRT, 227	Audits
^%ZTLOAD, 241, 242, 299	Failed Access Attempts, 47
^%ZTLOAD API, 231	Option Use, 127
^DIE, 52	Signon, 46
^XUP, 227	Authentication
DIC, 52	2-Factor Authentication, 21
DIE, 52	AUTO DESPOOL Field (#31)
DQ^%ZTLOAD, 299	DEVICE File (#3.5), 223
ENABLE^XUFILE3 Routine, 64	AUTO MENU Field, 20, 117
ERR^ZU, 181	AUTO MENU Field (#.06), 57

AUTO MENU Field (#200.06), 12, 35, 126 Auto Print Mode, 233	XUSSPKI SAN, 111 BYPASS DEVICE LOCK-OUT Field, 16
Auto-despooling, 219, 223	BTI ASS DE VICE LOCK-OUT TICIU, TO
AUTO-GENERATE ACCESS CODES Field, 19	С
Automatic Deactivation of Users Option, 41	Caché
Automatically	Systems
Deactivating Users, 41	DCL Context, 263
	VAX ENVIRONMENT FOR DCL Field
В	(#9), 252
D.G. 6 205	Cache/VMS DCL Context Setup, 263
B Cross-references, 297	Callout Boxes, xli
BACK SPACE Field (#4)	Calls
TERMINAL TYPE File (#3.2), 206, 229	\$ZC, 185
Background Jobs	CAN DELETE WITHOUT PROCESSING
TaskMan	Field (#.1), 164
User Interface, 236	CAN MAKE INTO A MAIL MESSAGE Field
Backing Up Transport Globals (KIDS), 318 Parking a Transport Global Option, 218	(#41.2), 35, 221
Backup a Transport Global Option, 318 Realizin Poviniver for Unpressed Alerta 166	Change my Division Option 10
Backup Reviewer for Unprocessed Alerts, 166 BALANCE State, 260	Change my Division Option, 10 Change user's allocated keys to delegated keys
TaskMan, 301	Option, 145
Benefits	Changes in the Role of the PACKAGE File
DEA ePCS Utility, 71	(#9.4) (KIDS), 308
Block Count Utility, 179	Characteristics of Intended Users, 152
BOX-VOLUME PAIR Field, 259	Check Taskman's Environment Option, 279
BOX-VOLUME PAIR Field (#.01), 250, 251	CHECK*XTSUMBLD Routine, 315, 337
Broker Security Enhancement (BSE), 46	CHECK1 [^] XTSUMBLD Routine, 315, 337
Browse a Spool Document Option, 218	Checkpoints
Browser Device, 225	KIDS, 323
Storing Host Files in a Specific Directory, 227	CHECKSUM REPORT Field (#6), 336
System Management, 227	Checksums, 310, 335
User Interface, 225	KIDS, 315, 337
BROWSER Device, 203, 225	Choosing Options, 116
BROWSER Type, 227	Clean Error Log Over Range Of Dates Option,
BSE, 46	292
Build a New Menu Option, 151, 157	Clean Error Trap Option, 184
Build Entries and the BUILD File (#9.6), 307	Clean old Job Nodes in the XUTL Option, 134,
Build Entry	135
Components, 336	Clean Old Job Nodes in XUTL, 134
Definition, 304	Clean Task File Option, 284
BUILD File (#9.6), 304, 307, 315, 320, 325,	Cleanup Task List Option, 274
333, 335, 337	Clear all users at startup Option, 18, 22, 46
Purging, 333	Clear Electronic signature code Option, 68
Build File Print Option, 328	CLOSE EXECUTE Field
Build Primary Menu Trees Option, 136	TERMINAL TYPE File (#3.2), 193
Building Options, 152	CLOSE EXECUTE Field (#7)
BULLETIN File (#3.6), 171, 175	TERMINAL TYPE File (#3.2), 206, 228,
Bulletins	234, 235
Server Request, 168, 169, 171, 172, 175	CLOSE PRINTER PORT Field (#111), 234, 235
XQSERVER, 171, 175	Codes

Access, 1, 4, 5, 6, 7, 8, 9, 15, 16, 19, 24, 31,	Contents, xii
32, 40, 41, 42, 47, 48, 56, 63, 175, 205	Continue Option, 121
Assigning, 22	Control
Log, 48	How Can the Number of Instances of a Server
Old, 48	Option Be Controlled?, 169
Purging, 48	Conversion
Electronic Signature, 12	After File Access Security, 65
Verify, 1, 4, 5, 6, 7, 8, 12, 15, 16, 19, 23, 32,	File Access Security, 60
40, 47, 48, 56, 171, 175	Convert Loaded Package for Redistribution
Defining, 6	Option, 309, 330
Log, 48	COORDINATOR (IRM) Field, 31
Old, 48	Copy Everything About an Option to a New
Purging, 48	Option Option, 151, 157
Commands	Copy One Users Menus and Keys to others
%SPAWN, 242, 252	Option, 151
JOB, 242, 251, 252, 295	Copy Print Mode, 233
USE, 243	CPRS Configuration (IRM) Menu, 75
COMMERCIAL PHONE Field (#.135), 36	CPRS Manager Menu, 75
Common Menu, 6, 32, 117, 118, 120, 121, 130,	CPT File (#81), 341
143, 147, 158, 218, 221, 237	CPU
Redefining, 130	Cross-references, 195, 249
Compare local/national checksums report	Definition, 248
Option, 315, 337	CPU/Service/User/Device Stats Option, 34, 47
Compare Transport Global to Current System	Create a Set of Options to Mark Out-Of-Order
Option, 316	Option, 132
Comparing Loaded Transport Globals to the	Creating
Current System (KIDS), 316	Another Level of Delegation, 149
Components	Delegates, 153
Build Entry, 336	Device Types, 199
Definition, 304	Distributions, 306
Exported, 316	Help Frames, 179
Installations, 322	Menus and Options, 124
KIDS, 315	New User Account, 22
Missing, 336	Options and Menus, 124
Routine, 336	Resource Devices, 232
Software, 245, 307, 335, 337	Security Keys, 146
Transport Global, 311	Several Dummy Users, 23
Compute Server	Spooled Document, 220
Job List, 246, 278, 300	Tasks, 231
Node, 293	TaskMan User Interface, 236
Mode, 251	Terminal Types, 206
COMPUTE SERVER Type, 254	Transport Globals, 336
Computer Access Policy, 24	Critical Alerts, 158
Computer Account Notification, 24	Critical Alerts Count Report Option, 165
Configuration	Cross Reference Help Frames Option, 179
DEA ePCS Utility, 75	Cross-references
Multiple Managers	^XUSEC, 147
TaskMan, 259	AK, 146
TaskMan, 249	AOLD, 48
Caché and GT.M, 258	B, 297
CONNECTOR PROXY, 43, 44, 45	CPU, 195, 249

CUR, 43	Assign the XU EPCS EDIT DATA Option,
Devices, 211, 212	80
Errors, 291	Assign the XUEPCSEDIT Security Key, 78
Lookup-type, 31, 32	Assign the XUSSPKI UPN SET Option, 83
Options, 179	Benefits, 71
Parents, 179	Configuration, 75
Routines, 179	History, 69
VOLD, 48	Intended Audience, 71
CUR Cross-reference, 43	Options, 86
	Overview, 69
_	Parameter, 75
D	Processes
DA Return Code Edit Option, 19, 209	e-Prescribing Process, 73
DA RETURN CODES File (#3.22), 18, 19, 209	Manual Paper-based Process, 72
Global Location, 194	Requirements, 70
DA RETURN CODES File(#3.22), 194	DEA ePCS Utility Functions Main Menu, 86
Dangling Pointers	DEA EXPIRATION DATE Field (#747.44), 89,
OPTION File (#19), 131	90, 91, 92, 93
Data Dictionaries Being Audited Option, 52	DEA# Field (#53.2), 89, 90, 91, 92, 93, 94, 96
Data Dictionary	Deactivate a User Option, 40
Data Dictionary Utilities Menu, xliii	Deactivating
Listings, xliii	Users, 39, 40
DATA DICTIONARY Access, 49, 51, 53, 54,	Automatically, 41
55, 63	De-allocating
Data Dictionary Utilities Menu, 53	Security Keys, 144
DATE GIVEN Subfield (#2)	De-allocation of Security Keys Option, 144, 155
KEYS Multiple Field (#51), 98, 99	De-assigning
DATE/TIME EDITED Field (#.06)	Help Frame Editors, 179
XUEPCS DATA File (#8991.6), 100	DEFAULT # OF ATTEMPTS Field, 16
DAY(S) FOR TIME PERIOD Field (#.02), 134	Default Institution, 34
DAYS FOR BACKUP REVIEWER Field	DEFAULT INSTITUTION Field, 19
(#.15), 166	DEFAULT LANGUAGE Field, 36
DAYS TO KEEP OLD TASKS Field, 284	DEFAULT LANGUAGE Field (#207), 57
DAYS TO KEEP OLD TASKS Field (#8), 256	DEFAULT LOCK-OUT TIME Field, 16
DCL Command Files, 252, 263	DEFAULT MULTIPLE SIGN-ON Field, 18
DCL Commands	Defining
SET LOGINS/INTERACTIVE, 16	Environments
DCL Context	TaskMan, 249
Batch Queues, 269	Primary Menu, 124
OpenVMS User TASKMAN on ALPHA	Spool Device Types, 223
AXP Systems, 269	Caché, 223
Restarting, 266	GT.M, 223
Running TaskMan with a DCL Context, 263	Verify Codes (Passwords), 6
Set up for TaskMan and DCL Context in	Definitions
Cache/VMS, 263	KIDS, 304
TaskMan Cache/VMS, 263	Delegate keys Option, 145, 155
TASKMAN Queue, 269	Delegate's Menu Management Menu, 149, 151,
ZTMSWDCL.COM, 268	152, 154, 155
ZTMWDCL.COM, 267	DELEGATED KEYS Field (Multiple), 145, 155
DEA ePCS Utility	Delegating, 149
Add DEA ePCS Utility Users, 78	Options, 145, 154, 155

Security Keys, 145, 155	NAME Field (#.01), 195
DELEGATION LEVEL Field, 147	OPEN PARAMETERS Field (#19), 196, 214
Delete A Spool Document Option, 218	OpenVMS-Specific DEVICE Fields, 198
DELETE Access, 33, 49, 51, 53, 54	POST-CLOSE EXECUTE Field (#8), 196
DELETE ALL MAIL ACCESS Field, 40	PRE-OPEN EXECUTE Field (#7), 196
DELETE ALL MAIL ACCESS Field (#9.21),	PRIORITY AT RUN TIME Field (#25), 261
41	QUEUING Field (#5.5), 196
Delete Entries From Look-Up Option, 349, 350	SIGN-ON/SYSTEM DEVICE Field (#1.95),
Example, 350	195, 208, 211, 212
Multi-Term Look-Up (MTLU), 341	SUBTYPE Field (#3), 195, 206, 229
Delete Error Log Option, 292	TaskMan
DELETE KEYS AT TERMINATION Field, 40	Configuration, 261
DELETE KEYS AT TERMINATION Field	TASKMAN PRINT A HEADER PAGE?
(#9.22), 41	Field (#26), 261
Delete Old (>14 d) Alerts Option, 163	TYPE Field, 197
Delete Tasks Option, 248, 274	TYPE Field (#2), 195, 261
Delete Unreferenced Options Option, 131	USE PARAMETERS Field (#19.5), 196
Deleting	VOLUME SET(CPU) Field (#1.9), 195, 208,
Alerts, 160	211, 212, 261, 287
Security Keys, 147	DEVICE FOR QUEUED JOB OUTPUT Field
Dequeue Tasks Option, 248, 273, 274, 299	(#3), 286, 287
DESCRIPTION Field, 288	Device Handler, 1, 18, 33, 126, 139, 187, 190,
DESCRIPTION Field (#3.5)	191, 193, 194, 195, 196, 204, 207, 208, 209,
OPTION File (#19), 170	210, 211, 214, 216, 228, 230, 231, 234, 235,
Descriptions	243
Options, 129	Alternate Syntax, 192
DESPOOL DEVICES Field (#32, Multiple)	DA Return Codes, 209
DEVICE File (#3.5), 223	Home Device, 208
Device Allocation List, 277	Influence on TaskMan, 261
Node, 293	Out of Service Devices, 210
Device Chart	Page Length, 189
Multi-Term Look-Up (MTLU), 345	Queuing, 189
DEVICE File (#3.5), 2, 15, 16, 17, 18, 33, 169,	Right Margin, 189
172, 194, 195, 198, 199, 200, 203, 204, 206,	Security (Devices), 205
207, 208, 223, 224, 227, 228, 229, 230, 231,	Selecting Devices, 209
232, 234, 235, 247, 261, 287	Spool Document Formats, 192
\$I Field, 194, 197, 208, 211, 212, 215, 223,	Subtypes, 190
230, 231, 232, 234, 298, 300	Summary, 193
\$I Field (#1), 195, 208, 223	System Management, 194
ASK HFS I/O OPERATION Field (#5.2), 214	Terminal Type Information Retained by User,
ASK HOST FILE Field (#5.1), 214	208
ASK PARAMETERS Field (#5), 214	Test Pattern, 210
AUTO DESPOOL Field (#31), 223	Troubleshooting, 209
Cross-references, 211	User Interface, 187
DESPOOL DEVICES Field (#32, Multiple),	Virtual Terminals, 208
223	Device Lock-out Times, 16
Fields, 195	Device Management Menu, 199, 210
GENERATE SPL DOC NAME Field (#33),	Device Waiting List
224	Node, 294
Global Location, 194	Devices
Identification, 211	BROWSER, 203, 225, 227

Cross-references, 211, 212	^XTER, 184
Editing, 211	^XTERPUR, 184
File Entries, 234	TaskMan
HFS, 196, 200, 207, 213, 214, 232, 261, 304,	^ZTMON, 278
309, 310, 312	RESTART^ZTMB, 266
Home, 187, 189, 208, 234, 235	DISABLE USER Field, 40
Identification, 211	Disclaimers
IO List, 277	Documentation, xxxix
Magtape, 229	Software, xxxix
Network Channel, 230	DISEARCH, 53
NULL, 202	Disk Space Concerns, 179
P-MESSAGE, 203	Display
Printing, 187	Attributes, 18
RESOURCES Type, 169	Return Codes, 19
SDP, 232	Delegated Options, 157
Security, 205	Help Frames, 176
Selection at Signon, 208	Nodes, 137, 138
Sequential Disk Processor (SDP), 207, 232	Options, 129
Signon, 208	Description, 119
Slaved, 233	Help, 117
Special Devices, 225	Order, 126
SPOOLER, 216	Status of Tasks, 239
Synonyms, 211	Display Menus and Options Menu, 128, 129
TELNET, 203	DISPLAY OPTION Field, 126, 130
VMS	Display Patches for a Package Option, 333
Systems Virtual Devices, 208	Display factors for a factoring option, 333 Display status Option, 239
DI DDU Menu, xliii, 53	DISPLAY TEXT field (#.02), 166
Diagram Menus Option, 144, 147	Display User Characteristics Option, 13, 143
Diagramming Options, 128	Display/Edit Help Frames Option, 178, 179
DIALOG File (#.84), 57	Displaying Option Descriptions, 119
DIAUDIT DD Option, 52	Displaying Option Help, 117
DIAUDIT PURGE DATA Option, 52	DISTATISTICS Option, 53
DIAUDIT PURGE DD Option, 52	Distributions
DIAUDIT TURN ON/OFF Option, 52	Definition, 304
DIAUDITED FIELDS Option, 52	Global, 309, 310
DIC API, 52	KIDS, 305, 306, 309
OIC Routine, 51	Standard, 309, 310
DIDEL Variable, 51, 52	Transport Mechanism, 309
DIE API, 52	DISUSER Field, 42
DIE Routine, 51	DISUSER Field (#7), 35, 40, 41
DIEDFILE Option, 61	DISV Global, 40, 60, 61, 64, 65
DIEDIT Option, 51, 53, 54	KILLing, 60, 61, 64
DIFROM Utility, 304, 307, 309	DITRANSFER Option, 53, 54
DIGITAL PAGER Field (#.138), 11, 36, 67	DIUTILITY Menu, 53
DIINQUIRE Option, 53, 55	DIVISION Field (#16, Multiple), 34
OILIST Option, xliii, 53	DIVISION Field (#10, Multiple), 34 DIVISION Field (Multiple), 19
•	
DIMODIFY Option, 53, 55	DIVISION Multiple Field (#16), 57
OIP Routine, 142	Division of Labor
DIPRINT Option, 53 Direct Mode Utilities	TaskMan, 241
	DLAYGO Variable, 51, 52
Error Processing	Documentation

Symbols, xl	MULTIPLE SIGN-ON Field (#200.04), 35
VA Handbook 6500, 42	NAME Field (#.01), 31
Appendix D, 42	NETWORK USERNAME Field (#501.1), 35
Documentation Conventions, xl	NICK NAME Field (#13), 32
Documentation Disclaimer, xxxix	PAC (#14, Programmer Access Code), 35
Documentation Navigation, xlii	PREFERRED EDITOR Field (#31.3), 34
DOMAIN File (#4.2), 61, 64	PRIMARY MENU OPTION Field (#201), 32
Double Quote Jump, 121	PROHIBITED TIMES FOR SIGN-ON Field
Double Quote Shortcuts, 121	(#15), 35
DQ^%ZTLOAD API, 299	SECONDARY MENU OPTIONS Field
DSM for OpenVMS	(#203, Multiple), 32
Systems	SERVICE/SECTION Field (#29), 34
VAX	SSN Field (#9)
ENVIRONMENT FOR DCL Field (#9),	NEW PERSON File (#200), 32
252	TERMINATION DATE Field (#9.2), 35
DTIME Variable, 20, 35	TIMED READ Field (#200.1), 35
Duplicate Resolution Utilities	TITLE (#8), 32
Merge Capability	TYPE-AHEAD Field (#200.09), 35
Developing, 339	VERIFY CODE Field (#7.2), 32
DUZ	Edit an Existing User Option, 31, 80, 83
Description, 56	Edit Devices by Specific Types Option, 229
Variable, 57	Edit Error Screens Option, 182
DUZ("AG") Variable, 19	Edit Facility DEA# and Expiration Date Option,
DUZ("AUTO") Variable, 20	86, 89, 110
DUZ(0) Variable, 33, 50, 51, 54, 55, 60, 152,	Edit File Option, 61
205	Edit Install Status Option, 330
DUZ(2) Variable, 19	Edit Logical/Physical Mapping Option, 204
	Edit Menu
E	Line Editor, 50
E	Edit option Menu, 34
Edit a Build Option, 335	Edit options Option, 124, 126, 130, 134, 135,
Edit a User's Options Option, 150	170, 180
Example, 150	Edit Parameter Values Option, 75
Edit an Existing User	Edit task Option, 239
ACCESS CODE Field (#2), 32	Edit TaskMan Parameters Menu, 249, 261
ALLOWED TO USE SPOOLER Field (#41),	Edit User Characteristics
35	ASK DEVICE TYPE AT SIGN-ON Filed
ALWAYS SHOW SECONDARIES Field	(#200.05), 11
(#200.11), 35	AUTO MENU Field (#200.06), 12
ASK DEVICE TYPE AT SIGN-ON Filed	ELECTRONIC SIGNATURE CODE Field
(#200.05), 35	(#20.4), 12
AUTO MENU Field (#200.06), 35	Form and Template, 39
CAN MAKE INTO A MAIL MESSAGE	INITIAL Field (#1), 11
Field (#41.2), 35	NETWORK USERNAME Field (#501.1), 12
DISUSER Field (#7), 35	NICK NAME Field (#13), 11
DIVISION Field (#16, Multiple), 34	PREFERRED EDITOR Field (#31.3), 12
FILE MANAGER ACCESS CODE Field	TEXT TERMINATOR Field (#31.2), 12
(#3), 33	TITLE Field (#8), 11
FILE RANGE Field (#31.1), 35	TYPE-AHEAD Field (#200.09), 12
INITIAL Field (#1), 31	VERIFY CODE Field (#7.2), 12
MAIL CODE Field (#28), 32	
* **	

Edit User Characteristics Option, 6, 9, 11, 13,	Error Messages During Menu Jumping, 136
20, 32, 38, 39, 208	ERROR MESSAGES File (#3.076), 184
Kernel, 34	Error Processing, 9, 181
MailMan, 34	^XTER, 184
Edit User's Spooler Access Option, 221	^XTERPUR Direct Mode Utility, 184
EDITED BY Field (#.02)	Add Error Screens Option, 182
XUEPCS DATA File (#8991.6), 100	Clean Error Trap Option, 184
EDITED DATA (#.05)	Edit Error Screens Option, 182
XUEPCS DATA File (#8991.6), 100	Enhanced, 183
Editing	Error Screens, 181
Device Types, 199	Error Trap Display Option, 184
Devices, 211	Interactive Print of Error Messages option,
Help Frames, 179	186
Network Channel Devices, 230	List Error Screens Option, 182
Resource Devices, 232	P1 Print 1 occurrence of each error for T-1
Security Keys, 146	(QUEUE) Option, 183
Tasks, 239	P2 Print 2 occurrences of errors for T-1
Terminal Types, 206	(QUEUE), 183
Editors	Remove Error Screens Option, 183
Line, 12, 34, 50, 52	System Management, 181
Screen, 9, 18, 34	User Interface, 181
Edits and Distribution Menu, 306	Error Processing Menu, 183
Electronic Signature Block Edit Option, 67	Error Screens
Electronic Signature code Edit Option, 67, 68	Node, 293
ELECTRONIC SIGNATURE CODE Field	TaskMan, 246
(#20.4), 12	ERROR State
Electronic Signature code Option	TaskMan, 301
User's Toolbox, 67	Error Trap
Electronic Signatures, 67	Purging, 184
System Management, 67	Error Trap Auto Clean Option, 184
User Interface, 67	Error Trap Display Option, 184
Enable Building Options from Templates, 152	Errors
ENABLE^XUFILE3 API, 64	Cross-references, 291
Enabling/Disabling Logons, 22	Error Messages During Menu Jumping, 136
Enhanced Error Processing, 183	Error Screens
Enter or Edit File Entries Option, 51, 53, 54	Error Processing, 181
Enter Site Parameter	Errors Logged in Alpha/Beta Test (QUEUED)
DEA ePCS Utility, 75	Option, 326
Enter/Edit Kernel Site Parameters Option, 15,	Escaping from a Jumbled Screen, 9
20, 205	Establish System Audit Parameters Option, 127
Enter/Edit of Security Keys Option, 146	EVE Menu, 78, 80, 83, 138, 139, 156, 181, 305
ENTRY ACTION Field (#20), 133, 168, 170	EXIT ACTION Field (#15), 126, 133, 168, 170
Environment Check, 242, 310, 312	Exploding Key, 146
ePCS DEA Utility Functions Menu, 87	Exported
ePCS Edit Prescriber Data Option, 86, 110	Components, 316
ePCS Set SAN from PIV Card Option, 86, 110	Files, 32
ERR^ZU API, 181	Frames, 179
Error Log, 186	Keys, 147
Purge, 184	Menus, 124, 131
ERROR LOG File (#3.075), 181, 184, 291	Software, 304, 307, 316
Error Log Node, 293	Extended Help, 177

F	CAN MAKE INTO A MAIL MESSAGE
E 1 1 A	(#41.2), 35, 221
Failed Access Attempts Audit, 47	CHECKSUM REPORT (#6), 336
FAILED ACCESS ATTEMPTS LOG File	CLOSE EXECUTE
(#3.05), 47	TERMINAL TYPE File (#3.2), 193
FAX NUMBER Field (#.136), 36	CLOSE EXECUTE (#7)
FIELD EDITED Field (#.03)	TERMINAL TYPE File (#3.2), 206, 228,
XUEPCS DATA File (#8991.6), 100	234, 235
Fields	CLOSE PRINTER PORT (#111), 234, 235
\$I	COMMERCIAL PHONE (#.135), 36
DEVICE File (#3.5), 194, 197, 208, 211,	COORDINATOR (IRM), 31
212, 215, 223, 230, 231, 232, 298, 300	DATE GIVEN (#2)
\$I (#1)	KEYS Multiple (#51), 98, 99
DEVICE File (#3.5), 195, 208, 223	DATE/TIME EDITED (#.06)
\$IDEVICE File (#3.5), 234	XUEPCS DATA File (#8991.6), 100
ACADEMIC AFFILIATION WAIVER	DAY(S) FOR TIME PERIOD (#.02), 134
(#13), 42	DAYS FOR BACKUP REVIEWER (#.15),
ACCESS CODE, 32	
ACCESS CODE (#2), 32	166
ACCESSIBLE FILE Multiple (#32), 49, 50,	DAYS TO KEEP OLD TASKS, 284
55, 60, 61, 63, 64	DAYS TO KEEP OLD TASKS (#8), 256
AGENCY, 19	DEA EXPIRATION DATE (#747.44), 89,
AGENCY CODE (#9), 19, 57	90, 91, 92, 93
ALERT DATE/TIME Multiple (#.01), 166	DEA# (#53.2), 89, 90, 91, 92, 93, 94, 96
ALLOWED TO USE SPOOLER (#41), 35,	DEFAULT # OF ATTEMPTS, 16
221	DEFAULT INSTITUTION, 19
	DEFAULT LANGUAGE, 36
ALWAYS SHOW SECONDARIES, 130	DEFAULT LANGUAGE (#207), 57
ALWAYS SHOW SECONDARIES	DEFAULT LOCK-OUT TIME, 16
(#200.11), 35	DEFAULT MULTIPLE SIGN-ON, 18
ASK DEVICE TYPE AT SIGN-ON, 9, 18, 19	DELEGATED KEYS (Multiple), 145, 155
ASK DEVICE TYPE AT SIGN-ON	DELEGATION LEVEL, 147
(#200.05), 11, 35	DELETE ALL MAIL ACCESS, 40
ASK HFS I/O OPERATION (#5.2)	DELETE ALL MAIL ACCESS (#9.21), 41
DEVICE File (#3.5), 214	DELETE KEYS AT TERMINATION, 40
ASK HOST FILE	DELETE KEYS AT TERMINATION
DEVICE File (#3.5), 214	(#9.22), 41
ASK PARAMETERS (#5)	DESCRIPTION, 288
DEVICE File (#3.5), 196, 207, 214	DESCRIPTION (#3.5)
AUTO DESPOOL (#31)	OPTION File (#19), 170
DEVICE File (#3.5), 223	DESPOOL DEVICES (#32, Multiple)
AUTO MENU, 20, 117	DEVICE File (#3.5), 223
AUTO MENU (#.06), 57	DEVICE FOR QUEUED JOB OUTPUT (#3)
AUTO MENU (#200.06), 12, 35, 126	286, 287
AUTO-GENERATE ACCESS CODES, 19	DIGITAL PAGER (#.138), 11, 36, 67
BACK SPACE (#4)	DISABLE USER, 40
TERMINAL TYPE File (#3.2), 206, 229	DISPLAY OPTION, 126
BOX-VOLUME PAIR, 259	•
BOX-VOLUME PAIR (#.01), 250, 251	DISPLAY TEXT (#.02), 166
BYPASS DEVICE LOCK-OUT, 16	DISUSER, 42
CAN DELETE WITHOUT PROCESSING	DISUSER (#7), 35, 40, 41
(#.1), 164	DIVISION (#16, Multiple), 34
("''', 10"	DIVISION (Multiple), 19

DIVISION Multiple (#16), 57	LOAD BALANCE ROUTINE, 259, 260
EDITED BY (#.02)	LOAD BALANCE ROUTINE (#21), 253
XUEPCS DATA File (#8991.6), 100	LOCAL SYNONYM, 211
EDITED DATA (#.05)	LOCK (#3), 144, 147, 168, 170
XUEPCS DATA File (#8991.6), 100	LOG RESOURCE USAGE?, 294
ELECTRONIC SIGNATURE CODE (#20.4),	LOG TASKS? (#2), 250
12	LOGICAL DISK NAME (#504), 204
ENTRY ACTION (#20), 133, 168, 170	MAIL CODE (#28), 32
EXIT ACTION (#15), 126, 133, 168, 170	MARGIN WIDTH (#9)
FAX NUMBER (#.136), 36	DEVICE File(#3.5), 229
FIELD EDITED (#.03)	MAX SIGNON ALLOWED, 15, 16
XUEPCS DATA File (#8991.6), 100	MAX SIGNON ALLOWED (#41,2), 251
FILE MANAGER ACCESS CODE (#3), 33,	MAX SPOOL DOCUMENT LIFE-SPAN
40, 42, 49, 50, 51, 54, 55, 57, 60, 63, 64,	(#31.3), 222
124, 144, 145, 152, 205	MAX SPOOL DOCUMENT LIFE-SPAN
FILE RANGE (#31.1), 35	field (#31.3), 218
FORM FEED (#2)	MAX SPOOL DOCUMENTS PER USER
TERMINAL TYPE File (#3.2), 206, 229	(#31.2), 222
FROM UCI, 256	MAX SPOOL LINES PER USER (#31.1),
FROM UCI (#.01), 257	220, 222
FROM VOLUME SET, 256	MENU (item) (Multiple), 124
FROM VOLUME SET (#1), 257	MENU TEMPLATE (Multiple), 122
GENERATE SPL DOC NAME (#33)	MENU TEXT (#1), 170
DEVICE File (#3.5), 224	MESSAGES, 320, 323
GIVEN BY (#1)	MIXED OS (#.05), 204
KEYS Multiple (#51), 98, 99	Mixed OS Environment
GLOBAL LOCK (#36), 231	KERNEL SYSTEM PARAMETERS file
HEADER (#26), 133, 168, 171	(#8989.3), 204
HELP FRAME, 126, 179, 180	MNEMONIC, 211
INDEPENDENTLY INVOCABLE, 131	MODE OF TASKMAN, 254, 259
INHIBIT LOGONS?, 22	MODE OF TASKMAN (#8), 251, 254
INHIBIT LOGONS? (#1), 255	MULTI-DEVICE DESPOOLING (#41.1),
INITIAL (#1), 23	221
NEW PERSON File (#200), 11, 31, 32, 67	MULTIPLE SIGN-ON (#200.04), 35
INSTALL ANSWERS (Multiple), 320	NAME (#.01), 89, 91, 92, 93, 94, 96, 98, 99
INSTALL COMPLETE TIME (#17), 330	BUILD File (#9.6), 307
INTERACTIVE USER'S PRIORITY, 18	DEVICE File (#3.5), 195, 211
INTRO TEXT, 15, 20	NEW PERSON File (#200), 31, 67, 68
INVOKED BY ROUTINE, 179	OPTION File (#19), 125, 170
KEEP AT TERMINATE, 146	PARAMETER DEFINITION file
KEYS (Multiple), 144, 145, 151	(#8989.51), 166
LANGUAGE (#.01)	RESOURCES File (#3.54), 231
DIALOG File (#.84), 57	SECURITY KEY File (#19.1), 147
LANGUAGE File (#.85), 57	TERMINAL TYPE File (#3.2), 206
LANGUAGE (#200.07), 36, 57	XUEPCS DATA File (#8991.6), 100
LAST SIGN-ON DATE/TIME (#202), 42	NETWORK USERNAME (#501.1), 12, 35
LAT PORT SPEED #64), 198	NEW PERSON IDENTIFIERS, 23
LAT SERVER NODE (#61), 198	NICK NAME (#13), 11, 32
LAT SERVER PORT (#62), 198	OFFICE PHONE (#.132), 11, 36, 67
LIFETIME OF VERIFY CODE, 19	OPEN EXECUTE
LINK ACCESS (#2), 255	TERMINAL TYPE File (#3.2), 193

OPEN EXECUTE (#6) PROHIBITED TIMES FOR SIGN-ON, 16, TERMINAL TYPE File (#3.2), 206, 234, 17 PROHIBITED TIMES FOR SIGN-ON (#15), **OPEN PARAMETERS** DEVICE File (#3.5), 230 **OUEUED TO RUN AT WHAT TIME (#2).** OPEN PARAMETERS (#19) 286, 287, 288, 290 DEVICE File (#3.5), 196, 207, 214, 223, QUEUED TO RUN ON VOLUME SET (#5), 286, 287, 288 227, 231 OPEN PRINTER PORT (#110), 234, 235 **QUEUING** (#5.5) OpenVMS-Specific DEVICE Fields DEVICE File (#3.5), 196 DEVICE File (#3.5), 198 QUEUING REQUIRED (Multiple), 134 ORGANIZATION (#200.2), 21 REMOTE PRINTER NAME (#67), 198 ORIGINAL DATA (#.04) REPLACEMENT VOLUME SET (#7), 255 XUEPCS DATA File (#8991.6), 100 Required Fields OUT OF ORDER MESSAGE (#2), 133, 136, NEW PERSON File (#200), 23 REQUIRED VOLUME SET? (#4), 255 168, 170, 175 RESCHEDULE FREQUENCY (#6), 286, OUT OF SERVICE? (#3), 255 **OUT-OF-SERVICE DATE. 16** 287, 288 RESCHEDULING FREQUENCY (#6), 288, PAC (#14, Programmer Access Code), 35 PAGE LENGTH (#3) 290 TERMINAL TYPE File (#3.2), 206, 229 RESOURCE SLOTS (#35), 169, 172 PASSWORD, 205 DEVICE File (#3.5), 231, 232 PATCH APPLICATION HISTORY RESTRICT DEVICES, 134 (Multiple), 308 REVERSE/NEGATIVE LOCK, 147 PERFORM DEVICE CHECKING, 16 RIGHT MARGIN (#1) PERMITTED DEVICES (Multiple), 134 TERMINAL TYPE File (#3.2), 206 PERSON LOOKUP, 146 ROUTINE (#25), 168, 170, 175 PHONE #3 (#.133), 36 SCHEDULE II NARCOTIC (#55.1), 94, 96 SCHEDULE II NON-NARCOTIC (#55.2), PHONE #4 (#.134), 36 94, 96 PHONE (HOME) (#.131), 11, 36 PKI SERVER (#53.1), 112 SCHEDULE III NARCOTIC (#55.3), 94, 96 POST SIGN-IN MESSAGE, 20 SCHEDULE III NON-NARCOTIC (#55.4), POST-CLOSE EXECUTE (#19.8) 94, 96 DEVICE File (#3.5), 227 SCHEDULE IV (#55.5), 94, 96 POST-CLOSE EXECUTE (#8) SCHEDULE V (#55.6), 94, 96 DEVICE File (#3.5), 196 SCHEDULING RECOMMENDED (#209), PREFERRED EDITOR, 34 126, 286, 288 PREFERRED EDITOR (#31.3), 12, 34 SECONDARY \$I (#52), 200, 204 PRE-OPEN EXECUTE (#7) SECONDARY HFS DIRECTORY (#320.2), DEVICE File (#3.5), 196 204 PRIMARY HFS DIRECTORY (#320), 204 SECONDARY MENU OPTIONS (#203, PRIMARY MENU OPTION, 15, 22, 32, 42, Multiple), 32 SECONDARY MENU OPTIONS (Multiple), PRIMARY MENU OPTION (#201), 32 35, 130, 139, 151 PRINT SERVER NAME OR ADDRESS SECURITY, 16, 33, 205 SECURITY TOKEN SERVICE (#200.1), 21 (#65), 198PRIORITY (#3.8) SELECTABLE AT SIGN-ON Options, 126 TERMINAL TYPE File (#3.2), 19 Server Options, 170 SELECTABLE AT SIGN-ON (#.02) PRIORITY AT RUN TIME (#25), 261 TERMINAL TYPE File (#3.2), 206, 209

SERVER ACTION (#221), 169, 170, 171,	TERMINATION DATE (#9.2), 35, 40, 41,
172	91, 96
SERVER AUDIT (#223), 171	TEXT TERMINATOR, 38
SERVER BULLETIN (#220), 171	TEXT TERMINATOR (#31.2), 12
SERVER DEVICE (#227), 169, 172	TIED ROUTINE, 15
SERVER MAIL GROUP (#222), 171	TIME PERIOD (#.01), 134
SERVER REPLY (#225), 172	TIMED READ, 20
SERVICE/SECTION, 31	TIMED READ (#200.1), 35
SERVICE/SECTION (#29), 34	TIMES/DAYS PROHIBITED (#3.91)
SEX (#4)	(Multiple), 169, 170
NEW PERSON File (#200), 23	TITLE (#8), 11, 32
SIGNATURE BLOCK PRINTED NAME, 67	TO UCI (#3), 257
SIGNATURE BLOCK PRINTED NAME	TO VOLUME SET (#2), 257
(#20.2), 67	TRANSLATION Subfield (#.847), 57
SIGNATURE BLOCK TITLE (#20.3), 67	TRANSPORT BUILD NUMBER (#63), 315,
SIGN-ON/SYSTEM DEVICE (#1.95)	337
DEVICE File (#3.5), 195, 208, 211, 212	TYPE
SLAVE FROM DEVICE, 235	DEVICE File (#3.5), 197
SPECIAL QUEUEING (#9), 286	TYPE (#.1)
SPECIAL QUEUEING(#9), 288	VOLUME SET File (#14.5), 254, 255
SSN	TYPE (#2)
PATIENT File (#2), 55	DEVICE File (#3.5), 195, 261
SSN (#9)	TYPE (#4)
NEW PERSON File (#200), 22, 23, 32	OPTION File (#19), 170
START NEXT, 283	TYPE-AHEAD, 20
STATUS, 322	TYPE-AHEAD (#.09), 57
STATUS (#.02), 330	TYPE-AHEAD (#200.09), 12, 35
SUBJECT ORGANIZATION (#205.2), 21	UCI ASSOCIATION TABLE, 257
SUBJECT ORGANIZATION ID (#205.3), 21	USE PARAMETERS (#19.5)
SUBMANAGER RETENTION TIME (#5),	DEVICE File (#3.5), 196
251	USE TIMEOUT ON OPENS (#2009.5)
SUBORDINATE KEY (Multiple), 146	DEVICE File (#3.5), 230
SUBTYPE (#3)	USER CHARACTERISTICS TEMPLATE,
DEVICE File (#3.5), 195, 206, 229	39
SUPPRESS BULLETIN (#224), 172	USER CLASS (#9.5), 43
SUPPRESS FORM FEED AT CLOSE	VA# (#53.3), 94, 96
(#11.2), 228	VAX ENVIRONMENT FOR DCL (#9), 252,
SYNC FLAG, 283	263
TASK PARAMETERS, 48, 163, 184	VERIFY CODE, 32
TASK PARAMETERS (#15), 286, 288	VERIFY CODE (#7.2), 12, 32
TASK PARTITION SIZE (#4), 251	VERSION (Multiple), 308
TASKMAN FILES UCI (#5), 255	VMS DEVICE TYPE (#63), 198
TASKMAN FILES VOLUME SET (#6), 255	VOICE PAGER (#.137), 11, 36, 67
TASKMAN HANG BETWEEN NEW JOBS	VOLUME SET (#.01)
(#7), 251	VOLUME SET (#.01) VOLUME SET File (#14.5), 254
TASKMAN JOB LIMIT, 16, 249	VOLUME SET THE (#14.5), 254 VOLUME SET (#41, Multiple)
TASKMAN JOB LIMIT (#6), 251	KERNEL SYSTEM PARAMETERS File
TASKMAN PRINT A HEADER PAGE?	(#8989.3), 251
(#26), 261	VOLUME SET (Multiple)
(#20), 201 TELNET PORT (#66), 198	KERNEL SYSTEM PARAMETERS File
TERMINATION DATE, 23, 41, 42, 171	(#8989.3), 16
1 LIMILIA 11 DA 1 L, 23, 71, 72, 1/1	(110707.3), 10

VOLUME SET(CPU) (#1.9)	ALERT CRITICAL TEXT (#8992.3), 158
DEVICE File (#3.5), 195, 208, 211, 212,	ALERT TRACKING (#8992.1), 160, 162,
261, 287	163, 165, 166
Fields Being Audited Option, 52	ALTERNATE EDITOR (#1.2), 34
File Access Security, 31, 33, 49, 50	AUDIT (#1.1), 55
Access Level, 52	Audit Access, 55
AUDIT, 49, 51, 52, 54, 55	AUDIT LOG FOR OPTIONS (#19.081), 127
Conversion	168, 171
Advance Preparation, 60	BUILD (#9.6), 304, 307, 315, 320, 325, 333,
Advantages, 60	335, 337
After, 65	BULLETIN (#3.6), 171, 175
Instructions, 64	CPT (#81), 341
Summary, 63	DA RETURN CODES (#3.22), 18, 19, 194,
DATA DICTIONARY, 49, 51, 53, 54, 55, 63	209
DELETE, 49, 51, 53, 54	Global Location, 194
DELETE Access, 33, 51	DCL Command, 252, 263
LAYGO, 32, 49, 51, 53, 54, 63, 65, 124	DEVICE (#3.5), 2, 15, 16, 17, 18, 33, 169,
LAYGO Access, 51	172, 194, 195, 198, 199, 200, 203, 204,
Menu, 55, 56, 60, 64, 65, 66	206, 207, 208, 223, 224, 227, 228, 229,
Properties, 52	230, 231, 232, 234, 235, 247, 261, 287
READ, 49, 51, 53, 54, 65, 124	\$I Field, 194, 197, 208, 211, 212, 215, 223
READ Access, 33, 60	230, 231, 232, 234, 298, 300
Running the Conversion, 60	\$I Field (#1), 195, 208, 223
System Management, 50	ASK HFS I/O OPERATION Field (#5.2),
User Interface, 49	214
When is File Access Security Checked?, 51	ASK HOST FILE Field (#5.1), 214
Who Needs File Access?, 52	ASK PARAMETERS Field (#5), 214
WRITE, 49, 51, 54, 124	Cross-references, 211
WRITE Access, 33	Fields, 195
FILE MANAGER ACCESS CODE Field (#3),	Global Location, 194
33, 40, 42, 49, 50, 51, 54, 55, 57, 60, 63, 64,	MARGIN WIDTH Field (#9), 229
124, 144, 145, 152, 205	NAME Field (#.01), 195
File Merge Capability	OPEN PARAMETERS Field (#19), 196
Developing, 339	OpenVMS-Specific DEVICE Fields, 198
FILE RANGE Field (#31.1), 35	POST-CLOSE EXECUTE Field (#19.8),
FILE SERVER Type (Obsolete), 254	227
FileMan	POST-CLOSE EXECUTE Field (#8), 196
Browser Device, 225	PRE-OPEN EXECUTE Field (#7), 196
Limited File manger Options (Build) Option,	QUEUING Field (#5.5), 196
151	SIGN-ON/SYSTEM DEVICE Field
Line Editor, 12, 34, 50, 52	(#1.95), 195, 208, 211, 212
Menu, 49	SUBTYPE Field (#3), 195, 206, 229
Screen Editor, 9, 18, 34	TYPE Field, 197
What Happened to DIFROM, 309	TYPE Field (#2), 195
FileMan edit template Option, 170	USE PARAMETERS Field (#19.5), 196
FileMan Inquire to File Entries Option, 342	VOLUME SET(CPU) Field (#1.9), 195,
Files Adding Explicit File Access for System	208, 211, 212, 261, 287
Adding Explicit File Access for System	DEVICE File (#3.5)
Administrators, 61	OPEN PARAMETERS Field (#19), 227
AGENCY (#4.11), 19	Device File Entries, 234
ALERT (#8992), 162, 163, 164, 165, 166	DIALOG (#.84), 57

DOMAIN (#4.2), 61, 64 ERROR LOG (#3.075), 181, 184, 291 ERROR MESSAGES (#3.076), 184 Exported, 32 FAILED ACCESS ATTEMPTS LOG (#3.05), 47File Access Security Conversion Instructions, FORUM ROUTINE (#9.8), 315, 337 **FUNCTION (#.5), 33** HELP FRAME (#9.2), 178, 179, 180 Host, 213 How to Grant Access, 55 ICD DIAGNOSIS (#80), 341, 342 ICD OPERATION/PROCEDURE (#80.1), 341 INSTALL (#9.7), 307, 308, 310, 312, 320, 322, 323, 325, 329, 330, 333, 335 INSTITUTION (#4), 19, 89, 110 KERNEL PARAMETERS (#8989.2), 39 KERNEL SYSTEM PARAMETERS (#8989.3), 15, 16, 18, 19, 20, 21, 23, 36, 42, 57, 112, 204, 218, 220, 251, 294 KERNEL SYSTEM PARAMETERS file (#8989.3)Mixed OS Environment Fields, 204 KIDS, 307 LANGUAGE (#.85), 57 333 Levels of File Access Security, 52 LOCAL KEYWORD (#8984.1), 338, 341, 166 343, 349, 350, 353 LOCAL LOOKUP (#8984.4), 338, 341, 342, 346, 348, 349, 350, 353, 362 LOCAL SHORTCUT (#8984.2), 338, 341, 343, 346, 349, 350 LOCAL SYNONYM (#8984.3), 338, 341, 343, 349, 353 MESSAGE (#3.9), 220 NEW PERSON (#200), 6, 10, 11, 14, 15, 17, 18, 19, 20, 21, 22, 23, 31, 32, 33, 40, 41, 42, 43, 45, 46, 48, 49, 50, 55, 56, 57, 60, 63, 66, 67, 89, 90, 91, 92, 93, 94, 96, 98, 99, 109, 110, 111, 122, 130, 139, 144, 146, 147, 155, 175, 208, 221, 271 DEA EXPIRATION DATE (#747.44), 89, 90, 91, 92, 93 DEA# Field (#53.2), 89, 90, 91, 92, 93, 94, DUZ, 57, 94, 96, 98, 99 277

NAME Field (#.01), 89, 91, 92, 93, 94, 96, 98, 99 Required Fields, 23 SCHEDULE II NARCOTIC Field (#55.1), 94, 96 SCHEDULE II NON-NARCOTIC Field (#55.2), 94, 96SCHEDULE III NARCOTIC Field (#55.3), SCHEDULE III NON-NARCOTIC Field (#55.4), 94, 96SCHEDULE IV Field (#55.5), 94, 96 SCHEDULE V Field (#55.6), 94, 96 TERMINATION DATE (#9.2), 91 TERMINATION DATE Field (#9.2), 96 VA# Field (#53.3), 94, 96 NEW PERSON file (#200), 33 OLD ACCESS AND VERIFY CODES (#200 XREF), 47 OPTION (#19), 21, 33, 41, 118, 119, 122, 124, 125, 126, 131, 133, 136, 137, 138, 139, 140, 144, 149, 156, 168, 169, 173, 174, 175, 180, 286, 288 Dangling Pointers, 131, 179 OPTION SCHEDULING (#19.2), 135, 163, 241, 242, 247, 284, 285, 286, 287, 288, 290 Other TaskMan Files, 247 PACKAGE (#9.4), 53, 304, 307, 308, 309, PARAMETER DEFINITION (#8989.51), PARAMETERS (#8989.5), 166, 339 PATIENT (#2), 55 Purpose of Granting Access, 51 RESOURCE (#3.54), 231 ROUTINE (#9.8), 315, 336, 337 SCHEDULE, 241, 245, 246, 247, 249, 250, 275, 278, 297, 298, 299, 301 SECURITY KEY (#19.1), 144, 146, 147, 180 SERVICE/SECTION (#49), 31, 34 SIGN-ON LOG (#3.081), 43, 45, 46, 47 Purging, 46 SPOOL DATA (#3.519), 220 SPOOL DOCUMENT (#3.51), 192, 207, 220, 221, 224 TaskMan, 245 TASKMAN ERROR, 278 TASKMAN SITE PARAMETERS (#14.7), 16, 245, 247, 249, 250, 254, 258, 259, 265,

BOX-VOLUME PAIR Field (#.01), 250,	VOLUME SET (#14.5), 22, 245, 247, 249,
251	253, 257, 284, 300, 301, 302
Load Balance Routine, 259	DAYS TO KEEP OLD TASKS Field (#8)
LOAD BALANCE ROUTINE Field (#21),	256
253	INHIBIT LOGONS? Field (#1), 255
LOG TASKS? Field (#2), 250	LINK ACCESS Field (#2), 255
MODE OF TASKMAN Field (#8), 251	OUT OF SERVICE? Field (#3), 255
Standardized VA Caché and GT.M	REPLACEMENT VOLUME SET Field
Configuration, 258	(#7), 255
SUBMANAGER RETENTION TIME	REQUIRED VOLUME SET? Field (#4),
Field (#5), 251	255
TASK PARTITION SIZE Field (#4), 251	Standardized VA Caché and GT.M
TASKMAN HANG BETWEEN NEW	Configuration, 258
JOBS Field (#7), 251	TASKMAN FILES UCI Field (#5), 255
TASKMAN JOB LIMIT Field (#6), 251	TASKMAN FILES VOLUME SET Field
VAX ENVIRONMENT FOR DCL Field	(#6), 255
(#9), 252	TYPE Field (#.1), 254, 255
TASKS (#14.4), 239, 241, 242, 243, 245, 247,	VOLUME SET Field (#.01), 254
249, 250, 251, 271, 272, 273, 274, 284,	Who Needs File Access?, 52
286, 287, 291, 293, 295, 297, 299, 301	XUEPCS DATA (#8991.6), 88, 100, 102
TERMINAL TYPE (#3.2), 18, 19, 190, 194,	XUEPCS PSDRPH AUDIT (#8991.7), 89,
195, 206, 207, 209, 228, 229, 234	106
BACK SPACE Field (#4), 206, 229	Find a User Option, 43
CLOSE EXECUTE Field, 193	Fix Help Frame File Pointers Option, 179
CLOSE EXECUTE Field (#7), 206, 228,	Fix Option File Pointers Option, 131
234, 235	FORM FEED Field (#2)
FORM FEED Field (#2), 206, 229	TERMINAL TYPE File (#3.2), 206, 229
Global Location, 194	Form Feeds, 228
NAME Field (#.01), 206	SUPPRESS FORM FEED AT CLOSE Field
Naming Conventions, 207	(#11.2), 228
OPEN EXECUTE Field, 193	System Management, 228
OPEN EXECUTE Field (#6), 206, 234,	User Interface, 228
235	Forms
PAGE LENGTH Field (#3), 206, 229	Security, 23, 24
RIGHT MARGIN Field (#1), 206	FORUM ROUTINE File (#9.8), 315, 337
SELECTABLE AT SIGN-ON Field, 19	Forwarding
SELECTABLE AT SIGN-ON Field (#.02),	Alerts, 161
206, 209	FPHYSICAL DISK (#505), 204
Terminal Type File Entries, 234	FROM UCI Field, 256
TITLE (#3.1), 32	FROM UCI Field (#.01), 257
Transfer Entries, 53, 54	FROM VOLUME SET Field, 256
Transfer File Entries, 53	FROM VOLUME SET Field (#1), 257
UCI ASSOCIATION (#14.6), 245, 247, 249,	FUNCTION File (#.5), 33
256, 300	Functional Description
FROM UCI Field (#.01), 257	Multi-Term Look-Up (MTLU), 341
FROM VOLUME SET Field (#1), 257	Further Delegation, 156
Standardized VA Caché and GT.M	Future tasks Option, 272
Configuration, 258	
TO UCI Field (#3), 257	G
TO VOLUME SET Field (#2), 257	

August 2016

General Parameter Tools Option, 141	Purging, 134
General Processor Mode, 251	Scratch, 227
GENERAL PURPOSE VOLUME SET Type,	XUTL, 136, 142
254	Glossary, 363
GENERATE SPL DOC NAME Field (#33)	Intranet Website, 367
DEVICE File (#3.5), 224	Go-home Jump, 120
GET_METRIC.COM Script, 260	Grant Access by Profile Option, 23, 34
GETENV^%ZOSV API, 250	Granting File Access, Purpose, 51
GIVEN BY Subfield (#1)	
KEYS Multiple Field (#51), 98, 99	Н
Global Distributions, 309, 310	••
GLOBAL LOCK Field (#36), 231	Halt Option, 121
Globals	HEADER Field (#26), 133, 168, 171
^%ZIS, 247	Header Page
^%ZIS(1,, 194	TaskMan, 261
^%ZIS(2,, 194	Help
^%ZIS(3.22,, 194	At Prompts, xlii
^%ZISL, 231	Display Option Help, 117
^%ZTER, 181, 184	Displaying Option Descriptions, 119
^%ZTSCH, 241, 245, 247, 255, 259, 286,	Extended, 177
293, 298	Listing Options, 117
^%ZTSK, 241, 245, 255, 259, 271, 284, 297,	Listing Secondary and Common Options, 117
298	Online, xlii
^%ZUA(3.05, 47	Question Marks, xlii, 7, 20, 35, 50, 59, 116,
^DISV, 40, 60, 61, 64, 65	117, 119, 120, 123, 130, 143, 177, 180,
KILLing, 60, 61, 64	182, 183, 185, 188, 197, 238, 240, 273,
^TMP, 134, 135	278, 279, 319
^UTILITY(\$J, 63, 134, 135	HELP FRAME Field, 126, 179, 180
^XMB, 220	HELP FRAME File (#9.2), 178, 179, 180
^XMBS, 220	Help Frames
^XTMP, 133, 134, 135, 310, 312, 323	Creating, 179
^XUSEC(0,, 47, 134	Deleting Help Frames, 179
^XUTL, 134, 135, 140, 208	Disk Space Concerns, 179
Display Nodes, 138	Display, 176
Structure and Function, 137	Editing, 179
User Stacks, 137	Editors, 179
Installing Global Distributions, 324	Exported, 179
KIDS Transport Global, 304	Keywords, 180
Backup, 318	Layout Considerations, 180
Compare, 307, 310, 316	Linking Help to an Option or Menu, 180
Create, 306, 309, 336	Menu System, 177
Definition, 304	Namespacing, 180
Environment Check, 310	XUSER COMPUTER ACCOUNT, 24
Export, 306	Help Processor, 176
Install, 307	Cross Reference Help Frames Option, 179
Load from Distribution, 307, 310, 312	Deleting Help Frames, 179
Load from PackMan Messages, 307, 310	Display/Edit Help Frames Option, 178
Print, 307, 310, 316	Editors, 179
Processing, 319	Fix Help Frame File Pointers Option, 179
Verify, 336	Help System Actions, 177
Verifying Checksums, 315	Layout Considerations, 180
,	Layout Considerations, 100

Linking a Help Frame as Help for an Option or Menu, 180	Restart TaskMan when Running in a DCL Context, 266
List Help Frames Option, 178	Use this Manual, xxxviii
Menu, 178	
Menu System, 177 New/Revised Help Frames Option, 178	1
System Management, 178	ICD DIA CNOGIG E'I (1100) 241 242
User Interface, 176	ICD DIAGNOSIS File (#80), 341, 342
HFS Device, 200	ICD OPERATION/PROCEDURE File (#80.1),
HFS Devices, 196, 207, 213, 214, 232, 261, 304,	341
309, 310, 312	Identifying Locked Options, 144
History	Idle Node, 293
DEA ePCS Utility, 69	If the Option Invokes Non-VistA Applications,
History, Revisions to Documentation and	126
Patches, ii	If the Option Should Be Regularly Scheduled,
Home Device, 187, 189, 208, 234, 235	126
Home Pages	Implementation
Acronyms Intranet Website, 367	Multi-Term Look-Up (MTLU), 359
Adobe Website, xliii	INDEPENDENTLY INVOCABLE Field, 131
Enterprise Program Management Office	Information Stored in the INSTALL File (#9.7)
Website, xxxix	(KIDS), 320
Glossary Intranet Website, 367	INHIBIT LOGONS? Field, 22
KAAJEE Documentation Website, 5	INHIBIT LOGONS? Field (#1), 255
Kernel Website, xliii	INIT Routines, 304, 309
RPC Broker Documentation Website, 4	INITIAL Field (#1)
VA FileMan Documentation Website, 33, 49,	NEW PERSON File (#200), 11, 23, 31, 32, 67
52	Inquire Option, 129
	Inquire to File Entries Option, 53, 55
VA Software Document Library (VDL)	Inspecting the Tasks in the Monitor's Lists, 279
Website, xliii, 339, 340	INSTALL ANSWERS Field (Multiple), 320
HOME^%ZIS, 126	INSTALL COMPLETE TIME Field (#17), 330
Host File Server, 196, 207, 213, 214, 232, 261,	INSTALL File (#9.7), 307, 308, 310, 312, 320,
304, 309, 310, 312	322, 323, 325, 329, 330, 333, 335
Host File Server Device Edit Option, 200, 214	Purging, 333
Host Files, 213	Install File Print Option, 320, 322, 329
Caché Devices Setup, 215	Install Package(s) Option, 310, 319, 320
GT.M Devices Setup, 215	INSTALL/CHECK MESSAGE PackMan
Host File Server Device Edit Option, 214	Option, 310, 312
System Management, 214	Installation Menu, 307
User Interface, 213	Installation Menu (KIDS), 311, 318
How Can the Number of Instances of a Server	Installations
Option Be Controlled?, 169	Components, 322
How Shared Device and Terminal Type	Finish, 322
Attributes are Used, 207	Global Distributions (KIDS), 324
How the File Access Security Conversion	KIDS, 305, 307
Works	Menu (KIDS), 311
Summary, 63	Progress (KIDS), 322
How to	Restarting, 323
Delete a Regularly Scheduled Task, 286	Running (KIDS), 319
Grant File Access, 55	Scheduling (KIDS), 319
Obtain Technical Information Online, xlii	Sequence (KIDS), 310
Requeue a Regularly Scheduled Task, 286	Standard Distributions (KIDS), 310

Instances How Can the Number of Instances of a Server Option Be Controlled?, 169	Installation and Distribution System (KIDS), 304 KIDS, 304
INSTITUTION File (#4), 19, 89, 110	Signon Auditing Files, 47
Intended Audience, xxxix	Website, xliii
DEA ePCS Utility, 71	Kernel Installation & Distribution System Menu,
Intensity, 192	305
Interactive Print of Error Messages Option, 186 INTERACTIVE USER'S PRIORITY Field, 18 INTERACTIVE TEXT Field, 15, 20	Kernel Management Menu, 204 KERNEL PARAMETERS File (#8989.2), 39 KERNEL SYSTEM PARAMETERS file
INTRO TEXT Field, 15, 20	
Introduction, 1	(#8989.3), 204, 218
Multi-Term Look-Up (MTLU), 341	Mixed OS Environment Fields, 204
System Manager, 2	KERNEL SYSTEM PARAMETERS File
User, 1	(#8989.3), 15, 16, 18, 19, 20, 21, 23, 36, 42,
Introductory Text	57, 112, 204, 220, 251, 294
Signon/Security, 15	Key Management Menu, 78, 145, 146, 155
Introductory text edit Option, 15	Key Word In Context (KWIC), 342, 359
INVOKED BY ROUTINE Field, 179	Keys
Invoking Non-VistA Applications Options, 126	Delegating, 155
IO	Delegation Levels, 145, 147, 150, 155
List, 277	Exported, 147
Variables, 126	Management
IONOFF Variable, 228	Security Keys, 144
	Provider, 41, 145, 146
J	KEYS Field (Multiple), 144, 145, 151
	Keys For a Given Menu Tree Option, 145
JOB Command, 242, 251, 252, 295	Keyword Option
Job List, 246, 278	Multi-Term Look-Up (MTLU)
Node, 294	Example, 359
Jobs	Keywords
KILL, 278	Help Frames, 180
Jumbled Screen	Multi-Term Look-Up (MTLU), 341, 353
Escaping from, 9	Associated with a Single Term and Multiple
Jump Nodes, 137	Terms, 343
^XUTL Global, 140	Keywords Option
Jump Start	Multi-Term Look-Up (MTLU), 342, 356
Signon, 8	KIDS, 325, 336
Jumps	Aborted Installations, 323
Error Messages During Menu Jumping, 136	Recovering From, 323
Options, 120	Alpha/Beta Tracking, 326
Phantom, 136, 137	Answering Installation Questions for
Rubber-band Jump, 120	Transport Globals in a Distribution, 310
Up-arrow, 116, 120, 121, 122, 123, 135	Backup a Transport Global Option, 318
	Build Entry
V	Definition, 304
K	BUILD File (#9.6), 307
KAAJEE Documentation Website, 5	Build File Print Option, 328
KEEP AT TERMINATE Field, 146	Changes in the Role of the PACKAGE File
Kernel	(#9.4), 308
	Checkpoints, 323
	Checksums, 310, 315, 335, 337

Comparing Loaded Transport Globals to the	Progress Bar (Installations), 322
Current System, 316	Purge Build or Install Files Option, 333
Components, 315	Purging
Definition, 304	BUILD File, 325
Convert Loaded Package for Redistribution	INSTALL File, 325
Option, 330	Selected Entries, 334
Definitions, 304	Re-answering Installation Questions, 320
Deleting Security Keys, 147	Reasons to Retain BUILD and INSTALL File
Display Patches for a Package Option, 333	Entries, 335
Distributions, 305, 306	Recovering from an Aborted Distribution
Definition, 304	Load, 323
Global, 309, 324	REPLACE, 324
Split Across Diskettes, 312	Restarting Aborted Installations, 323
Standard, 309	Rollup Patches into a Build Option, 335
Transport Mechanism, 309	ROUTINE File (#9.8), 336
Edit Install Status Option, 330	Running Installations, 319
Environment Check, 310, 312	Scheduling Installations, 319
Exported	Selecting Software Names for Purging, 334
Components, 316	Software Installation, 311
Files, 307	Standard Distributions, 309, 310
Global Distributions, 309, 310	System Management
Information Stored in the INSTALL File	Installations, 304
(#9.7), 320	Utilities, 327
INSTALL File (#9.7), 308	Transport Global, 304
Information, 320	Backup, 318
Install File Print Option, 329	Checksums, 315
Installations, 294, 305, 307	Compare, 307, 310, 316
Answering Questions, 319	Create, 306, 309, 336
Global Distributions, 324	Definition, 304
Menu, 311	Environment Check, 310
Progress, 322	Export, 306
Progress Bar, 322	Install, 307
Queued, 319	Load from Distribution, 307, 310, 312
Re-answering Questions, 320	Load from PackMan Messages, 307, 310
Restarting, 323	Print, 307, 310, 316
Sequence, 310	Processing, 319
Software, 311	Verify, 336
Standard Distributions, 310	Verifying Checksums, 315
Loading	Transport Mechanism
Standard Distributions, 312	Distributions, 309
Transport Globals from a Distribution or	Update Routine File Option, 336
PackMan Message, 310	Verify a Build Option, 336
Once the Installation Finishes, 322	Verify Package Integrity Option, 337
Options, 305	Verifying Checksums in a Transport Global,
OVERWRITE, 324	315
Package	Versions to Retain, 333
Definition, 304	When the Distribution is Split Across
PACKAGE File (#9.4), 308	Diskettes, 312
Patches, 308, 309, 318, 335	When the Installation is Queued, 319
Printing Loaded Transport Globals, 316	KILL
Processing Each Transport Global, 319	^DISV Global, 60, 61, 64

^TMP Global, 135	List of tasks Option, 272
^UTILITY(\$J Global, 135	List Options by Parents and Use Option, 128
^XTMP Global	List own tasks Option, 240
INSTALL File (#9.7) Entries and Transport	List Spool Documents Option, 218
Globals, 310	List Tasks Option, 271, 273, 279, 298
Device Allocation List Node, 293	All your tasks, 272
IO Variables, 126	Future tasks, 272
Jobs, 278	List of tasks, 272
Signon Nodes, 135	Running tasks, 272
Software-wide Variables, 131	Tasks waiting for a device, 272
Subscript (\$J) or Namespace, \$J in the	Unsuccessful tasks, 272
^UTILITY(\$J or ^TMP Global, 135	Your future tasks, 272
TaskMan Process, 283	List the Defined Options Sets Option, 133
Tasks, 278	List Users Option, 43
Update Node, 295	Listing and Printing Tasks, 240
KILL off a users' job Option, 278, 295	Listing Options, 117
KWIC, 342, 359	Listing Primary, Secondary, and Common Menu Options, 118
	Listing Secondary and Common Options, 117
L	LKUP^XTLKMGR API, 362
LANGUAGE Field (#.01)	Load a Distribution Option, 309, 310, 312, 313,
DIALOG File (#.84), 57	324
LANGUAGE File (#.85), 57	Load Balance Routine
LANGUAGE Field (#200.07), 36, 57	TASKMAN SITE PARAMETERS File
LANGUAGE File (#.85), 57	(#14.7), 259
LAST SIGN-ON DATE/TIME Field (#202), 42	LOAD BALANCE ROUTINE Field, 259, 260
LAT PORT SPEED Field (#64), 198	LOAD BALANCE ROUTINE Field (#21), 253
LAT SERVER NODE Field (#61), 198	Load Balancing and Multiple Managers, 259
LAT SERVER PORT Field (#62), 198	Load List Node, 294
LAYGO Access, 32, 49, 51, 53, 54, 63, 65, 124	Load Node, 294
Levels of File Access Authority, 52	Loading
LIFETIME OF VERIFY CODE Field, 19	Standard Distributions (KIDS), 312
Limited File Manager Options (Build) Option,	Transport Globals from a Distribution or
151, 152, 157	PackMan Message (KIDS), 310
Example, 153	LOCAL KEYWORD File (#8984.1), 338, 341,
Limiting Simultaneous Running of a Particular	343, 349, 350, 353
Task, 231	LOCAL LOOKUP File (#8984.4), 338, 341,
Line Editor	342, 346, 348, 349, 350, 353, 362
VA FileMan, 12, 34, 50, 52	LOCAL SHORTCUT File (#8984.2), 338, 341,
LINK ACCESS Field (#2), 255	343, 346, 349, 350
Link List, 246	LOCAL SYNONYM Field, 211
Link List Node, 294	LOCAL SYNONYM File (#8984.3), 338, 341,
Linking a Help Frame as Help for an Option or	343, 349, 353
Menu, 180	LOCK Field (#3), 144, 147, 168, 170
List Alerts for a user from a specified date	Locked Options
Option, 165	Identifying, 144
List Delegated Options and their Users Option,	Lock-out Times, 16
157	Locks
List Error Screens Option, 182	Negative, 133
List File Attributes Option, xliii, 53	Options, 130, 133
List Help Frames Option, 178, 180	Reverse, 133, 144, 147
* · · · · · · · · · · · · · · · · · · ·	

388

LOG RESOURCE USAGE? Field, 294	Mail
Log Resources Node, 294	Purging, 42
LOG TASKS? Field (#2), 250	MAIL CODE Field (#28), 32
LOGICAL DISK NAME Field (#504), 204	Make an Alert on the Fly Option, 164
LOGIN Menu Template, 7, 122	Make spool document into a mail message
Logon, 4	Option, 219
Logs	Manager
Add Error Screens Option, 182	Startup TaskMan, 259
AUDIT LOG FOR OPTIONS File (#19.081),	TaskMan, 241, 242
127, 168, 171	UCI Definition, 248
Clean Error Log Over Range Of Dates	Managing
Option, 292	Delegates, 153
Clean Error Trap Option, 184	System Management, 153
Delete Error Log Option, 292	Display Attributes (DA) Return Codes, 209
Edit Error Screens Option, 182	Menus and Options, 130
Error Log, 186	Out-Of-Order Option Sets, 132
ERROR LOG File (#3.075), 181, 184, 291	Primary Menus, 130
Error Log Node, 293	Spool Documents, 221
Error Log Purge, 184	Map Pointer Relations Option, 53
FAILED ACCESS ATTEMPTS LOG File	MARGIN WIDTH Field (#9)
(#3.05), 47	DEVICE File (#3.5), 229
List Error Screens Option, 182	Mark Option Set Out-Of-Order Option, 133
LOG RESOURCE USAGE? Field, 294	MAX SIGNON ALLOWED Field, 15, 16
Log Resources Node, 294	MAX SIGNON ALLOWED Field (#41,2), 251
LOG TASKS? Field (#2), 250	MAX SPOOL DOCUMENT LIFE-SPAN Field
Old Access Codes Stored in the Whole-file	(#31.3), 218, 222
AOLD Cross-reference in File #200, 48	MAX SPOOL DOCUMENTS PER USER Field
Old Verify Codes Stored in the Whole-file	(#31.2), 222
VOLD Cross-reference in File #200, 48	MAX SPOOL LINES PER USER Field (#31.1),
Purge Error Log Of Type Of Error Option,	220, 222
292	MENU (item) Field (Multiple), 124
Queuable Task Log Clean Up Option, 284	Menu Management Menu, 78, 153
Remove Error Screens Option, 183	Menu Manager
Show Error Log Option, 291	AUTO MENU, 117
SIGN-ON LOG File (#3.081), 43, 45, 46, 47	Diagramming Options, 128
Purging, 46	Display Options, 129
Taskman Error Log	Double Quote Jump, 121
Menu, 291	Fixing Option File Pointers, 131
TaskMan Error Log, 181, 246, 278, 284, 291	Go-home Jump, 120
XUSCZONK Option	Local modifications, 131
Purging File #3.081, 46	LOGIN Menu Template, 7
XUTM QCLEAN Option, 291	Menu jumping, 120
Lookup-type Cross-reference, 31, 32	Menu Tree Rebuilding, 135
Loopback Test of Device Port Option, 210	Options that Should Be Scheduled, 134
Low Usage of Alpha/Beta Test Options Option,	Primary Menu, 117
326	Rebuilding Menu Trees, 135
	Restricting Option Usage, 133
	Rubber-band Jump, 120
M	Summary, 123
Magtape Devices, 229	System Management, 124
System Management, 229	Out-Of-Order Set Management Menu, 132
Dysich ivianagement, 227	

Templates	Menu Templates Option, 122
LOGIN Menu, 122	Multi-Term Lookup (MTLU) Main Menu,
Up-arrow Jump, 120	343
User Interface, 116	Navigating, 116
Variables, Troubleshooting, 142	Operations Management, 43, 326
MENU TEMPLATE Field (Multiple), 122	OR PARAM IRM MENU, 75
Menu Templates Option, 122	ORMGR, 75
MENU TEXT Field (#1), 170	Out-Of-Order Set Management, 132
Menus	PARENT OF QUEUABLE OPTIONS, 46,
Alert Management, 161, 163	134, 222, 285
Alpha/Beta Test Option Usage Menu, 127,	Primary, 5, 8, 9, 15, 22, 32, 116, 120, 124,
326	128, 130, 131, 138, 140, 142
Altering Exported Menus, 131	Assigning, 22
Application Utilities, 343	Managing, 130
Audit Features, 127	Trees, 135, 136, 137, 140, 142
Common, 6, 32, 117, 118, 120, 121, 130, 143,	Programmer Options, 144, 305
147, 158, 218, 221, 237	Rebuilding, 135
Redefining, 130	Report Menu for Alerts, 164
CPRS Configuration (IRM), 75	Secondary, 35, 117, 120, 128, 129, 130, 131,
CPRS Manager Menu, 75	137, 139, 145, 149, 150
Creating, 124	Assigning, 130
Data Dictionary Utilities, xliii, 53	Trees, 130, 138
DEA ePCS Utility, 86	Secure Menu Delegation, 152, 153, 154, 156
DEA ePCS Utility Functions, 86	Secure Menu Management, 149, 152
Delegate's Menu Management, 149, 151, 152,	Spool Management, 220, 221, 222
154, 155	Spooler Menu, 218, 219, 221
Device Management, 199, 210	Systems Manager Menu, 78, 80, 83, 305
DI DDU, xliii, 53	Taskman Error Log, 181, 291
Diagramming, 128	Taskman Management, 181
Display Menus and Options, 128, 129	TaskMan Management Menu, 270
Displaying, 128	Taskman Management Utilities, 181, 275
DIUTILITY, 53	Testing, 132
Edit	Text, 125
Line Editor, 50	User Management, 39, 49, 80, 83
Edit option, 34	User Management Menu, 43, 55, 60, 65
Edit TaskMan Parameters, 249, 261	User's Toolbox, 6, 9, 10, 11, 13, 67, 68, 121,
Edits and Distribution, 306	122, 218, 237
ePCS DEA Utility Functions, 87	Utilities For MTLU, 349
Error Processing, 183	Utilities Menu
EVE, 78, 80, 83, 138, 139, 156, 181, 305	KIDS, 327
Exported, 124, 131	Utility Functions, 53
File Access Security, 55, 56, 60, 64, 65, 66	VA FileMan, 49
General Parameter Tools, 75	XPAR MENU TOOLS, 75
Help Processor, 178	XPD DISTRIBUTION MENU, 306
Installation (KIDS), 307, 311, 318	XPD INSTALLATION, 311
Kernel Installation & Distribution System,	XPD INSTALLATION MENU, 307
305	XPD MAIN, 305
Kernel Management Menu, 204	XPD UTILITY, 327
Key Management, 78, 145, 146, 155	XQAB MENU, 326
Managing, 130	XQAL REPORTS MENU, 164
Menu Management, 78, 153	XQALERT MGR, 163

XQDISPLAY OPTIONS, 128, 129	Compute Server, 251
XQHELP-MENU, 178	Copy Print, 233
XQOOMAIN, 132	General Processor, 251
XQSMD MGR, 153, 156	Other Non-TaskMan, 251
XQSMD USER MENU, 149, 151, 152, 154,	Print Server, 251
155	Printer Controller, 233
XTLKUSER2, 343	Transparent Print, 233
XTLKUTILITIES, 349	Modify File Attributes Option, 53, 55
XTMENU, 343	Monitor TaskMan
XU EPCS UTILITY FUNCTIONS, 86, 87	Inspecting the Tasks in the Monitor's Lists,
XUAUDIT MENU, 127	279
XUCOMMAND, 130	Monitor Taskman Option, 260, 275, 301
XUERRS, 183	Action Prompt, 278
XUFILEACCESS, 55, 56, 60, 64, 65, 66	IO List, 277
XUKERNEL, 204	Job List, 278
XUKEYMGMT, 78	RUN Node, 276
XUMAINT, 78	Schedule List, 277
XUOPTUSER, 43	Status List, 276
XUPROG, 305	Task List, 278
XUSER, 39, 49, 55, 60, 65, 83	Mounted Volume Sets
XUSERTOOLS, 10	Definition, 248
XUSITEMGR, 43, 326	MULTI-DEVICE DESPOOLING Field (#41.1),
XU-SPL-MGR, 221, 222	221
XUTIO, 199, 210	Multiple Copies
XUTM ERROR, 181, 291	Spooling, 216
XUTM MGR, 181, 270	Multiple Managers and Load Balancing, 259
XUTM UTIL, 181, 275	MULTIPLE SIGN-ON Field (#200.04), 35
ZTMQUEUABLE OPTIONS, 41, 222, 284,	Multiple Sign-On Restriction, 18
285	Multi-Term Look-Up (MTLU), 341
MenusXQSMD MGR, 152	Add Entries To Look-Up File Option, 341,
Merge Capability	349, 350
Duplicate Resolution Utilities	Example, 353
Developing, 339	Add/Modify Utility
MESSAGE File (#3.9), 220	Keywords Option, 353
	Shortcuts Option, 353
Messages Answerback, 18	*
	Synonyms Option, 353 Add/Modify Utility Option, 342, 349, 353
PackMan, 307, 309, 310, 312	· · · · · · · · · · · · · · · · · · ·
TaskMan Rejection Messages, 300	Examples, 358
TaskMan States:, 301	Synonyms, 357
MESSAGES Field, 320, 323	Delete Entries From Look-Up Option, 341,
METRIC_SCHEDULE.COM Script, 260	349, 350
Missing Components, 336	Example, 350
Mixed OS Environment Fields	Functional Description, 341
KERNEL SYSTEM PARAMETERS file	Implementation, 359
(#8989.3), 204	Introduction, 341
MIXED OS Field (#.05), 204	Keyword Option
MNEMONIC Field, 211	Example, 359
MODE OF TASKMAN Field, 254, 259	Keywords, 341, 353
MODE OF TASKMAN Field (#8), 251, 254	Associated with a Single Term and Multiple
Modes	Terms, 343
Auto Print, 233	Keywords Option, 342, 356

Lexical Variants, 342	RESOURCES File (#3.54), 231
LOCAL KEYWORD File (#8984.1), 341,	SECURITY KEY File (#19.1), 147
343, 349, 350, 353	TERMINAL TYPE File (#3.2), 206
LOCAL LOOKUP file (#8984.4), 362	NAME Field(#.01)
LOCAL LOOKUP File (#8984.4), 341, 342,	XUEPCS DATA File (#8991.6), 100
346, 348, 349, 350, 353	Namespaces
LOCAL SHORTCUT File (#8984.2), 341,	Help Frames, 180
343, 346, 349, 350	XQSRV, 171
LOCAL SYNONYM File (#8984.3), 341,	XUFI, 63
343, 349, 353	XUTM (TaskMan), 245
Look-Up	Z, 157
How to Request, 342	ZTM (TaskMan), 245
Lookups on Database Files, 342	Naming Conventions
Multi-Term Lookup (MTLU) Main Menu,	TERMINAL TYPE File (#3.2), 207
343	Navigating Kernel's Menus, 116
Multi-Term Lookup (MTLU) Option, 346	Network Channel Device Edit Option, 230
Example, 347	Network Channel Devices, 230
Overview, 341	Editing, 230
Print Utility Option, 341, 348	System Management, 230
Example, 349	NETWORK USERNAME Field (#501.1), 12,
Shortcuts, 341, 353	35
Point to a Single Word or Phrase, 343	NEW PERSON file (#200), 10, 14, 33
Shortcuts Option, 342, 354	NEW PERSON File (#200), 6, 11, 15, 17, 18,
Example, 358	19, 20, 21, 22, 23, 31, 32, 33, 40, 41, 42, 43,
Standard Device Chart, 345	45, 46, 48, 49, 50, 55, 56, 57, 60, 63, 66, 67,
Synonym Option	89, 90, 91, 92, 93, 94, 96, 98, 99, 109, 110,
Example, 359	111, 122, 130, 139, 144, 146, 147, 155, 175,
Synonyms, 341, 353	208, 221, 271
Associated with Multiple Terms, 343	DEA EXPIRATION DATE (#747.44), 89,
Multiple Tokens, 343 Synonyms Option, 342, 357	90, 91, 92, 93 DEA# Field (#53.2), 89, 90, 91, 92, 93, 94, 96
Systems Management, 359	DEA# Field (#35.2), 89, 90, 91, 92, 93, 94, 90 DUZ, 57, 94, 96, 98, 99
Usage Considerations, 342	NAME Field (#.01), 89, 91, 92, 93, 94, 96,
User Interface, 343	98, 99
Utilities for MTLU Menu, 349	Required Fields, 23
Multi-Term Lookup (MTLU) Main Menu, 343	SCHEDULE II NARCOTIC Field (#55.1),
Multi-Term Lookup (MTLU) Option, 341, 346	94, 96
Example, 347	SCHEDULE II NON-NARCOTIC Field
Example, 547	(#55.2), 94, 96
	SCHEDULE III NARCOTIC Field (#55.3),
N	94, 96
Name	SCHEDULE III NON-NARCOTIC Field
Options, 118	(#55.4), 94, 96
NAME Field (#.01), 89, 91, 92, 93, 94, 96, 98,	SCHEDULE IV Field (#55.5), 94, 96
99	SCHEDULE V Field (#55.6), 94, 96
BUILD File (#9.6), 307	TERMINATION DATE (#9.2), 91
DEVICE File (#3.5), 195, 211	TERMINATION DATE Field (#9.2), 96
NEW PERSON File (#200), 31, 67, 68	VA# Field (#53.3), 94, 96
OPTION File (#19), 125, 170	NEW PERSON IDENTIFIERS Field, 23
PARAMETER DEFINITION file (#8989.51),	New/Revised Help Frames Option, 178
166	NICK NAME Field (#13), 11, 32

No Options Node, 294	Documentation, xlii
Nodes	Technical Information, How to Obtain, xlii
^%ZIS("14.5","LOGON","volume set"), 22	OPEN EXECUTE Field
^%ZOSF, 302	TERMINAL TYPE File (#3.2), 193
^%ZOSF("VOL"), 254	OPEN EXECUTE Field (#6)
^%ZTSK(task #, 0), 247	TERMINAL TYPE File (#3.2), 206, 234, 235
^%ZTSK(task#,.3), 247	OPEN PARAMETERS Field
^XUSEC(0,"CUR",DUZ,DATE), 135	DEVICE File (#3.5), 230
^XUTL("XQ", \$J, "T") Node, 138	OPEN PARAMETERS Field (#19)
^XUTL("XQ", \$J, "XQM") Node, 138	DEVICE File (#3.5), 196, 207, 214, 223, 227,
Compute Server Job List, 293	231
Device Allocation List, 293	OPEN PRINTER PORT Field (#110), 234, 235
Device Waiting List, 294	OpenVMS Interactive Logins Parameter, 16
Display, 137, 138	OpenVMS-Specific DEVICE Fields
Error Log, 293	DEVICE File (#3.5), 198
Error Screens, 293	Operations Management Menu, 43, 326
Idle, 293	Option Access by User Option, 129
Job List, 294	Option Audit Display Option, 127
Jump, 137, 140	OPTION File (#19), 21, 33, 41, 118, 119, 122,
Link List, 294	124, 125, 126, 131, 133, 136, 137, 138, 139,
Load, 294	140, 144, 149, 156, 168, 169, 173, 174, 175,
Load List, 294	180, 286, 288
Log Resources, 294	Dangling Pointers, 131, 179
No Options, 294	Option Restrictions, 118
RUN, 246, 276, 282, 294	Option Scheduling
Schedule List, 293	Deleting and requeuing, 286
Startup List, 295	List Background Options, 285
Status List, 295	One-time Option Queue Option, 290
Stop, 295	PARENT OF QUEUABLE OPTIONS Menu,
Sub, 295	285
Task List, 295	Problems, 290
TaskMan Error Log, 293	Queuing an option, 286
Update, 295	Schedule/Unschedule Options Option, 286
User Stacks, 137	Scheduling Frequency Code Formats, 289
Wait, 295	Special Queueing settings, 288
XQ, 138	TaskMan, 285
XQT (MENU Templates), 138	Through the OPTION SCHEDULING File
Normal Signoff, 8	(#19.2)
NULL Device, 202	TaskMan, 242
NVSTNSET Routine, 198	Which Options to Queue, 285
TVISITION TOURING, 170	OPTION SCHEDULING File (#19.2), 135, 163,
	241, 242, 247, 284, 285, 286, 287, 288, 290
0	Options
Ohtoinina	Actual Usage of Alpha/Beta Test Options,
Obtaining Data Diationary Listings while	326
Data Dictionary Listings, xliii	Add a New User, 23
OFFICE PHONE Field (#.132), 11, 36, 67	Add a New User to the System, 22, 23
OLD ACCESS AND VERIFY CODES File	Add Entries To Look-Up File, 349, 350
(#200 XREF), 47	Example, 353
Once the Installation Finishes (KIDS), 322	Multi-Term Look-Up (MTLU), 341
One-time Option Queue Option, 290	Add Error Screens, 182
Online	Aud Litor Scients, 102

Add/Modify Utility, 349, 353 Convert Loaded Package for Redistribution, Multi-Term Lookup (MTLU), 342 309, 330 Multi-Term Look-Up (MTLU) Copy Everything About an Option to a New Examples, 358 Option, 151, 157 Copy One Users Menus and Keys to others, Alert Management, 161, 163 Alerts - Set/Remove Surrogate for User, 163 151 All Keys a User Needs, 145 CPRS Configuration (IRM), 75 All your tasks, 272 CPRS Manager Menu, 75 Allocate/De-Allocate of PSDRPH Key, 89, CPU/Service/User/Device Stats, 34, 47 Create a Set of Options to Mark Out-Of-Order, 132 Allocation of Security Keys, 78, 144, 145, 155 Creating, 124 Allow other users access to spool documents, Critical Alerts Count Report, 165 Cross Reference Help Frames, 179 Cross-references, 179 Alpha/Beta Test Option Usage Menu, 127, 326 DA Return Code Edit, 19, 209 Data Dictionaries Being Audited, 52 Application Utilities, 343 Data Dictionary Utilities, xliii, 53 Assign Editors, 179 DEA ePCS Utility, 86 Assign the XU EPCS EDIT DATA Option, DEA ePCS Utility Functions, 86 Assign the XUSSPKI UPN SET Option, 83 Deactivate a User, 40 Audit Features, 127 De-allocation of Security Keys, 144, 155 Audited Options Purge, 127 Delegate keys, 145, 155 Audits, 127 Delegate's Menu Management, 149, 151, 152, Automatic Deactivation of Users, 41 154, 155 Backup a Transport Global, 318 Delegating, 145, 154, 155 Browse a Spool Document, 218 Delete A Spool Document, 218 Build a New Menu, 151, 157 Delete Entries From Look-Up, 349, 350 Build File Print, 328 Example, 350 Multi-Term Look-Up (MTLU), 341 Build Primary Menu Trees, 136 Building, 152 Delete Error Log, 292 Change my Division, 10 Delete Old (>14 d) Alerts, 163 Change user's allocated keys to delegated Delete Tasks, 248, 274 keys, 145 Delete Unreferenced Options, 131 Check Taskman's Environment Option, 279 Dequeue Tasks, 248, 273, 274, 299 Choosing, 116 Descriptions, 129 Device Management, 199, 210 Clean Error Log Over Range Of Dates, 292 DI DDU, xliii, 53 Clean Error Trap, 184 Clean old Job Nodes in the XUTL, 134, 135 Diagram Menus, 144, 147 Clean Task File, 284 Diagramming, 128 Cleanup Task List, 274 DIAUDIT DD, 52 Clear all users at startup, 18, 22, 46 DIAUDIT PURGE DATA, 52 Clear Electronic signature code, 68 DIAUDIT PURGE DD, 52 Common, 6, 32, 117, 118, 120, 121, 130, 143, DIAUDIT TURN ON/OFF, 52 147, 158, 218, 221, 237 DIAUDITED FIELDS, 52 Redefining, 130 DIEDFILE, 61 Compare local/national checksums report, DIEDIT, 51, 53, 54 315, 337 DIINQUIRE, 53, 55 Compare Transport Global to Current System, DILIST, xliii, 53 316 **DIMODIFY**, 53, 55 Continue, 121 DIPRINT, 53

DISEARCH, 53	Fields Being Audited, 52
Display, 128, 129	File Access Security, 55, 56, 60, 64, 65, 66
Description, 119	FileMan edit template, 170
Help, 117	FileMan Inquire to File Entries option, 342
Order, 126	Find a User, 43
Display Menus and Options, 128, 129	Fix Help Frame File Pointers, 179
Display Patches for a Package, 333	Fix Option File Pointers, 131
Display status, 239	Future tasks, 272
Display User Characteristics, 13, 143	General Parameter Tools, 75, 141
Display/Edit Help Frames, 178, 179	Grant Access by Profile, 23, 34
DISTATISTICS, 53	Halt, 121
DITRANSFER, 53, 54	Help Processor, 178
DIUTILITY, 53	Host File Server Device Edit, 200, 214
Edit a Build, 335	Inquire, 129
Edit a User's Options, 150	Inquire to File Entries, 53, 55
Example, 150	Install File Print, 320, 322, 329
Edit an Existing User, 31, 80, 83	Install Package(s), 310, 319, 320
Edit Devices by Specific Types, 229	INSTALL/CHECK MESSAGE PackMan,
Edit Error Screens, 182	310, 312
Edit Facility DEA# and Expiration Date, 86,	Installation (KIDS), 307, 311, 318
89, 110	Interactive Print of Error Messages, 186
Edit File, 61	Introductory text edit, 15
Edit Install Status, 330	Invoking Non-VistA Applications, 126
Edit Line Editor, 50	Kernel Installation & Distribution System,
Edit Logical/Physical Mapping, 204	305
Edit options, 34, 124, 126, 130, 134, 135, 170,	Kernel Management Menu, 204
180	Key Management, 78, 145, 146, 155
Edit Parameter Values, 75	Keys For a Given Menu Tree, 145
Edit task, 239	Keyword
Edit TaskMan Parameters, 249, 261	Multi-Term Look-Up (MTLU)
Edit User Characteristics, 6, 9, 11, 13, 20, 32,	Example, 359
38, 39, 208	Keywords
Kernel, 34	Multi-Term Look-Up (MTLU), 342, 356
MailMan, 34	KIDS, 305
Edit User's Spooler Access, 221	KILL off a users' job, 278, 295
Edits and Distribution, 306	Limited File Manager Options (Build), 151,
Electronic Signature Block Edit, 67	152, 157
Electronic Signature code Edit, 67, 68	Example, 153
Enter or Edit File Entries, 51, 53, 54	List Alerts for a user from a specified date,
Enter/Edit Kernel Site Parameters, 15, 20, 205	165
Enter/Edit of Security Keys, 146	List Delegated Options and their Users, 157
ePCS DEA Utility Functions, 87	List Error Screens, 182
ePCS Edit Prescriber Data, 86, 110	List File Attributes, xliii, 53
ePCS Set SAN from PIV Card, 86, 110	List Help Frames, 178, 180
Error Processing, 183	List of tasks, 272
Error Trap Auto Clean, 184	List Options by Parents and Use, 128
Error Trap Display Option, 184	List own tasks, 240
Errors Logged in Alpha/Beta Test	List Spool Documents, 218
(QUEUED), 326	List Tasks, 271, 273, 279, 298
Establish System Audit Parameters, 127	All your tasks, 272
EVE, 78, 80, 83, 138, 139, 156, 181, 305	Future tasks, 272
, -,,,,,,,	

List of tasks, 272 Post sign-in Text Edit, 20 Running tasks, 272 Print 2 occurrences of errors on T-1 (QUEUED), 183 Tasks waiting for a device, 272 Unsuccessful tasks, 272 Print A Spool Document, 219 Print All Delegates and their Options, 157 Your future tasks, 272 Print Alpha/Beta Errors List the Defined Options Sets, 133 List Users, 43 (Date/Site/Num/Rou/Err), 326 Print Audits for Prescriber Editing, 88, 100 Load a Distribution, 309, 310, 312, 313, 324 Print DEA Expiration Date Expires 30 days, Locked, Identifying, 144 Locks, 130, 133 87, 92 Loopback Test of Device Port, 210 Print DEA Expiration Date Null, 87, 89 Low Usage of Alpha/Beta Test Options, 326 Print DISUSER DEA Expiration Date Expires Make an Alert on the Fly, 164 30 days, 87, 93 Make spool document into a mail message, Print DISUSER DEA Expiration Date Null, 219 87, 90 Managing, 130 Print DISUSER Prescribers with Privileges, Map Pointer Relations, 53 88, 96 Mark Option Set Out-Of-Order, 133 Print File Entries, 53 Menu Management, 153 Print Option File, 129 Menu Management menu, 78 Print Options Recommended for Queueing Menu Templates Option, 122 TaskMan, 285 Modify File Attributes, 53, 55 Print Options that are Scheduled to run, 285 Monitor Taskman, 260, 275, 301 Print Prescribers with Privileges, 88, 94 Multi-Term Lookup (MTLU), 341, 346 Print PSDRPH Key Holders, 88, 98 Print Setting Parameters Privileges, 88, 99 Example, 347 Print Sign-on Log, 43 Multi-Term Lookup (MTLU) Main Menu, 343 Print task, 240 Name, 118 Print Transport Global, 316 **Print Utility** Name and Menu Text, 125 Network Channel Device Edit Option, 230 Multi-Term Look-Up (MTLU), 341, 348 Example, 349 New/Revised Help Frames, 178 One-time Option Queue, 290 Programmer mode, 35, 144 Operations Management, 43, 326 Programmer Options, 144, 305 Option Access by User, 129 Prohibited Times, 134 Option Audit Display, 127 Protocols Marked Out-of-Order in Protocol Options in the Option File that are Out-of-File Option, 133 Proxy (Connector) Detail Report, 44 Order, 133 Proxy (Connector) Inquire, 45 Options that Should Be Scheduled, 134 Options to be Delegated, 155 Proxy User List, 43 OR PARAM IRM MENU, 75 Purge Alerts for a User, 164 Purge Build or Install Files, 333 ORMGR, 75 OUT OF ORDER MESSAGE Field (#2), 133 Purge Data Audits, 52 Out of Service Set/Clear, 210 Purge DD Audits, 52 Purge Error Log Of Type Of Error, 292 Out-Of-Order Set Management, 132 P1 Print 1 occurrence of each error for T-1 Purge Inactive Users' Attributes Utility, 42 Purge Log of Old Access and Verify Codes (QUEUE), 183 PARENT OF QUEUABLE OPTIONS, 46, Option, 48 134, 222, 285 Purge old spool documents, 222 Patient Alert List for specified date, 165 Queuable Task Log Clean Up, 284 Permitted Devices, 134 Reactivate a User, 40, 42

396

Place Taskman in a WAIT State, 282

Recover Deleted Option Set, 133

Reindex the users key's, 147 Stop task, 239 Reindexing All Users' Security Keys, 147 Stop Task Manager, 283 Release user, 45 Stop TaskMan, 303 Remote Access User Sign-on Log, 46 Surrogate for which Users?, 167 Remove Error Screens, 183 Switch Identities, 132 Remove Options Previously Delegated, 156 Switch UCI, 14 Remove Out-Of-Order Messages from a Set SYNC flag file control Option, 283 of Options, 133 Synonym Remove Taskman from WAIT State, 283 Multi-Term Look-Up (MTLU) Replace a Delegate, 156 Example, 359 Replicate or Replace a Delegate, 154, 156 Synonyms, 116, 118, 120, 126, 140, 177 Report Menu for Alerts, 164 Multi-Term Look-Up (MTLU), 342, 357 Reprint Access Agreement Letter, 31 Systems Manager Menu, 78, 80, 83, 305 Task Allocation Audit of PSDRPH Key Requeue Tasks, 169, 248, 273, 299 Report, 89, 106 Resource Device Edit, 232 Restart Install Of Package(s), 323 Task Changes to DEA Prescribing Privileges Report, 88, 102 Restart Session, 121 Taskman Error Log, 181 Restart Task Manager Option, 282 Restart TaskMan, 266 Taskman Error Log Menu, 291 Restrict Availability of Options, 133 Taskman Management, 181 Restricting Usage, 133 TaskMan Management Menu, 270 Rollup Patches into a Build, 335 Taskman Management Utilities, 181, 275 Running tasks, 272 TaskMan User, 237, 238, 239, 299 Schedule/Unschedule Options, 126, 284, 286, Tasks waiting for a device, 272 290 Time, 121 Scheduling, 126 Toggle Options/Protocols On and Off, 133 Search File Entries, 53 Transfer Entries, 53 Secure Menu Delegation, 153, 154, 156 Transfer Lines from Another Document, 50, Secure Menu Management, 149, 152 Select another task, 240 Transport a Distribution, 309, 331 Select Options to be Delegated, 154, 156 TRM or VTRM Device Edit, 202 Send Alpha/Beta Usage to Programmers, 326 Turn Data Audit On/Off, 52 Send Test Pattern to Terminal, 210 UCI Association Table Edit, 256 Server-type, 168 Unassign Editor, 179 Set Backup Reviewer for Alerts, 166 Unload a Distribution, 323 Shortcuts Unreferenced, 131 Multi-Term Look-Up (MTLU), 342, 354 Unsuccessful tasks, 272 Update Routine File, 336 Example, 358 Show a Delegate's Options, 157 User Alerts Count Report, 166 Show Error Log, 291 User Inquiry, 46 Show the Security Keys of a Particular User, User Management, 39, 49, 80, 83 155 User Management Menu, 43, 55, 60, 65 Show Users with Selected Primary Menu, 129 User start-up event, 21, 86 Site Parameters Edit, 261 User Status Report, 46 Specify Allowable New Menu Prefix, 152, User's Toolbox, 6, 9, 10, 11, 13, 67, 68, 121, 157 122, 218, 237 Spool Device Edit, 223 Users with Foreign Visits, 46 Spool Management, 220, 221, 222 Utilities For MTLU, 349 Spooler Menu, 218, 219, 221 Utilities Menu Spooler Site Parameters Edit, 222 KIDS, 327 Statistics, 53 Utility Functions, 53

VA FileMan, 49 XQAL VIEW ALERT TRACKING ENTRY, Verify a Build, 336 166 Verify Checksums in Transport Global, 315 XQALERT, 9 Verify Package Integrity, 337 **XQALERT BY USER DELETE, 164** View Alerts "VA", 9, 121, 158, 159 XOALERT DELETE OLD, 163 View data for Alert Tracking file entry, 166 XQALERT MAKE, 164 Volume Set Edit Option, 253 XQALERT MGR, 163 Where am I?, 121 XQALERT SURROGATE SET/REMOVE, XPAR EDIT PARAMETER, 75 161, 163 XPAR MENU TOOLS, 75, 141 XQBUILDTREEQUE, 135, 287 XQCOPYOP, 151 XPD BACKUP, 318 XPD COMPARE TO SYSTEM, 316 XQDISPLAY OPTIONS, 128, 129 XPD CONVERT PACKAGE, 330 XQHELP-ASSIGN, 179 XQHELP-DEASSIGN, 179 XPD DISTRIBUTION MENU, 306 XPD EDIT INSTALL, 330 XQHELP-DISPLAY, 178 XQHELPFIX, 179 XPD INSTALL BUILD, 319 XPD INSTALLATION, 311 XQHELP-LIST, 178 XPD INSTALLATION MENU, 307 XQHELP-MENU, 178 XQHELP-UPDATE, 178 XPD LOAD DISTRIBUTION, 312, 313 XPD MAIN, 305 XQHELP-XREF, 179 XPD PRINT BUILD, 328 XOKEYALTODEL, 145 XPD PRINT CHECKSUM, 315 XQKEYDEL, 145, 155 XPD PRINT INSTALL, 316 XQLOCK1, 145 XPD PRINT INSTALL FILE, 329 XQLOCK2, 145 XPD PRINT PACKAGE PATCHES, 333 XQOOFF, 133 XPD PURGE FILE, 333 XQOOMAIN, 132 XPD RESTART INSTALL, 323 XQOOMAKE, 132 XPD ROLLUP PATCHES, 335 XOOON, 133 XQOOREDO, 133 XPD ROUTINE UPDATE, 336 XPD UNLOAD DISTRIBUTION, 323 XQOOSHOFIL, 133 XPD UTILITY, 327 XQOOSHOPRO, 133 XPD VERIFY BUILD, 336 XOOOSHOW, 133 XPD VERIFY INTEGRITY, 337 X000T0G, 133 XQOPTFIX, 131 XQ UNREF'D OPTIONS, 131 XQ XUTL \$J NODES, 134, 135 XORESTRICT, 133 XQAB ACTUAL OPTION USAGE, 326 XQSMD ADD, 154, 156 XQAB AUTO SEND, 326 **XQSMD BUILD MENU, 151** XOSMD COPY USER, 151 XQAB ERR DATE/SITE/NUM/ROU/ERR, **XQSMD EDIT OPTIONS, 150** Example, 150 **XQAB ERROR LOG XMIT, 326** XQAB LIST LOW USAGE OPTS, 326 XQSMD LIMITED FM OPTIONS, 152 XQAB MENU, 326 Example, 153 XQSMD MGR, 152, 153, 156 XQAL ALERT LIST FROM DATE, 165 XQAL CRITICAL ALERT COUNT, 165 **XQSMD REPLICATE**, 156 **XQAL PATIENT ALERT LIST, 165 XQSMD SET PREFIX, 152 XQAL REPORTS MENU, 164** XQSMD USER MENU, 149, 151, 152, 154, XQAL SET BACKUP REVIEWER, 166 155 XTLKLKUP, 341, 346 XOAL SURROGATE FOR WHICH USERS. 167 XTLKMODKY, 342, 356

XQAL USER ALERTS COUNT, 166

XTLKMODPARK, 341, 349, 350 XTLKMODPARS, 341, 349, 350 XTLKMODSH, 342 XTLKMODSH, 354 XTLKMODSY, 342, 357 XTLKMODUTL, 342, 349, 353 XTLKPRTUTL, 341, 348 XTLKUSER2, 343 XTLKUTILITIES, 349 XTMENU, 343 XU CHECKSUM REPORT, 315, 337 XU DA EDIT, 209 XU EPCS, 86 XU EPCS DISUSER EXP DATE, 87, 90 XU EPCS DISUSER PRIVS, 87, 88, 96 XU EPCS DISUSER XDATE EXPIRES, 87, 93 XU EPCS EDIT DATA, 80, 86, 110 XU EPCS EDIT DEA# AND XDATE, 86, 87, 89, 110 XU EPCS EXP DATE, 87, 89 XU EPCS LOGICAL ACCESS, 87, 88, 102 XU EPCS PRINT EDIT AUDIT, 87, 88, 100 XU EPCS PRIVS, 87, 88, 94 XU EPCS PSDRPH, 87, 88, 98 XU EPCS PSDRPH AUDIT, 87, 89, 106 XU EPCS PSDRPH KEY, 87, 89, 109 XU EPCS SET PARMS, 87, 88, 99 XU EPCS UTILITY FUNCTIONS, 86, 87 XU EPCS XDATE EXPIRES, 87, 92 XU FINDUSER, 43 XU OPTION QUEUE, 290 XU SID EDIT, 204 XU SWITCH UCI, 14 XU USER SIGN-ON, 20, 21 XU USER START-UP, 21 XUAUDIT, 127 XUAUDIT MENU, 127 **XUAUTODEACTIVATE, 41** XUCOMMAND, 130 XUDEVEDIT, 229 XUDEVEDITCHAN, 230 XUDEVEDITHFS, 200, 214 **XUDEVEDITRES**, 232 XUDEVEDITSPL, 223

XUDEVEDITTRM, 202 **XUEDITOPT**, 124, 170 XUERRS, 183 XUERTRAP, 184 XUERTRP AUTO CLEAN, 184 XUERTRP CLEAN, 184 **XUERTRP PRINT ERRS, 186** XUERTRP PRINT T-1 1 ERR, 183 Kernel 8.0 & Kernel Toolkit 7.3

XUERTRP PRINT T-1 2 ERR, 183 XUFILEACCESS, 55, 56, 60, 64, 65, 66 XUKERNEL, 204 XUKEYALL, 78, 144, 145 XUKEYDEALL, 144 XUKEYEDIT, 146 XUKEYMGMT, 78 XUMAINT, 78 XUOPTDISP, 127 XUOPTPURGE, 127 XUOPTUSER, 43 XUOPTWHO, 129 XUOUT, 210 XUPRINT, 129 XUPROG, 305 XUPROGMODE, 138 XURESJOB, 278, 295 XUS VISIT USERS, 46 XUSAP PROXY CONN DETAIL ALL, 44 XUSAP PROXY CONN DETAIL INQ, 45 XUSAP PROXY LIST, 43 XUSC LIST, 43 XUSCZONK, 46

XUSEC REMOTE ACCESS, 46 XUSER, 39, 49, 55, 60, 65, 83 XUSER DIV CHG, 10 XUSER KEY RE-INDEX, 147 XUSERAOLD, 48 XUSERBLK, 23

XUSER-CLEAR-ALL, 22 XUSERDEACT, 40 XUSEREDIT, 31, 80, 83 XUSEREDITSELF, 11, 208 XUSERINQ, 46

XUSERINT Option, 15 XUSERLIST, 43 **XUSERNEW**, 22, 23 XUSERPOST, 20 XUSERPURGEATT, 42 XUSERREACT, 40, 42 XUSERREL, 45 XUSERTOOLS, 10 XUSESIG, 67, 68 XUSESIG BLOCK, 67 **XUSESIG CLEAR, 68** XUSITEMGR, 43, 326 XUSITEPARM, 15, 205 XU-SPL-ALLOW, 218 XU-SPL-BROWSE, 218 XU-SPL-DELETE, 218 XU-SPL-LIST, 218

XU-SPL-MAIL, 219 XU-SPL-MGR, 221, 222	Options in the Option File that are Out-of-Order Option, 133
XU-SPL-PRINT, 219	
·	Options to be Delegated Option, 155
XU-SPL-PURGE, 222	Optoions Secure Many Polegation, 152
XU-SPL-SITE, 222	Secure Menu Delegation, 152
XU-SPL-USER, 221	OR PARAM IRM MENU, 75
XUSSPKI UPN SET, 83, 86, 110	ORGANIZATION Field (#200.2), 21
XUSTAT, 34, 47	Orientation, xxxviii
XUTESTUSER, 132	ORIGINAL DATA (#.04)
XUTIO, 199, 210	XUEPCS DATA File (#8991.6), 100
XUTLOOPBACK, 210	ORMGR, 75
XUTM BACKGROUND PRINT, 285	Other Files
XUTM BACKGROUND RECOMMENDED	TaskMan, 247
TaskMan, 285	Other Non-TaskMan Mode, 251
XUTM CHECK ENV, 279	OTHER NON-TASKMAN VOLUME SET
XUTM CLEAN, 284	Type, 254
XUTM DEL, 248, 274	Other Sources of Tasks, 236
XUTM DQ, 248, 273, 299	OUT OF ORDER MESSAGE Field (#2), 133,
XUTM ERROR, 181, 291	136, 168, 170, 175
XUTM ERROR DELETE, 292	Out of Service Set/Clear Option, 210
XUTM ERROR LOG CLEAN RANGE, 292	OUT OF SERVICE? Field (#3), 255
XUTM ERROR PURGE TYPE, 292	Out-Of-Order Set Management Menu, 132
XUTM ERROR SCREEN ADD, 182	OUT-OF-SERVICE DATE Field, 16
XUTM ERROR SCREEN EDIT, 182	Overflowing Spool Document Storage, 220
XUTM ERROR SCREEN LIST, 182	Overview
XUTM ERROR SCREEN REMOVE, 183	DEA ePCS Utility, 69
XUTM ERROR SHOW, 291	Multi-Term Look-Up (MTLU), 341
XUTM INQ, 271	OVERWRITE, 324
XUTM MGR, 181, 270	· · · · · · · · · · · · · · · · · · ·
XUTM QCLEAN, 256, 284, 291, 297	_
XUTM REQ, 248, 273, 299	P
XUTM RESTART, 282	P1 Print 1 occurrence of each error for T-1
XUTM RUN, 283	
XUTM SCHEDULE, 286	(QUEUE) Option, 183
XUTM STOP, 282, 283, 294	PAC (#14, Programmer Access Code) Field, 35
XUTM SYNC, 283	Package
XUTM TL CLEAN, 274	Definition, 304
XUTM UCI, 256	PACKAGE File (#9.4), 53, 304, 307, 308, 309,
•	333
XUTM USER, 237, 299	PackMan Messages, 307, 309, 310, 312
XUTM UTIL, 181, 275	PAGE LENGTH Field (#3)
XUTM VOLUME, 253	TERMINAL TYPE File (#3.2), 206, 229
XUTM WAIT, 282, 283	PARAMETER DEFINITION File (#8989.51),
XUTM ZTMON, 260, 275, 301	166
XUTTEST, 210	Parameters
XUUSERDISP, 13	Checked during Signon, 15
XUUSERSTATUS, 46	DEA ePCS Utility
XUXREF, 128	Enter Site Parameters, 75
XUXREF-2, 129	OpenVMS Interactive Logins, 16
Your future tasks, 272	XQ MENUMANAGER PROMPT, 141
ZTMQUEUABLE OPTIONS, 41, 222, 284,	XUEPCS REPORT DEVICE, 75, 77, 102,
285	106

PARAMETERS File (#8989.5), 166, 339	Defining, 124
PARENT OF QUEUABLE OPTIONS Menu,	Managing, 130
46, 134, 222, 285	Rebuilding Menu Trees, 135
Parents Cross-reference, 179	Trees, 135, 136, 137, 140, 142
Parsing Algorithms, 31	PRIMARY MENU OPTION Field, 15, 22, 32,
Part 3 of the Kernel Installation (See File Access	42, 150, 151
Security), 33, 49	PRIMARY MENU OPTION Field #201), 32
Partition Size, 251	Print 2 occurrences of errors on T-1 (QUEUED)
PASSWORD Field, 205	Option, 183
Passwords	Print A Spool Document Option, 219
Defining, 6	Print All Delegates and their Options, 157
Why Longer Passwords?, 7	Print Alpha/Beta Errors
PATCH APPLICATION HISTORY Field	(Date/Site/Num/Rou/Err) Option, 326
(Multiple), 308	Print Audits for Prescriber Editing Option, 88,
Patches	100
History, xi	Print DEA Expiration Date Expires 30 days
KIDS, 308, 309, 318, 335	Option, 87, 92
Patient Alert List for specified date Option, 165	Print DEA Expiration Date Null Option, 87, 89
PATIENT File (#2), 55	Print DISUSER DEA Expiration Date Expires
PATIENT^XQALERT API, 162	30 days Option, 87, 93
PAUSE State, 255, 302	Print DISUSER DEA Expiration Date Null
P-BROWSER Type, 227	Option, 87, 90
PERFORM DEVICE CHECKING Field, 16	Print DISUSER Prescribers with Privileges
Permitted Devices	Option, 88, 96
Options, 134	Print File Entries Option, 53
PERMITTED DEVICES Field (Multiple), 134	Print Option File Option, 129
PERSON LOOKUP Field, 146	Print Options Recommended for Queueing
Phantom Jumps, 136, 137	Option Options
PHONE #3 Field (#.133), 36	TaskMan, 285
PHONE #4 Field (#.134), 36	Print Options that are Scheduled to run Option,
PHONE (HOME) Field (#.131), 11, 36	285
PHYSICAL DISK Field (#505), 204	Print Prescribers with Privileges Option, 88, 94
Pitch, 192	Print PSDRPH Key Holders Option, 88, 98
PKI SERVER Field (#53.1), 112	Print Server Mode, 251
Place Taskman in a WAIT State Option, 282	PRINT SERVER NAME OR ADDRESS Field
P-MESSAGE Device, 203	(#65), 198
POST SIGN-IN MESSAGE Field, 20	PRINT SERVER Type, 254
Post sign-in Text Edit Option, 20	Print Setting Parameters Privileges Option, 88,
POST-CLOSE EXECUTE Field (#19.8)	99
DEVICE File (#3.5), 227	Print Sign-on Log Option, 43
POST-CLOSE EXECUTE Field (#8)	Print task Option, 240
DEVICE File (#3.5), 196	Print Transport Global Option, 316
PREFERRED EDITOR Field, 34	Print Utility Option
PREFERRED EDITOR Field (#31.3), 12, 34	Multi-Term Look-Up (MTLU), 341, 348
PRE-OPEN EXECUTE Field (#7)	Example, 349
DEVICE File (#3.5), 196	Printer Controller Mode, 233
PRIMARY HFS DIRECTORY Field (#320),	Printers
204	Slaved, 233, 234
Primary Menu, 5, 8, 9, 15, 22, 32, 116, 120, 128,	Printing
130, 131, 138, 140, 142	Loaded Transport Globals (KIDS), 316
Assigning, 22	To Devices, 187

Priority	Purge Log of Old Access and Verify Codes
Interactive Users, 18	Option, 48
PRIORITY AT RUN TIME Field (#25), 261	Purge old spool documents Option, 222
PRIORITY Field (#3.8)	Purging
Options, 126	^UTILITY(\$J, 134
Server Options, 170	^XTMP, 134
Privileges	Alerts, 163, 164
Audit, 55	Audited options, 127
Spooling, 216, 220	BUILD File, 325
Processes	Error Trap, 184
DEA ePCS Utility	Failed Access Attempts Log Purge, 47
e-Prescribing, 73	Inactive Users' Attributes, 42
Manual Paper-based Process, 72	INSTALL File, 325
Processing Alerts, 158	Mail for Inactive Users, 42
Processing Each Transport Global (KIDS), 319	Old Access and Verify Codes, 48
Producing Reports, Searches, and Statistics	Old Job Nodes in XUTL, 134
Through Standardized Encoding of Diagnoses	Options (unreferenced), 131
and Procedures, 341	Security Keys for Inactive Users, 42
Programmer mode Option, 35, 144	Selected Entries (KIDS), 334
Programmer Options Menu, 144, 305	SIGN-ON LOG File (#3.081), 46, 47
Progress Bar	Signon Nodes, 134
KIDS Installations, 322	Spool Documents, 218, 222
Prohibited Times	Taskman Error Log Menu, 183, 292
Options, 134	Tasks, 284, 297
PROHIBITED TIMES FOR SIGN-ON Field,	Purpose for Granting File Access, 51
16, 17	Turpose for Granding The Fleeess, 21
·	
PROHIBITED TIMES FOR SIGN-ON Field	
PROHIBITED TIMES FOR SIGN-ON Field (#15) 35	Q
(#15), 35	
(#15), 35 Prompts	Quality, 192
(#15), 35 Prompts Terminal Type, 9	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116
(#15), 35 Prompts Terminal Type, 9 Protocols	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182,
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279,
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File Option, 133	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319 Queuable Task Log Clean Up Option, 284
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File Option, 133 Provider Key, 145, 146	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319 Queuable Task Log Clean Up Option, 284 QUEUED TO RUN AT WHAT TIME Field,
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File Option, 133 Provider Key, 145, 146 Provider Security Key, 41	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319 Queuable Task Log Clean Up Option, 284 QUEUED TO RUN AT WHAT TIME Field, 286
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File Option, 133 Provider Key, 145, 146 Provider Security Key, 41 Proxies	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319 Queuable Task Log Clean Up Option, 284 QUEUED TO RUN AT WHAT TIME Field, 286 QUEUED TO RUN AT WHAT TIME Field
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File Option, 133 Provider Key, 145, 146 Provider Security Key, 41 Proxies APPLICATION PROXY, 43	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319 Queuable Task Log Clean Up Option, 284 QUEUED TO RUN AT WHAT TIME Field, 286 QUEUED TO RUN AT WHAT TIME Field (#2), 286, 287, 288, 290
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File Option, 133 Provider Key, 145, 146 Provider Security Key, 41 Proxies APPLICATION PROXY, 43 CONNECTOR PROXY, 43, 44, 45	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319 Queuable Task Log Clean Up Option, 284 QUEUED TO RUN AT WHAT TIME Field, 286 QUEUED TO RUN AT WHAT TIME Field (#2), 286, 287, 288, 290 QUEUED TO RUN ON VOLUME SET Field
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File Option, 133 Provider Key, 145, 146 Provider Security Key, 41 Proxies APPLICATION PROXY, 43 CONNECTOR PROXY, 43, 44, 45 Proxy (Connector) Detail Report Option, 44	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319 Queuable Task Log Clean Up Option, 284 QUEUED TO RUN AT WHAT TIME Field, 286 QUEUED TO RUN AT WHAT TIME Field (#2), 286, 287, 288, 290 QUEUED TO RUN ON VOLUME SET Field (#5), 286, 287, 288
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File Option, 133 Provider Key, 145, 146 Provider Security Key, 41 Proxies APPLICATION PROXY, 43 CONNECTOR PROXY, 43, 44, 45 Proxy (Connector) Detail Report Option, 44 Proxy (Connector) Inquire Option, 45	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319 Queuable Task Log Clean Up Option, 284 QUEUED TO RUN AT WHAT TIME Field, 286 QUEUED TO RUN AT WHAT TIME Field (#2), 286, 287, 288, 290 QUEUED TO RUN ON VOLUME SET Field (#5), 286, 287, 288 Queuers
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File Option, 133 Provider Key, 145, 146 Provider Security Key, 41 Proxies APPLICATION PROXY, 43 CONNECTOR PROXY, 43, 44, 45 Proxy (Connector) Detail Report Option, 44 Proxy (Connector) Inquire Option, 45 Proxy User List Option, 43	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319 Queuable Task Log Clean Up Option, 284 QUEUED TO RUN AT WHAT TIME Field, 286 QUEUED TO RUN AT WHAT TIME Field (#2), 286, 287, 288, 290 QUEUED TO RUN ON VOLUME SET Field (#5), 286, 287, 288 Queuers TaskMan, 241
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File Option, 133 Provider Key, 145, 146 Provider Security Key, 41 Proxies APPLICATION PROXY, 43 CONNECTOR PROXY, 43, 44, 45 Proxy (Connector) Detail Report Option, 44 Proxy (Connector) Inquire Option, 45 Proxy User List Option, 43 PS Anonymous Directories, xliii	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319 Queuable Task Log Clean Up Option, 284 QUEUED TO RUN AT WHAT TIME Field, 286 QUEUED TO RUN AT WHAT TIME Field (#2), 286, 287, 288, 290 QUEUED TO RUN ON VOLUME SET Field (#5), 286, 287, 288 Queuers TaskMan, 241 Queuing
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File Option, 133 Provider Key, 145, 146 Provider Security Key, 41 Proxies APPLICATION PROXY, 43 CONNECTOR PROXY, 43, 44, 45 Proxy (Connector) Detail Report Option, 44 Proxy (Connector) Inquire Option, 45 Proxy User List Option, 43 PS Anonymous Directories, xliii PSDRPH Security Key, 88, 89, 98, 99, 106, 109	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319 Queuable Task Log Clean Up Option, 284 QUEUED TO RUN AT WHAT TIME Field, 286 QUEUED TO RUN AT WHAT TIME Field (#2), 286, 287, 288, 290 QUEUED TO RUN ON VOLUME SET Field (#5), 286, 287, 288 Queuers TaskMan, 241 Queuing Device Handler, 189
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File Option, 133 Provider Key, 145, 146 Provider Security Key, 41 Proxies APPLICATION PROXY, 43 CONNECTOR PROXY, 43, 44, 45 Proxy (Connector) Detail Report Option, 44 Proxy (Connector) Inquire Option, 45 Proxy User List Option, 43 PS Anonymous Directories, xliii PSDRPH Security Key, 88, 89, 98, 99, 106, 109 Purge Alerts for a User Option, 164	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319 Queuable Task Log Clean Up Option, 284 QUEUED TO RUN AT WHAT TIME Field, 286 QUEUED TO RUN AT WHAT TIME Field (#2), 286, 287, 288, 290 QUEUED TO RUN ON VOLUME SET Field (#5), 286, 287, 288 Queuers TaskMan, 241 Queuing Device Handler, 189 File Access Specifications, 60
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File Option, 133 Provider Key, 145, 146 Provider Security Key, 41 Proxies APPLICATION PROXY, 43 CONNECTOR PROXY, 43, 44, 45 Proxy (Connector) Detail Report Option, 44 Proxy (Connector) Inquire Option, 45 Proxy User List Option, 43 PS Anonymous Directories, xliii PSDRPH Security Key, 88, 89, 98, 99, 106, 109 Purge Alerts for a User Option, 164 Purge Build or Install Files Option, 333	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319 Queuable Task Log Clean Up Option, 284 QUEUED TO RUN AT WHAT TIME Field, 286 QUEUED TO RUN AT WHAT TIME Field (#2), 286, 287, 288, 290 QUEUED TO RUN ON VOLUME SET Field (#5), 286, 287, 288 Queuers TaskMan, 241 Queuing Device Handler, 189 File Access Specifications, 60 Forced Queuing, 196
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File Option, 133 Provider Key, 145, 146 Provider Security Key, 41 Proxies APPLICATION PROXY, 43 CONNECTOR PROXY, 43, 44, 45 Proxy (Connector) Detail Report Option, 44 Proxy (Connector) Inquire Option, 45 Proxy User List Option, 43 PS Anonymous Directories, xliii PSDRPH Security Key, 88, 89, 98, 99, 106, 109 Purge Alerts for a User Option, 164 Purge Build or Install Files Option, 333 Purge Data Audits Option, 52	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319 Queuable Task Log Clean Up Option, 284 QUEUED TO RUN AT WHAT TIME Field, 286 QUEUED TO RUN AT WHAT TIME Field (#2), 286, 287, 288, 290 QUEUED TO RUN ON VOLUME SET Field (#5), 286, 287, 288 Queuers TaskMan, 241 Queuing Device Handler, 189 File Access Specifications, 60 Forced Queuing, 196 KIDS Installations, 319
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File Option, 133 Provider Key, 145, 146 Provider Security Key, 41 Proxies APPLICATION PROXY, 43 CONNECTOR PROXY, 43, 44, 45 Proxy (Connector) Detail Report Option, 44 Proxy (Connector) Inquire Option, 45 Proxy User List Option, 43 PS Anonymous Directories, xliii PSDRPH Security Key, 88, 89, 98, 99, 106, 109 Purge Alerts for a User Option, 164 Purge Build or Install Files Option, 333 Purge Data Audits Option, 52 Purge DD Audits Option, 52	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319 Queuable Task Log Clean Up Option, 284 QUEUED TO RUN AT WHAT TIME Field, 286 QUEUED TO RUN AT WHAT TIME Field (#2), 286, 287, 288, 290 QUEUED TO RUN ON VOLUME SET Field (#5), 286, 287, 288 Queuers TaskMan, 241 Queuing Device Handler, 189 File Access Specifications, 60 Forced Queuing, 196
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File Option, 133 Provider Key, 145, 146 Provider Security Key, 41 Proxies APPLICATION PROXY, 43 CONNECTOR PROXY, 43, 44, 45 Proxy (Connector) Detail Report Option, 44 Proxy (Connector) Inquire Option, 45 Proxy User List Option, 43 PS Anonymous Directories, xliii PSDRPH Security Key, 88, 89, 98, 99, 106, 109 Purge Alerts for a User Option, 164 Purge Build or Install Files Option, 333 Purge Data Audits Option, 52 Purge Error Log Of Type Of Error Option, 292	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319 Queuable Task Log Clean Up Option, 284 QUEUED TO RUN AT WHAT TIME Field, 286 QUEUED TO RUN AT WHAT TIME Field (#2), 286, 287, 288, 290 QUEUED TO RUN ON VOLUME SET Field (#5), 286, 287, 288 Queuers TaskMan, 241 Queuing Device Handler, 189 File Access Specifications, 60 Forced Queuing, 196 KIDS Installations, 319
(#15), 35 Prompts Terminal Type, 9 Protocols XU USER TERMINATE, 41 Protocols Marked Out-of-Order in Protocol File Option, 133 Provider Key, 145, 146 Provider Security Key, 41 Proxies APPLICATION PROXY, 43 CONNECTOR PROXY, 43, 44, 45 Proxy (Connector) Detail Report Option, 44 Proxy (Connector) Inquire Option, 45 Proxy User List Option, 43 PS Anonymous Directories, xliii PSDRPH Security Key, 88, 89, 98, 99, 106, 109 Purge Alerts for a User Option, 164 Purge Build or Install Files Option, 333 Purge Data Audits Option, 52 Purge DD Audits Option, 52	Quality, 192 Question Mark Help, xlii, 7, 20, 35, 50, 59, 116 117, 119, 120, 123, 130, 143, 177, 180, 182, 183, 185, 188, 197, 238, 240, 273, 278, 279, 319 Queuable Task Log Clean Up Option, 284 QUEUED TO RUN AT WHAT TIME Field, 286 QUEUED TO RUN AT WHAT TIME Field (#2), 286, 287, 288, 290 QUEUED TO RUN ON VOLUME SET Field (#5), 286, 287, 288 Queuers TaskMan, 241 Queuing Device Handler, 189 File Access Specifications, 60 Forced Queuing, 196 KIDS Installations, 319 Options, 286

To the Spooler, 216	REQUIRED VOLUME SET? Field (#4), 255
QUEUING Field (#5.5)	Requirements
DEVICE File (#3.5), 196	DEA ePCS Utility, 70
QUEUING REQUIRED Field (Multiple), 134	RESCHEDULE FREQUENCY Field (#6), 286, 287, 288
R	RESCHEDULING FREQUENCY Field (#6), 288, 290
Reactivate a User Option, 40, 42	Resource Device Edit Option, 232
Reactivating Reactivating	Resource Devices
Users, 39, 42	Editing, 232
READ Access, 33, 49, 51, 53, 54, 60, 65, 124	RESOURCE File (#3.54), 231
Re-answering Installation Questions (KIDS), 320	RESOURCE SLOTS Field (#35), 169, 172 DEVICE File (#3.5), 231, 232
Reasons to Retain BUILD and INSTALL File	Resources
Entries (KIDS), 335	Creating Resource Devices, 232
Rebuilding Primary Menu Trees, 135	Devices
Recover Deleted Option Set Option, 133	RESOURCE File (#3.54), 231
Recovering from an Aborted Distribution Load	Limiting Simultaneous Running of a
(KIDS), 323	Particular Task, 231
Redefining	Running Sequences of Tasks, 232
Common Menu, 130	Special Devices, 231
Reference Materials, xliii	SYNC FLAGs, 232
Reindex the users key's Option, 147	System Management, 231
Reindexing All Users' Security Keys Option,	RESOURCES Device Type, 169
147	Response Time, 18, 251
Rejection Messages	Restart Install Of Package(s) Option, 323
TaskMan, 300	Restart Session Option, 121 Restart Task Manager Option, 282
Release user Option, 45	Restart Task Manager Option, 282 Restart TaskMan Option, 266
Remote Access User Sign-on Log Option, 46	RESTART^ZTMB Direct Mode Utility, 266
REMOTE PRINTER NAME Field (#67), 198	Restarting Aborted Installations (KIDS), 323
Remove Error Screens Option, 183	Restrict Availability of Options Option, 133
Remove Options Previously Delegated Option, 156	RESTRICT DEVICES Field, 134
Remove Out-Of-Order Messages from a Set of	Retrieving Spool Documents, 218
Options Option, 133	Return Codes
Remove Taskman from WAIT State Option, 283	Display
REPLACE, 324	Attributes, 19
Replace a Delegate Option, 156	Reverse Locks, 144, 147
REPLACEMENT VOLUME SET Field (#7), 255	REVERSE/NEGATIVE LOCK Field, 147 Revision History, ii
Replicate or Replace a Delegate Option, 154, 156	Patches, xi RIGHT MARGIN Field (#1)
Report Menu for Alerts Menu, 164	TERMINAL TYPE File (#3.2), 206
Reports	Rollup Patches into a Build Option, 335
Alerts, 164, 165, 166, 167	ROUTINE Field (#25), 168, 170, 175
First Occurrence of Each Error, 183	ROUTINE File (#9.8), 315, 336, 337
First Two Occurrences of Each Error, 183	Routine Tools
Secure Menu Delegation, 157	Compare local/national checksums report
Reprint Access Agreement Letter Option, 31	Option, 315, 337
REQ^%ZTLOAD API, 299	Routines
Requeue Tasks Option, 169, 248, 273, 299	%ZTER*, 181

^%ZTMSH, 261	SCHEDULE V Field (#55.6), 94, 96
^XTLKDICL, 342, 362	Schedule/Unschedule Options Option, 126, 284,
^XTLKWIC, 359	286, 290
^ZU, 22	Scheduling
CHECK^XTSUMBLD, 315, 337	Installations (KIDS), 319
CHECK1 [^] XTSUMBLD, 315, 337	Options, 126
Component Editing, 336	TaskMan, 285
Cross-references, 179	SCHEDULING RECOMMENDED Field
DIC, 51	(#209), 126, 286, 288
DIE, 51	Scratch Global, 227
DIP, 142	Screen Editor
INIT, 304, 309	VA FileMan, 9, 18, 34
NVSTNSET, 198	Scripts
XPAREDIT, 77	GET_METRIC.COM, 260
XQ12, 21	METRIC_SCHEDULE.COM, 260
XTER*, 181	SDP
XTLATSET Routine, 198	Devices, 232
XTLKTOKN, 342	Search File Entries Option, 53
XUINCON, 65	SECONDARY \$1 Field (#52), 200, 204
XUSCLEAN, 135	SECONDARY HFS DIRECTORY Field
ZSTU, 259	(#320.2), 204
RPC Broker Documentation Website, 4	Secondary Menu, 35, 117, 120, 128, 129, 130,
Rubber-band Jump, 120, 123	131, 137, 139, 145, 149, 150
RUN Node, 246, 276, 282, 294	Assigning, 130
RUN State	Trees, 130, 138
	SECONDARY MENU OPTIONS Field (#203,
TaskMan, 302	•
Running Eile Access Security Conversion 60	Multiple), 32
File Access Security Conversion, 60	SECONDARY MENU OPTIONS Field
Advance Preparation, 60	(Multiple), 35, 130, 139, 151
Advantages, 60	Secure Menu Delegation, 32, 40, 149
Sequences of Tasks, 232	Build a New Menu Option, 151
TaskMan with a DCL Context, 263	Copy Everything About an Option to a New
Running tasks Option, 272	Option Option, 151
	Copy One Users Menus and Keys to others
S	Option, 151
-	Delegate's Menu Management Menu, 149
SAC, 131, 284	Delegating Keys, 155
SCHEDULE File, 241, 245, 246, 247, 249, 250,	Delegating Options
275, 278, 297, 298, 299, 301	Select Options to be Delegated, 154
TaskMan, 293	Delegation Levels, 155
SCHEDULE II NARCOTIC Field (#55.1), 94,	Edit a User's Options, 150
96	Limited File Manager Options (Build), 151
SCHEDULE II NON-NARCOTIC Field	Menu Prefix, 157
(#55.2), 94, 96	Options too Sensitive to Delegate, 156
SCHEDULE III NARCOTIC Field (#55.3), 94,	Remove Options Previously Delegated
96	Option, 156
SCHEDULE III NON-NARCOTIC Field	Replicate or Replace a Delegate, 156
(#55.4), 94, 96	Reports, 157
SCHEDULE IV Field (#55.5), 94, 96	System Management, 153
Schedule List, 246, 277	User Interface
Node, 293	Acting as a Delegate, 149

404

Secure Menu Delegation Menu, 152, 153, 154,	TERMINAL TYPE File (#3.2), 206, 209
156	Selecting
Utilities, 143	Common Options with the Double Quote, 121
Secure Menu Management Menu, 149, 152	Software Names for Purging (KIDS), 334
Security	Tasks
Devices, 205	TaskMan User Interface, 238
File Access Security, 52	Send Alpha/Beta Usage to Programmers Option,
SECURITY Field, 16, 33, 205	326
Security Forms, 23, 24	Send Test Pattern to Terminal Option, 210
SECURITY KEY File (#19.1), 144, 146, 147,	Sending Output to the Spooler, 216
180	Sequential Disk Processor (SDP), 232
Security Keys	Device Types, 207, 232
XTLKZMGR, 349, 350	SERVER ACTION Field (#221), 169, 170, 171,
Security Keys, 130, 143	172
Allocating Keys, 144	SERVER AUDIT Field (#223), 171
Assign the XUEPCSEDIT Security Key, 78	SERVER BULLETIN Field (#220), 171
Creating, 146	SERVER DEVICE Field (#227), 169, 172
De-allocating Keys, 144	SERVER MAIL GROUP Field (#222), 171
Delegating, 145, 155	Server Options, 168
Delegation Levels, 145, 147, 150, 155	Denying Server Requests, 168
Deleting, 147	Errors and Warnings, 174
Editing, 146	How Can the Number of Instances of a Server
Exploding Key, 146	Option Be Controlled?, 169
Exported, 147	Server Request, 168
Key Management, 144	Setting up a Server Option, 170
Person Lookup, 146	System Management, 168
Provider, 41, 145, 146	Testing, 173
PSDRPH, 88, 89, 98, 99, 106, 109	What Can Server Options Do?, 168
Purging, 42	What is a Server Option?, 168
Reverse Locks, 147	XQSCHK Utility, 173
Subordinate Keys, 146	XQSPING Utility, 173
System Management, 144	SERVER REPLY Field (#225), 172
User Interface, 143	Servers
XMNOPRIV, 147	
	Compute Mode, 251 General Processor, 251
XQAL-DELETE, 164	
XQSMDFM, 152	Other Non-TaskMan, 251
XTLKZMGR, 341, 349	Print Server Mode, 251
XUAUTHOR, 179	SERVICE/SECTION Field, 31
XUEPCSEDIT, 78, 88, 99, 110	SERVICE/SECTION Field (#29), 34
XUMGR, 22, 23, 32, 68, 144, 145, 155, 221	SERVICE/SECTION File (#49), 31, 34
XUPROG. 35, 131, 143, 144, 305	Set Backup Reviewer for Alerts Option, 166
XUPROGMODE, 35, 144, 184	SET LOGINS/INTERACTIVE DCL Command,
XUSPF200, 23, 32	16
ZTMQ, 248, 271, 273, 274	Setting up a Server Option, 170
SECURITY TOKEN SERVICE Field (#200.1),	Setup
21	TaskMan and DCL Context in Cache/VMS,
Select another task Option, 240	263
Select Options to be Delegated Option, 154, 156	SEX Field (#4)
SELECTABLE AT SIGN-ON Field	NEW PERSON File (#200), 23
TERMINAL TYPE File (#3.2), 19	Shared Device and Terminal Type Attributes,
SELECTABLE AT SIGN-ON Field (#.02)	How are They Used, 207

Shortcuts	SIGN-ON/SYSTEM DEVICE Field (#1.95)
Double Quote and Option Name, 121	DEVICE File (#3.5), 195, 208, 211, 212
Multi-Term Look-Up (MTLU), 341, 353	Site Parameters, 15, 250
Point to a Single Word or Phrase, 343	Site Parameters Edit Option, 261
Signon, 8	SLAVE FROM DEVICE Field, 235
Up-arrow Jump, 120, 121	Slaved Printers, 233, 234
Shortcuts Option	Auto Print Mode, 233
Multi-Term Look-Up (MTLU), 342, 354	Copy Print Mode, 233
Example, 358	Device and Terminal Type File Entries, 234
Show a Delegate's Options, 157	Printer Controller Mode, 233
Show Error Log Option, 291	Processing Steps, 235
Show the Security Keys of a Particular User	Queuing, 235
Option, 155	System Management, 233
Show Users with Selected Primary Menu	Transparent Print Mode, 233
Option, 129	User Interface, 233
SIGNATURE BLOCK PRINTED NAME Field,	Software
67	Components, 245, 307, 335, 337
SIGNATURE BLOCK PRINTED NAME Field	Exported, 304, 307, 316
(#20.2), 67	KIDS Installations, 311
SIGNATURE BLOCK TITLE Field (#20.3), 67	Software Disclaimer, xxxix
Signature Codes, 12	SPAWN Command, 242, 252
Signoff	Special Devices, 225
Error Handling, 9	Browser Device, 225
Normal, 8	Magtape, 229
Signon, 4	Network Channel Device Edit Option, 230
Audits, 46	Network Channel Devices, 230
Devices, 208	Resources, 231
Enabling/Disabling Logons, 22	SDP, 232
Flow Chart, 17	SPECIAL QUEUEING Field (#9), 286, 288
Jump Start, 8	Specify Allowable New Menu Prefix Option,
Lock-out Times, 16	152, 157
Multiple Sign-On Restriction, 18	Specifying
Parameters Checked, 15	Right Margin and Page Length, 189
Process, 15	Special Subtype, 190
Selecting Devices, 208	SPOOL DATA File (#3.519), 220
Shortcuts, 8	Spool Device Edit Option, 223
Statistics, 47	SPOOL DOCUMENT File (#3.51), 192, 207,
Terminal Type Selection, 209	220, 221, 224
Signon Attempts, 16	Spool Documents
SIGN-ON LOG File (#3.081), 43, 45, 46, 47	Making into Mail Messages, 35
Purging, 46	Name, 192, 207, 216, 224
Signon/Security	Name—An Exception, 192
Introductory Text, 15	Spool Management Menu, 221, 222
Summary, 14	SPOOLER Device, 216
System Management, 15	Spooler Menu, 218, 219, 221
Add a New User to the System Option, 22	Spooler Site Parameters Edit Option, 222
Grant Access by Profile Option, 23	Spooling, 216
User Interface, 4	Attributes, 216
Change my Division Option, 10	Auto-despooling, 223
Edit User Characteristics Option, 11	Document Name Prompt, 216
Switch UCI Option, 14	Generating Names, 224

Granting Privileges, 220	Stop TaskMan Option, 293, 303
Making Into Mail Messages, 219	Stopping Tasks, 239
Managing Spool Documents, 221	Storing Host Files in a Specific Directory, 227
Printing spool documents, 219	Sub Node, 295
Privileges, 35	SUBJECT ORGANIZATION Field (#205.2), 21
Privileges, 216	SUBJECT ORGANIZATION ID Field (#205.3),
Privileges, 216	21
Privileges, 220	SUBMANAGER RETENTION TIME Field
Privileges, 220	(#5), 251
Purge old Spool documents Option, 222	Submanagers
Retrieving Spool Documents, 218	TaskMan, 241, 243
Sending Output to the Spooler, 216	SUBORDINATE KEY Field (Multiple), 146
Spool Device Edit Option, 223	Subordinate Keys, 146
Spool Device Types, 223	SUBTYPE Field (#3)
Spool Document Name, 192, 207	DEVICE File (#3.5), 195, 206, 229
Spool Document Storage, 220	Summary
Overflowing, 220	Device Handler, 193
Spool Management Menu, 220	File Access Security Conversion, 63
Spooler Menu, 218, 219, 221	Menu Manager, 123
Storage Overflows, 220	Signon/Security, 14
System Defaults, 222	TaskMan
System Management, 220	User Interface, 240
User Interface, 216	SUPPRESS BULLETIN Field(#224), 172
Viewing spool documents, 218	SUPPRESS FORM FEED AT CLOSE Field
SSN Field	(#11.2), 228
PATIENT File (#2), 55	Surrogate for which Users? Option, 167
SSN Field (#9)	Surrogates
NEW PERSON File (#200), 22, 23, 32	Alerts, 161, 163
STACK Variable, 183	Switch Identities Option, 132
Standard Device Chart	Switch UCI Option, 14
Multi-Term Look-Up (MTLU), 345	Switching
Standard Distributions, 309, 310	UCIs, 135, 250
START NEXT Field, 283	Symbols
Starting Up, Pausing, and Stopping Multiple	Found in the Documentation, xl
Managers, 259	SYNC FLAG Field, 283
Startup List Node, 295	SYNC flag file control Option, 283
States	SYNC FLAGs, 232, 283
Messages	Synonym
TaskMan, 301	Options, 118
Statistics	Synonym Option
Signon, 47	Multi-Term Look-Up (MTLU)
Statistics Option, 53	Example, 359
Status Codes	Synonyms
TaskMan, 298	Devices, 211
STATUS Field, 322	Multi-Term Look-Up (MTLU), 341, 353
STATUS Field (#.02), 330	Associated with Multiple Terms, 343
Status List, 246, 276	Multiple Tokens, 343
Node, 295	Options, 116, 118, 120, 126, 140, 177
Stop Node, 295	Synonyms Option
Stop Task Manager Option, 283	Multi-Term Look-Up (MTLU), 342, 357
Stop task Option, 239	

System Administrator Setup to Enable Building	Task Rejection Messages
Options from Templates, 152	TaskMan, 300
System Configuration	Task Status Codes
TaskMan Terminology, 248	TaskMan, 298
System Management	TaskMan, 236
Alerts, 162	^%ZTSCH Global, 245
Browser Device, 227	^%ZTSK Global, 245
Device Handler, 194	API, 241
Electronic Signatures, 67	Check Taskman's Environment Option, 279
Error Processing, 181	Clean Task File Option, 284
File Access Security, 50	Cleanup Task List Option, 274
Form Feeds, 228	Configuration, 249
Help Processor, 178	DEVICE File (#3.5), 261
Host Files, 214	Multiple Managers, 259
KIDS	Standardized VA Caché and GT.M, 258
Installations, 304	DCL Context, 263
Utilities, 327	Batch Queues, 269
Magtape Devices, 229	Cache/VMS, 263
Managing Delegates, 153	OpenVMS User TASKMAN on ALPHA
Menu Manager, 124	AXP Systems, 269
Network Channel Devices, 230	Restarting, 266
Resources, 231	TASKMAN Queue, 269
Secure Menu Delegation, 153	ZTMSWDCL.COM, 268
Security Keys, 144	ZTMWDCL.COM, 267
Server Options, 168	Defining Environments, 249
Signon/Security, 15	Delete Tasks Option, 274
Slaved Printers, 233	Dequeue Tasks Option, 273
TaskMan	DESCRIPTION Field, 288
Configuration, 249	DEVICE FOR QUEUED JOB OUTPUT
Operation, 270	Field (#3), 286, 287
Overview, 241	Division of Labor, 241
System Manager	Error Screens, 246
Introduction, 2	Files, 245
System Parameters, 15	Header Page, 261
Systems Management	Inspecting the Tasks in the Monitor's Lists,
Multi-Term Look-Up (MTLU), 359	279
Systems Manager Menu, 78, 80, 83, 305	IO List, 277
	Job Limit, 251
_	Job List, 278
Т	List Tasks Option, 270
Table of Contents, xii	Load Balancing, 259
Task Allocation Audit of PSDRPH Key Report	Manager, 241, 242
Option, 89, 106	Startup, 259
Task Changes to DEA Prescribing Privileges	Monitor Action Prompt, 278
Report Option, 88, 102	Multiple Managers and Load Balancing, 259
Task File Cleanup, 284	Option Scheduling, 285
Task List, 246, 278	List Background Options, 285
Node, 295	One-time Option Queue Option, 290
TASK PARAMETERS Field, 48, 163, 184	PARENT OF QUEUABLE OPTIONS
TASK PARAMETERS Field (#15), 286, 288	Menu, 285
TASK PARTITION SIZE Field (#4), 251	Problems, 290

Queuing an option, 286	TASK PARAMETERS Field (#15), 286
Schedule/Unschedule Options Option, 286	Task Rejection Messages, 300
Through the OPTION SCHEDULING File	Task Status Codes, 298
(#19.2), 242	Taskman Error Log
Which Options to Queue, 285	Menu, 291
Other Files, 247	TaskMan Error Log, 181, 246, 278, 284, 291
QUEUED TO RUN AT WHAT TIME Field	TaskMan Management Menu, 270
(#2), 286, 287, 288, 290	Taskman Management Utilities
QUEUED TO RUN ON VOLUME SET Field	Menu, 275
(#5), 286, 287, 288	TaskMan's Reach, 250
Queuers, 241	TaskmMn Error Log
Queuing an Option, 286	Node, 293
Queuing Output, 236	TASKS File (#14.4), 247, 297
Rejection Messages, 300	Terminology, 248
Remove Taskman from WAIT State Option,	Troubleshooting, 277, 279, 293, 301
283	User Interface, 236
Requeue Tasks Option, 273	Background Jobs, 236
RESCHEDULE FREQUENCY Field (#6),	Creating Tasks, 236
286, 287, 288	Display Status of Tasks, 239
RESCHEDULING FREQUENCY Field (#6),	Editing Tasks, 239
288, 290	Listing and Printing Tasks, 240
Restart Task Manager Option, 282	Other Sources of Tasks, 236
Restarting	Queuing Output, 236
DCL Context, 266	Select another task Option, 240
SCHEDULE File, 246, 293	Selecting Tasks, 238
Schedule List, 277	Stopping Tasks, 239
Select another task Option, 240	Summary, 240
Sequences of Tasks, 232	Tasks in the Task List, 238
SPECIAL QUEUEING Field (#9), 286	Working with Tasks, 237
Starting Up, Pausing, and Stopping Multiple	Working with Tasks, 237
Managers, 259	ZTMQ Security Key, 248
Startup, 259	TASKMAN ERROR File, 278
States	Taskman Error Log
BALANCE, 260, 301	Menu, 291
ERROR, 301	TaskMan Error Log, 181, 246, 278, 284, 291
Messages, 301	Node, 293
PAUSE, 255, 302	Taskman Error Log Menu, 181
RUN, 302	Add Error Screens Option, 182
WAIT, 259, 282, 283, 303	Clean Error Log Over Range Of Dates
Status Codes, 298	Option, 292
Stop Task Manager Option, 283	Delete Error Log Option, 292
Stopping, 283	Edit Error Screens Option, 182
Tasks, 239	List Error Screens Option, 182
Submanagers, 241, 243	Purge Error Log Of Type Of Error Option,
SYNC flag file control Option, 283	292
SYNC FLAGs, 232	Remove Error Screens Option, 183
System Management	Taskman Error Log Menu
Configuration, 249	Show Error Log Option, 291
Operation, 270	TASKMAN FILES UCI Field (#5), 255
Overview, 241	TASKMAN FILES VOLUME SET Field (#6),
Task List, 278	255

TASKMAN HANG BETWEEN NEW JOBS	Tasks in the Task List, 238
Field (#7), 251	Working with Tasks, 237
TASKMAN JOB LIMIT Field, 16, 249	Tasks
TASKMAN JOB LIMIT Field (#6), 251	Creating, 231
Taskman Management Menu, 181	Editing, 239
Cleanup Task List Option, 274	In the Task List, 238
Delete Tasks Option, 274	KILL, 278
Dequeue Tasks Option, 273	Waiting for a Volume Set, 242
List Tasks Option, 270	Waiting to Start on a Compute Server, 246
Requeue Tasks Option, 273	TASKS File (#14.4), 239, 241, 242, 243, 245,
TaskMan Management Menu, 270	247, 249, 250, 251, 271, 272, 273, 274, 284,
Taskman Management Utilities	286, 287, 291, 293, 295, 297, 299, 301
Check Taskman's Environment Option, 279	Tasks waiting for a device Option, 272
Clean Task File Option, 284	Telnet Device, 203
Menu, 275	TELNET PORT Field (#66), 198
Monitor Taskman, 275	Templates
Place Taskman in a WAIT State Option, 282	LOGIN Menu, 7, 122
Queuable Task Log Clean Up Option, 284	System Administrator Setup to Enable
Remove Taskman from a WAIT State Option,	Building Options from Templates, 152
283	XUEDIT CHARACTERISTICS, 39
Restart Task Manager Option, 282	Terminal Type
Stop Task Manager Option, 283	Attributes, 18, 207, 208
SYNC flag file control Option, 283	Entries, 190, 209, 234
Taskman Management Utilities Menu, 181	Identity, 8
TASKMAN PRINT A HEADER PAGE? Field	Information Retained by User, 208
(#26), 261	Naming Conventions, 207
TASKMAN SITE PARAMETERS File (#14.7),	P-BROWSER, 227
16, 245, 247, 249, 250, 254, 258, 259, 265,	Prompt, 9, 18
277	Query, 8, 9
BOX-VOLUME PAIR Field (#.01), 250, 251	Selection at Signon, 209
Load Balance Routine, 259	Setup, 18, 39
LOAD BALANCE ROUTINE Field (#21),	Specifications, 192
253	TERMINAL TYPE File (#3.2), 18, 19, 190,
LOG TASKS? Field (#2), 250	194, 195, 206, 207, 209, 228, 229, 234
MODE OF TASKMAN Field (#8), 251	BACK SPACE Field (#4), 206, 229
Standardized VA Caché and GT.M	CLOSE EXECUTE Field, 193
Configuration, 258	CLOSE EXECUTE Field (#7), 206, 228, 234
SUBMANAGER RETENTION TIME Field	235
(#5), 251	FORM FEED Field (#2), 206, 229
TASK PARTITION SIZE Field (#4), 251	Global Location, 194
TASKMAN HANG BETWEEN NEW JOBS	NAME Field (#.01), 206
Field (#7), 251	Naming Conventions, 207
TASKMAN JOB LIMIT Field (#6), 251	OPEN EXECUTE Field, 193
VAX ENVIRONMENT FOR DCL Field	OPEN EXECUTE Field (#6), 206, 234, 235
(#9), 252	PAGE LENGTH Field (#3), 206, 229
TaskMan User Option, 237, 238, 239, 299	RIGHT MARGIN Field (#1), 206
Display Status of Tasks, 239	SELECTABLE AT SIGN-ON Field, 19
Editing Tasks, 239	SELECTABLE AT SIGN-ON Field (#.02),
Listing and Printing Tasks, 240	206, 209
Stopping Tasks, 239	Terminating
Summary, 240	Users, 39
·- ··	- ~ = = , = -

TERMINATION DATE Field, 23, 41, 42, 171	Export, 306
TERMINATION DATE Field (#9.2), 35, 40, 41,	Install, 307
91, 96	Load from Distribution, 307, 310, 312
Termination Process, 41	Load from PackMan Messages, 307, 310
Terminology MDS 204	Print, 307, 310, 316
KIDS, 304	Processing, 319
TaskMan, 248	Verify, 336
Testing	Verifying Checksums, 315
User's Menus, 132	Transport Mechanism
XQSCHK Server Option, 173	Distributions, 309
TEXT TERMINATOR Field, 38	TRM or VTRM Device Edit Option, 202
TEXT TERMINATOR Field (#31.2), 12	TRM Type, 235
TIED ROUTINE Field, 15	Troubleshooting
Time Option, 121	Device Handler, 209
TIME PERIOD Field (#.01), 134	Menu Manager Variables, 142
TIMED READ Field, 20	TaskMan, 277, 279, 293, 301
TIMED READ Field (#200.1), 35	Turn Data Audit On/Off Option, 52
TIMES/DAYS PROHIBITED Field (#3.91)	TYPE Field
(Multiple), 169, 170	DEVICE File (#3.5), 197
TITLE Field (#8), 11, 32	TYPE Field (#.1)
TITLE File (#3.1), 32	VOLUME SET File (#14.5), 254, 255
TMP Global, 134, 135	TYPE Field (#2)
TO UCI Field (#3), 257	DEVICE File (#3.5), 195, 261
TO VOLUME SET Field (#2), 257	TYPE Field (#4)
Toggle Options/Protocols On and Off Option,	OPTION File (#19), 168, 170
133	TYPE-AHEAD Field, 20
Tokenizing Routine, 342	TYPE-AHEAD Field (#.09), 57
Toolbox	TYPE-AHEAD Field (#200.09), 12, 35
Display User Characteristics Option, 13	Types
Electronic Signature code Option, 67	BROWSER, 227
Menu, 6, 9, 10, 11, 13, 67, 68, 121, 122, 218,	COMPUTE SERVER, 254
237	FILE SERVER (Obsolete), 254
Toolkit Queuable Options menu	GENERAL PURPOSE VOLUME SET, 254
Errors Logged in Alpha/Beta Test (QUEUED)	OTHER NON-TASKMAN VOLUME SET,
Option, 326	254
Transfer Entries Option, 53, 54	P-BROWSER, 227
Transfer File Entries Option, 53	PRINT SERVER, 254
Transfer Lines from Another Document Option,	RESOURCES, 169
50, 52	TRM, 235
TRANSLATION Subfield (#.847), 57	
Transparent Print Mode, 233	ш
Transport a Distribution Option, 309, 331	U
TRANSPORT BUILD NUMBER Field (#63),	UCI
315, 337	Definition, 248
Transport Global, 304	Switching, 135, 250
Backup, 318	UCI ASSOCIATION File (#14.6), 245, 247,
Compare, 307, 310, 316	249, 256, 300
Components, 311	FROM UCI Field (#.01), 257
Create, 306, 309, 336	FROM VOLUME SET Field (#1), 257
Definition, 304	Standardized VA Caché and GT.M
Environment Check, 310	Configuration, 258
	0 ,

TO UCI Field (#3), 257	Menu Manager, 116
TO VOLUME SET Field (#2), 257	Multi-Term Look-Up (MTLU), 343
UCI Association Table Edit Option, 256	Secure Menu Delegation
UCI ASSOCIATION TABLE Field, 257	Acting as a Delegate, 149
Unassign Editor Option, 179	Security Keys, 143
Understanding DUZ (User Number), 56	Signon/Security, 4
Unload a Distribution Option, 323	Slaved Printers, 233
Unsuccessful tasks Option, 272	Spooling, 216
Up-arrow Jump, 116, 120, 121, 122, 123, 135	TaskMan, 236
Update Node, 295	User Management menu, 83
Update Routine File Option, 336	User Management Menu, 39, 43, 49, 55, 60, 65
URLs	80
Acronyms Intranet Website, 367	Operations Managemernt Menu, 43
Adobe Website, xliii	User Stacks, 134, 135, 137
Enterprise Program Management Office	Nodes, 137
Website, xxxix	User start-up event Option, 21, 86
Glossary Intranet Website, 367	User Status Report Option, 46
KAAJEE Documentation Website, 5	USER^XQALERT API, 162
Kernel Website, xliii	User's Toolbox Menu, 6, 9, 10, 11, 13, 67, 68,
RPC Broker Documentation Website, 4	121, 122, 218, 237
VA FileMan Documentation Website, 33, 49,	Display User Characteristics Option, 13
52	Electronic Signature code Option, 67
VA Software Document Library (VDL)	Users
Website, xliii	Adding New, 22
Usage Considerations	Attributes, 15, 22, 23, 31
Multi-Term Look-Up (MTLU), 342	Deactivating, 40
USE AS LINK FOR MENU ITEMS Action,	Deactivating Automatically, 41
311, 319	Introduction, 1
USE Command, 243	Reactivating, 42
Use of Slaved Printer	Terminating, 39
Processing Steps, 235	Users with Foreign Visits Option, 46
USE PARAMETERS Field (#19.5)	Using
DEVICE File (#3.5), 196	File Access Options, 56
Use this Manual, How to, xxxviii	Multi-Term Lookup (MTLU) Option, 346
USE TIMEOUT ON OPENS Field (#2009.5)	Print Utility Option, 348
DEVICE File (#3.5), 230	Ranges of File Numbers, 59
User Alerts Count Report Option, 166	Security Keys with Reverse Locks, 147
USER CHARACTERISTICS TEMPLATE	Utilities for MTLU Option, 349
Field, 39	Utilities
USER CLASS Field (#9.5), 43	^%ZTMOVE
User Inquiry Option, 46	Toolkit, 299
User Interface, 1	Block Count, 179
Alerts, 158	DIFROM, 304, 307, 309
Browser Device, 225	Secure Menu Delegation Menu, 143
Device Handler, 187	XQSCHK Server Option, 173
Electronic Signatures, 67	XQSPING, 173
Error Processing, 181	XTSPING, 173
File Access Security, 49	Utilities For MTLU Menu, 349
Form Feeds, 228	Utilities Menu
Help Processor, 176	KIDS, 327
Host Files, 213	Utility Functions Menu, 53

UTILITY(\$J Global, 63, 134, 135	ZTCPU, 263
Purging, 134	ZTQPARAM, 288
	ZTSTOP, 299
V	VAX ENVIRONMENT FOR DCL Field (#9),
Y. F. N.	252, 263 Varify a Build Option 236
VA FileMan	Verify a Build Option, 336 Verify Checksums in Transport Global Option,
Browser Device, 225	315
File Access Security	VERIFY CODE Field, 32
Properties, 52	VERIFY CODE Field, 32 VERIFY CODE Field (#7.2), 12, 32
Limited File manger Options (Build) Option,	Verify Codes, 1, 4, 5, 6, 7, 8, 12, 15, 16, 19, 23
151	32, 40, 47, 48, 56, 171, 175
Line Editor, 12, 34, 50, 52	
Menu, 49	Defining, 6
Screen Editor, 9, 18, 34	Log, 48
What Happened to DIFROM, 309	Old, 48
VA FileMan Documentation Website, 33, 49, 52	Purging, 48
VA Handbook 6500, 42	Verify Package Integrity Option, 337
Appendix D, 42	Verifying Checksums in a Transport Global
VA Software Document Library (VDL)	(KIDS), 315
Website, xliii, 339	VERSION Field (Multiple), 308
Website, 339	Versions to Retain (KIDS), 333
Website, 339	View Alerts "VA" Option, 9, 121, 158, 159
Website, 340	View data for Alert Tracking file entry Option, 166
VA# Field (#53.3), 94, 96	
Variables	Virtual Devices
\$HOROLOG, 276, 295	VMS Systems, 208
\$STACK, 183	Virtual Terminals, 208 VMS
%ZISQUIT, 196	
DIDEL, 51, 52	Systems Virtual Devices, 208
DLAYGO, 51, 52	VIIIdai Devices, 208 VMS DEVICE TYPE Field (#63), 198
DTIME, 20, 35	VOICE PAGER Field (#.137), 11, 36, 67
DUZ, 57	VOICE PAGER Field (#.137), 11, 30, 67 VOLD Cross-reference, 48
DUZ("AG"), 19	Volume
DUZ("AUTO"), 20	Set Definition, 248
DUZ(0), 33, 50, 51, 54, 55, 60, 152, 205	Volume Set Edit Option, 253
DUZ(2), 19	VOLUME SET Field (#.01)
IO, 126	VOLUME SET File (#.01)
IONOFF, 228	VOLUME SET Field (#41, Multiple)
Menu Manager, Troubleshooting, 142	KERNEL SYSTEM PARAMETERS File
XQABTST, 142	(#8989.3), 251
XQACNDEL, 160	VOLUME SET Field (Multiple)
XQDIC, 142	KERNEL SYSTEM PARAMETERS File
XQMM("J"), 137	(#8989.3), 16
XQPSM, 142	VOLUME SET File (#14.5), 22, 245, 247, 249,
XQT, 142	253, 257, 284, 300, 301, 302
XQUIT, 136, 170	DAYS TO KEEP OLD TASKS Field (#8),
XQUR, 142	256
XQUSER, 142	INHIBIT LOGONS? Field (#1), 255
XQXFLG, 142	LINK ACCESS Field (#2), 255
XQY, 142 YOY0, 142	OUT OF SERVICE? Field (#3), 255
XQY0, 142	001 01 SER (10E. 110H (113), 233

REPLACEMENT VOLUME SET Field (#7), 255	X
REQUIRED VOLUME SET? Field (#4), 255	XMB Global, 220
Standardized VA Caché and GT.M	XMBS Global, 220
Configuration, 258	XMNOPRIV Security Key, 147
TASKMAN FILES UCI Field (#5), 255	XPAR EDIT PARAMETER Option, 75
TASKMAN FILES VOLUME SET Field	XPAR MENU TOOLS Menu, 75
(#6), 255	XPAR MENU TOOLS Option, 141
TYPE Field (#.1), 254, 255	XPAREDIT Routine, 77
VOLUME SET Field (#.01), 254	XPD BACKUP Option, 318
VOLUME SET(CPU) Field (#1.9)	XPD COMPARE TO SYSTEM Option, 316
DEVICE File (#3.5), 195, 208, 211, 212, 261,	XPD CONVERT PACKAGE Option, 330
287	XPD DISTRIBUTION MENU, 306
	XPD EDIT INSTALL Option, 330
	XPD INSTALL BUILD Option, 319
W	XPD INSTALLATION MENU Menu, 307, 311
Wait Node, 295	XPD LOAD DISTRIBUTION Option, 312, 313
WAIT State, 295	XPD MAIN Menu, 305
TaskMan, 259, 282, 283, 303	XPD PRINT BUILD Option, 328
Waiting List, 246	XPD PRINT CHECKSUM Option, 315
Waivers	XPD PRINT INSTALL FILE Option, 329
Academic Afiliation Waiver, 42	XPD PRINT INSTALL Option, 316
Websites	XPD PRINT PACKAGE PATCHES Option,
Acronyms Intranet Website, 367	333
Adobe Website, xliii	XPD PURGE FILE Option, 333
Enterprise Program Management Office	XPD RESTART INSTALL Option, 323
Website, xxxix	XPD ROLLUP PATCHES Option, 335
Glossary Intranet Website, 367	XPD ROUTINE UPDATE Option, 336
KAAJEE Documentation Website, 5	XPD UNLOAD DISTRIBUTION Option, 323
Kernel Website, xliii	XPD UTILITY Menu, 327
RPC Broker Documentation Website, 4	XPD VERIFY BUILD Option, 336
VA FileMan Documentation Website, 33, 49,	XPD VERIFY INTEGRITY Option, 337
52	XQ MENUMANAGER PROMPT Parameter,
VA Software Document Library (VDL)	141
Website, xliii, 339, 340	XQ Nodes, 138
What Can Server Options Do?, 168	XQ UNREF'D OPTIONS Option, 131
What Happened to DIFROM, 309	XQ XUTL \$J NODES Option, 134, 135
What in VA FileMan is Still Protected by the	XQ12 Routine, 21
File Manager Access Code?, 51	XQAB ACTUAL OPTION USAGE Option,
What is a Server Option?, 168	326
When is File Access Security Checked?, 51	XQAB AUTO SEND Option, 326
When the Distribution is Split Across Diskettes	XQAB ERR DATE/SITE/NUM/ROU/ERR Option, 326
(KIDS), 312	XQAB ERROR LOG XMIT Option, 326
When the KIDS Installation is Queued, 319	XQAB LIST LOW USAGE OPTS Option, 326
Where am I? Option, 121	XQAB MENU Menu, 326
Which Options to Queue	XQABTST Variable, 142
TaskMan, 285	XQACNDEL Variable, 160
Who Needs File Access?, 52	XQAL ALERT LIST FROM DATE Option,
Why Longer Passwords?, 7	165
Working with Tasks, 237	XQAL BACKUP REVIEWER, 166
WRITE Access, 33, 49, 51, 54, 124	TYTE DISCISOF KEVIEWER, 100

XQAL CRITICAL ALERT COUNT Option, XQSMD ADD Option, 154, 156 165 XQSMD BUILD MENU Option, 151 XQAL PATIENT ALERT LIST Option, 165 XQSMD COPY USER Option, 151 XQAL REPORTS MENU Menu, 164 XQSMD EDIT OPTIONS Option, 150 XOAL SET BACKUP REVIEWER Option, 166 Example, 150 XQSMD LIMITED FM OPTIONS Option, 152 XQAL SURROGATE FOR WHICH USERS Example, 153 Option, 167 XQAL USER ALERTS COUNT Option, 166 XQSMD MGR Menu, 152, 153, 156 XQAL VIEW ALERT TRACKING ENTRY **XQSMD REPLICATE Option, 156** XQSMD SET PREFIX Option, 152 Option, 166 XOSMD USER MENU, 149, 151, 152, 154, 155 XQAL-DELETE Security Key, 164 XQALERT BY USER DELETE Option, 164 XQSMDFM Security Key, 152 **XQALERT DELETE OLD Option, 163 XOSPING Utility**, 173 XQSRV Namespace, 171 **XQALERT MAKE Option, 164** XQT Nodes (MENU Templates), 138 XOALERT MGR Menu, 163 XQALERT Option, 9 XQT Variable, 142 XQALERT SURROGATE SET/REMOVE XQUIT Variable, 136, 170 Option, 161, 163 XOUR Variable, 142 XQBUILDTREEQUE Option, 135, 287 XOUSER Variable, 142 XQCOPYOP Option, 151 XQXFLG Variable, 142 XODIC Variable, 142 XOY Variable, 142 XQDISPLAY OPTIONS Menu, 128, 129 XQY0 Variable, 142 **XQHELP-ASSIGN Option, 179** XTER* Routines, 181 XQHELP-DEASSIGN Option, 179 XTLATSET Routine, 198 XQHELP-DISPLAY Option, 178 XTLKLKUP Option, 341, 346 XQHELPFIX Option, 179 XTLKMODKY Option, 342, 356 XQHELP-LIST Option, 178 XTLKMODPARK Option, 341, 349, 350 XOHELP-MENU Menu, 178 XTLKMODPARS Option, 341, 350 XTLKMODPARS Options, 349 XQHELP-UPDATE Option, 178 XTLKMODSH Option, 342, 354 XQHELP-XREF Option, 179 **XQKEYALTODEL Option, 145** XTLKMODSY, 342 XQKEYDEL Option, 145, 155 XTLKMODSY Option, 357 XQLOCK1 Option, 145 XTLKMODUTL Option, 342, 349, 353 XQLOCK2 Option, 145 XTLKPRTUTL Option, 341, 348 XQMM("J") Variable, 137 XTLKTOKN Routine, 342 XQOOFF Option, 133 XTLKUSER2 Menu, 343 XQOOMAIN Menu, 132 XTLKUTILITIES, 349 XQOOMAKE Option, 132 XTLKZMGR Security Key, 341, 349, 350 XQOON Option, 133 XTMENU Menu, 343 XQOOREDO Option, 133 XTMP Global, 133, 134, 135, 310, 312, 323 XQOOSHOFIL Option, 133 XTSPING Utility, 173 XQOOSHOPRO Option, 133 XU CHECKSUM REPORT Option, 315, 337 XQOOSHOW Option, 133 XU DA EDIT Option, 209 XQOOTOG Option, 133 XU EPCS DISUSER EXP DATE Option, 87, 90 XQOPTFIX Option, 131 XU EPCS DISUSER PRIVS Option, 87, 88, 96 XQPSM Variable, 142 XU EPCS DISUSER XDATE EXPIRES **XQRESTRICT Option, 133** Option, 87, 93 **XOSCHK Server Option** XU EPCS EDIT DATA Option, 80, 86, 110 Errors and Warnings, 174 XU EPCS EDIT DEA# AND XDATE Option, Testing, 173 86, 87, 89, 110 XQSERVER Bulletin, 171, 175 XU EPCS EXP DATE Option, 87, 89

XU EPCS LOGICAL ACCESS Option, 87, 88, XUKERNEL, 204 102 XUKEYALL Option, 78, 144, 145 XU EPCS Option, 86 XUKEYDEALL Option, 144 XU EPCS PRINT EDIT AUDIT Option, 87, 88, XUKEYEDIT Option, 146 XUKEYMGMT Menu, 78 XU EPCS PRIVS Option, 87, 88, 94 XUMAINT Menu, 78 XU EPCS PSDRPH AUDIT Option, 87, 89, 106 XUMGR Security Key, 22, 23, 32, 68, 144, 145, XU EPCS PSDRPH KEY Option, 87, 89, 109 155, 221 XU EPCS PSDRPH Option, 87, 88, 98 XUOPTDISP Option, 127 XUOPTPURGE Option, 127 XU EPCS SET PARMS Option, 87, 88, 99 XUOPTUSER Menu, 43 XU EPCS UTILITY FUNCTIONS Menu, 86, 87 XUOPTWHO Option, 129 XU EPCS XDATE EXPIRES Option, 87, 92 XUOUT Option, 210 XUP API, 227 XU FINDUSER Option, 43 XUPRINT Option, 129 XU OPTION QUEUE Option, 290 XU SID EDIT Option, 204 XUPROG Menu, 305 XUPROG Security Key, 35, 131, 143, 144, 305 XU SWITCH UCI Option, 14 XU USER SIGN-ON Extended Action, 21 XUPROGMODE Option, 138 XU USER SIGN-ON Option, 20, 21 XUPROGMODE Security Key, 35, 144, 184 XU USER START-UP Extended Action, 21 XURESJOB Option, 278, 295 XU USER TERMINATE Protocol, 41 XUS VISIT USERS Option, 46 XUSAP PROXY CONN DETAIL ALL Option, XUAUDIT MENU, 127 XUAUDIT Option, 127 XUAUTHOR Security Key, 179 XUSAP PROXY CONN DETAIL INQ Option, XUAUTODEACTIVATE Option, 41 XUCOMMAND Menu, 130 XUSAP PROXY LIST Option, 43 XUDEVEDIT Option, 229 XUSC LIST Option, 43 XUDEVEDITCHAN Option, 230 XUSCLEAN Routine, 135 XUDEVEDITHFS Option, 200, 214 XUSCZONK Option, 46 XUDEVEDITRES Option, 232 XUSEC Cross-reference, 147 XUDEVEDITSPL Option, 223 XUSEC REMOTE ACCESS Option, 46 XUDEVEDITTRM Option, 202 XUSEC(0, Global, 47, 134 **XUEDIT CHARACTERISTICS Template**, 39 XUSEC(0,"CUR",DUZ,DATE), 135 XUEDITOPT Option, 124, 170 XUSER COMPUTER ACCOUNT Help Frame, XUEPCS DATA File (#8991.6), 88, 100, 102 24 XUSER DIV CHG Option, 10 XUEPCS PSDRPH AUDIT File (#8991.7), 89, XUSER KEY RE-INDEX Option, 147 XUEPCS REPORT DEVICE parameter, 75, XUSER Menu, 39, 49, 55, 60, 65, 83 XUSERAOLD Option, 48 102, 106 XUEPCS REPORT DEVICE Parameter, 77 XUSERBLK Option, 23 XUEPCSEDIT Security Key, 78, 88, 99, 110 XUSER-CLEAR-ALL Option, 22 XUERRS Menu, 183 XUSERDEACT Option, 40 XUERTRAP Option, 184 XUSEREDIT Option, 31, 80, 83 XUERTRP AUTO CLEAN Option, 184 XUSEREDITSELF Option, 11, 208 XUERTRP CLEAN Option, 184 XUSERINO Option, 46 XUERTRP PRINT ERRS Option, 186 **XUSERINT Option, 15** XUERTRP PRINT T-1 1 ERR Option, 183 XUSERLIST Option, 43 XUERTRP PRINT T-1 2 ERR Option, 183 XUSERNEW Option, 22, 23 XUFI Namespace, 63 XUSERPOST Option, 20 XUFILEACCESS Menu, 55, 56, 60, 64, 65, 66 XUSERPURGEATT Option, 42

XUINCON Routine, 65

XUSERREACT Option, 40, 42

XUSERREL Option, 45	XUTM MGR Men
XUSERTOOLS Menu, 10	XUTM QCLEAN
XUSESIG BLOCK Option, 67	XUTM REQ Option
XUSESIG CLEAR Option, 68	XUTM RESTART
XUSESIG Option, 67, 68	XUTM RUN Option
XUSITEMGR Menu, 43, 326	XUTM SCHEDUL
XUSITEPARM Option, 15, 205	XUTM STOP Opti
XUSPF200 Security Key, 23, 32	XUTM SYNC Opt
XU-SPL-ALLOW Option, 218	XUTM TaskMan N
XU-SPL-BROWSE Option, 218	XUTM TL CLEAN
XU-SPL-DELETE Option, 218	XUTM UCI Option
XU-SPL-LIST Option, 218	XUTM USER Opt
XU-SPL-MAIL Option, 219	XUTM UTIL Men
XU-SPL-MGR Menu, 221, 222	XUTM VOLUME
XU-SPL-PRINT Option, 219	XUTM WAIT Opt
XU-SPL-PURGE Option, 222	XUTM ZTMON O
XU-SPL-SITE Option, 222	XUTTEST Option
XU-SPL-USER Option, 221	XUUSERDISP Op
XUSSPKI SAN Bulletin, 111	XUUSERSTATUS
XUSSPKI UPN SET Option, 83, 86, 110	XUXREF Option,
XUSTAT Option, 34, 47	XUXREF-2 Option
XUTESTUSER Option, 132	
XUTIO Menu, 199, 210	Υ
XUTL Global, 134, 135, 136, 142, 208	
Display Nodes, 138	Your future tasks (
Jump Nodes, 140	
Structure and Function, 137	Z
User Stacks, 137	4
XUTL("XQ", \$J, "T") Node, 138	Z Namespace, 157
XUTL("XQ", \$J, "XQM") Node, 138	ZIS Global, 247
	215 O100a1, 247
XUTLOOPBACK Option, 210	
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285	ZIS(1, Global, 194
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED	ZIS(1, Global, 194 ZIS(2, Global, 194
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED Option	ZIS(1, Global, 194
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED Option TaskMan, 285	ZIS(1, Global, 194 ZIS(2, Global, 194 ZIS(3.22, Global, 1 ZISL Global, 231
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED Option TaskMan, 285 XUTM CHECK ENV Option, 279	ZIS(1, Global, 194 ZIS(2, Global, 194 ZIS(3.22, Global, 1 ZISL Global, 231 ZISQUIT Variable
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED Option TaskMan, 285 XUTM CHECK ENV Option, 279 XUTM CLEAN Option, 284	ZIS(1, Global, 194 ZIS(2, Global, 194 ZIS(3.22, Global, 1 ZISL Global, 231
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED Option TaskMan, 285 XUTM CHECK ENV Option, 279 XUTM CLEAN Option, 284 XUTM DEL Option, 248, 274	ZIS(1, Global, 194 ZIS(2, Global, 194 ZIS(3.22, Global, 1 ZISL Global, 231 ZISQUIT Variable ZOSF Nodes, 302
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED Option TaskMan, 285 XUTM CHECK ENV Option, 279 XUTM CLEAN Option, 284 XUTM DEL Option, 248, 274 XUTM DQ Option, 248, 273, 299	ZIS(1, Global, 194 ZIS(2, Global, 194 ZIS(3.22, Global, 1 ZISL Global, 231 ZISQUIT Variable ZOSF Nodes, 302 ZOSF("VOL") No
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED Option TaskMan, 285 XUTM CHECK ENV Option, 279 XUTM CLEAN Option, 284 XUTM DEL Option, 248, 274 XUTM DQ Option, 248, 273, 299 XUTM ERROR DELETE Option, 292	ZIS(1, Global, 194 ZIS(2, Global, 194 ZIS(3.22, Global, 1 ZISL Global, 231 ZISQUIT Variable ZOSF Nodes, 302 ZOSF("VOL") No ZSTU Routine, 259
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED Option TaskMan, 285 XUTM CHECK ENV Option, 279 XUTM CLEAN Option, 284 XUTM DEL Option, 248, 274 XUTM DQ Option, 248, 273, 299 XUTM ERROR DELETE Option, 292 XUTM ERROR LOG CLEAN RANGE Option,	ZIS(1, Global, 194 ZIS(2, Global, 194 ZIS(3.22, Global, 1 ZISL Global, 231 ZISQUIT Variable ZOSF Nodes, 302 ZOSF("VOL") No ZSTU Routine, 259 ZTCPU Variable, 2
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED Option TaskMan, 285 XUTM CHECK ENV Option, 279 XUTM CLEAN Option, 284 XUTM DEL Option, 248, 274 XUTM DQ Option, 248, 273, 299 XUTM ERROR DELETE Option, 292 XUTM ERROR LOG CLEAN RANGE Option, 292	ZIS(1, Global, 194 ZIS(2, Global, 194 ZIS(3.22, Global, 1 ZISL Global, 231 ZISQUIT Variable ZOSF Nodes, 302 ZOSF("VOL") No ZSTU Routine, 259 ZTCPU Variable, 2 ZTER Global, 181
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED Option TaskMan, 285 XUTM CHECK ENV Option, 279 XUTM CLEAN Option, 284 XUTM DEL Option, 248, 274 XUTM DQ Option, 248, 273, 299 XUTM ERROR DELETE Option, 292 XUTM ERROR LOG CLEAN RANGE Option, 292 XUTM ERROR Menu, 181, 291	ZIS(1, Global, 194 ZIS(2, Global, 194 ZIS(3.22, Global, 1 ZISL Global, 231 ZISQUIT Variable ZOSF Nodes, 302 ZOSF("VOL") No ZSTU Routine, 259 ZTCPU Variable, 2 ZTER Global, 181 ZTER* Routines, 1
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED Option TaskMan, 285 XUTM CHECK ENV Option, 279 XUTM CLEAN Option, 284 XUTM DEL Option, 248, 274 XUTM DQ Option, 248, 273, 299 XUTM ERROR DELETE Option, 292 XUTM ERROR LOG CLEAN RANGE Option, 292 XUTM ERROR Menu, 181, 291 XUTM ERROR PURGE TYPE Option, 292	ZIS(1, Global, 194 ZIS(2, Global, 194 ZIS(3.22, Global, 1 ZISL Global, 231 ZISQUIT Variable ZOSF Nodes, 302 ZOSF("VOL") No ZSTU Routine, 259 ZTCPU Variable, 2 ZTER Global, 181 ZTER* Routines, 1 ZTLOAD API, 231
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED Option TaskMan, 285 XUTM CHECK ENV Option, 279 XUTM CLEAN Option, 284 XUTM DEL Option, 248, 274 XUTM DQ Option, 248, 273, 299 XUTM ERROR DELETE Option, 292 XUTM ERROR LOG CLEAN RANGE Option, 292 XUTM ERROR Menu, 181, 291 XUTM ERROR PURGE TYPE Option, 292 XUTM ERROR SCREEN ADD Option, 182	ZIS(1, Global, 194 ZIS(2, Global, 194 ZIS(3.22, Global, 1 ZISL Global, 231 ZISQUIT Variable ZOSF Nodes, 302 ZOSF("VOL") No ZSTU Routine, 259 ZTCPU Variable, 2 ZTER Global, 181 ZTER* Routines, 1 ZTLOAD API, 231 ZTM TaskMan Na
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED Option TaskMan, 285 XUTM CHECK ENV Option, 279 XUTM CLEAN Option, 284 XUTM DEL Option, 248, 274 XUTM DQ Option, 248, 273, 299 XUTM ERROR DELETE Option, 292 XUTM ERROR LOG CLEAN RANGE Option, 292 XUTM ERROR Menu, 181, 291 XUTM ERROR PURGE TYPE Option, 292 XUTM ERROR SCREEN ADD Option, 182 XUTM ERROR SCREEN EDIT Option, 182	ZIS(1, Global, 194 ZIS(2, Global, 194 ZIS(3.22, Global, 194 ZISL Global, 231 ZISQUIT Variable ZOSF Nodes, 302 ZOSF("VOL") No ZSTU Routine, 259 ZTCPU Variable, 2 ZTER Global, 181 ZTER* Routines, 1 ZTER* Routines, 1 ZTLOAD API, 231 ZTM TaskMan Na ZTMOVE Utility
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED Option TaskMan, 285 XUTM CHECK ENV Option, 279 XUTM CLEAN Option, 284 XUTM DEL Option, 248, 274 XUTM DQ Option, 248, 273, 299 XUTM ERROR DELETE Option, 292 XUTM ERROR LOG CLEAN RANGE Option, 292 XUTM ERROR Menu, 181, 291 XUTM ERROR PURGE TYPE Option, 292 XUTM ERROR SCREEN ADD Option, 182 XUTM ERROR SCREEN EDIT Option, 182 XUTM ERROR SCREEN LIST Option, 182	ZIS(1, Global, 194 ZIS(2, Global, 194 ZIS(3.22, Global, 194 ZISL Global, 231 ZISL Global, 231 ZISQUIT Variable ZOSF Nodes, 302 ZOSF("VOL") No ZSTU Routine, 259 ZTCPU Variable, 2 ZTER Global, 181 ZTER* Routines, 1 ZTLOAD API, 231 ZTM TaskMan Na ZTMOVE Utility Toolkit, 299
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED Option TaskMan, 285 XUTM CHECK ENV Option, 279 XUTM CLEAN Option, 284 XUTM DEL Option, 248, 274 XUTM DQ Option, 248, 273, 299 XUTM ERROR DELETE Option, 292 XUTM ERROR LOG CLEAN RANGE Option, 292 XUTM ERROR Menu, 181, 291 XUTM ERROR PURGE TYPE Option, 292 XUTM ERROR SCREEN ADD Option, 182 XUTM ERROR SCREEN EDIT Option, 182 XUTM ERROR SCREEN LIST Option, 182 XUTM ERROR SCREEN REMOVE Option,	ZIS(1, Global, 194 ZIS(2, Global, 194 ZIS(3.22, Global, 1 ZISL Global, 231 ZISQUIT Variable ZOSF Nodes, 302 ZOSF("VOL") No ZSTU Routine, 259 ZTER Global, 181 ZTER* Routines, 1 ZTER* Routines, 1 ZTLOAD API, 231 ZTM TaskMan Na ZTMOVE Utility Toolkit, 299 ZTMQ Security Keep
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED Option TaskMan, 285 XUTM CHECK ENV Option, 279 XUTM CLEAN Option, 284 XUTM DEL Option, 248, 274 XUTM DQ Option, 248, 273, 299 XUTM ERROR DELETE Option, 292 XUTM ERROR LOG CLEAN RANGE Option, 292 XUTM ERROR Menu, 181, 291 XUTM ERROR PURGE TYPE Option, 292 XUTM ERROR SCREEN ADD Option, 182 XUTM ERROR SCREEN EDIT Option, 182 XUTM ERROR SCREEN LIST Option, 182 XUTM ERROR SCREEN REMOVE Option, 183	ZIS(1, Global, 194 ZIS(2, Global, 194 ZIS(3.22, Global, 1 ZISL Global, 231 ZISQUIT Variable ZOSF Nodes, 302 ZOSF("VOL") No ZSTU Routine, 259 ZTCPU Variable, 2 ZTER Global, 181 ZTER* Routines, 1 ZTER* Routines, 1 ZTLOAD API, 231 ZTM TaskMan Na ZTMOVE Utility Toolkit, 299 ZTMQ Security Ke ZTMQUEUABLE
XUTLOOPBACK Option, 210 XUTM BACKGROUND PRINT Option, 285 XUTM BACKGROUND RECOMMENDED Option TaskMan, 285 XUTM CHECK ENV Option, 279 XUTM CLEAN Option, 284 XUTM DEL Option, 248, 274 XUTM DQ Option, 248, 273, 299 XUTM ERROR DELETE Option, 292 XUTM ERROR LOG CLEAN RANGE Option, 292 XUTM ERROR Menu, 181, 291 XUTM ERROR PURGE TYPE Option, 292 XUTM ERROR SCREEN ADD Option, 182 XUTM ERROR SCREEN EDIT Option, 182 XUTM ERROR SCREEN LIST Option, 182 XUTM ERROR SCREEN REMOVE Option,	ZIS(1, Global, 194 ZIS(2, Global, 194 ZIS(3.22, Global, 1 ZISL Global, 231 ZISQUIT Variable ZOSF Nodes, 302 ZOSF("VOL") No ZSTU Routine, 259 ZTCPU Variable, 2 ZTER Global, 181 ZTER* Routines, 1 ZTLOAD API, 231 ZTM TaskMan Na ZTMOVE Utility Toolkit, 299 ZTMQ Security Ke ZTMQUEUABLE 284, 285

R Menu, 181, 270 LEAN Option, 256, 284, 291, 297 Q Option, 248, 273, 299 START Option, 282 N Option, 283 HEDULE Option, 286 OP Option, 282, 283, 294 NC Option, 283 kMan Namespace, 245 CLEAN Option, 274 Option, 256 ER Option, 237, 299 IL Menu, 181, 275 LUME Option, 253 ATT Option, 282, 283 MON Option, 260, 275, 301 Option, 210 OISP Option, 13 TATUS Option, 46 Option, 128 Option, 129

tasks Option, 272

247 al, 194 al. 194 Global, 194 al, 231 ariable, 196 es, 302 L") Node, 254 ine, 259 riable, 263 oal, 181, 184 itines, 181 API, 231, 241, 242, 299 Man Namespace, 245 Utility 299 urity Key, 248, 271, 273, 274 VABLE OPTIONS Menu, 41, 222, outine, 261 CL.COM, 268

ZTMWDCL.COM, 267 ZTQPARAM Variable, 288 ZTSCH Global, 241, 245, 247, 255, 259, 286, 293, 298 ZTSK Global, 241, 245, 255, 259, 271, 284, 297, 298 ZTSK(task #, 0) Node, 247 ZTSK(task #, 3) Node, 247 ZTSTOP Variable, 299 ZU Routine, 22 ZUA(3.05 Global, 47