#### $\chi$ pods and Mixing Efficiency

Andy Pickering

March 24, 2017

Introduction

TIWE

EQ14

Applying  $\chi$ pod method to patches

Summary

#### The CTD- $\chi$ pod

- Measures temperature gradient w/ FP07 thermistor
- Easily deployed on traditional CTD, Tz not as sensitive to package vibration
- ► Goal: estimate  $\chi$  and  $\epsilon$  w/o full microstructure



#### $\chi$ pod Method

#### In small windows:

- Convert dT/dt to dT/dz using fallspeed, frozen-flow hypothesis
- Compute spectra of dT/dz
- Iterative method to estimate  $\chi, \epsilon$
- ▶ Assumes  $K_T = K_\rho$
- Assumes mixing efficency (coefficient)  $\gamma = 0.2$

$$\gamma_{\chi\epsilon} = \frac{N^2 \chi}{2\epsilon T_z^2} \tag{1}$$

# CTD- $\chi$ pod Validation

- ► To validate, compare w/ Chamelon microstructure profiles (1m avg).
- Apply  $\chi$ pod method to Chameleon thermistor data only (no shear probes)
- Compare to 'true' Chameleon estimates using shear probes.

#### Results:

- $\triangleright \chi$  compares well
- ▶ But  $\epsilon$  biased low by about 10X

#### Why is $\epsilon$ Biased so Low?

- ▶ Turns out using the 1m avg Chameleon data,  $\gamma \approx$  0.02, not 0.2 .
- Apparently Sasha found something similar for EQ08 and other Chameleon datasets?

### What if We Compute $\gamma$ over patches?


- ▶ But everyone says  $\gamma = 0.2...$
- Maybe we have to compute it over patches. If there's no mixing, does  $\gamma$  even make sense?
- So began the journey into patches...

#### **Patches**

- ▶ Turns out computing  $\gamma$  over patches not so simple...
- ▶ Lots of options for how to identify patches, calculate  $T_z$  and  $N^2$  etc.
- Lots of salinity spikes, need to use temperature.

#### Salinity spikes

- Salinity looks noisy, lots of spikes.
- Not a constant T-S relationship
- use  $R^2$  to quanity 'tight' T-S relationships in patches?



### dT/dz and N2

- T<sub>z</sub> "bin': Interpolate binned T<sub>z</sub> to mean depth of each patch.
- T<sub>z</sub> ''line': Fit a straight line to sorted temperature within patch.
- ► T<sub>z</sub> 'bulk' : Method from Smyth et al 2001. More robust when there are multiple layers within patch?


- N<sup>2</sup> ''bin': Interpolate binned N<sup>2</sup> to mean depth of each patch.
- N<sup>2</sup> ''line': Fit a straight line to sorted density within patch.
- N<sup>2</sup> ''fit': Fit a straight line to density computed from T-S fit in patch.
- ▶  $N^2$  'bulk' : Use 'bulk'  $T_z$ , and ratio between density and temperature.

#### This gives us several estimates of $\gamma$ :

- $ightharpoonup \gamma$  bin : Binned  $T_z, N^2$  interpolated to patch locations.
- $ightharpoonup \gamma$  ''line' : 'line'  $T_z$ ,  $N^2$
- $ightharpoonup \gamma$  'bulk' : 'bulk'  $T_z$ ,  $N^2$
- $ightharpoonup \gamma$  'linefit' : 'line'  $T_z$ , ''line-fit'  $N^2$


#### TIWE - Overview

- ▶ Looked at TIWE 1st. because there were some previous patch analayis and gamma estimates (Bill, Jim).
- ▶ Not sure why  $\chi$  isn't full-depth for 1st part of experiment
- Use profiles from yday 324-327




# TIWE binned $\gamma$

▶ Binned  $\gamma$  smaller than 0.2, has median of xx...



# TIWE patch $\gamma$

- ▶ Patch estimates of  $\gamma$  are all equal or greater than 0.2
- 'bin' and ''line-fit' are centered close to 0.1 . 'line' and 'bulk' are centered greater than 0.2




#### Results table

Table: Statistics for patches using various parameters.  $\gamma$  values are medians for each distribution. Only patches between 60-200m and on yday 324-327 are considered for all.

minOT	usetemp	minR2	$\gamma$ bin	$\gamma$ line	$\gamma$ fit	$\gamma$ bulk	Npatches
0.4	1	0	0.13	0.57	0.11	0.53	16329
0.4	1	0.5	0.14	0.22	0.12	0.21	3761
0.75	1	0	0.15	0.62	0.14	0.59	9175
0.75	1	0.5	0.15	0.25	0.16	0.26	2358
1	1	0	0.16	0.71	0.15	0.68	6893
1	1	0.5	0.16	0.29	0.17	0.29	1779

#### EQ14 binned





▶ Binned  $\gamma$  smaller than 0.2, has median of xx...

Figure:  $\gamma$  estimated from 1m binned

# EQ14 patch $\gamma$

- Patch estimates of γ vary depending on method used.
- bin and line-fit are smaller than 0.2. line and bulk are centered near 0.2.






#### **EQ14**

Table: Statistics for patches using various parameters.  $\gamma$  values are medians for each distribution. Only patches between 60-200m are considered.

minOT	usetemp	minR2	$\gamma$ bin	$\gamma$ line	$\gamma$ fit	$\gamma$ bulk	Npatches
0.4	1	0	0.03	0.15	0.02	0.13	9326
0.4	1	0.5	0.03	0.09	0.02	0.08	1301
0.75	1	0	0.05	0.13	0.02	0.12	4075
0.75	1	0.5	0.05	0.08	0.03	0.08	520
1	1	0	0.06	0.12	0.02	0.12	2829
1	1	0.5	0.05	0.08	0.04	0.08	387






Figure: Ratio of  $\chi$  pod estimated  $\epsilon$  to Chameleon  $\epsilon$  for patches.

# Summary

- $ightharpoonup \gamma$  sensitive to many choices of parameters/methods. Difficult to tell if  $\gamma$  actually changes.
- In general, it seems that using 1m binned data tends to give  $\gamma$  smaller than 0.2, while using patches gives something closer to 0.2 .
- ▶ Suggests we should be using some kind of patch values in CTD  $\chi$ pod calculations (since a constant  $\gamma = 0.2$  is assumed).
- ▶ Applying  $\chi$ pod method to patches from EQ14 Chameleon profiles improves magnitude of  $\epsilon$  estimates, but dependence on actual  $\epsilon$  may be off.