
# Operating System Fundamentals



# Robert Power & Robert Ford

Operating System Fundamentals Robert Power & Robert Ford

School of Information Technology College of the North Atlantic-Qatar © 2009

# **Table of Contents**

Introduction	5
Unit 1: Computer Architecture Review	
Why Review Computer Architecture? A Map of Your Computer's Architecture The CPU Memory Talking to Devices Unit Summary Key Terms Review Questions	6 7 10 11 12 13 13
Unit 2: Operating System Principles	
What is an Operating System? Examples of Operating Systems The Structure of Operating Systems Interfacing with an Operating System Managing System Resources Unit Summary Key Terms Review Questions	14 14 15 19 20 23 23 24
Unit 3: Processes	
Processes and Multitasking Process State Changing Process Creation Stopping a Process Threads Inter Process Communication Process Scheduling Algorithms Unit Summary Key Terms Review Questions	25 28 32 34 35 37 47 53 53
Unit 4: Memory Management	
What is Memory Management? The Memory Manager Virtual Memory Unit Summary Key Terms Review Questions	55 55 58 62 63 63

# Unit 5: Input/Output

What are Input/Output Resources? I/O Resources I/O Management Software Managing Magnetic Disks System Clocks Unit Summary Key Terms	64 65 68 70 74 74
Review Questions	76
Unit 6: File Systems	
Managing Files Long Term Storage of Information The File Manager Data Storage Strategies File Systems The Master Boot Record and Partition Table Interacting with File Systems Unit Summary Key Terms Review Questions	77 77 78 78 81 82 83 85 86
Classacia	00
Glossary	88
References	102

# Introduction

This textbook is designed to give you an overview of what an operating system is, and how a modern operating system works. There are many different examples of operating systems available for computers. The most popular operating systems belong to the Microsoft Windows family (such as Windows 98, XP and Vista). Other examples are Unix and Linux, Mac OS X, and specialized operating systems for handheld devices like mobile phones.



An operating system is the software that controls (or operates) all of the parts of your computer. It manages all of your resources, and lets you interface with the computer. This textbook takes a look at the main problems that an operating system must be able to overcome, and the main functions that it must be able to perform. We begin by reviewing the architecture (or structure) of the physical parts of a computer, and how they communicate with each other. Then we take a look at fundamental operating system concepts, processes and management, memory management, controlling input and output devices, and file system management.

# **Unit 1: Computer Architecture Review**

# Why Review Computer Architecture?

This textbook focuses on how operating systems work. *Operating systems* (or *system software*) are one of the two main types of software (the other is *application software*). However, we need to know some important things about the hardware inside of a computer in order to understand some of the critical functions of any operating system.

Computer architecture refers to the overall design of the physical parts of the computer. That is, it refers to:

- what the main parts are;
- how they are physically connected to each other; and
- how they work together;


Although all of the parts of a computer are connected to each other by the *motherboard*, the operating system is essential in order to control how those parts talk to each other. Without the operating system, the parts of the computer would not be able to do anything that the user needs them to do! We need to know some basics about how the main parts of a computer are physically connected to each other before we can truly understand what an operating system does.



A motherboard

In this chapter we will look at a general map of a computer's architecture, showing the physical structure that allows all of the parts to exchange information and instructions. We will also take a brief look at some of the major components of a computer that an operating system must be concerned with, including the CPU, memory and how devices actually talk to each other.

# A Map of Your Computer's Architecture



Lines (traces) on a motherboard are like roads in a city

You can think of the *motherboard* as a big city, and all of the parts of the computer as buildings throughout the city. Of course, there are roads to get between all of the buildings. These roads are those little metal lines (called *traces*) running all over the motherboard. These traces are part of what is called the *system bus*. There are several different busses on the motherboard, depending upon which devices they are connecting.

Some of the major components of your computer's architecture (the main buildings) that are controlled by the operating system include:

#### **CPU - Central Processing Unit**

• This is the brain of your computer. It performs all of the calculations.

#### **RAM – Random Access Memory**

- This is your system memory.
- This is like a desk, or a workspace, where your computer temporarily stores all of the information (data) and instructions (software or program code) that it is currently using.
- Most computers today have between 1 to 4 Gigabytes (GB) of RAM.

#### **Graphics**

- Many computers have a dedicated system bus and expansion card slot just for a video card.
- Many video cards include their own memory so that you do not need to use up all of the RAM to run your monitor.

#### I/O Busses

- Special busses (roads) connecting all of your input/output devices to your motherboard.
- The three main types of I/O busses are ISA, PCI and USB.
- ISA Industry Standard Architecture
  - o This was the industry standard in the 1980s and early 1990s.
  - o It is now used to provide support for older and slower devices.
  - Common devices connected to the ISA bus might include an older modem, a joystick, a mouse, or a printer (using the older, wide-style printer port).
- PCI Peripheral Component Interconnect
  - This is for newer and faster devices than ISA.
  - You can think of this like a wider road, with a faster speed limit!
  - Some common devices connected to the PCI bus include your network card, EIDE devices (hard disk, CD/DVD drive, etc).
- USB Universal Serial Bus
  - o Many new devices can connect to your computer using a USB port.
  - o Examples include webcams, MP3 players, printers, PDAs, etc.

Figure 1.1 (below) is a diagram of the architecture of these main components (how they are all connected)




Figure 1.1
Diagram of system bus architecture

# **Busses and Bridges**

In Figure 1.1 we see that the major components are all connected by different busses. The Front Side Bus provides the main connection between the CPU, RAM, the graphics card (AGP - Accelerated Graphics Port), and the Northern and Southern Bridges. The Front Side Bus looks wider than the I/O busses because it is wider and faster. It contains more wires (traces) for the transmission of data between the devices. In the comparison to a city, the Front Side Bus is like a major freeway with a fast speed limit. The smaller I/O busses are like smaller side streets. Some of the I/O busses are narrower and slower than others.

The two bridges in Figure 1.1 perform the same function inside your computer that would be performed by bridges or roundabouts in a city. They are major intersections where data from

different devices cross paths. Of course, like any bridge or roundabout, there needs to be traffic laws to govern who goes first. If there were no rules (and no police to enforce the rules) then everyone would crash together. In computer terms, your data would become corrupted, and no information would ever reach its destination.

Figure 1.2 (below) compares the system bus architecture to a series of city streets with roundabouts:




Figure 1.2
A different view of system bus architecture

# The Central Processing Unit (CPU)

The *CPU* is the brain of your computer. It performs all of the calculations. Of course, in order to do its job, the CPU needs commands to perform, and data to work with. These instructions and data travel to and from the CPU on the system bus. The operating system provides rules for how that information gets back and forth, and how it will be used by the CPU.



#### **Inside the CPU**

Inside the CPU there are many important parts:




Figure 1.3
The parts inside a typical CPU

- The *Arithmetic Logic Unit* (*ALU*), which performs the calculations
- The Control Unit, which controls the flow of data inside the CPU
- The Interface Unit, or the I/O Unit, which acts like a gate for information entering and leaving the CPU
- Registers, which temporarily hold data and instructions waiting to be used
- The Program Counter (PC Register), which is a special register holding the address of the next instruction the CPU needs from the RAM

# The Fetch—Decode—Execute Cycle

The CPU finds, interprets, and executes program code using a specific cycle, as follows:

- 1. The CPU looks in the PC register for the location of the next program instruction.
- 2. The CPU retrieves the next instruction from RAM, and places it in a register.
- 3. The CPU changes the PC register with the address in RAM for the next instruction.
- 4. The CPU performs the first instruction, and repeats the cycle until the power is lost.




Figure 1.4
The Fetch—Decode—Execute Cycle

# Memory

Memory is stored on Radom Access Memory (RAM) chips. A typical computer today has between 1 Gigabyte (GB) and 4 GB of RAM.

#### Memory is used to:

- Store data
- Store commands (instructions)
- Store system settings




Figure 1.5
Address structure of RAM



Each RAM chip contains millions of address spaces. Each address space is the same size, and has its own unique identifying number (address). The operating system provides the rules for using these memory spaces, and controls storage and retrieval of information from RAM.

#### Fast fact – RAM is a device!

Without an operating system, a computer would not be able to use RAM chips. This is because your computer treats the RAM chips like a device that has been installed (just like a webcam, or a printer). When your computer first starts up, it can only use a small amount of RAM memory (1 Megabyte (MB)) that is built into the motherboard. Device drivers for RAM chips are included with the operating system, and must be loaded as part of the boot process in order for the RAM to work!

**Problem:** If RAM needs an operating system to work, and an operating system needs RAM in order to work, how does your computer activate its RAM to load the operating system?

# Talking to Devices

Devices talk to each other and to the CPU. They need to communicate in order to share information, and in order to be told what to do! There are two types of devices that are controlled by information from the CPU:

- Programmed devices, and
- Interrupt-driven devices

#### **Programmed Input/Output Devices**

Programmed I/O devices need to be completely controlled by the CPU. That means the CPU must stop whatever task it is doing, and focus on the device until it has finished whatever it has been told to do. This wastes a lot of processing time!

#### **Interrupt-Driven Devices**



A more efficient way to control devices is by using an *interrupt controller*. The interrupt controlled keeps track of whichever devices need to talk to the CPU, and gives different priority to different devices. For example, the keyboard gets higher priority than a modem. When a device needs new instructions, or when it has finished a task, the interrupt controller issues an interrupt to the CPU (like raising your hand in class). The CPU stops whatever it is doing long enough to talk to the device. Although this is more difficult to program, it results in better computer performance.

Of course, the operating system provides all of the rules for communicating with both programmed and *interrupt-driven devices*.

# **Direct Memory Access**

Sometimes devices may want to talk to each other without 'going through' the CPU. The *DMA Controller* controls access to the system bus, and RAM, and bypasses the CPU. The CPU does not need to get involved in the process, other than to set up the transfer. The CPU will get an interrupt when the transfer is complete.

Direct Memory Access is like adding police officers to a roundabout who will let traffic go through to other streets when the road is clear.




Figure 1.6

DMA is like an extra police office who guides cars through a busy intersection without bothering anyone back at the police station first

# **Unit Summary**

A computer is a system of devices that are all connected together, just like buildings throughout a city. All of these devices are connected through the motherboard. A system of wires, called traces, provides a means for information to be exchanged between all of the devices. These wires are called busses, and they are like the roads throughout a city. Just like in a city, there must be traffic laws and police officers to enforce the flow of traffic, or it will all crash together and become useless. The rules for data transfer, and the control of devices installed in a computer, are provided and enforced by the operating system.

# **Key Terms**

Address

AGP

ALU

Application software

**Busses** 

Computer architecture

Control Unit (CU)

CPU DMA

DMA Controller

Fetch—Decode—Execute cycle

Front Side Bus

Graphics I/O Busses

**Instructions** 

Interface (I/O) Unit

Interrupt

Interrupt Controller

Interrupt-driven I/O devices

ISA Memory Motherboard Northern Bridge

PCI

**Program Counter** 

Operating System

Programmed I/O devices

RAM Registers

Southern Bridge

System bus

Traces USB

# **Review Questions**

- 1. Describe the difference between pre-emptive multitasking and cooperative multitasking.
- 2. What are registers?
- 3. List and briefly describe any three busses that are used to transport data.
- 4. Briefly describe the Fetch—Decode—Execute cycle.
- 5. Describe the difference between programmed I/O devices and interrupt-driven I/O devices.
- 6. What is the benefit of DMA?

# **Unit 2: Operating System Fundamentals**

# What is an Operating System?

You need two types of software in order to use your computer (or any other computerized device). These are *applications* and *system software*. Applications are the programs you use to do tasks, such as write a document, surf the web, or play games. System software runs the computer system for you. Another name for system software is an operating system. There are many different operating systems, but they all have a similar architecture (or structure). That is because they must all overcome the same problems and perform the same basic functions. An operating system must be able to:

- Manage system resources
  - CPU scheduling
  - o Process management
  - Memory management
  - Input/Output device management
  - Storage device management (hard disks, CD/DVD drives, etc)
  - File System Management
- Simplify the development and use of applications

# **Examples of Operating Systems**

A number of operating systems are available for personal computers. The most popular is Microsoft Windows, which is the operating system used on over ninety percent of the world's personal computer systems. Another popular operating system is *Mac OS X*, which is the operating system used for Apple Macintosh computers (like the Mac Book Pro laptop series). While IMB PCs (mostly Windows) and Mac computers are not directly compatible, it is possible to use virtualization to run one operating system on an incompatible computer.

Another group of widely used operating systems is based on *UNIX*. UNIX was a command line interface operating system developed for large scale computers and networks in the 1960s. The latest generation of operating systems derived from UNIX is called *Linux*. It is a free, open-source operating system that is supported by most computer platforms.



# **Special Purpose Operating Systems**

Operating systems are not limited to just personal computers. Most electronic devices today use an operating system to manage their physical components and to make it easier to develop applications for use on the devices. Examples include the *Symbian*, *Blackberry*, *Palm* and *Windows Mobile* operating systems used for personal digital assistants (*PDA*s) and mobile phones. *Specialized operating systems* have even been developed to control computerized aircraft systems (*VxWorks*, *pSOS* and *QNX* are examples).

# The Structure of Operating Systems

#### Layers

Accessing computer resources is divided into *layers*. The user represents one layer at one end of the system. Your computer's hardware represents the layer at the opposite end of the system. In order to use your hardware to do anything with the computer, you need software. Software forms the layers in between the user and the hardware and is divided up into application software and the operating system. The operating system must be able to manage resources from both the applications and hardware layers.

In the computer layer system the user interacts directly with software applications. The applications interact with both the user and the operating system. The operating system interacts with the applications and controls the hardware.

Each layer is isolated and only interacts directly with the layer below or above it. If you make changes to any one layer, they only directly affect the layer next to it. For example, if you install a new hardware device you do not need to change anything about the user or applications. However, you do need to make changes to the operating system. You need to install the device drivers that the operating system will use to control the new device. If you install a new software application you do not need to make any changes to your hardware. But you do need to make sure the application is supported by the operating system and the user will need to learn how to use the new application. If you change the operating system you need to make sure that both your applications and your hardware will work with the new operating system.




Figure 2.1
Layers in a computer system

# **Running Multiple Operating Systems**

It is possible to install more than one operating system on a computer. You can do this by partitioning your hard disk(s) and installing different operating systems on different *partitions*. This can be very useful, because you may want to use different operating systems to perform different tasks. For example, you may have specialized applications that will only work with one operating system, making them incompatible with the rest of your software. When you turn your computer on, you are given a choice of which You can only run one operating system to use. operating system at a time. Figure 2.2 (right) shows the system of layers when multiple operating systems are installed on the same computer.




Figure 2.2
Layers in a computer with multiple partitions and operating systems




Figure 2.3
Layers with a virtual operating system

# **Running a Virtual Operating System**

What happens if you want to work on applications in two operating systems at the same time? What about if you want to run an operating system that is not compatible with your computer's hardware? (For example, you cannot install the Mac OS X operating system on an IBM compatible PC). You can get around these problems by running a virtual computer.

A virtual computer is really an application within one operating system that lets you pretend you have a different operating system installed. Virtual computer applications like VMWare and Virtual PC act as translators. They convert instructions from the virtual operating system into instructions from the real operating system, which then controls your computer's hardware.

Figure 2.3 (left) shows the structure of layers when you run a virtual operating system within a Windows operating system. As far as Windows is concerned, it is simply running another application. Notice that the layers between the virtual computer application and the user are just like the layers for a single operating system (Figure 2.1).

# **Operating System Modes**

A typical operating system has two *modes* of operation. These are like layers of operation within the operating system layer (Figure 2.1). The *User Mode* is concerned with the actual interface between the user and the system. It controls things like running applications and accessing files. The *Kernel Mode* is concerned with everything running in the background. It controls things like accessing system resources, controlling hardware functions and processing program instructions. The *Kernel* forms the core of the operating system, and it acts like a supervisor for everything that is happening in the computer. In the *client-server model* of an operating system, the User Mode is considered a client. That is, the User Mode accesses resources provided by the Kernel (the server). Figure 2.4 (below) shows what operating system functions are controlled by the User Mode and Kernel Mode.




Figure 2.4

Typical structure in the Client (User Mode) – Server (Kernel Mode) model of an operating system

# **Starting an Operating System**

Most personal computers have similar architecture and can use a variety of different operating systems. When a computer is first made, there is no operating system installed. Even after you have an operating system installed, you can remove it and install a different one. As we discussed earlier, you can even have multiple operating systems installed on the same personal computer. This raises the question—how does your computer start the operating system? If you have more than one operating system installed, how does your computer choose which operating system to use?

Your computer is designed to start in stages. In the first stage, you turn on the power supply to your computer. This sends electricity to the motherboard on a wire called the 'Voltage Good' line. If the power supply is good, then the BIOS (Basic Input/Output System) chip takes over. At this stage the computer's CPU is operating in Real Mode (or real address mode), which means that it is only capable of using approximately 1 MB of memory built into the motherboard. RAM will be initialized later using device drivers from the operating system.

The BIOS chip contains basic instructions for starting up the rest of the computer system. The first thing that it will do is a *Power-On Self Test (POST)*, which will check to make sure all your

hardware is working properly. If the hardware is all working, BIOS will then look for a small sector at the very beginning of your primary hard disk called the *Master Boot Record* (MBR). The MBR contains a list, or map, of all of the partitions on your computer's hard disk (or disks). After the MBR is found the *Bootstrap Loader* follows basic instructions for starting up the rest of the computer, including the operating system. If multiple operating systems are installed, the user will be given a choice of which operating system to use.

#### Remember - RAM is a device!

In the first unit we said that without an operating system a computer would not be able to use RAM chips. Your computer treats RAM chips like a device that has been installed. When your computer first starts up, it can only use a small amount of RAM memory (1 MB) that is built into the motherboard. Device drivers for RAM chips are included with the operating system, and must be loaded as part of the boot process in order for the RAM to work!

**Problem:** If RAM needs an operating system to work, and an operating system needs RAM in order to work, how does your computer activate its RAM to load the operating system?

**Solution:** Device drivers for RAM are loaded during the Early Kernel Initialization stage.

The next stage is called *Early Kernel Initialization*. Remember that the Kernel is the core of the operating system, and it regulates all of the background functions of your computer. In the Early Kernel Initialization stage, a smaller core of the Kernel is activated. This core includes the device drivers needed to use your computer's RAM chips. Without the extra memory provided by RAM, it is not possible to run the more complicated code for the remainder of the operating system.

Once the Early Kernel Initialization is complete, the CPU switches to *Protected Mode*. The computer can now take advantage of the extended memory address system provided by RAM, and the operating system's Kernel is fully initialized. Only at this stage are the first User Mode processes initialized, and the user can begin interacting with the operating system, applications and hardware. Figure 2.5 (below) shows the stages in starting an operating system.




Figure 2.5
Stages in the startup of an operating system

# Interfacing with an Operating System

#### **Types of User Interfaces**

An operating system operates the functions of a computer. It also provides a way for users to interface with, or access, a computer's applications, resources and hardware. There are two main types of user interfaces for an operating system:

- Command Line Interface
- Graphical User Interface (GUI)

A command line interface uses typed commands to issue instructions to the computer. It can be more difficult to use because the user must type the precise commands and locations of files. DOS (Disk Operating System) and UNIX are examples of command line interface operating systems.

A *GUI* uses graphics (or pictures) and menus to help the user access resources and issue commands. Windows XP, Linux and Mac OS X are examples of GUI operating systems.





Figure 2.6
Examples of a command line and GUI interface

# The Command Line Interpreter

Applications are accessed at the User Mode level. This means that they do not have the authority to directly access system resources that are controlled at the Kernel Mode level. When a user types a command (in a command line interface) or performs a task within an application (using a GUI), *processes* are initiated. Since those processes usually require access to system resources, the command line interpreter converts them into system actions (called *system calls*). Most interpreters execute applications to perform the system calls.

# Managing System Resources

An operating system needs to manage a wide range of system resources. Some of the main resources controlled by the operating system include CPU scheduling and process management, memory (RAM), access to peripheral devices and file system management.

#### **CPU Scheduling**

Memory is like a workspace for the information and program instructions that are being used by the computer. The Central Processing Unit (CPU) is the component that actually does the work. The CPU performs all of the program instructions, sends commands to devices, and receives information back from those devices. Just like memory, something needs to regulate which devices and applications get to use the CPU, and for how long. This task is handled by the operating system.

Most modern CPUs and operating systems can handle *multitasking* and *multithreading*. That is, they can run more than one application at a time and they can process threads from more than one device and application at a time. However, the CPU has limited resources. It needs a schedule of processes to carry out, or nothing will run properly.

In older operating systems, it was up to each application to determine how long it needed to use the CPU and what priority it should be given over other applications or interrupts from devices. was called *cooperative multitasking*. Unfortunately, this system was rather like having roads with no traffic laws or police officers. If someone wanted to take complete control and cut off all other traffic, it possible. Newer operating systems use preemptive multitasking. That is, the operating system sets out the rules for the use of the CPU and enforces those rules. Preemptive multitasking means that the operating system shares the CPU between everything that needs its attention. It also gives priority to certain devices and applications based on how critical they are to keeping the whole system functioning.

# Applications Word Internet Explorer Microsoft Outlook Adobe Acrobat

Figure 2.7
An operating system shares the CPU between applications




Figure 2.8
The Windows XP Task Manager showing processes from the process table

#### The Process Table

As previously discussed, processes need to share the Sometimes the CPU does not complete an CPU. entire process before the operating system tells it to start working on another one. This system of sharing is what makes multitasking possible. Keeping track of all of the processes is done with the Process Table. The Process Table lists all of the processes that are currently being run, those that are waiting to be executed and those that have been temporarily suspended. It also keeps track of the current status, or state, of each process. This allows the CPU to restart those processes again when they are needed. Figure 2.8 (right) shows processes from the Windows XP process table, as displayed in the Task Manager. We will take a closer look at processes and process management in Unit 3.

# **Memory Management**

Memory is used by a computer to temporarily hold data and instructions that are being used by applications, the operating system and hardware devices. Since a typical computer has between 1 and 4 GB of memory (RAM), and since modern operating systems can run many devices and applications at the same time, there is a lot of memory to keep track of. As we noted in the previous chapter, RAM is divided up into small spaces (usually 32 bits). Each space has its own address. An operating system must be able to keep track of all of those memory addresses and how they are currently being used. The operating system typically performs three major functions with respect to memory management:

- 1. Gives memory to each application and device as needed;
- 2. Protects applications (and their data) from each other;
- 3. Protects the system from 'bad' applications (that might try to use too much memory, or corrupt data from other applications);

We will take a more detailed look at how operating systems manage memory in Unit 4.




Figure 2.9
An operating system shares memory between applications

#### **Peripherals**

Peripheral devices are hardware devices that are connected to the computer by connection ports on the motherboard. Examples include the monitor, keyboard, mouse, webcam and printer. Peripheral devices are difficult to program and manage. Although many different applications need to use peripheral devices, the task of accessing them is simplified by the operating system. Applications do not directly access peripheral devices. These devices are programmed and controlled using *device drivers* provided by the operating system. When an application needs to use a device it talks to the device drivers. The device drivers then tell the device what to do.



When a new device is installed, the operating system looks for built in device drivers or adds new drivers to control the device. Most newer operating systems and devices are Plug and Play compatible, which means that the operating system will handle everything related to installing the new device and its drivers without any action from the user (other than confirming installation options).

We'll take a closer look at Input/Output management in Unit 5

#### **File System**

Your computer contains more than just your hardware resources. It also contains all of the information that you use and manipulate. This information is stored on your hard disk, CD/DVD discs, and removable storage devices. Your operating system controls the actual physical operation of these storage devices. It also helps you to manage the files stored on these devices.

Different operating systems use different file systems to encode and organize your information. For example, older versions of Windows used either *FAT16* or *FAT32* (FAT stands for File Allocation Table). These older file systems limited the amount of information you could store on a hard disk, so newer versions of Windows (XP, Vista, and




Figure 2.10
Windows Explorer is a tool for viewing and navigating your computer's file system

Windows 7) use NTFS (New Technology File System). NTFS lets you store up to 2 Terabytes (TB) of information on a single volume and provides greater file security than the older FAT file systems. Other operating systems use different file systems such as EXT3 for Linux, or HFS+ for Mac OS X.

Regardless of which file system an operating system uses, the operating system must perform certain key file management tasks for the user:

- Manage the storage and retrieval of information; and
- Provide a common, easy to navigate system for viewing and accessing storage devices and the information stored on them.

We'll take a closer look at file system management in Unit 6

# **Unit Summary**

Computerized devices need an operating system to control the actual functioning of the device. Whether the device is a personal computer, mobile phone, or computerized aircraft controls, an operating system must provide some way for the user to interface with the device. Modern operating systems use a graphical user interface approach to simplify access to applications and hardware resources. Operating systems act as one layer in the functioning of a device. Other layers include the hardware, applications and the user. It is possible to install more than one operating system on a computer, which creates multiple sets of layers (however, only one of these sets of identical layers can operate at any given time). It is also possible to use virtualization to simulate the use of two different operating systems at the same time. Regardless of which operating system is being used, there are similar tasks that the operating system must perform. The primary tasks performed by the operating system include the management of CPU scheduling and tracking processes, memory management, management of Input/Output systems and file system management.

# Key Terms

Applications BIOS

Blackberry OS Bootstrap loader Client-server model

Command Line Interface Command Line Interpreter Cooperative multitasking

Device drivers

DOS

Early Kernel Initialization

EXT3 FAT 16 FAT 32 File system

Full Kernel Initialization Graphical User Interface HFS+

Kernel mode

Layers Linux

Master Boot Record (MBR)

Max OS X Mode Multitasking

Multithreading

**NTFS** 

Operating system

Palm OS Partition PDA

Preemptive multitasking

Process

Process state

Process Table
Protected mode

pSOS QNX

Real mode

Special purpose operating

system
Symbian
System call
System software

UNIX
User mode
Virtual computer
Virtualization
Voltage good line

VxWorks

Windows Mobile

# **Review Questions**

- 1. Describe two tasks that are performed by an operating system.
- 2. Describe the four layers of interaction in an operating system model.
- 3. Briefly describe how you can install multiple operating systems on the same computer.
- 4. Draw a diagram to demonstrate how virtualization can be used to run multiple operating systems at the same time.
- 5. Briefly describe the client-server model of an operating system.
- 6. Draw a simple diagram to show the two modes of operations of an OS.
- 7. Briefly describe the function of the Command Line Interpreter.
- 8. What are the major differences between System Calls and Interrupts?
- 9. Describe the purpose of the Process Table.

# **Unit 3: Processes**

# Processes and Multitasking

Many people like to try to speed up several tasks by performing them at the same time, such as using a mobile phone while driving. While this seems like you are accomplishing two things at the same time, the truth is that your brain specifically focuses on just a single task at any specific time. The act of talking only occurs while you are not actively making decisions about the task of driving. To put this into perspective, if you know you are about to have an accident, you will stop talking.

To further illustrate the idea of performing simultaneous actions consider the problem of reading a text message while watching TV. Your eyes can only look at one device at a time. You must switch back and forth between the two devices, or look at the mobile phone only while unimportant things are happening on the TV.

A CPU inside a computer is simply a high speed calculator that can perform relatively simple operations on a set of data. If we ignore for the moment the idea of *dual* and *quad core CPUs*, the CPU can only process a single instruction at any given time from a program. If we would like to have more than one program executing on the processor at the same time, the programs will need to take turns using the CPU. Since the computer switches back and forth between the two programs often enough, then it will look like both applications are running at the same time.

This unit takes a detailed look at the definitions of *processes* and *threads*, and how the operating system manages processes and threads in *multitasking* environments. The first section deals with the definition of a process, and the concept of *process states*. We then take a look at *state changing*, process creation and stopping processes. From there, we compare processes to threads, and take a look at why threads are important. This is followed with a detailed look at *inter process* (and *inter thread*) *communication*, including process synchronization, memory sharing, the use of *signals* (or *semaphores*), *critical sections*, and the use of *message queues*. We conclude by looking at how an operating system actually handles *process scheduling*. This will include topics like completion scheduling, *round robin scheduling*, *priority-based scheduling*, and scheduling in multi-core/multi-processor environments.

#### Process

#### **Definition**

In order to manage individual applications (or what we often refer to as programs) most operating systems use the term *process*. An application or program is a set of instructions. A process is the actual execution of those instructions, along with the memory and I/O devices assigned to execute the given instructions.

#### **State Machines**

Without the need to switch from one process to the next, the creation of an operating system is significantly reduced. In fact, many embedded systems that have no multi-tasking often do not include an operating system for cost reasons.

If we consider the act of attempting to read a text message while we are driving, we know that the driver will only take their eyes off the road when the traffic appears to be under control. The driver will then quickly look at some of the text on the mobile phone and then return to looking at the road. This process will continue as long as there are text messages to be read or places to drive to.

If we draw a small diagram showing these two actions we have something like this:




Figure 3.1 Example of a simple state machine

This diagram shows that we start off by watching the road and when we feel that the road conditions look okay (no cars or pedestrians) we then look at the mobile phone. We then read the message on the mobile phone until one of two things occurs:

- 1. We hear something that needs our attention such as some screeching tire or we notice something in our peripheral vision.
- 2. We have been looking at the mobile phone for some time and realize that we should probably see if we are about to hit something.

Figure 3.1 (above) is used in many computer design documents and is called a *state machine*. The circles represent the state of the machine and the arrows represent actions that cause us to change from one state to another. In the case of our texting driver, there are two states: looking at the road, or looking at the mobile. Although it may be possible to hold the phone in such a way that the peripheral vision encounters most of the road, it remains a fact that you cannot actually look at both the phone and the road at the same time. Regardless of the opinion of texting while driving, a single core CPU can only perform one instruction at a time which is the whole reason for describing this analogy. The important thing to take away from this analogy is that some things in life are modeled really well by state machines and that events can cause some resources to change from one state to the next.

#### **Computer Process**

We now return to the world of computers and processes again. The fact that a single-core CPU can only process one instruction stream at a time means that two applications must take turns running on the CPU. Although a rather obvious statement, if we consider just one single process we realize that it must be either running or is must not be running. This sounds suspiciously like a set of states. In addition to two states, the next question that should be asked is how does a process go from 'not-running' to the 'running' state?

We will call the 'not-running' state the 'Ready' state because it indicates that the process would like to run but currently cannot (suggests that some other process is actually running). We will also introduce two new terms:

- *Dispatch* means that the operating system has decided that the process should start running now.
- Interrupt means that the operating system has decided that the process should now stop running so that another process can have a turn.

Putting all of this information into a single state diagram produces this version.




Figure 3.2
A computer-based simple state machine

Many operating system students see diagrams such as this and easily understand the concept, but many textbooks fail to remind the students that there are in fact probably several processes (each with their own state machine) going at the same time.

The operating system would normally keep a list of all processes current loaded in a table known simply as the *process table*. The process table would need to keep the current state value. So if an operating system were running four programs (Word, Internet Explorer, Excel, and Visio) the table might look like this:

Process ID	Name	State
4	Word.exe	Running
6	IExplorer.exe	Ready
7	Excel.exe	Ready
8	Visio.exe	Ready

Figure 3.3 A sample process table

At no time would it be possible to have two processes both with the state 'Running' as we are assuming for now that the CPU has only a single core.

#### **Processor Preservation**

An important concept in operating system design is the ability to hide multi-tasking concepts from the applications so that they do not know that other applications are running at the same time and sharing the CPU.

The registers in the CPU become a resource that is shared by every process on the operating system, including the operating system itself. Keeping these values correct is critical to making an operating system that functions correctly. As an example if one application performs the instruction "mov \$50, "eax" it means that the program expects the value 50 to be placed into the EAX register. If this instruction were executed then another process ran that put the value 0 into the EAX register, the old value of 50 needs to be replaced before the first process runs again.

Each process on the system requires a place where the registers can be stored while the process is not running. The operating system can either put this information directly into the process table or it can store the information somewhere else but keep a pointer to the information in the process table.

# State Changing

Changing the state of a process from one state to another is usually the responsibility of the operating system. The actual switch could occur because the process has informed the operating system that it is finished, or the operating system could determine that the process has simply used too much time and it is another process' turn to run.

Of course, the operating system itself is software that must run on the CPU along with the applications. So how does the application actually become active so that it can stop Word in the example above? Many hardware platforms include a clock that periodically fires interrupts and the operating system has likely attached a function called a *scheduler* to the *interrupt* so that every so many milliseconds (a typical number is 10 ms) the operating system scheduler gets executed.

When the scheduler is called (by the interrupt) the scheduler code can manipulate the process table and set the state of the processes involved and then allow the new process to take over.

As an example suppose that the process table looks like the example above with the four processes and Word.exe executing. Here is the order in which things happen.

- 1. The word process is executing normally using the CPU registers as it requires.
- 2. The clock triggers an interrupt.
- 3. The interrupt service routine attached to the clock runs the OS scheduler.
- 4. The scheduler searches the process table for the process in the Running state.
- 5. The scheduler changes the state of the running process to "ready".
- 6. The scheduler copies all of the current value of the registers into the process table (or information block)
- 7. The scheduler looks in the table to find the next process to run. The topic of selecting a process to run is covered in the next chapter but for here let's assume that iexplorer is about to run.
- 8. The scheduler marks iexplorer as "Running"
- 9. The scheduler copies all of the registers for iexplorer into the CPU from the process table.
- 10. The scheduler then jumps to the next instruction that iexplorer should perform.

# **Preemptive and Non-preemptive Switching**

The steps above describe a type of *process switching* known as *preemptive switching*. The operating system always has control of the computer by way of the interrupt service routine and will always be able to stop the currently executing process.

In a *non-preemptive* operating system, the operating system never interrupts the currently executing process but waits for the process to release control voluntarily. In such a system, the operating system is generally less complex. However, if a process does not wish to cooperate with the other processes on the computer then this could lead to other processes, including some operating system parts, never having a chance to execute.

The most recent popular non-preemptive operating system was Windows 3.1. In this operating system, a programmer who accidentally created certain types of infinite loops would often have to reboot their computer in order to stop their program. As a result, most operating systems today utilize preemptive process switching so that no single process can monopolize the computer.

# **Blocking**

Generally the CPU executes instructions very quickly and transferring data to and from RAM also takes place with very little delay. Unfortunately, if a process wishes to interact with some external device the CPU cannot do very much useful work.

As an example, suppose we have written a very simple program that does nothing until the user presses a key on the keyboard. The computer instructions may look something like this:

```
Main() {
    System.in.read(value);
}
```

When this process is started, there will be some instructions required to get the application ready, but eventually the instruction "wait for key" is reached. When the process reaches this instruction what does the operating system do with the process state? In our two state process model introduced earlier (see Figure 3.2), leaving the process as 'Running' is probably not a good idea because it really is not doing anything. Moving the process to the 'Ready' state does not help either because the process is not actually ready to run. It needs to wait for the user to do something.

We solve this problem by the introduction of a third state that we will call '*Blocked*'. This state tells the operating system that the process is currently waiting for something, and therefore it should never be considered by the scheduler when a new process is being selected for running. The term blocked exists because the execution is being "blocked" by some external event. Some operating systems might use the term *wait*.




Figure 3.4
A state machine with a blocked state

In this model, a process can never become blocked unless it is actually running. Once a process has been put into the blocked state, it must eventually be *unblocked* or *released* and put back in to the 'Ready' state before it can run again.

How does the operating system manage these extra state changes? As mentioned in the earlier sections of the book, the operating system is responsible for managing all system resources including I/O devices. In the case of waiting for the user to press a key, the program actually issues a request to the operating system (through a function call) asking to wait for a key. In response, the operating system changes the state of the process to 'blocked' and runs the scheduler *algorithm* to find a new process to run.

How does the process get out of the blocked state? Each I/O device has its own mechanism that it uses to interact with the operating system. We will consider just the keyboard example here. During boot up, the operating system has probably attached a service routine to the keyboard interrupt. Each time that the user presses a key, it generates an interrupt which causes the operating system routine to generate a key event and the scheduler routine will be called. The scheduler will then look through all of the blocked processes waiting for key events and the state will be changed from blocked to ready. Whether this keyboard interrupt causes the currently running process to be moved from Running to Ready depends on the operating system itself. If you were to examine the states of processes on most computers, you will probably find that just about every process on the system is blocked most of the time.

Having a lot of blocked processes is a good thing. This means that the CPU is not actually being used for any useful work. Normally when a CPU does works it consumes power, while if it is not doing work it can be put into a low power state. Tricks such as these are used in mobile devices such as phones in order to extend the life of the battery. A process that is actively using the CPU will consume more power, which is why batteries do not last as long when you are watching videos on your mobile phone than when you are simply on stand-by waiting for calls.

# A Typical State Model

There are two additional states that most operating systems include in addition to the Ready, Running, and Blocked states. These two extra states are used for house keeping, and only exist for a short amount of time during the creation and the removal of processes.

When a new process is created there needs to be a new entry placed into the process table. Setting the process table entry actually takes a bit of time. If the new process was marked as 'Ready' and the operating system was in the middle of initializing the other columns in the process table, and suddenly a reschedule operating occurred, how would the operating system know that it should not select this new process? We control this by the introduction of a 'New' state. This is simply a place holder that is used by the operating system until the process is actually ready to start going.

Similarly there is an 'Exit' state that is used when a process is being cleaned up. This state is also temporary, and the operating system will mark the process first then remove it from the process table.




Figure 3.5
A typical state machine

#### **Switch Prevention**

There may be situations where a process is in the middle of doing something really important and it would like to ensure that no other process is allowed to run in the meantime. There are two mechanisms that are typically available: disabling the scheduler and disabling interrupts. By disabling the scheduler the process is requesting to the operating system that even if the timer fires, the process would like the operating system to skip the selection of a new process. In the case of disabling interrupts, the program is actually asking the CPU to ignore any interrupts that occur.

Both of these techniques have the ability to seriously hinder the functionality of the computer. As such, most operating systems will refuse to comply with such requests unless the programs doing the request have enough privileges. However, some parts of the operating system itself are very vulnerable to interruption and the operating system itself is allowed to prevent switching and even interrupts if required. How privileges are enforced is a topic for later discussion.

#### **Process Creation**

The actual creation of a new process on a computer is very specific to the operating system itself and is often tied very closely to the hardware. We will attempt to describe the creation of processes in a high level view.

Most operating systems utilize a process table to track all of the processes currently residing on the system. The creation of a new process will usually require a new entry to be created within the process table. During the addition of the new entry, the table needs to be locked or switching needs to be prevented so that the full details can be added without interruption. Marking the state as 'New' is only part of the problem. The table itself might have issues if the scheduler sees it partially updated.

In addition to the process table entry, most operating systems keep information about the process in a separate space called the "process information block" (although this can be viewed as part of the process table). The space for this process information block needs to be set aside as part of the process creation step.

Each process will be executing some code. Part of the process creation step will be to set aside enough memory for the code, and then possibly load the code from the executable (some operating systems work a little differently as explained next).

# **Process Creation in Unix/Linux**

In the Unix (and Linux) operating system, new processes are created by a simple system call named 'fork()'. The term fork comes from the description of hitting a fork-in-the-road, in other words a place where a decision has to be made. It is easily shown by this diagram.

Suppose a program has the following statements:

```
Statement_A();
Statement_B();
Statement_C();
Fork();
Statement_D();
Statement_E();
Statement_F();
```

If the fork() call was not included it is easy to see that the program simply executes the statements one at a time. However with the inclusion of the fork() command, things get a bit more interesting.




Figure 3.6
A program issuing the fork() command in Unix

When the system called is made at *fork()*, the operating system will actually duplicate the current process so that there are now two. This means that the original process will keep running statements D through F, but there will also be another process also running statement D through F.

When a Unix program issues the fork() system call, the operating system duplicates the current process exactly and once completed there are now two processes executing that look identical. However, they will be two distinct processes sharing the CPU. Any variables (memory) associated with one process will be different than the memory associated with the other process.

Who issues the fork command? Most applications that developers write would never use the fork system call unless they were trying to create a program that starts another program. In fact the fork() system call remains a mystery to most software developers, so if you never see it again outside of this text, that would be quite When you are working in the normal. GNOME desktop environment, you select applications from a launch menu. When you finally select OpenOffice Write, guess what happens? Yes, GNOME will issue a fork() system call.

If you are comfortable with the idea of the fork() system call, you should now ask the question: "If GNOME issues the fork() call, why then do we see OpenOffice Write instead

of another copy of GNOME?". As soon as the new process is created the second process will replace its current executable code with new code from the drive.

The source code for launching a new application then typically looks like this:

```
Main()
{
    While (true) {
        Display prompt on screen
        Wait for user to enter command (i.e. block!)
        If command is a shell command process the command (i.e. set, echo)
        Assume the command is a program, check if the program exists.
        Fork() a new process.
        If (we are original process) {
            Wait for new program to finish
        }
        Else { // we must be the new process
            Load the program and run it
        }
    }
}
```

# Stopping a Process

There are three typical ways that a process will terminate and release the memory back to the operating system:

- 1. The process can request the operating system to stop itself. This is actually accomplished when the "main" member function of most programming languages finishes. The programs that you write are actually linked with some library functions to look after making the system call for you. Generally an application will always have permission to terminate itself.
- 2. The process could generate an *unmanaged exception*. An exception is simply an error that has occurred that cannot be dealt with by the program. Examples of exceptions include division by zero and the process trying to perform an instruction that is not permitted by the operating system. You have likely seen the failure on Windows which states something like "This program has performed and illegal operation".
- 3. One process can request that another process be terminated. Most operating systems provide some form of security to prevent processes from terminating other processes unless the originating process has some sort of privilege. In Linux, the *kill* system is used to send a variety of messages including a message to terminate a target program.

#### **Threads**

Although on a CPU with a single core it is not possible to execute more than one instruction at the same time, there are often reasons why a programmer would prefer to structure a program in such a way that it is really programmed more like two or more separate programs. Take for example the program Outlook. We are all familiar that when using Outlook, you can be in the middle of creating a mail message and even while you are writing the message, a new mail messages can arrive causing Outlook to play a sound and show the arrival flag in the tool tray.

One way that the program could be organized is in the following pseudocode:

```
Forever(;;) {
     Wait for a single key
     Add the character to the message
     If there is a new message raise flag and play sound
}
```

The pseudocode above is valid but not really efficient. Notice that the algorithm only checks for new mail every time that a key is pressed. On the positive side, it is expected that the program will not be very intensive on the CPU because it will spend a great deal of time waiting for the keyboard.

In order to solve the problem of only checking after each key is pressed we could change the algorithm as follows:

```
Forever(;;) {
    Wait up to 1 second for a new key
    If a key was pressed add it to the message
    If there is new mail, raise the flag
}
```

This approach solves the problem of only checking for mail every time that the user is present, but it comes at an expense of efficiency. If a user starts to type a message and then leaves for several hours, the program will wake up every 1 second and see if there was a key pressed and check to see if there is mail. It would be more efficient to do neither if nothing is happening.

A second point about this solution is that as we add more features to our e-mail program, this main loop becomes more and more complex.

If we are able to organize the program into two tasks, each solving just one problem, then we could have the following:

```
While (!messageNotSent) {
     Wait for key
     Add character to message
}

Forever() {
     Sleep 10 seconds
     Check for mail
Raise flag if new mail
}
```

And

If both of these small algorithms can run at the same time within the same application then we have organized our program into a much easier to understand system, and in a way that adding more features can be easier.

Now that we have a model to help make the program easier to create, we need a mechanism by which a program can be organized. These two independent mini-programs have their own set of instructions that need to be executed on a single processor. This concept sounds very similar to multi-processing that was covered in the previous chapter, only in this case these mini-programs are actually part of a single large application.

In an operating system a single sequence of instructions being executed is called a *thread*. Every process will always contain at least one thread of execution unless it has been written in a special way such as what we have described for our e-mail program. In our application we have one thread whose task is to read the keyboard and compose the message, and another thread responsible for occasionally checking to see if there is new mail.

Because there are now two separate threads of execution, there will need to be the concept of *switching* and *scheduling* within our application. Luckily, a lot of operating systems look after this as part of their services, and the way they function is nearly identical to *process switching*.

In addition to making certain types of programs easier to create, a second advantage of using multiple threads arises when a processor with more than one core is used (*dual-core*, *quad-core*, etc.). If a program is created that equally divides a lot of work into four separate threads, then running the application on a quad core processor will make that application run four times faster. The art of developing programs this way is the topic of a full course.

### Why threads?

Performing a quick search on the Internet or looking at most textbooks will often provide the description that a thread is a "light-weight" process. It is starting to appear that processes and threads are almost interchangeable terms. If you recall one from the section on the overview of an operating system, most operating systems have a responsibility of protecting one application from another application (if Internet Explorer crashes it should not cause Word to crash or lose data). As a result, having two processes communicate or share information is a bit complex due to the security. However, within a single application there is usually no such protection between threads. As a result, it is often very easy for two threads to cooperate on a common set of data.

If the lack of protection between threads sounds like it is a bit risky, then you are completely correct! Improperly designed applications that rely on multiple threads can result in very difficult to solve problems that only sometimes occur. With multiple threads, the scheduler is still allowed to select any thread to run that is ready and this means that if you run a multi-threaded program ten times, it might actually run ten different ways (sometimes one thread might get more time at the start). This is often why a program might work fine today, but might crash unexpectedly tomorrow. Multi-threaded programs written correctly have a great advantage but it takes the right type of programming design and testing to remove bugs.

In many life critical systems such as medical equipment or avionics systems, and even high demand systems such as telephone equipment, the design team will often avoid using more than one thread to reduce unpredictability at the cost of increasing the complexity of the code.

#### **Inter Process Communication**

The term *inter process communication* refers to information being exchanged between two processes. Although the title of the section seems to suggest that the techniques described here are only for processes, they actually work equally for multiple threads within a single process.

When two or more threads (regardless if they are in the same process or not) are trying to cooperatively work on a solution to some problem, they need some sort of mechanism to exchange information so that they can decide which part of the problem will be solved by which thread, and to ensure that they do not both try to work on a single part of the problem at the same time. There may be other situations where one thread would like to wait for the other thread to finish first before continuing on. All of these cases require some sort of communication so that the two threads can coordinate.

### **Synchronization**

We will start with a very simple task. Suppose that we have two threads (again, if they are in the same or different processes the same problems exist) as follows:

```
threadA()
{
   system.out.print("Thread A");
   sysmtem.out.println();
}
threadB()
{
      system.out.print("Thread B");
      system.out.println();
}
```

Suppose we were to start the threads at exactly the same time (this is not actually possibly by the way...why?). The result should be that both messages will appear in the output window. The question that has to arise however is which message appears first? Does it look like this?

```
Thread A Thread B
```

Does the result look like this?

```
Thread B
Thread A
```

Does the result look like this?

```
Thread A Thread B
```

Unfortunately, with the information provided the output is actually unknown! This type of solution is called *non-deterministic* because we cannot predict (or determine) what will happen every time. In fact every time that we run the program we might see a different result.

Why do we end up with so many possible results? It looks like in the first example the first thread got to run completed, then the scheduler switched to the second thread. In the last

example, the first thread got to run but was not completed (it did not make it to the println() function), then threadB ran and then threadA finished. Non-deterministic solutions are extremely dangerous in critical systems where people's lives are at stake.

Unfortunately we did not actually say what the desired output should actually look like. Let us suppose that we want the output to be in the order of "Thread A" followed by "Thread B" on the next line, and we want to be guaranteed of this order, regardless of what else possibly happens. This suggests that we need some mechanism of making sure threadB waits for threadA to finish. As always, we would like to try to minimize the amount of CPU time actually used. This first thing we will talk about is called *synchronization*.

### **Shared Memory**

Our first technique that we will try to introduce is the concept of *shared memory*. This is a very simple to understand concept but, unfortunately, not a very good method in most cases.

The term shared memory means that both threads have access to a piece of memory that they can both read and write to at the same time. If one thread puts a value into the memory location, then when the second thread looks at the memory it will see exactly the same thing. Of course, unless the two threads are executing on a multi-core processor, there will only be a single thread executing at a given instant. Configuring a variable to be shared between two processes on an operating system is usually possible. However, it is not particularly easy due to the security. The creation of shared variables between two threads of the same process is generally easy (in fact, too easy because a lot of mistakes are generally made by assuming).

For the purpose of discussion we will assume that there is a variable called "turn" which is a simple integer that is available to both threadA and threadB. We will assume that the sharing is already set up. Now consider the following pseudocode:

Configure shared variable turn
Turn = 1
Start threadA
Start threadB

You might jump to the conclusion that threadA will be ahead of threadB because we asked it to start first. Keep in mind that the scheduler is responsible for picking the order. Just because you asked to start A first does not mean it actually had a chance to run! Now let's try to modify the two threads to make use of the 'turn' variable to make sure that threadA runs first then threadB.

Let us take a quick look to see if this actually does what we want. Notice that we started by setting the shared variable called turn (both A and B can see this) to the value 1. When threadA is finished it sets the value to 2. If we look at threadB() we see that it looks at the value of turn and if it is equal to 1 it does nothing, but we expect that eventually threadA will finish and the value will be set to 2, allowing threadB to execute.

This is good; this provides us a way that allows the two threads to synchronize. It does not matter if threadB gets to run for ten minutes before threadA even starts, because it will do nothing until threadA is finished. The variable called turn is an example of a *synchronization variable*.

Although this solution works, it does pose a bit of a problem. Look again at threadB, we see that it starts with a loop that continuously checks the value called turn. Now if threadB were to run for five seconds, would the value of turn ever change? Of course not, it is threadA that changes it. This type of checking is called *polling* and burns a lot of CPU time, which may consume more power from our battery (or may just cause the processor to heat up for no reason).

#### **Self-Yield**

A better option would be to have threadB look, and if the turn variable is not set then it should voluntarily go into the blocked state. Moving into the blocked state would allow the scheduler to run the other thread. We will introduce a new command called "sleep" which causes the current thread (and possibly process) to go into the blocked state until a certain amount of time has passed.

```
threadB()
{
     While (turn == 1)
          Thread.sleep(5000); // sleep for 5000ms or 5 seconds
     System.out.print("Thread B");
     System.out.println();
}
```

This code is much better for the CPU because now even if threadB runs first, it will immediately go into a blocked state and will wake up only every five seconds to see if the turn variable has been set. Therefore, even if threadA takes hours to complete, at least threadB is not using too much CPU time. Of course there is still a bit of a problem with this solution. Suppose that threadB executed and saw that the turn variable was still 1 and went to sleep for five seconds.

Then threadA ran and set the value turn value one second later... threadB would only wake up in another four seconds to see if the variable was set. This means that our problem has been slowed down because threadB was asleep. You may be tempted to reduce the amount of sleeping time but this means that threadB will wake up more often and use more CPU time. A better option would be to have threadA actually wake up threadB when it is finished.

### **Signals or Semaphores**

A signal (or semaphore) is a special type of variable supporting two operations called wait and raise (when using the term semaphore the operation names are usually take and give). Because the term signal is used in Unix to mean something critical has occurred (such as a crash), we will avoid using the term signal here. However, keep in mind that many books use the terms interchangeably. Semaphores can be used in a number of ways, but the first thing that we will consider is using them for synchronization.

The two operations are:

- Take: When a thread asks to take a semaphore, either the thread is given immediate
  control because the semaphore is available or else it goes into a blocked state waiting for
  the semaphore to become available. As soon as the semaphore is made available (usually
  by some other thread) the requesting thread will be immediately woken up.
- 2. *Give*: When a thread gives a semaphore it is potentially waking up another thread that is waiting.

We turn back to our example of the two threads again and consider the pseudocode to get things started:

Create a semaphore variable called "turn"
Make sure the semaphore turn is not available
Start threadA
Start threadB

Now we change the thread code slightly:

We had changed our startup code to indicate that we need to actually create the variable called turn. We have also included an instruction to make sure that the semaphore is not actually available to start. This is very important. We want to make sure that the "give" instruction in threadA is the one that makes the semaphore available.

When threadB starts it will try to take the semaphore. If the semaphore is not available, the operating system scheduler will move the thread (and possibly the process) into the blocked state. While in this blocked state, the thread (and process) will consume no CPU. When threadA finishes its tasks, it will give the semaphore and the give operation will cause the operating system scheduler to wake up the blocked thread and make it as ready.

The creation of these semaphores is very specific to each operating system, and there are often a lot of options available for dealing with very complex problems. As an example, suppose there are two threads waiting on a single semaphore. Which thread gets the semaphore when it is given? You will probably have an opinion of this immediately by saying the first thread to ask should receive it, but perhaps the second thread was actually much more important. The options provided for the semaphores can be used to control specific behavior depending on the needs of the application. Another issue that we are deferring to the section on scheduling is how long does threadB wait? In our particular example we probably want to wait until threadA is finished, regardless of how long it actually takes. In some programs waiting a really long time might not be the right answer, and often the semaphore take operations allow for an alarm clock to wake them if the semaphore is not actually given. Of course what you do when you wake up from an alarm, rather than actually receiving the semaphore, is very specific to the problem at hand. It is impossible to suggest in this text how to properly handle the situation.

#### **Critical Sections**

A *critical section* is a part of code (or more often a set of variables) that must be accessed in a controlled way when dealing with a multi-threaded system. Again, as previously mentioned, it does not really matter if the multiple threads are within the same process or spread across multiple processes. Critical code sections are actually quite difficult to visualize, so we will start with a very simple example and build up a solution technique. We will then introduce some more typical programming requirements.

Suppose again that we have two threads which we will call threadA and threadB. This time both threads are responsible for doing some long calculation (the actual calculation is not relevant), and once the calculation is finished then each thread prints some information on the screen. We will add some additional complexity to cover a new topic.

```
threadA()
{
    Long calculation
    System.out.print("Thread A is finished: ");
    For (I = 0; I < 10; i++) {
         System.out.print(i);
         System.out.print(" ");
    }
    System.out.println();
}</pre>
```

Let us assume that threadB looks identical except for the message "Thread B is finished: ". Although these examples are nonsense, they are easy to describe and introduce the concept of a critical section of code.

First we consider what happens when we run threadA without adding threadB to the mix. This thread will perform some long calculation and then print out the numbers 0 through 9 on a

single line with a space between each. The behavior of the program is really quite simple. However, if we now launch both threads at the same time we might end up with the scheduler switching back and forth several times. The result could look something like this:

Thread A is finished: 0Thread B is finished: 0 1 2 1 2 3 4 5 6 7 3 4 5 6 7 8 8 9

9

We have marked the output from threadB using italics so that you can see what is happening. The problem is that the scheduler keeps switching back and forth between the two threads while they are printing to the screen. This is quite common. Most operating systems will take an I/O request as a chance to reschedule the threads or processes. Unfortunately, there are no actual guarantees of when the rescheduling will occur. Our goal for this small program is to make sure that the output does not get mixed up. The problem is that all of the output statements in our threads are part of a critical section, which means that we do not want the other thread interfering while we are trying to write to the screen.

### **Preventing Rescheduling**

The first technique that we consider is having the thread/process make a request to the operating system to disallow rescheduling while they are performing the output. The thread code then looks something like this:

```
threadA {
    Long calculation
    Lock Rescheduler
    System.out.print("Thread A is finished: ");
    For (I = 0; I < 10; i++) {
         System.out.print(i);
         System.out.print(" ");
    }
    System.out.println();
    Unlock Rescheduler
}</pre>
```

By putting a lock and an unlock around the print statements we are asking the operating system to no do any type of scheduling operation while these statements are being executed.

This solution is completely valid, and if the other thread does the same operation the outcome will function perfectly fine. Again as expected, this simple approach does have some downfalls. Suppose that we execute the program containing these two threads but there is another application (such as Outlook) running on the same computer. If the first thread requests that the scheduler be disabled then the other applications will not have a chance to run at all, even though they may have no interest in the screen. The problem here is that the thread has asked that no other threads, regardless of who they are or what they want, are allowed to run.

An alternative solution that might be suggested is to use a synchronization semaphore, and make sure that threadA runs to completion before threadB. This is also a valid solution. However, one should ask if that is actually a valid requirement. We have not provided any details about the length of the "long operation". Suppose that we were to implement a synchronization semaphore and always forced taskA to finish before taskB. Now suppose that the "long" calculation in taskB takes one second, but the long calculation in taskA takes 100

seconds. Using the synchronization variable means that taskB has to wait 100 seconds before it can even run. If taskB could have run after one second maybe we should have let it.

To solve the problem in the best way it seems that we should have a race between threadA and threadB to see who gets to the end of the long calculation first, and then once the first thread passes a gate we lock out the other thread. We will start by trying to use a simple variable...

```
threadA {
    Long calculation
    While (busy == 1)
    Do nothing;
    Busy = 1;
    System.out.print("Thread A is finished: ");
    For (I = 0; I < 10; i++) {
         System.out.print(i);
         System.out.print(" ");
    }
    System.out.print();
Busy = 0
}</pre>
```

Here we assume that a simple integer variable called busy has been created and initialized to 0 before starting. Both threadA and threadB look nearly identical with the exception of the printed message. At first glance this code looks like it is going to solve our problem. The first thread to finish the long calculation will see that the busy variable is zero and will then set it to 1. If the second thread comes along it will see that the busy flag is 1 and will wait for the other thread to clear it. There are two problems with this solution. The first problem is the while loop which is a form of busy waiting, this burns CPU time. The second problem which is much more important is that the solution does not actually work.

Suppose that threadA checks the busy flag and sees that it is zero. This means that the next instruction is the "busy = 1". But lets suppose that just as threadA is about to change the value to 1, that the scheduler causes threadB to execute and threadB checks the value of busy. The value of busy is still 0 because nobody has set it. The result now is that both threads are executing within their critical section and you will end up with a messed up output. It looks like there is actually another critical section between the value of the flag checking and the setting.

Let us look again at the use of a semaphore, because it allowed one task to block (without consuming CPU) until another thread gave the semaphore. However, this time we are going to initialize the semaphore just a little bit differently. Here is the pseudocode that starts everything:

```
Main()
{
    Create semaphore called lock
    Make sure that the lock is available
    Start ThreadA
    Start threadB
}
```

Now for the thread code, again threadB looks identical except for the message displayed.

```
threadA {
    Long calculation
    Lock.take();
    System.out.print("Thread A is finished: ");
    For (I = 0; I < 10; i++) {
         System.out.print(i);
         System.out.print(" ");
    }
    System.out.println();
Lock.give();
}</pre>
```

In this case the first thread through the long calculation will take the semaphore, and the second thread to complete will have to wait because the first thread already took it. The operating system code would have ensured that if there were critical sections in the take and give code, they would be protected against switches (likely by disabling interrupts). As soon as the first thread gets through the critical section, the semaphore lock is given and the other thread would be woken up and would execute.

This example of a program that does some calculations and prints some numbers to the screen is just meant to be an easy to understand example. We now consider a real problem involved with our e-mail program.

To set this up, let us suppose that an individual e-mail message is stored in a Java object of type EmailMessage. Our e-mail program keeps the e-mail messages in a simple array of EmailMessage, and there is an integer variable called inboxCount that keeps track of how many messages are actually in the inbox.

```
EmailMessage inBox[1000];
Int inboxCount;
```

Suppose that the software developer responsible for the e-mail program has decided that if there are 10 messages in the inbox, they will be stored in the array in locations 0 through 9. New messages that arrive will always be placed in the very last position and the inboxCount will be increased by 1 and that the developer has created the following member function to handle new messages:

```
Void newMessage(EmailMessage msg)
{
    inbox[inboxCount] = msg;
    inboxCount++;
}
```

So we put the new message into the array at the current count position and increment the counter by one for the next message that comes in.

Now suppose that the software developer has decided that there needs to be a function that removes a single message from the inbox given the "index" of the message. This code would likely look something like this:

The function operates by releasing all of the information for the message at the given location then shifts all the messages to the left to fill in the gap. It then finishes by reducing the number of messages by one.

Now suppose that the software developer decides that new messages coming in should be filled in by a separate thread than the thread interacting with the user in order to make programming easier.

Unfortunately the above code may lead to some difficulties with multiple threads. Suppose that a user is trying to delete a message and is part way through the deleteMessage function. Just before the inboxCount is about to be reduced a new message arrives, and the newMessage() function is called. The fact that both the variables inbox and inboxCount are being updated by two separate threads creates what is called a *race condition*. A race condition is simply a sequence of code executed by two or more threads in which the end result depends on which thread finishes first. In this case if either completely finishes, then it is not a race condition. However, if one of the threads is interrupted during the critical section, the results may not be as expected.

This example should show that although simple code solutions work, when more than a single thread is introduced into the solution there is a risk when it comes to shared variables.

### **Message Queues**

A popular mechanism provided by many operating systems for the purpose of inter process communication is the concept of a *message queue*. In many multi-threaded programs there is often a lot of information that one thread will want to exchange with another thread rather than just doing synchronization.

In order to send actual data from one thread to another, most operating systems provide a mechanism known as a message queue or a *pipe*. In a message queue there is always at least one sender and one receiver. The sender creates a message and puts it into a queue for delivery by the operating system. The receiver listens to the queue for messages and will often block waiting for messages to arrive. Once the message arrives, the receiver is woken up and the message is processed.

As an example we will slightly reconsider our e-mail program. Suppose that we have a single thread that is responsible for adding and removing e-mail from the inbox. We have seen that by having only one thread we remove critical sections. Is it possible in this type of solution to still have a separate thread that checks for new messages? Yes! A solution is to configure a message queue between the checking thread and the inbox manager thread as follows:



Figure 3.7
Configuring a message queue

The main message processor will accept messages either a receiving thread or from a user interface thread. The processing thread can only process one single message at a time and its pseudocode would look like this:

The message queues in many operating systems will allow for the listener to time-out if that is important for the program being developed. Most operating systems send data across their message queues in a first-in-first-out (FIFO) arrangement, and some allow for queue jumping so that important messages can be inserted at the very front of the list.

Most operating system message queues provide for a "backlog" of messages. If a sender quickly sends ten messages, the receiver must request each of the messages to remove them from the queue. This leads to a significant problem in that if the receiver is not able to process the messages fast enough, you can end up with some strange results. Most people have probably used a computer at one time that was not responding even though you were typing. After a few seconds, the program suddenly responded and all of the characters typed appeared instantly. This is an example where the typed characters were put into a message queue but the receiver (the program) was busy doing other tasks.

## **Process Scheduling Algorithms**

In this section we will describe the common algorithms that are used for scheduling processes and threads. Here the word *scheduling* will refer to the task of deciding which process or thread should be selected from the process table and put into the Run state.

Most current operating systems actually implement thread scheduling so that it does not matter if the two threads are in the same process or different processes. In this section we will try to use only the term "process scheduling." However, if the term thread is mentioned it really does mean the same thing.

#### Scheduler and the Process Table

The *scheduler* is a piece of software code (it is generally a function) that is included as part of the operating system. The scheduler is often tied to the periodic clock interrupt and to most of the operating system calls. By connecting to both a clock and the I/O, it means that processes can be scheduled each time there is a clock tick and they can be scheduled each time that the process talks to the OS (such as when it asks to take a semaphore, asks to sleep, or performs an I/O operation).

Each time that the scheduler code is executed, the code will examine the process table and make a decision (based on what it reads from the process table) about which process should be run next. Over the next few sections we may realize that some additional items are required to be added to the process table to help the scheduler.

### **Round-Robin Scheduling**

If a computer has four processes currently running, it would seem logical that one of the fairest ways to divide the CPU time is to give each process a turn in a certain order and continue to use that order. For example if the processes are called A, B, C, and D then the order could be: A, B, C, D, A, B, C, D, A, B, etc. This type of scheduling is called *round-robin scheduling*. Most modern operating systems provide this type of scheduling algorithms and it is one of the easiest algorithms to understand.

A common way of showing the algorithm is to create a small table that looks like this:

Process	T1	T2	T3	T4	T5	T6	T7	T8	T9
Α									
В									
С									
D									

The labels T1, T2, etc. refer to small units of time called *time slices* or *quantums*. The actual number of seconds (or more likely milliseconds) is dependent on the operating system but can sometimes be configured. Typical values for the time slices are in the order of 10ms.

Each process is given a number of milliseconds to execute and then interrupted, and the scheduling algorithm will pick the next process in the list. However, if the process blocks (waits for a semaphore or sleeps) the scheduler would wake up early and schedule the next process. While a process is in the blocked state it will be not considered until it gets back into the ready state.

The size of the time slice is quite important. If you pick a really large time slice (say ten seconds), then it means that each process gets to execute for up to ten seconds. If Windows used a ten second time slice, then it means when you click on the start menu (part of the Explorer process) you might have to wait up to ten seconds for Word to finish what it is doing before seeing the menu appear. On the other extreme, if you set the time slice to a really small value (such as 1 ms) then it means that the scheduler is executing 1,000 times per second. When the scheduler code is busy selecting a process it means that no other process can be running. The result is an inefficient system that spends more time trying to decide what to do than actually doing something.

### **Priority-Based Scheduling**

The round-robin type scheduling appears to be a very fair algorithm, and in most cases the use of this algorithm works well. However, there are some situations where another form of scheduling leads to a better system from the user's point of view.

Most people have probably used a computer at one time when the computer did not seem to be responding. While using MS Word you may find yourself typing a few keys but nothing appears on the screen for a few seconds, then suddenly all of the characters you typed appear at the same time. Although it might be okay if this happens just once a month, it should not be happening every few minutes. While the user is typing they generally like to have some sort of instant feedback so they know their keys are being accepted. If it took five seconds for your phone to show the digit you pressed when dialing a number, you would find this quite unacceptable.

Unfortunately, with round-robin scheduling instant feedback is not possible unless we choose a very small time slice and we do not




Figure 3.8
Windows Task Manager Showing Process Priorities

have a lot of processes. While your computer (or mobile) is running another process, we need some way of having the user application interrupt other applications. In order to keep track of which processes are more important, the process table generally contains an entry called the *priority*. Each time the scheduling algorithm is executed, the scheduler will look at the process table for the process that is in the Ready state and pick the process with the highest priority.

An operating system could allow the process itself to pick its own priority, or the priority could be picked by the operating system. In some operating systems, priorities are simply low, medium or high. In other operating systems, the priorities may be arranged between 0 and 255 with 0 being the highest and 255 being the lowest (the meanings could be reversed with a larger number being higher in priority). What do we do if there are two processes with the same priority? The usual implementation is to utilize round-robin scheduling for all processes that are of equal priority.

When a process is put into the Run state, it will get to run until one of the following things happens:

- 1. it finishes,
- 2. it blocks,
- 3. a higher priority process becomes ready.

What if the process never blocks or finishes? Then the process gets to monopolize the CPU and never allows any other process to run. When a process never gets to run because a high priority process is using all of the time, it is called *starvation*. Starvation is a danger of any operating system relying on priorities for scheduling and it requires careful programming to ensure that it does not happen. You may be wondering how a higher priority process would ever become ready if another process is running all of the time. As long as the currently running process eventually waits or gives a semaphore that the higher priority process is waiting for, then the high priority process gets to run.

In most operating systems, processes started by the user (application) are assigned the same priority, and generally the processes created by the operating system are provided a higher priority so that the developers do no need to worry about this aspect. In the Windows Task manager, it is possible to change the priority of the processes. Linux also allows for the user to lower the priority of a process.

### **Case Study: Priority Does Not Mean Importance**

A nuclear power plant produces power by having a nuclear reaction heat up water which generates steam and the steam is used to turn a turbine. To slow down the reaction the plant can insert control rods into the reactor. If the reactor gets too hot, you might cause a nuclear meltdown (you do not want this to happen!). Putting in the control rods is usually done by a robot and takes a certain amount of time.

Suppose there is a sensor on the reactor that notifies a controlling computer when the temperature gets too hot. Also let us pretend that the computer program to move the control rods into place takes 30 seconds to complete, but if you do not get the task done in 60 seconds there is a meltdown.

Meanwhile, inside the break room at the power plant is a coffee maker. The coffee maker has a sensor which can detect when the pot is about to overflow, and it sends a signal to a computer program which is responsible for switching off the pot. It takes one second for the computer to switch off the pot, but if you do not switch it off within five seconds the pot will overflow.

Due to cost cutting, the owner of the nuclear power plant has decided to buy only one computer to control both the reactor rods and the coffee pot! You of course have two processes running,

one for the coffee and the other for the reactor. Which process should have the higher priority? We will assume that both alarms happen at the same time.

#### Scenario One: The Control Rods get Higher Priority

This makes sense because preventing a meltdown is a lot more important!

- 1. Time = 0s. Both alarms trigger. Control rod robot activated, ignoring coffee pot.
- 2. Time = 5s. Coffee pot starts overflowing.
- 3. Time = 30s. Control rods in place. Lots of water on the floor. Coffee pot is instructed to switch off.
- 4. Time = 31s. Coffee pot is off.

Is this a good solution? The plant did not meltdown, therefore this is good. The coffeepot overflowed which means there is a mess in the break room, but we only need a mop.

#### Scenario Two: The Coffee Pot gets Higher Priority



This sounds like a silly idea but consider the sequence of events.

- 1. Time = 0s. Both alarms sound. Coffee pot starts to be switched off.
- 2. Time = 1s. Coffee pot is switched off. Reactor rod robot started.
- 3. Time = 31s. Reactor rods inserted and meltdown prevented.

In this solution, the control rods were inserted well within the required time and we also avoided the flooded break room.

#### Conclusion

Processes with important responsibilities do not always need the highest priority. The selection of priorities is based a combination of how quickly a process must react and how long it will take to complete.

### **Other Scheduling Algorithms**

There are a number of other scheduling algorithms that are described in various texts, but they are often based on older operating systems where programs ran without a user sitting in front of the computer. We include a brief description of each of these for completeness.

#### **First Come First Serve**

In this algorithm, there is no pre-emptive switching. When a process is scheduled it runs until it is completely finished (or perhaps until it blocks). The idea is quite simple once a process is started the most efficient thing to do is to let it run until is completely finished before allowing another process to run.

This scheduling algorithm does not work for situations where two processes are working together to solve some problem however from a purely efficiency point of view it works well and there is no fear of having one process being interrupted by any other process.

In a system running this type of scheduling the process table is created with a list of all the processes and then run without modification until all tasks are done (or new tasks added only between processes).

### **Shortest Task Remaining**

The idea for this algorithm is to figure out which process will finish in the shorted amount of time and schedule the processes in an order that finishes as quickly as possible. It tends to favor short processes over longer processes. The danger is that a lot of short processes could easily starve a longer process. It is also not practical because you cannot actually know for certain how much more time is remaining for a given process.

## **Scheduling and Blocking**

The scheduling algorithms presented earlier in this section have completely ignored tasks which are currently blocked. We finish the section on scheduling by looking at one particular problem of blocking from a scheduling point of view.

Suppose we have the following processes:

Process A (priority high)
Wait for 10 seconds
Take semaphore S (block until it is available)
Do calculation

Process B (priority medium)
Sleep 5 seconds
Do calculation that takes 3000 seconds

Process C (low priority)
Take semaphore S
Do calculation that takes 10 seconds
Give semaphore S

Suppose that all three processes are started at exactly the same time and that the semaphore S is available to the first process that requests it.

As soon as all processes are started the process table will look like this:

Name	Priority	State
Process A	High	Ready
Process B	Medium	Ready
Process C	Low	Ready

This means that the scheduler will select process A because it is the highest process that is 'Ready'. Process A will execute, but the first thing that it does is sleep. This means that its state will become 'Blocked'.

Now the scheduler will wake up and select Process B because it is the highest process that is ready to run, but as soon as Process B runs its state turns to block because of the Sleep. Next, process C gets a chance to run, and it takes the semaphore S and starts doing some calculations. Process C does not block because it is running some long calculation.

After five seconds, Process B wakes up and runs its 3000 second calculation. Remember that process C is still 'Ready' because it has another five seconds to go and it is also holding semaphore S.

At ten seconds, process A wakes up from its sleep but immediately goes into a blocked state because it requests semaphore S (but C has it). The scheduler then runs process B because it is the process with the highest priority that is available.

The problem here is that Process A has the highest priority and wants to run, but it cannot because Process C has a semaphore it needs. But Process C is not able to run because Process B is monopolizing the CPU. This problem is called *priority inversion* because the medium priority process is preventing the high priority process from running.

Solutions to this problem are not covered in this text, but two observations are noted:

- 1. There is a shared semaphore between a high and low priority task; this is generally a bad idea.
- 2. The task in the middle has a high priority but it monopolizes the CPU for a relatively long period of time. Such a lengthy task should probably have had a lower priority.

### **Unit Summary**

Processes are instances of programs that are currently being run in a computer system. In order to improve the efficiency of process execution and CPU scheduling, processes are often broken down into smaller units called threads. Processes and threads are managed in by the operating system using a Process Table, which lists all processes and threads and their current state. A process or thread can either be running, ready to run, or blocked (which means that they will be ignored by the process scheduler until their state has been changed back to "Ready"). Processes can also be marked in the Process Table as either "new" or "exit," which is a form of blocking preventing them from being executed because they are not actually ready.

A number of different strategies are used to allow processes and threads to exchange information so that they can synchronize themselves, or arrange themselves to be scheduled only in the correct sequence (or when specific required information is available). The most common methods of inter process communication include the use of signals (often called semaphores) and message queues. When exchanging information between processes or threads, certain critical sections of code most be handled carefully to make sure that they are not corrupted, that they are accessible when needed by other processes or threads, and that the desired outcome is achieved by the instructions being executed.

The scheduling of processes can be handled using a variety of algorithms, but the most common methods are to handle all processes or threads in sequence (round-robin scheduling), or to schedule based on process priority (priority-based scheduling).

## **Key Terms**

Algorithm Blocked Blocking Critical section

Dispatch Dual-core

Exit

First come first serve

*fork()* Give

Inter process communication

Interrupt

Message queues

Multicore Multiprocessor Multitasking

Multithreading

Non-deterministic solution

Non-preemptive switching

Pipe Polling

Preemptive switching

Priority

Priority inversion

Priority-based scheduling

Process

Process scheduling

Process table

Processor preservation

Quad-core Quantum Race condition

Raise Ready

Round-robin scheduling

Running Scheduler Self-yield Semaphore Shared memory

Shortest task remaining

Signal
Sleep
Starvation
State changing
State machine
Synchronization

Synchronization variable

Take Thread Time slice

Unmanaged exception

Variable Wait

### **Review Questions**

- 1. What is a thread? What is the relationship between a process and its threads?
- 2. Define multitasking and multithreading.
- 3. List and describe five major process states.
- 4. Draw a diagram of a typical state machine, showing the five major process states.
- 5. List and describe two common problems that may overload a CPU during program execution.
- 6. Why is inter process communication important?
- 7. Briefly define Process Synchronization.
- 8. What is a Critical Section?
- 9. Describe the purpose of a signal/semaphore.
- 10.Describe the purpose of a message queue.
- 11. Fully describe how "round robin scheduling" and "priority-based scheduling" scheduling strategies works.
- 12. With regards to "round robin scheduling" and "priority-based scheduling" scheduling strategies, give some situations where one strategy works better than the other.

# **Unit 4: Memory Management**

### What is Memory Management?

Memory is vital to the functioning of any computer or computerized device. As discussed in Units 1 and 2, memory consists primarily of RAM chips that are installed on the motherboard of a computer. A typical computer now has between 1 GB and 4 GB of RAM. RAM is divided into segments (typically 32 bits) that are used to temporarily store data and instructions that are being used by the computer. This is different from your hard drive, which permanently stores files and programs. RAM is much faster than your hard drive, so your data and instructions are loaded from your hard drive into RAM



when the computer is using them. When you turn off the power, everything stored in RAM is gone. In addition to the physical RAM installed in your computer, most modern operating systems allow your computer to use a *virtual memory* system. Virtual memory allows your computer to use part of a permanent storage device (such as a hard disk) as extra memory.

Memory resources are managed by the operating system. The operating system is responsible for allocating memory address ranges as needed to run applications and processes. In this unit, we will look at the function of the memory manager in an operating system, and the types of problems that the memory manager must resolve. We will look at some of the techniques that operating systems can use to actually allocate memory, and some of the problems that can occur when using specific memory allocation strategies. We will also look at the purpose of virtual memory and how it works. This will include a look at page files, the page table, and the page replacement policies used by operating systems to manage virtual memory.

## The Memory Manager

The *memory manager* is part of the kernel (core) of the operating system. It is responsible for efficiently managing all memory resources including RAM and virtual memory, and allocating memory space to applications and processes as needed. The memory manager must keep track of all memory addresses and what they are currently being used for. It must also protect those address ranges, and the data and instructions stored in them, from data and instructions being used by other processes. The memory manager is also responsible for freeing up memory when it is no longer being used so that other processes can use it.

The memory manager is responsible for four critical tasks:

- 1. Allocating *main memory* to processes
- 2. Retrieving and storing the contents to and from main memory when requested
- 3. Effective sharing of main memory
- 4. Minimizing memory access time

### **Efficient Memory Management**

A well designed operating system should make access and the management of resources as efficient as possible for both the user and the system. Efficient memory management includes keeping track of all memory resources that have been allocated to different processes. It also includes using different strategies for allocating free memory as it is needed by new processes.

When it comes to the allocation of memory spaces and the retrieval of data from memory, you can compare the memory manager to the local telephone company. There are many ways that the phone company can keep track of telephone numbers that have been assigned to customers. One way is to keep a sequential list of all phone numbers, along with the names of the subscribers. Another way is to keep track of the names of subscribers, along with their assigned phone numbers (like a phone book). An efficient memory manager would use both types of strategies to keep track of data stored in RAM. The first strategy is useful for examining address ranges and finding free memory that is available for use. The second strategy is useful for examining individual processes, and keeping track of what memory each process is using.

An operating system's memory manager is also responsible for using different strategies to allocate free memory to new processes. Each strategy has its advantages and disadvantages. The aim of the operating system is to use the most effective strategy to both minimize the time needed to save and access data, and to maximize the amount of usable space left in memory. You can compare this task to parking vehicles in a parking lot. For example, you could park a motorcycle in the first available space. If it is a very big space, then you will end up reducing the maximum number of vehicles you can park in the lot, because the rest of the space may not be quite big enough to fit another vehicle. Conversely, you could try looking for the smallest possible parking space where the motorcycle will fit. The drawback here is that it might take you longer to find such a spot.

There are three main strategies that the memory manager can use when allocating free memory to processes:




Figure 4.1
Using memory allocation strategies to assign 12KB of memory

#### Best Fit

- Find the smallest free memory block that will fit the process needs
- Idea is minimize wastage of free memory space

#### Worst Fit

- Find the largest free memory block that will fit the process needs
- Idea is to increase the possibility that another process can use the left-over space

#### First Fit

- Find the first space to fit the memory needs
- Minimize the time to analyze the memory space available

### **Fragmentation**

The use of particular memory allocation strategies may result in wasting valuable free memory. That is because using either the best fit or first fit strategies may leave small chunks of free memory that are not large enough to be useful for any other processes (like parking a motorcycle in a parking space, and not having enough space left for another vehicle). The allocation and deallocation of memory creates а condition fragmentation. This means that there are lots of small fragments (or holes) of free memory that cannot be used by any other process. This results in a reduction in the amount of total available memory.

The worst fit memory allocation strategy attempts to minimize fragmentation by finding the largest chunk of free memory available to allocate to a process. By doing this, the memory manager tries to ensure that the unused memory "holes" it leaves are as large as possible. The goal is to leave as many big chunks of memory as possible so that as many fragments as possible are large enough to be used by other processes.




Figure 4.2
The worst fit strategy assigns the largest free memory chunk so that it leaves behind the largest possible fragment

### Relocation

Another task that must be handled by the Memory Manager is the *relocation* of applications in memory. Applications have certain memory requirements when they are loaded. However, it is not possible for the application to know in advance which memory range it will be allocated, because the application itself does not know what other processes will be running, how much physical memory the system will have available to it, and whether or not some of its required memory will be comprised of *virtual memory* pages (see next topic). For this reason, the application will only make reference to "*relative*" or "*logical*" address ranges. When the




Figure 4.3
Allocation of Physical Memory

application is compiled to load a process into memory, the operating system will allocate the actual address range based upon the relative ranges provided by the application, and the actual memory resources available. As demonstrated in Figure 4.3 (right), the process that is loaded will provide a *logical address*, which is combined with a *base address* provided by the operating system, to determine its actual location in memory. The application itself will be unaware of its location in memory. However, once a process has been started, it is not possible for the Memory Manager to relocate that process in memory unless it is aware of the relocation, and the new base address.

### Virtual Memory

Despite the fact that most modern computers have between 1 GB and 4 GB of RAM, it is possible to run out of memory. This can happen when you are running too many processes at the same time, or when a process requires more memory than is currently available (unused). One solution to this problem is to use *virtual memory*.

Virtual memory means that the operating system's memory manager will use a portion of another storage device to act as if it is extra RAM. In most cases, this virtual memory space will be on a permanent storage device such as a hard disk. However, some newer operating systems (such as Windows Vista and Windows 7) also allow you to use a removable media device like a USB flash drive as virtual memory (called *Windows Ready Boost*). The memory manager will manage this resource so that it gives the illusion that your computer has more RAM than is actually installed.

### **How Virtual Memory Works**

Virtual memory works by breaking down large programs into smaller units called *pages*. The memory manager will store these pages on an area of the storage device (hard disk) that has been allocated for use as virtual memory. This area is called a *Page File* (or Paging File).

All of the pages that are currently loaded in *main memory* (RAM) will be listed in a *Page Table*, which is maintained by the memory manager. If a process requests a page that is not currently loaded into RAM (in the Page Table), then a *page fault* will be generated. The memory manager will attempt to resolve the page fault by locating the requested page in virtual memory and then loading it into RAM (and listing it in the Page File). The memory manager will then try to reexecute the instruction that caused the fault.

## Pages, Virtual Addresses and Physical Memory

Figure 4.3 (right) shows how pages, virtual addresses and physical memory are combined to create a virtual memory system. The memory manager maintains both a virtual memory space and a Page Table. All processes and data that are loaded into either main memory or the page file (hard disk) are given addresses in the virtual memory space. The Page Table keeps track of the locations of all the pages. Although pages may be located on different physical devices, the memory manager treats them as if they are all contained in one large memory system. When a page is actually needed for processing, it is loaded into main memory (RAM). Older pages that are not currently being processed may be swapped from RAM back to the paging device (usually a hard disk).




Figure 4.4
Combining Elements to Create
a Virtual Memory System

### **Swapping Pages**

Whenever main memory (RAM) is full, or when a page is requested that is located in virtual memory, the memory manager needs to *swap* old or unused pages from RAM into virtual memory in order to make space for the new pages being loaded. There are a number of strategies used by the memory manager to handle this task. These strategies are often called *replacement policies*. There are five main replacement policies that are used by operating systems:

- Random Replacement
- First In First Out (FIFO)
- Second Chance
- · Least Recently used
- Least Frequently Used

Each of these replacement policies uses different algorithms for selecting pages to be swapped from RAM into the page file.

#### **Random Replacement**

- Replace pages in main memory randomly.
- On the average, does not work well.

#### **FIFO**

- Uses a queue data structure to keep track of the pages in main memory.
- Oldest page at the front (head) and newest page at the back (tail).
- Always replace (get rid of) the oldest page.
- Does not always work, because the oldest page may still be used by the process.

#### **Second Chance**

- Another version of FIFO to address the problem of FIFO.
- All pages in the page table are tracked to see if they have been referenced recently by a process.
- A Reference (R) bit for each page is used for this purpose:
  - o R = 1 when the page is being referenced.
  - $\circ$  R = 0 when the page has not been used after a time period.
  - o The OS will periodically check the (R) bit for each page and move the pages those (R) = 1 to the tail of the queue thus given a  $2^{nd}$  chance.

#### Least recently Used (LRU)

Replace the page in main memory that has not been used the longest.

#### **Least Frequently Used (LFU)**

- Counter are used to record the number of times each page have been used.
- The pages that have been used the least (lowest count) would be replaced.

### Hit Ratios: Determining Which Replacement Policy to Use

Using each of the five main replacement policies to swap pages between main memory and the page file will result in different hit ratios. A *hit ratio* is the number of times that a page is actually found in main memory, as opposed to the number of page faults generated (requiring the memory manager to retrieve the page from virtual memory). To calculate the hit ratio, we divide the number of non page faults by the total number of page requests (the number of times that data has been sent between the CPU and main memory). Remember—page faults occur when a page is requested by the CPU that is not currently in the page table (in other words, not currently in RAM). The memory manager resolves the page fault be swapping an old page from RAM to the page file (on the hard disk), then retrieving the requested page from virtual memory to RAM, and then re-executing the instruction. Since there are extra steps involved in order to execute the instruction, and since retrieving a page from a hard disk is slower than RAM, page faults result in longer processing time. We use hit ratios to determine which replacement policy will result in the fewest number of page faults, and the fastest overall processing time. The policy that produces the lowest number of page faults is usually the policy we want to use.

### **Calculating Hit Ratios**

To understand how to calculate hit ratios, we will examine an example that uses a RAM space of three (3) frames, and the following processing sequence:

12131415232415

In these examples, Y = a hit (the page is found in RAM), and N = a page fault (the page must be retrieved from virtual memory. A frame is a segment of RAM that can be allocated to hold a page, and is typically the same size as a page. Frames 1-3 are located in RAM. Frames 4-5 represent pages located in virtual memory.

### **Using FIFO:**

Sequence	1	2	1	3	1	4	1	5	2	3	2	4	1	5
Hit?	N	N	Y	N	Y	N	N	N	N	N	Y	N	N	N
Frame 1	1		1		1	<del>1</del> 4			42		2		<del>2</del> 1	
Frame 2		2					<del>2</del> 1			13				35
Frame 3				3				<del>3</del> 5				<del>5</del> 4		
Hit Ratio	3/14													

Using the First In First Out (FIFO) policy, we end up with a total of only three hits out of fourteen attempts to send information between the CPU and RAM.

### **Using LRU:**

Sequence	1	2	1	3	1	4	1	5	2	3	2	4	1	5
Hit?	N	N	Y	N	Y	N	Y	N	N	N	Y	N	N	N
Frame 1	1		1		1		1			13				<del>3</del> 5
Frame 2		2				24			42		2		<del>2</del> 1	
Frame 3				3				3.5				<del>5</del> 4		
Hit Ratio	4/14													

Using the *Least Recently Used (LRU)* replacement policy, we end up with a total of four hits out of fourteen attempts to send information between the CPU and RAM.

### **Using LFU:**

Sequence	1	2	1	3	1	4	1	5	2	3	2	4	1	5
Hit?	N	N	Y	N	Y	N	Y	N	N	N	Y	N	Y	N
Frame 1	1		1		1		1						1	
Frame 2		2				24			42		2			
Frame 3				3				35		<del>5</del> 3		<del>5</del> 4		4 5
Count	1	1	2	1	3	1	4	1	1	1	2	1	5	1
Hit Ratio	5/14			-	-		-							

Using the *Least Frequently Used* (*LFU*) replacement policy, we end up with a total of five hits out of fourteen attempts to exchange information between the CPU and RAM. In this example, the LFU replacement policy has resulted in the highest hit ratio, and the least number of page faults. That means that using the LFU replacement policy will result in the least amount of times swapping pages between RAM and the page file, and the lowest overall processing time.

## **Thrashing in Virtual Memory**

The use of virtual memory has both benefits and drawbacks. The main benefit is that it artificially increases the overall amount of memory available for the execution of processes. However, as we have seen, swapping pages between RAM and virtual memory slows down the overall processing time. It takes much more time to locate and retrieve data from a hard disk than it does from RAM. When your computer spends too much time swapping pages between RAM and the page file, we call this condition *thrashing*. Thrashing not only results in longer processing time, it also leads to increased wear and tear on your hard disk. Normally, your computer only reads data from your hard disk when you are loading it into memory to be used. Your computer normally only writes data to your hard disk when you are finished with it, and you want to save it.

### What Causes Thrashing?

Thrashing is typically caused when you have too many processes running at the same time. All of these processes will compete for the limited amount of physical memory installed in your computer. If your computer is thrashing, your applications may stop responding (or run very slowly). At the same time, you may notice your hard drive light blinking (and you may hear the hard drive spinning). There are really only two ways to correct thrashing:

- 1. Kill (stop) some of the processes (temporary solution)
- 2. Install more RAM

### **Quick Tip:**

You can change the size of your operating system's page file (virtual memory). How you do this depends on the specific operating system. However, your page file should never be bigger than 1.5 times the size of the amount of RAM installed in your computer. If it is bigger than that, your memory manager will rely too much on your virtual memory, and you will experience thrashing.

## **Unit Summary**

The memory manager has the responsibility of allocating memory resources to processes and threads as needed. This task includes assigning memory as needed and retrieving information from memory when it is needed by the CPU. The memory manager also has the responsibility for managing available memory as efficiently as possible to make sure that as much memory as possible is actually usable by processes, and to make sure that processes can be executed as quickly as possible. The three main strategies used to assign memory spaces are called Best Fit, Worst Fit and First Fit. Most modern operating systems also use virtual memory, which uses part of another storage device to act as extra RAM. The memory manager must handle swapping pages (chucks of data and process code) between main memory (RAM) and virtual memory (storage device). The page table is used to keep track of the location of pages in RAM, and if a page is requested that is not located in RAM a page fault will be generated. The memory manager must find the requested page in virtual memory, load it into RAM, and reexecute the instruction. There are five main strategies (called policies) that are used the manage page swapping between RAM and virtual memory. The memory manager must use the most appropriate strategy to minimize the number of page faults that are generated, thus minimizing the overall time needed to execute a process. When too many processes are competing for main memory, and too many pages are being swapped between RAM and virtual memory, a condition called thrashing is created. Thrashing can cause undue wear and tear on a hard disk, and increases the amount of time needed to execute an instruction set. The memory manager tries to minimize thrashing, but the only real solutions are to either reduce the number of running processes or add more RAM to the system.

### **Key Terms**

Access time Base address

Best fit First fit

First In First Out (FIFO) Fragmentation

Hit Hit ratio

Least Frequently Used

(LFU)

Least Recently Used (LRU)

Logical address Main memory Memory manager

Page
Page fault
Page file
Page request
Page table
Paging device

Physical memory Random replacement Relative address

Relocation

Replacement policy Second Chance

Swap file Swapping Thrashing

Virtual memory

Virtual memory space Windows Ready Boost

Worst fit

# **Review Questions**

- 1. What is the purpose of the memory manager in an operating system?
- 2. What types of problems must the memory manager protect against in a multiprogramming system?
- 3. Describe any two memory allocation strategies.
- 4. What is fragmentation and what causes it?
- 5. What is virtual memory and what does it try to accomplish?
- 6. Explain in steps how virtual memory works.
- 7. What is a replacement policy use for?
- 8. Describe any three (3) replacement policies.
- 9. There are 5 replacement policies. Which seems the simplest to implement? Why? (If it is easy to explain, it is usually easy to implement or program)
- 10.Of the five (5) replacement policies, which seems the most difficult to implement? Why?
- 11. Which policy do you think has the best hit ratio? Why?

# **Unit 5: Input/Output**

### What are Input/Output Resources?

Input/Output devices were briefly discussed in Unit 1: Architecture Review. Input devices are any devices that allow data to be input into a computer system. The most common examples are the keyboard and mouse, although there are many others. Output devices are any devices to which the computer can send output data, such as the monitor or printer. These I/O devices are connected to the CPU by a series of system busses on the motherboard. The operating system is responsible for issuing commands to I/O devices, as well as handling all interrupts and errors generated by the devices. The operating system needs some way to efficiently manage all of these devices and the flow of data coming in from them, or going out to them. These responsibilities are complicated by the fact that many processes being executed by the operating system may need to share the same I/O resources. In this unit, we will examine I/O resource management from two perspectives.

First, we will look at I/O resource management from a hardware management perspective. We will examine the role of device controllers, as well as the differences between preemptable and non-preemptable I/O resources, and block and character I/O devices. Later in the unit, we will take a detailed look at the actual management of one of the most common I/O hardware devices in any computer system: magnetic storage devices (hard disks and floppy disks).



**Common Input Devices** 



**Common Output Device** 

We will also be examining I/O resource management from a software perspective. We will take a look at the role of I/O management software, and I/O software system layers. This will include an examination of the software operating at each layer. In particular, we will focus on the role and structure of device drivers.

We will conclude this unit with a brief look at the role of the system *clock* in the management of I/O resources.

## I/O Resources

Input/Output resources are any I/O devices (and their supporting hardware and software components) that are available for use by processes being executed by the operating system. These resources are frequently shared between processes, so the operating system must have some way to regulate access to the resources to prevent conflicts and deadlocks. The operating system uses device controllers to handle communications with I/O devices. I/O resources can be categorized as either preemptable or non-preemptable. In addition to regulating access to I/O resources, the operating system must also control how data is transmitted to and from I/O devices. Data transmission can be handled as either character or block transmission, depended upon the type of I/O device.

#### **Device Controllers**

Device controllers are components on the motherboard (or on expansion cards) that act as an interface between the CPU and the actual device. The operating system actually controls the device by using device controllers, which interpret the commands being issued to the device. Instructions sent to the device are compared to a list of device commands stored on the controller, which then forwards the appropriate command directly to the device. When a device needs to access the CPU, the device controller issues an Interrupt Request (IRQ), which is then forwarded to the interrupt controller. The interrupt controller then forwards the request to the CPU.

Some of the more common device controllers found in a typical computer include:

- Keyboard Controller controls the keyboard and PS/2 mouse (not always needed in newer systems)
- DMA Controller controls Direct Memory Access
- Network Adaptor Controller controls the Network Adaptor/ Network Interface Card (NIC)
- IDE Controller controls EIDE devices, including the hard disk and CD/DVD drive
- Graphics Adaptor controls video output devices, such as a monitor or LCD projector
- USB Controller controls devices connected by USB

### The Interrupt Controller

The *interrupt controller* is a special component on the motherboard manages all interrupts, prioritizes them on а predetermined priority sequence, and then forwards the interrupts to the CPU. You can think of the interrupt controller like a police officer at a busy intersection, or a security guard at the main gate to a government office. When a device wants the CPU's attention, its device driver initiates an interrupt request (IRQ). Each type of device has a different IRO number assigned to it, so when multiple devices signal for the CPU's attention at the same time, the interrupt controller checks their IRQ number, and places them in a queue. The device with the lowest IRQ number gets the highest priority, just like a police officer letting more important vehicles (perhaps a government convoy or ambulance) proceed through intersection first.




Figure 5.1
The Interrupt Controller is like a traffic officer giving priority to more important vehicles

### **Managing Interrupts**

A typical modern computer system has two interrupt controllers that function as one unit. Each controller has eight lines. (This is because in the first personal computers developed in the late 1970s and early 1980s, the system bus was only eight bits wide.) Since every function of the computer needs the system clock in order to manage its timing, the highest priority is given to the system clock (which is given IRQ 0). The keyboard gets the next highest priority, since it is needed in order to manually override any other processes being carried by the computer. Thus, the keyboard is given IRQ 1.

Although we say that the higher the IRQ number is, the lower priority the device is given, devices using IRQ numbers 8-15 actually get higher priority than devices using IRQ numbers 3-7. This is because of the use of two controllers acting as one unit. All interrupt requests coming from the second controller are actually sent to IRQ number 2 on the first controller, which then forwards them on to the CPU. Figure 5.2 (below) demonstrates the structure of the interrupt controller system.




Figure 5.2
Structure of the Interrupt Controller System

### Preemptable I/O Resources

Preemptable I/O resources are resources that can be taken away from a process that is currently using them. In order to be considered a preemptable resource, the reallocation of the resource must have no negative effect on the processes involved (other than the overall time needed to complete the process execution). A common example would be memory. When a resource is preempted, or taken away from a process, the process is often placed into a blocked state, and must wait until the resources is made available again before it can return to a ready state and continue being executed.



Memory is a preemptable resource

### Non-Preemptable I/O Resources



Optical storage devices are non-preemtable

Non-preemptable I/O resources are resources that cannot be taken away from a process that is currently using them without having some negative effect. An example of a non-preemptable resource would be a CD/DVD drive. If a process is reading from or writing to an optical storage device, it is difficult to take that resource away from the process without corrupting whatever is being read or written to the drive.

#### **Deadlocks**

Deadlocks occur when multiple processes are holding I/O resources, and they each require resources that currently in use by another process that is unwilling to release the resource. When this occurs, neither process is able to make any progress. For example, one process may currently hold control of the optical storage (CD/DVD) drive, and may need to send something to the printer. A second process may hold control of the printer, and may need to access data from the CD/DVD drive. If neither process is willing to give up control of the resources it currently holds, then neither process will be able to proceed.

### **Block I/O Devices**

Some I/O devices send and receive data from the computer system in blocks of characters. Such devices are referred to as *block I/O devices*. The operating system manages reading and writing data to block devices by using a data buffer system. *Data buffers* are allocated to hold a single block of characters. When the buffer is full, the data in the buffer is then sent to or from the I/O device in one chunk. Common examples of block I/O devices are hard disks, optical storage drives, and memory regions.

### **Character I/O Devices**

Some I/O devices send and receive data from the computer one character at a time. Such devices are called *character I/O devices*. Common examples include virtual terminals and serial modems. Character transmission to character devices is *unbuffered*.

## I/O Management Software

From a software perspective, there are really two main elements to consider. The first is *device drivers*, which are the operating system software components that interact with the devices controllers. The second element is the *interrupt handler*. This software is really part of the device driver, but it is responsible for issuing interrupt signals to the interrupt controller when a device requests access to the CPU.

The I/O software system functions in layers, as illustrated in Figure 5.3 (below). One layer is the device drivers. Each type of device shown below has its own controller, which is responsible for relaying instructions to all devices connected to it. Device drivers issue instructions from the operating system to the device controller, which in turn handles the actual functioning of the device. Another layer is the interrupts. When a device controller issues a request from a device to gain access to the CPU, the interrupt handler (part of the device driver) sends the interrupt signal to the interrupt controller. The interrupt is then relayed to the CPU, as outlined in the previous section.




Figure 5.3 I/O Software System Layers

#### **Device Drivers**

Device drivers are essential components of an operating system. They translate instructions from the operating system and other processes into instructions that are used to drive the device controllers. In order to handle controlling the input/output devices that are part of the computer system, device drivers are structured into two layers. The *Upper Half* of the device driver handles taking requests in from the operating system, and places them in a "Shared Requests List." The Lower Half of the device driver handles taking requests from the shared requests list, and programs them for the device control to carry out the instructions. The interrupt handler is part of the Lower Half of the device driver. It is used when the device controller calls for an interrupt request, and it handles the issuing of the interrupt request to the interrupt controller. Figure 5.4 (below) illustrates the structure of a typical device driver.




Figure 5.4
Device Driver Structure

In this diagram, the blue box represents the device driver, which is divided into the Upper Half and Lower Half. The red arrows represent the flow of instructions from the operating system, which first pass into the Upper Half, then into the Shared Request List. These instructions are then programmed by the Lower Half, and forwarded to the device controller for execution. The blue arrows represent the flow of requests and data out of the device driver. In this diagram, the device controller is returning results back to the device driver, which then sends them back out to the operating system. The interrupt handler is also demonstrated issuing an interrupt request to the interrupt controller.

### Managing Magnetic Disks

Magnetic disk storage represents one of the most popular categories of I/O resources used by a computer. Processes and threads must be able to read data from, and write data to magnetic storage devices such as hard disks and floppy disks. This is most frequently done when accessing pages from virtual memory, but it also occurs when processes try to open or close files stored on disks. In this section, we will look at how magnetic storage devices are formatted to hold data, and how that data is structured on a disk so that the operating system can read and manage it. We will also take a look at the elevator algorithm, which is a pattern used by operating systems to manage data retrieval as efficiently as possible.



Hard disks are common I/O resources

### **Disk Formatting**

Disk formatting is the process of preparing a disk to hold data. When you reformat a disk, it destroys all of the data previously stored on it. There are three key stages to the formatting process for a disk:

#### Low-level formatting:

- Takes place at the factory.
- Involves physically drawing tracks and sectors on the disk surface.

#### Partitioning:

- Done by the user.
- Involves dividing the disk into logical sections.
- Only primary hard disks can be partitioned (cannot partition external hard disks or floppy disks)

#### High-level formatting:

- Done by the user.
- Involves the selection of a file system (such as FAT or NTFS for Windows), and the installation of an operating system.
- Different partitions can use different file systems, and can even be used to install different operating systems in the same computer.

#### What are Partitions?

Partitions are logical divisions of a hard disk. That is, you divide your hard disk into sections that will be used for different purposes. You could create multiple partitions if you want to install multiple operating systems. (When you boot your computer and select the operating system to use, it will use the appropriate partition, and ignore the others.) You could also partition a hard disk so that you can store files using two different file systems, or so that you can provide additional security for your files (for example, if you store your personal files on a different partition than your operating system and software, then your files will be less likely to get infected by a virus). Partitioning a hard disk has other file system benefits, such as reducing the size of file *clusters* (which results in less wasted space as more files are stored on the disk).

A hard disk can only have four primary partitions, each of which could be used for a different file system and/or operating system. A partition that contains an operating system is called an active partition. However, once an operating system is installed, you can select a partition and further divide it into logical drives (each of which would be assigned a drive letter). Although the data on logical drives is not physically isolated (as it is in partitions), each logical drive appears as if it were a separate disk for file management purposes. This could be useful for organizing file storage, or for allocating logical drive space for the exclusive use of different computer users.

### How is Data Structured on a Magnetic Disk?

Data on magnetic disks is physically organized using *tracks*, *sectors* and *clusters*. On hard disks, data is also organized using *platters* (a floppy disk has only one platter, while a hard disk can have several physical platters, which are each organized into tracks, sectors and clusters). A *track* is a concentric circle on a disk or platter. A *sector* is a division in a concentric circle. A *cluster* is the smallest unit of storage space available on a disk. The larger a hard disk is, the bigger the clusters become. On a floppy disk, the cluster size is the same as the size of a sector (512 bytes). Figure 5.5 (below) shows the organization of tracks and sectors on a floppy disk.




Figure 5.5
Tracks and Sectors on a Floppy Disk

In addition to creating tracks and sectors, when you format a floppy disk, you also create a *boot record*, a *File Allocation Table* (*FAT*) and a *Root Directory*. The *boot record* is always the first sector on a disk. It contains a *bootstrap loader*, which can be used to boot a computer from the disk, as well as information about how the disk is organized. The *File Allocation Table* lists the location of all clusters on the disk, and how they are currently being used. The *Root Directory* lists all of the files and subdirectories currently stored on the disk.

Hard disks are somewhat different from floppy disks. A hard disk contains several physical platters which are stacked on top of each other. Each platter is double-sided, with tracks and sectors drawn on the surface. All of the concentric tracks that line up with each other on each platter are referred to as a *cylinder*. Figure 5.6 (below) shows how the platters stack up inside of a hard disk. There is a *read/write arm* (with a *read/write head*) for each platter surface.




Figure 5.6
Inside a Hard Disk

Another difference between the physical structure of a floppy disk and a hard disk is the size of the sectors and clusters on the disk. Cluster size varies on hard disks, depending upon the actual size of the disk, the file system used, and the number of partitions. On a floppy disk, the sector size is fixed at 512 bytes. That means, the closer you get to the center of the physical disk, the fewer the number of sectors per track. On newer hard disks, the sectors get smaller as you get closer to the center of the disk. This means that you can have the same number of sectors for each track. The differences in how tracks are divided into sectors on floppy disks and hard disks are shown in Figure 5.7 (below).




Figure 5.7
Tracks and Sectors on Floppy Disks and Hard Disks

#### The Elevator Algorithm

Now that we know how magnetic disks are physically structured, we can turn our attention to how the interrupt handler actually handles requests to retrieve information from disk resources. This is typically done using the *elevator algorithm*. For this discussion, we will concentrate on requests for data from a hard disk. However, it should be noted that the elevator algorithm can be used by the interrupt handler to handle requests for data from other storage devices, as well.

The elevator algorithm is a strategy used by the interrupt handler to find data on a storage device when it is requested by a process. Using a first come first serve strategy to fill requests for data that have accumulated in the shared request folder is not an effective strategy, because it would actually take too long to constantly change the direction of travel of a disk's read/write head. This strategy would also increase wear and tear on a disk. Instead, the elevator algorithm organizes data requests based on the data's cylinder location on a disk. Using the elevator algorithm, the read/write head will only move in one direction at a time, and will "pick up" requested data as it moves from cylinder to cylinder.

The actual decision making process used by the interrupt handler is:

- 1. If the request queue is empty, exit interrupt handler
- 2. If read/write arm's direction is UP, move from the current cylinder (just completed request) to the next higher cylinder to perform that request.
- 3. If direction is DOWN, move the arm from the current cylinder (just completed request) to next lower cylinder to perform that request.
- 4. If no request lies in current direction, reverse direction.

Using this algorithm, we can examine the handling of requests for data from cylinders on a hard disk. Assume that the original request order in the shared request folder is for data from the following cylinders:

Figure 5.8 (below) shows the current position of the disk's read/write head, the current direction of movement and the locations of the requested data.

**Current Position of Read/Write Head** 

# 

Figure 5.8
Retrieving Data using the Elevator Algorithm

**Arm's Direction** 

In this example, the read/write head is currently located at cylinder 17, and the arm is moving in the Up direction. The next piece of data requested in the current direction is on cylinder 29, so the actual order in which the data requests are filled would be:

29, 31, 16, 12, 11, 9, 1

# System Clocks



Every process carried out by a computer is timed by a clock. While we generally refer to the *system clock* as one single timing device, there are actually several clocks operating in a modern computer.

The main system clock is part of the motherboard, and is typically timed in *Gigahertz* (*GHz*). One *hertz* means one cycle per second, so a system clock operating a 2.4 GHz (a typical speed for a modern PC) operates at 2.4 billion ticks (or cycles) per second. A single *cycle* of a system clock is the shortest possible amount of time that any process running in a computer can be completed. The main system bus operates in time with the main

system clock. Other clocks in a modern computer include the processor clock, the cache clock and clocks for the various I/O busses. The operating speeds for each of these clocks are different, but they are all tied to the main system clock. Their clock speeds are calculated by either multiplying or dividing the system clock speed by a set number.

Some clocks operate more slowly than others because the types of devices they regulate (such as I/O devices) cannot function at speeds as high as the system clock. Typically, the CPU operates at a faster speed than the system clock. It is obvious that, since some devices operate at slower intervals, the processor may actually spend extra time waiting for those devices to complete tasks before it can continue with a particular process from the Process Table. However, this does not necessarily mean that the entire computer system will be slowed down, as the process waiting on a device can go into a blocked or wait state, and the process scheduler can cycle to another process from the Process Table.

# **Unit Summary**

Every computer has numerous input/output devices that must be managed by the operating system. The operating system needs to control the functioning of these devices. It must also manage sending and receiving information from the devices, and sharing these resources amongst the many processes that are running (or waiting to be run) at any given time. In order to help the operating system with these tasks, each type of I/O device usually has its own device controller. The device controller talks to the operating system's device drivers, and translates instructions from the operating system so that they can be carried out by the device. A special device called the Interrupt Controller handles the task of receiving interrupt requests (IRQs – requests to either send or receive information from the CPU), and prioritizes them to be forwarded to the processor.

Some I/O resources (like memory) are considered preemtable. That means that if they are being shared by multiple processes, they can be taken away from whatever process is currently using them and reallocated to another process. Other I/O resources (like CD/DVD drives) are considered non-preemptable. That means that once they have been allocated to a process, they cannot be taken away from that process until it has been completed (without causing some sort of problem or corruption to the task). Deadlocks can occur when two (or more) processes have control of different I/O resources that are needed by the other processes, and they are unwilling to give up control of the device. When this happens, neither process is able to be completed.

From a software perspective, there are two main elements that come into play in managing I/O resources. The first is the device driver, which is supplied by the operating system to control an

I/O device. Device drivers are structured into an Upper Half and a Lower Half. The Upper Half handles taking requests from the operating system and places them into a shared request folder for the device. The Lower Half takes requests from the shared request folder, and programs them to be carried out by the device. The second major element is the interrupt handler, which is really a part of the Lower Half of the device driver. It is responsible for issuing interrupt signals to the computers interrupt controller when a device needs the attention of the CPU.

One of the most common types of I/O device managed by an operating system is magnetic storage devices. Devices such as floppy disks and hard disk drives need to be physically formatted into tracks, sectors and cylinders (for hard disks), and they need to be formatted with a file system that the operating system knows how to read. When retrieving data from a hard disk, the operating system often relies on the Elevator Algorithm to determine in which direction to move the disk's read/write head to find the next nearest piece of data, and in which order the data should be most efficiently retrieved.

All of the I/O resources in a computer system operate in time with the main system clock. There are actually several clocks inside of a modern computer, each operating at different speeds (depending upon what can be handled by the type of device they govern). Each of these clocks is actually tied to the main system clock, and their speeds can be determined by either multiplying or dividing the system clock speed by a set number. One cycle of a system clock is the shortest amount of time that any process running in a computer can actually be completed.

#### **Key Terms**

Active partition Block I/O devices

Boot record

Bootstrap loader

Character I/O devices

Cluster Cycle Cylinder Data buffer Deadlock

Device controller Elevator algorithm

File Allocation Table (FAT)

Formatting Gigahertz (GHz) Graphics adaptor Hertz (Hz)

High-level formatting

IDE controller

Input/Output resources Interrupt controller Interrupt handler Keyboard controller

Logical drive Lower Half

Low-level formatting
Magnetic disk storage
Network adaptor controller
Non-preemptable I/O resources

Partition Partitioning Platter

Preemptable I/O resources

Read/write arm Read/write head Root directory

Sector

Shared requests folder

System clock

Track Unbuffered Upper Half USB controller

## **Review Questions**

- 1. Describe the difference between preemptable and non-preemptable I/O resources. Provide an example of each type of resource.
- 2. Describe the difference between character and block transmission I/O resources.
- 3. With respect to shared I/O resources, what is a deadlock?
- 4. How is a hardware interrupt initiated?
  - a. If two devices signal for attention at the same time, how does the controller generally decide which one gets priority? Why is this not always true?
  - b. Which IRQ does the keyboard use?
- 5. Describe in full the working structure of a device driver.
- 6. What is the purpose of the interrupt handler in a device driver?
- 7. Describe what happens at each of the three levels of formatting for magnetic disk drives.
- 8. Describe the purpose of the File Allocation Table, Root Directory and Boot Record created when a floppy disk is formatted.
- 9. What is the purpose of the Elevator Algorithm?
- 10. Describe the purpose of clocks in a computer system.

# **Unit 6: File Systems**

# Managing File Systems

We have already taken a detailed look at the structure of a typical operating system, as well as how an operating system manages all of a computer's hardware resources, RAM and the scheduling of all of the processes and threads that need to be executed. In this unit, we will examine the last key element of a user's experience with a computer system. File system management encompasses the provision of a way to store your data in a computer, as well as a way for you to find and access that data when you need it.

We will begin this unit by looking at the requirements in a computer system in order to provide long-term storage of information. We will also look at an operating system's File Manager and all of its responsibilities. This will be followed by an examination of common strategies used by the File Manager to store and retrieve information from storage media. From there, we will turn our attention to the file systems that are created when an operating system formats a storage device (such as a hard disk). This will include a comparison of the characteristics of the FAT32 and NTFS file systems, as well the purposes of the Master Boot Record and Partition Tables created on a hard disk during formatting. We will conclude this unit with a look at how users actually interact with a file system. This will include an examination of the purposes of directories or folders, and the navigation of hierarchical file structures.

# Long-Term Storage of Information

When we examined computer memory, we saw that RAM is only useful for the temporary storage of data and instructions that are currently being used by a computer. Although RAM is very fast, it is *volatile memory*. That is, when you turn off the power to the computer, all data stored in RAM is lost. In addition, a typical computer has a relatively small amount of RAM compared to a user's long-term data storage needs. In order to permanently store information, an operating system has several requirements:



Hard disks: the most common long-term storage media

- A storage device (typically a magnetic hard disk).
- A device controller and device driver for the storage disk.
- Strategies for reading and writing data to a disk.
- A file system that provides a structure and rules for file encoding, management and security.

Although long-term data storage can be achieved using a variety of media (ranging from optical discs to floppy disks and USB Flash drives), this unit will focus on magnetic hard disks. That is because every personal computer system relies upon hard disk storage, and hard disks are by far the most common long-term data storage media.

# The File Manager

The *File Manager* is the part of the operating system that is responsible for the management of long-term storage devices such as hard disks. The File Manager provides a framework (or a *hierarchical structure*) for the organization of data that is stored on a disk. The primary responsibilities of the File Manager include:

- The organization of similar data (text, images, music and sounds, video, etc) in some manner, and putting that data into files.
- The organization of files into directories and folders.
- The organization of different levels of folders.
- The management of different partitions in a disk.
- The management of multiple disks for data storage.

The File Manager has additional responsibilities that are based on the primary responsibilities listed above. These include:

- Partitioning and formatting disks.
- Establishing file-naming rules or conventions.
- Providing data integrity.
- Providing error recovery and prevention tools.
- Providing file security.
- Providing directory paths.
- Providing command sets to manipulate files.

# **Data Storage Strategies**

Data storage strategies refer to how the operating system physically organizes and stores pieces of files on a disk. There are three common data storage strategies:

- 1. Contiguous Allocation Strategy
- 2. Linked Allocation Strategy
- 3. Indexed Allocation Strategy

# **Contiguous Allocation Strategy**

The contiguous allocation strategy is perhaps the simplest strategy for an operating system to set up. In a contiguous allocation file system, all pieces of a file are stored in contiguous (or physically adjacent) storage spaces on a disk. To keep track of files stored on the disk, the operating system maintains a file directory that lists the names of the files, the start block for the file on the disk, and the actual size of the file. The contiguous strategy has both advantages and disadvantages.


Advantages of the Contiguous Allocation Strategy

- Easy to set up.
- Easy approach for the sequential access of data.

Disadvantages of the Contiguous Allocation Strategy

- Not easy to expand the size of a file.
- Difficult to manage file fragmentation.
- OS must allocate and reserve contiguous space during the initial creation of the file.

Figure 6.1 (below) shows the allocation of disk space for files, and a file directory, for a sample hard disk.



File	Start	File
Number	Block	Size
1	1	3
2	4	6
3	10	2
1	12	2

**Contiguous File Table** 

Figure 6.1
Contiguous File Allocation

#### **Linked Allocation Strategy**

Using the linked allocation strategy, the contents of a file can be stored anywhere on a disk (they do not need to be *contiguous*). The operating system maintains a file directory which contains the file name and the start block number. Each block of data belonging to a file contains a pointer, which points to the next block of data belonging to that file. The last block of data contains a special *End of File (EOF) indicator*, so that the operating system will know that it has retrieved all of the data for the file. Figure 6.2 (right) shows the File Directory entry and the entries in the File Allocation Table for a sample file using the Linked allocation Strategy.

The linked allocation strategy also has advantages and disadvantages.

Advantages of the Linked Allocation Strategy

- No file fragmentation issues.
- Easy to expand the size of a file.




Figure 6.2
Linked Allocation Strategy

Disadvantages of the Linked Allocation Strategy

- The pointers field for each block of data uses up storage space.
- There are some inefficiencies in the direct access of data.

#### **Indexed Allocation Strategy**

When using an *indexed allocation strategy*, the operating system creates a file directory to track all of the files on a disk, and an index block for each file. The file directory entry for each file includes the file name, just like with the contiguous and linked allocation strategies. However, instead of listing the starting block on the disk for each file, the file directory entry will include its index block number. The *index block* contains pointers to all of the data blocks belonging to that file. Again, the indexed allocation strategy has both advantages and disadvantages.


Advantages of the Indexed Allocation Strategy

- Grouping all pointers in one place increases reliability.
- Makes direct access of the contents of a file more efficient.

Disadvantages of the Indexed Allocation Strategy

 If a file is small, the index block containing all of the file pointers may contain a lot of wasted disk space.

Figure 6.3 (below) shows the allocation of disk space, the File Directory and the Index Block for a sample file on a hard disk using the Indexed Allocation Strategy.



File Directory

File	Index Block
File 1	20
File 2	•••

The entry for File 1 in the File Directory points to Index Block 20.

Each entry in the Index Block points to the location on the hard disk of the next piece of File 1.

Index Block 20	
3	
12 5	
11 14	
8	

Figure 6.3
Indexed File Allocation

## File Systems

File systems provide the conventions for the encoding, storage and management of data on a storage device such as a hard disk. They also provide the tools that help users to interact with files. Different operating systems use different file systems, and files created/stored using one file system are not always compatible with an operating system that uses a different file system. As discussed in Unit 2: Operating System Fundamentals, some of the more common file systems include:

- FAT12 (floppy disks)
- FAT16 (DOS and older versions of Windows)
- FAT32 (older versions of Windows)
- NTFS (newer versions of Windows)
- EXT3 (Unix/Linux)
- HFS+ (Max OS X)

Regardless of which file system an operating system uses, the file system provides the following conventions and information for file management:

- Data and time the directory (folder) or file was created.
- Date and time the directory or file was last modified.
- Directory or file size.
- Directory or file attributes.

Each file system has its advantages and limitations. For example, the *FAT12* (12-bit *File Allocation Table*) file system used for floppy disks is ideal use with media with small storage capacities (a floppy disk can hold approximately 1.2 MB of data). However, it limits the disk to a maximum of 512 entries in the file table, which means a maximum of 512 files and folders (even if each file is only 1 byte!

Two of the most common file systems are the FAT32 (32-bit File Allocation Table) and NTFS (New Technology File System) systems used by later versions of Windows. FAT32 is an older file system with a disk size limitation of 32 GB. FAT32 also limits the size of any single file to a maximum of 4 GB. NTFS allows for disk (or volume) sizes of up to 2 terabytes (TB), with an unlimited number of files and folders. It also eliminates the 4 GB file size restriction. Table 6.1 (below) compares the characteristics of FAT32 and NTFS.

Table 6.1
Comparison of FAT32 and NTFS

Comparison of FA132 and N1FS			
FAT32	NTFS		
<ul> <li>Used for older versions of Windows.</li> <li>Still used for smaller capacity storage devices, such as USB flash drives.</li> <li>Maximum disk (or volume) size of 32 GB.</li> <li>Maximum file size of 4 GB.</li> <li>File fragmentation issues.</li> </ul>	<ul> <li>Default file system for Windows XP, Vista, and Windows 7.</li> <li>Maximum disk (or volume) size of 2 TB.</li> <li>No maximum file size.</li> <li>No maximum number of files.</li> <li>Greater security features, including individual file compression, disk quotas, and file encryption.</li> <li>Easy to convert volumes from FAT32 to NTFS.</li> </ul>		

In today's modern computing environment, where large hard disk sizes are standard on most personal computers, NTFS is a much more efficient file system for users of Windows operating systems. The reason for this lies in how NTFS handles space efficiency. Unlike FAT16 and FAT32, NTFS does not use a file allocation table. It operates as an actual database in terms of how it keeps track of files and their associated clusters. NTFS also allows for smaller cluster sizes on large disks, which results in less wasted space than FAT32. With FAT32, the larger the disk becomes, the larger the cluster size becomes. (Remember that a cluster is the smallest unit of storage space that can be allocated to a file. Even if a cluster only contains the last 2 KB of data from a file, if the cluster is 1024 KB, then the remaining 1022 KB cannot be used to store any other data!).

The database created by the operating system to manage file and cluster information for NTFS does use up a lot of space compared to the cluster maps used by FAT32. For instance, on a 50 MB disk drive, the NTFS cluster database could take up as much as 10 MB of space (which, obviously, cannot then be used to store actual files). For today's larger disk drives, the amount of space used by NTFS to manage files is relatively small and is therefore not a concern. NTFS also provides greater file compression capabilities than FAT32, which means that the same files may actually take up less space on a disk. However, for smaller capacity storage devices (such as USB flash drives or flash memory cards used by mobile phones and digital cameras), FAT32 is still a useful file system because it wastes less space to manage files and their associated clusters.

When working with larger hard disks, NTFS also provides increased file security over FAT32. Individual file compression is one technique used to achieve increased file security. File compression means that redundant data in files (ex: all of the information that is common between all MS Word files) is removed while the files are being stored, and added back in when the files are in use. NTFS allows operating system administrators to assign disk space quotas to individual user accounts, preventing users from using too much storage space. File encryption means that one user's files are encoded in such a way that they cannot be accessed by another user on the same computer (if the two users are using different accounts and if the files are not marked as "shared" files).

#### Master Boot Record and Partition Table

When a disk is partitioned and formatted for use with one or more file systems and operating systems, a *Master Boot Record* and a *Partition Table* are created. The Master Boot Record is located in the first 512 byte sector of a partitioned hard disk. It is actually located outside of any of the partitions that are created on the disk, and it serves the following purposes:

- Holds the partition table.
- Contains a bootstrap loader to continue the computer booting process after BIOS has completed its initial boot routines.
- Identifies each individual disk with a unique 32-bit disk signature.

The Partition Table is part of the Master Boot Record of a partitioned disk. It contains information about the size and type of partitions that have been created on a disk, including both the primary and extended partitions. Since Partition Table is always 64-bits in size, and each entry in the partition table is 16-bits, a disk can contain a maximum of four primary

partitions (although an extended partition can be further artificially subdivided into logical drives).

## Interacting with File Systems

In this section, we will take a look at interacting with file systems from a user's point of view. Regardless of which file system your operating system uses, there are several concepts that are common to all operating systems. The first is the concept of a file. A file is simply a collection of data that is being used together. Pieces of a file may be scattered throughout a hard disk but, as we have seen, keeping track of all of those pieces is the responsibility of the File Manager. From a user's perspective, a file exists as a single item on a storage device. Files are organized based on file type (which is specified by a file extension) that associates the file with the application used to create (or view) it. Directories (or folders) are simply a means of organizing files so that they are easier for the user to find and manage. Sub-directories (or sub-folders) can exists inside of other folders, and act as a means of further organizing files for ease of management. For example, you can create a folder called "Operating System Fundamentals" to store all of your notes and assignments for a course on operating systems. Inside of that parent folder, you could create several child folders for each unit. A folder for this particular unit could be called "File Systems." You might also decide to keep your assignments in a separate folder called "Assignments."

In most operating systems, directories (or folders) are organized into a hierarchical structure. That is, they are organized from a root level (such as the C:\ drive in Windows), which then branches out like a tree into all of the directories and subdirectories created by the user. Some directories are created at the root level by the operating system itself, such as C:\Windows (which stores all of the files used by the operating system), or C:\Programs (which stores the files belonging to most of the applications installed on the computer). Figure 6.4 (below) shows the hierarchical structure of folders on a Windows XP system (as viewed using Windows Explorer).




Figure 6.4
Hierarchical File Structure in Windows XP

The location of a file in a directory on a computer is referred to as its *path*. When we give the location of a file, we can provide it as either an *absolute path* or a *relative path*. An absolute

path provides the complete path to the file from the root level. For instance, in the example described above for folders you created for an operating systems course, the absolute path to that folder might be:

 $\hbox{$C:\Documents and Settings\Users\User 1$\My Documents\Operating System Fundamentals\Assignment\_1.doc} \\$ 

This path provides the absolute location in the hierarchical file structure of a Microsoft Word document called Assignment\_1.doc. We could also describe the location of this file using a relative path. A relative path is simply the path to a file from a predetermined relative level. For instance, we could provide the relative path for Assignment 1.doc as:

My Documents\Operating System Fundamentals\Assignments\Assignment 1.doc

Alternately, we could provide the relative path from the course directory:

Operating System Fundamentals\Assignments\Assignment 1.doc

Windows XP and Vista provide tools for navigating and managing files and folders. The most common tool is *Windows Explorer*, which is shown in Figure 6.4 (above). Windows Explorer shows the hierarchical directory structure of the folders in the left pane, and shows the contents of the currently selected folder in the right pane. The hierarchical file structure for in Windows Explorer usually shows shortcuts to the "Desktop" and the user's "My Documents" folders at the top of the left pane, followed by "Local Disk C:," which is the root level of the primary hard disk (or hard disk partition).

Windows Explorer also allows the user to specify how information about files will be displayed in the right pane. For instance, you can show just icons or tiles for each file (with a graphical depiction of the file type). You could also list all of the files, along with their associated sizes, attributes and their creation and modification dates. In addition, Windows Explorer provides the user with the ability to manipulate files and folders. Users can use Explorer to rename, delete, copy, paste, move or even create new files and folders.

File attributes allow the user control access to files, as well as the archiving and backup of files. The most common file *attributes* in Windows are:

- Read Only the file can be read, but not modified.
- Hidden the file is hidden from other users (usually used to hide critical operating system files so that they are not accidently modified by users).
- Archive the file is marked for archiving, so that it will be included when the next file system backup operation is carried out.
- Index the file is indexed in a database so that it will be easier for the operating system to find and retrieve the file from the disk when it is needed.

Of course, there are many other advanced attributes in Windows XP and Vista that can be set for particular users or groups of users.

Like Windows, Linux also uses a hierarchical file structure. Unlike Windows, the root level in Linux is actually called "Root." Even when logged into a Linux system as an administrator, the "Root" directory is usually hidden from the user when using the File Manager tool. As shown in Figure 6.5 (below), when a user is logged in with root level privileges, the *Linux File Manager* will display a warning to prevent the user from accidentally manipulating critical operating system files.




Figure 6.5
The Linux File Manager Tool

As with Windows Explorer, the Linux File Manager tool provides a graphical depiction of a disk's hierarchical file structure in the left pane. Again, icons depicting a selected directory's contents are shown in the right pane, and the user can select several options for what information is displayed about the files and folders listed.

# **Unit Summary**

When using any computer, both the system and the user will need to store files when they are not in use. Because the RAM used to store data and instructions while they are in use is temporary, permanent data storage is achieved using large capacity storage devices such as magnetic hard disks. The operating system's File Manager is responsible for managing the data stored on a storage device, which includes providing a file system with rules for encoding, storing, organizing and retrieving data. This data is typically organized into files and folders in a hierarchical structure. Modern operating systems use a variety of strategies for allocating and managing the space used by pieces of files, which are often scattered (or fragmented) throughout a hard disk. The most common are the Contiguous Allocation, Linked Allocation and Indexed Allocation strategies. Each strategy uses a different method of allocating and tracking space for files, and each has advantages and disadvantages.

Different operating systems use different file systems for encoding and managing data. Two of the most common file systems are FAT32 and NTFS. While NTFS is used by newer versions of Windows (including XP, Vista and Windows 7), FAT32 is still useful because it is more efficient for use with smaller capacity storage devices (such as USB flash drives, memory cards, or flash memory in mobile devices).

When a hard disk is formatted and partitioned for use with a file system (and an operating system), a Master Boot Record is created before the first primary partition. The Master Boot Record contains instructions for booting a system once BIOS routines have been completed. It also contains a Partition Table, which describes the partitions that have been created on the disk.

From a user's perspective, files exist on a storage device as single items. Files are categorized by file type, which is indicated by a file extension. The extension associates a file with the application that will use it. Files also have associated attributes, which can be used to improve file security and management. Files are organized into directories (or folders) and subdirectories (or subfolders). Windows operating systems provide a tool called Windows Explorer which helps the user to graphically navigate and manipulate files and folders in the hierarchical file structure of a disk. A similar tool, called the File Manager, is provided by Linux.

# **Key Terms**

Absolute path

Archive

Attributes

Contiguous

Contiguous allocation strategy

Directory

Disk quota

End of File (EOF) indicator

Extension FAT12

File

File compression File directory File encryption File Manager File system

File type Folder

Hidden

Hierarchical structure

Index

Index block

Indexed allocation strategy Linked allocation strategy

Linked allocation strated Linux File Manager

Master Boot Record

**NTFS** 

File Allocation Table

Partition Table

Path

Read Only

Relative path

Root

Shared files

Subdirectory

Subfolder

Volatile memory

Windows Explorer

## **Review Questions:**

- 1. List any 5 responsibilities of the File Manager.
- 2. Name the 3 common Data Storage Strategies. Briefly describe how they work.
- 3. What are the advantages and disadvantages of the Indexed Allocation Method?
- 4. What are the advantages and disadvantages of the Linked Allocation method?
- 5. In what ways are NTFS more reliable than FAT32 file system?
- 6. How does NTFS handle space efficiency?
- 7. List all security features provided by NTFS.
- 8. Describe the purpose of the Master Boot Record and Partition Table.
- 9. Describe the hierarchical file structure used by Windows.
- 10. What is the difference between an absolute path and a relative path to a file?
- 11.List and describe four file attributes associated with files in NTFS.

# **Glossary**

Absolute path – the complete path to a file/folder on a storage device from the root level.

Access time – the amount of time it takes to retrieve a page from either main memory or virtual memory once it has been requested by the CPU.

Active partition – a partition that contains an operating system.

Address – location in memory.

AGP – Accelerated graphics port (used for video cards).

Algorithm – a set process or pattern to follow to complete a task.

ALU – Arithmetic Logic Unit. A component inside the CPU that performs the mathematical calculations.

Application software – Software accessed by the user to perform tasks using a computer or computerized device.

Archive – a file attribute indicating that a file has been marked for archiving/backup the next time a partial backup operation is executed.

Attributes – characteristics assigned to a file to control user access levels and/or indicate whether a file has been marked for archiving or indexing.

Base address – the address of the beginning block of memory assigned to a process when it is loaded into memory, supplied by the operating system.

Best fit – a memory allocation strategy that finds the smallest block of free space that will meet the current process needs. The idea is to minimize wasted space in main memory (RAM).

BIOS – Basic Input/Output System. Contained on a ROM chip on the motherboard. Contains instruction set to control basic input and output devices needed to start a computer and install an operating system on a new computer.

Blackberry OS – specialized operating system for Blackberry mobile devices.

Block I/O devices – I/O devices that receive and transmit data in blocks of characters.

Blocked – a process state where the process is prevented from being executed.

Blocking – preventing a process from being marked as ready for execution.

Boot record – the first sector on a magnetic disk. It contains a bootstrap loader, which can be used to boot a computer system.

Bootstrap loader – a small program that contains instructions for finding and starting the operating system.

Busses – System for exchanging electronic data between devices connected to the motherboard.

Character I/O devices – I/O devices that send and receive data one character at a time.

Client-server model – An operating system model consisting of two modes. The User Mode is the client, and the Kernel Mode is the server.

Cluster – the smallest unit of space on a magnetic disk that can be used to store data.

Command Line Interface – An operating system interface using typed commands from the user.

Command Line Interpreter – Interprets typed commands and translates them into system calls to be executed by the CPU.

Computer architecture – The structure of how all of the parts of a computer are interconnected.

Contiguous – segments (pieces) of a file are stored in sequence in adjacent spaces on a storage device.

Contiguous allocation strategy – a file storage strategy that involves allocating contiguous (adjacent) spaces on a storage device to a file.

Control Unit (CU) – A component in the CPU that controls all activities inside the processor.

Cooperative multitasking – A system whereby applications control their own processor scheduling, and cooperate to share access to the CPU and system resources.

CPU – Central Processing Unit. The brain of the computer. A microchip that carries out the processing of software commands.

Critical section – a part of code (or a set of variables) that must be accessed in a controlled way when dealing with a multi-threaded system.

Cycle – a single "tick" of a system clock. The smallest unit of time in which any computer process can be completed.

Cylinder – all of the adjacent tracks from the multiple platters of a magnetic hard disk.

Data buffer – a memory block assigned by the operating system to temporarily store data that will be transferred to another device once the buffer is full.

Deadlock – when two or more processes require I/O resources that are in use by the other processes, and neither process is willing to release the resources so that they can be used by another process. Results in an inability for either process to complete its task.

Device controller – a hardware component on the motherboard or an expansion card that handles controlling a type of I/O device by communicating with device drivers, translating operating system instructions, and programming them to be carried out by the devices.

Device drivers – Instructions for the control of hardware devices. Provided by the operating system.

Directory – a means of organizing files so that they are easier for the user to find and manage (see *Folder*).

Disk quota – a specified amount of space on a storage device that has been assigned to a specific user.

Dispatch – the operating system has decided that the process should start running.

DMA – Direct Memory Access. A means of accessing system resources like RAM without going through the CPU.

DMA Controller – Component that controls DMA.

DOS – Disk Operating System. An example of a command line interface operating system. Precursor to Windows.

Dual-core – a computer system containing two processor units (CPUs).

Early Kernel Initialization – Initialization of the part of the core of the operating system while the CPU is still functioning in Real Mode. Includes the loading of device drivers needed to utilize RAM and the extended addressing system.

Elevator algorithm – a method used to determine the most efficient order for retrieving requested data from a storage device such as a magnetic hard disk.

End of File (EOF) indicator – a marker in the entry for the last piece of a file in a File Table to indicate to the operating system that all pieces of the file have been retrieved.

Exit – a temporary process state indicating that the process is marked for removal from the process table, and should not be selected by the operating system for execution.

EXT3 – A file system used by Linux.

Extension – a three or four character designation at the end of a filename that indicates which type of application (or for which purpose) a file is associated.

FAT12 - a 12-bit File Allocation Table file system used for floppy disks.

Fetch—Decode—Execute cycle – Cycle used by the CPU to find and processes instructions stored in RAM.

FAT16 – A 16 bit version of the File Allocation Table file system used by earlier versions of the Windows operating system.

FAT32 - A 32 bit version of the File Allocation Table file system.

File – a collection of pieces of data that belong together, and that are retrieved and loaded together when used by an application.

File Allocation Table (FAT) – a table created when a disk is formatted. It contains a listing of all of the clusters on a disk, and how they are currently being used to store data.

File compression – the removal of redundant (program specific) information from a file, leaving only its unique contents, for the purpose of reducing the amount of storage space required on a disk.

File directory – a record maintained by the File Manager to track file names and their associated blocks of storage space. The file directory for the Contiguous allocation strategy includes the file name, start block number, and the file size. The file directory for the Linked allocation strategy includes the file name and the start block number (while the blocks themselves will contain pointers to the next block belonging to the file). The file directory for the Indexed allocation strategy will include the file name and an index block number (the index block will contain the information about the actual blocks associated with the file).

File encryption – using an encryption method to encode files so that they can only be accessed by the user who created (or owns) them.

File Manager – part of the operating system that is responsible for the long term storage and management of data stored on a storage device such as a hard disk.

File system – A method of encoding, organizing and providing access to information stored on a computer or storage device.

File system – provide the conventions for the encoding, storage and management of data on a storage device such as a hard disk. They also provide the tools that help users to interact with files.

File type – files are organized based on file type (which is specified by a file extension) that associates the file with the application used to create (or view) it.

First come first serve – a process scheduling algorithm where the first process marked with a process state of "Ready" that is found in the Process Table will be executed.

First fit – a memory allocation strategy that finds the first available block of free space that will meet the current process needs. The idea is to minimize the amount of time it takes to analyze available memory and allocate free space to a process.

First In First Out (FIFO) – a virtual memory page replacement policy that removes the oldest page from RAM (first page listed in the Page Table) and replaces it with a new page from virtual memory (and places it as the last page listed in the Page Table).

Folder – a means of organizing files so that they are easier for the user to find and manage (see *Directory*).

fork() - a Unix system call used to create new processes.

Formatting – preparing a magnetic storage device to hold data. Involves the creation of tracks, sectors and clusters, as well as a file system on the disk.

Fragmentation – a condition that results from repeated allocation and de-allocation of space in memory, leaving behind blocks of wasted space that are not large enough to be useful for new processes.

Front Side Bus – the main system bus used to exchange information between the CPU, RAM, AGP and I/O busses.

Full Kernel Initialization – Initialization of the remainder of the core of an operating system after the CPU has switched to Protected Mode.

Gigahertz (GHz) – one billion cycles per second. The typical measurement of speed for modern system clocks and processors.

Give – when a thread gives a semaphore it is potentially waking up another thread that is waiting (see *Raise*).

Graphical User Interface – An operating system interface using graphics and menus to provide the user with access to applications, files, and system resources.

Graphics – Images drawn on the monitor or other display device.

Graphics adaptor – a specialized device controller for graphics devices, such as monitors and projectors.

Hertz (Hz) – measurement of computer speed in cycles per second. One Hertz (1 Hz) = one cycle per second.

HFS+ -- A file system used by the Mac OS X operating system.

Hidden – a file attribute that indicates that a file is normally hidden from users (typically used to protect critical system files from accidental modification or deletion).

Hierarchical structure – files and folders are organized from a root level (such as the C:\ drive in Windows), which then branches out like a tree into all of the directories and subdirectories created by the system and the user.

High-level formatting – disk formatting carried out by the user. Involves the creation of a file system and the installation of an operating system.

Hit – when a page is requested by the CPU and it is currently located (found) in RAM.

Hit ratio – the number of times that requested pages are found in RAM divided by the number of page requests actually issued.

I/O Busses – Busses used to exchange information between Input/Output devices, and to provide I/O devices with access to the main system bus.

IDE controller – a specialized device controller for devices connected to the motherboard by EIDE cables (such as hard disks and CD/DVD drives).

Index – a file attribute that indicates that a file is indexed in a database so that it will be easier for the operating system to find and retrieve the file from the disk when it is needed.

Index block – a block of space on a storage device used to store information about all of the blocks of space that are associated with a filename.

Indexed allocation strategy – a file storage strategy that uses an index block to contain information about the locations of pieces of a file on a storage device.

Input/Output resources – I/O devices that are available to be used by processes.

Instructions – Program commands.

Inter process communication – the exchange of information between two processes (or threads).

Interface (I/O) Unit – A component inside the CPU that regulates information entering and leaving the processor.

Interrupt – i) A request from a device for access to the CPU.

ii) the operating system has decided that the process should stop running so that another process can have a turn.

Interrupt Controller – A component on the motherboard that controls sending interrupts to the CPU, and prioritizes the requests coming from different devices.

Interrupt handler – part of the Lower Half of a device driver that handles issuing interrupt request to the interrupt controller when a device requests to either send or receive data from the processor.

Interrupt-driven I/O devices – Devices that gain access to the CPU using requests called interrupts.

ISA – Industry Standard Architecture. A bus system used by older and slower I/O devices.

Kernel mode – The operating system mode that handles all of the background functions of the operating system, and the management of system resources.

Keyboard controller – a specialized device controller that handles devices including the keyboard and PS/2 mouse. Most modern personal computer motherboards no longer include a keyboard controller, as these functions have been integrated into more advanced chipsets on the motherboard.

Layers – The levels of interaction for computerized devices, including the user, applications, operating system and hardware.

Least Frequently Used (LFU) – a virtual memory page replacement policy that replaces the page in RAM that has been used the least with the new page requested from virtual memory.

Least Recently Used (LRU) – a virtual memory page replacement policy that replaces the page in RAM that has not been used for the longest amount of time with the new page requested from virtual memory.

Linked allocation strategy – a file storage strategy that inserts pointers at the end of each block of a file to indicate the location of the next block associated with the file on a storage device.

Linux – An open-source GUI operating system platform derived from UNIX.

Linux File Manager – a file management utility provided by Linux-based operating systems.

Logical drive – an artificial division of an extended partition on a hard disk that involves assigning a drive letter to a specified amount of space, so that it appears to be an actual partition or physical disk for file management purposes.

Lower Half – part of a device driver handles taking requests from the shared requests list, and programming them for the device control to carry out the instructions.

Low-level formatting – formatting of a magnetic storage device carried out at the factory, involving the creation of tracks and sectors on the surface of the disk.

Magnetic disk storage – storage devices that use magnetic read/write heads to manipulate the alignment of magnetized particles on the disk so that the particles can be read by the computer as binary code.

Main memory – the physical memory installed on the motherboard (RAM).

Master Boot Record – located in the first 512 byte sector of a partitioned hard disk, the MBR contains the partition table, a bootstrap loader, and a unique disk identification signature.

Master Boot Record (MBR) – A sector at the beginning of a primary hard disk that contains information about the organization of partitions on the disk.

Max OS X - An operating system used by Apple Macintosh computers.

Memory – used by the computer to temporarily store data and instructions that are currently in use.

Memory manager – the part of the kernel (core) of the operating system that is responsible for efficiently managing all memory resources including RAM and virtual memory, and allocating memory space to applications and processes as needed.

Message queue – an inter process communication system where one process (the *sender*) places a message into a queue (for delivery by the operating system), and another process (the *receiver*) listens to the queue (often in a blocked state) waiting for the messages to arrive (see *Pipe*).

Mode – A level of an operating system used to separate resources accessible directly by the user and the operating system itself.

Motherboard – The largest circuit board in a computer. It connects all other components to each other and to the CPU.

Multicore – a computer system consisting of multiple processor units (CPUs).

Multiprocessor – a computer system consisting of multiple processor units (CPUs).

Multitasking – The ability of an operating system to run multiple applications at the same time.

Multithreading – The ability of a CPU to process multiple instructions at the same time.

Network adaptor controller – a specialized device controller that handles controlling network interface cards (NICs).

New – a temporary process state used for the creation and addition of new processes in the Process Table, so that the operating system will not select the process for execution.

Non-deterministic solution – a coding (programming) solution where it is not possible to predict the outcome each time the code is executed.

Non-preemptable I/O resources – I/O resources that cannot be preempted, or taken away from a process, until the process using the resources has completed its task.

Non-preemptive switching – the operating system never interrupts the currently executing process, but waits for the process to release control voluntarily (see *Cooperative Multitasking*).

Northern Bridge – A component that regulates the flow of information along the Front Side Bus between the CPU, AGP, RAM, and the I/O busses.

NTFS – New Technology File System. File system used by the Windows XP, Windows Vista and Windows 7 operating systems.

NTFS – New Technology File System. The 64-bit file system that is the primary file system used by newer versions of Windows (such as Windows XP, Vista, and Windows 7).

Operating system – System software concerned with the operation of the hardware, and managing access to system resources.

Page – a segment of a process or thread that has been broken down into a unit of fixed size in order to manage the storage of the data/instructions in RAM and virtual memory.

Page fault – an error that is generated when a page is requested by the CPU, but it is not currently listed in the Page Table (and, therefore, is not currently stored in RAM). The memory manager will then be responsible for located the requested page in virtual memory, and loading it into RAM so that the instruction can be re-executed by the CPU.

Page file – a portion of a storage device (typically a hard disk) that has been allocated for use as virtual memory (see *Swap file*).

Page request – a request by the CPU for a page needed in order to execute an instruction set.

Page table – a record that is maintained by the memory manager to track the location and status of all pages in main memory (RAM).

Paging device – a storage device that is being used to house a page file (typically a hard disk).

Palm OS - An operating system used by Palm PDAs and mobile devices.

Partition – a physical division of a hard disk.

Partition Table – part of the Master Boot Record of a partitioned disk. It contains information about the size and type of partitions that have been created on a disk, including both the primary and extended partitions.

Partitioning – formatting a hard disk into multiple units that act as separate disks, and that can be used for different purposes, or further formatted using different file systems and/or operating systems.

Path – the location of a file or folder on a storage device.

PCI – Peripheral Component Interconnect. A bus system used by newer I/O devices.

PDA - Personal Digital Assistant.

Physical memory – memory (RAM) installed on the motherboard.

Pipe – an inter process communication system where one process (the *sender*) places a message into a queue (for delivery by the operating system), and another process (the *receiver*) listens to the queue (often in a blocked state) waiting for the messages to arrive (see *Message queue*).

Platter – a metal or ceramic disk inside of a hard disk drive. A typical hard disk contains several platters.

Polling – a system where a thread continuously checks for the value of a variable until a required value is found (this system uses excessive CPU time, and consumes a lot of processing power).

Preemptable I/O resources – I/O resources that can be taken away from a process so that they can be used by another process.

Preemptive multitasking – A multitasking model where the operating system regulates access to the CPU and system resources by applications and hardware.

Preemptive switching – the operating system always has control of the computer by way of the interrupt service routine and will always be able to stop the currently executing process (see *Preemptive Multitasking*).

Priority – a ranking system used to determine which processes should be considered for execution first.

Priority inversion – a problem that occurs when a lower priority process prevents a higher priority process from executing because it is using too much processor time.

Priority-based scheduling – a process scheduling algorithm that uses process priorities to determine which process should be executed next. The scheduler will look for the highest priority process that is marked as "Ready" in the Process Table.

Process – An instance of a program, consisting of one or more threads, that is currently be executed by a computer system.

Process – the actual execution of program instructions, along with the memory and I/O devices assigned to execute the given instructions.

Process scheduling – using an algorithm (strategy) to determine which process should be executed next.

Process state – The current status of a process that is being executed, or that is waiting to be executed by the CPU.

Process Table – A tool used by the operating system to keep track of all processes and their current state.

Processor preservation – the ability to hide multi-tasking concepts from the applications so that they do not know that other applications are running at the same time and sharing the CPU.

Program Counter – A special register in the CPU that is used to hold the address of the next instruction code to be retrieved from memory.

Programmed I/O devices – Input/Output devices that require direct and complete control from the CPU.

Protected mode – Also called protected virtual address mode. Allows the operating system, CPU and applications to take advantage of extended memory addresses and other system resources, such as virtual memory, paging and safe multitasking.

pSOS – A specialized operating system for aircraft systems.

QNX - A specialized operating system for aircraft systems.

Quad-core – a computer system consisting of four processing units (CPUs).

Quantum – the amount of time assigned by the Process Scheduler for a process to execute (have the attention of the CPU) (see *Time slice*).

Raise – when a thread gives a semaphore it is potentially waking up another thread that is waiting (see *Give*).

Race condition – a sequence of code executed by two or more threads in which the end result depends on which thread finishes first.

RAM – Random Access Memory. High speed, temporary data storage on specialized cards attached to the motherboard. Used to store data and instructions currently being used by the system.

Random replacement – a virtual memory page replacement policy that works by randomly selecting pages from RAM to be swapped for pages from virtual memory. Typically, random replacement does not work very effectively.

Read only – a file attribute indicating that a file can be read, but cannot be modified by users.

Read/write arm – component inside of a hard disk drive that moves the read/write head across the surface of a platter.

Read/write head – component in a floppy disk drive or hard disk drive that reads and writes data on the surface of a magnetic storage disk.

Ready – a process state where the process is marked as ready (waiting) for execution by the CPU.

Real mode – Also called real address mode. A system state where the CPU and the computer are only capable of using a 16 bit addressing system and approximately 1 MB of memory built into the motherboard.

Registers - Components inside the CPU used to store data.

Relative path – the path to a file or folder on a storage device, relative to a predetermined parent folder.

Replacement policy – a strategy used by the memory manager to manage swapping pages between RAM and virtual memory.

Root – the base level of a hierarchical file structure on a storage device.

Root directory – lists all of the files and subdirectories currently stored on the disk.

Round-robin scheduling – a process scheduling algorithm that executes each process from the Process Table in sequence, regardless of priority.

Running – a process state where the process is currently being executed by the CPU.

Scheduler – a piece of software code (it is generally a function) that is included as part of the operating system, and that is responsible for analyzing the Process Table and selecting the next process to be executed.

Second Chance – a version of the FIFO virtual memory page replacement policy that uses a reference bit to track whether a page in RAM has been used within a set amount of time. If the reference bit indicates that a page has been recently referenced, it will not be swapped into virtual memory.

Sector – a physical division of a track (concentric circle) on the surface of a magnetic storage disk.

Self-yield – an inter process communication method where a process checks for the availability of a required variable, and voluntarily goes into a blocked state if the variable is not available (allowing another process or thread to gain access to the CPU).

Semaphore – a special type of variable used in inter process communication to support the wait (take) and raise (give) operations (see *Signal*).

Shared files – files that have been marked as shared so that they can be accessed by users other than the original creator/owner of the file.

Shared memory – when multiple threads have access to the same piece of memory, and each has the ability to read and write to that memory location at the same time.

Shared requests folder – part of a device driver used to store requests that have been received from the operating system with instructions to be carried out by a device.

Shortest task remaining – a process scheduling algorithm that attempts to determine which process in the Process Table has the shortest time remaining to be completed, and then selects that process to be executed next.

Signal – a special type of variable used in inter process communication to support the wait (take) and raise (give) operations (see *Semaphore*).

Sleep – a command that causes a process (or thread) to go into a blocked state for a specified amount of time.

Southern Bridge – A component that regulates the flow of electronic information from the Input/Output busses to the main system bus.

Special purpose operating system – an operating system designed for specialized computerized devices.

Starvation – when a process never gets a chance to run because a higher priority process is using too much processor time.

State changing – changing the state of a process to mark it as either *Running*, *Ready*, *Blocked*, *New* or *Exit*. This task is usually the responsibility of the operating system.

State machine – a diagram used to illustrate the states of a machine (computer), and the actions that would cause the machine to change its state.

Subdirectory – a directory that has been created inside of another directory (see *Subfolder*).

Subfolder – a folder that has been created inside of another folder (see *Subdirectory*).

Swap file – a portion of a storage device (typically a hard disk) that has been allocated for use as virtual memory (see *Page file*).

Swapping – exchanging pages between RAM and virtual memory when pages residing in virtual memory are needed by a process being executed by the CPU.

Symbian – A specialized operating system used by mobile devices.

Synchronization – a system where multiple processes (or threads) must coordinate in some way to share resources and to perform required actions in a predetermined order.

Synchronization variable – variables that are used to help coordinate communication, the sharing of resources, and the scheduling of actions between processes (or threads).

System bus – the main data path (usually 32, 64 or 128-bits wide, depending upon the type of motherboard) that connects the CPU to RAM, the graphics controller, and all of the I/O busses.

System call – Processes that have been converted into system actions to be executed by the CPU.

System clock – component on a motherboard that regulates the timing of processes carried out by a computer system.

System software – An operating system.

Take – an operation where a thread requests a signal (semaphore), and then either takes control if the signal is available, or goes into a blocked state until the signal is available (see *Wait*).

Thrashing – a condition that exists when the memory manager is swapping pages between RAM and virtual memory too frequently. Thrashing can result in increased processing time and undue wear and tear on a hard disk.

Thread – a single sequence of instructions to be executed. Often a subset of instructions (or a *mini-program*) that is part of a larger program.

Time slice – the amount of time assigned by the Process Scheduler for a process to execute (have the attention of the CPU) (see *Quantum*).

Traces – Metal lines on circuit boards used to transmit electronic data in binary form.

Track – a concentric circle on the surface of a magnetic storage disk.

UNIX – A command line interface operating system designed in the 1960's for large scale computer and network systems.

Unbuffered – data transfer that does not use a buffer to temporarily hold the data before it is transmitted to a device.

Unmanaged exception – an error that cannot be handled by the program currently being executed.

Upper Half – part of a device driver that handles taking requests from the operating system and placing them into the shared requests folder so that they can be programmed to be carried out by the device.

USB – Universal Serial Bus. An I/O bus designed for newer, high-speed Input and Output devices.

USB controller – a specialized device controller that handles controlling all devices connected to a computer by USB.

User mode – The operating system level accessed directly by the user to run applications.

Variable – a value that can be changed, and that is used to help determine the actions to be taken by a set of program instructions.

Virtual computer – A simulated computer operating system run from inside of another operating system using a virtualization application.

Virtual memory – a system that uses part of a storage device (typically a hard disk) to act as if it is extra RAM, thereby increasing the total amount of memory available for processing.

Virtual memory space – a memory addressing system maintained by the memory manager to allocate space to pages in both physical and virtual memory.

Virtualization – Simulating an operating system using a virtualization application to translate one operating system's functions into instructions understand by the actual operating system.

Volatile memory – RAM memory that loses its contents when its power supply is interrupted.

Voltage good line – a wire used by the computer to test electrical voltage when the system is first turned on.

VxWorks – A specialized operating system for aircraft systems.

Wait – an operation where a thread requests a signal (semaphore), and then either takes control if the signal is available, or goes into a blocked state until the signal is available (see *Take*).

Windows Explorer – a file management tool provided by Windows operating systems.

Windows Mobile – A specialized operating system for mobile devices.

Windows Ready Boost – a feature of newer Windows operating systems (Windows Vista and Windows 7) that allows removable storage devices (such as USB flash drives) to be used to expand virtual memory.

Worst fit – a memory allocation strategy that finds the largest available free space in RAM to store date. The idea is to minimize wasted space in RAM by leaving behind the largest possible chunk of free space, thereby increasing the possibility that the memory fragment will be large enough to be useful to another process.

## References

- Andrews, Jean (2007). A+ Guide to Managing & Maintaining Your PC Comprehensive, 6 ed. Edition Canada: Thompson Course Technology
- Palmer, Michael and Walters, Michael. (2007). *Guide to operating systems, enhanced edition*. Boston, MA, USA: Thomson Course Technology.
- Stallings, William (2009). *Operating systems: Internals and design principles*. 6 ed. Upper Saddle River, NJ, USA: Pearson Education International.