

Oliver Killane

14/02/22

### Lecture Recording

Lecture recording is available here

# The Transport Layer

Provides connection ( $\mathbf{TCP}$ ) and connection-less ( $\mathbf{UDP}$ ) services to allow communication between  $\mathbf{end}$ -systems/hosts.

- Connection decision is made at this level.
- Only runs on end hosts, not on routers or switches.
- Requires the lower layers in order to operate (Network, Data-link and Physical).
- Protocols in this layer work on the assumption that the lower levels are working, however must
  consider that IP is best effort, and gives no guarantees on data integrity or order of delivery
  for packets.

Other layer-4/Transport Layer protocols include:

$\mathbf{QUIC}$	A UDP based transport layer designed by google employees to replace TCP us-			
	ing multiple multiplexed connections using UDP, focused on improving HTTP			
	performance. The wikipedia article goes into more detail.			
UDP-Lite	A UDP like connectionless protocol that allows potentially damaged data pay-			
	loads to be propagated to the application layer, and hence allows the application			
	layer to discern data integrity and act accordingly (Wikipedia article).			
DCCP	The Datagram Congestion Control Protocol is a message-oriented protocol			
	that uses reliable connection setup, close and has explicit congestion notification			
	(Wikipedia article).			
$\mathbf{SCTP}$	The Stream Control Transmission Protocol is a message-oriented protocol			
	based on <b>UDP</b> (Wikipedia article).			
RSVP	The Resource Eservation Protocol is used to reserve network resources to			
	ensure quality of service (Wikipedia article).			

### **Terminology**

Layer	No	Data Name
Application	5	Data
Transport	4	TCP Segments (created by segmentation) of UDP Datagrams
Network/Internet	3	IP Datagrams (a.k.a. packets) (created by fragmentation)
Data Link	2	Frames
Physical	1	Bits

#### Port Numbers

#### Definition: Ports

Used to connect applications together/ separate different application's connections.

The transport layer uses port numbers to differentiate between many different network communications. Each application on a host uses a unique port number.

Port numbers are cross-platform, meaning on many different devices, computer architectures and OSes they are the same for the same types of applications (e.g HTTP, IMAP).

Ports		8	Use
0	$\rightarrow$	1023	(well known/reserved for certain protocols)
1024	$\rightarrow$	49151	(for any user application to use or register, e.g HTTP $\rightarrow 80$ )
49152	$\rightarrow$	65535	(dynamic/ephemeral/private) and are used by clients temporarily)

## TCP

#### Definition: Transission Control Protocol (TCP)

A connection-oriented transport layer protocol.

- Data is split into **segments**.
- Reliable data transfer (integrity of data and (possibly) ordered delivery)
- Not secure (other mechanisms need to be used to ensure security)
- Can offer stream connections (ordered delivery, only accept segments in order, e.g received 4, waiting for 5, but received 6, 7, ignore 6 and 7 until 5 is received.)
- Congestion Control (avoids destructive congestion on the network)
- Requires A handshake to start the connection.
- Full-Duplex so both sides can send and receive at the same time.

To identify a socket connection we use the **IP Address**, port number and protocol (**TCP/UDP**).

61.195.17.146 : 80 TCP

IP Address Port Protocol

### Definition: Berkely Socket Interface

3. LISTEN

An interface adpoted by all UNIX systems and windows.

1. **SOCKET** Create a new communication endpoint.

2. BIND Attach a local address to the socket. The client and server both bind a transport level address and name to the locally created socket.

Prepare for / Annouce ability to accept, n connections. The kernel now waits for connections from clients.


**4. ACCEPT** Block until some remove client wants to establish a connection, hence the server can now wait, receive a request and choose to accept or deny a connection.

**5. CONNECT** Attempt to establish a connection. When a client connects it must provide the full transport-level address to locate the socket.

6. SEND Send data over the connection.7. RECEIVE Receive data over a connection.

8. CLOSE Release the connection, communication ends when the socket is

#### A connection-oriented example:



In a connection-less scenario, LISTEN, ACCEPT and CONNECT are not required.

#### Example: Simple Java Web Client

```
import java.io.BufferedReader;
    import java.io.IOException;
    import java.io.InputStreamReader;
    {\color{red} \mathbf{import}} \hspace{0.2cm} \mathbf{java.io.OutputStreamWriter};
 4
 5
    {\color{red} \mathbf{import}} \quad {\color{gray}\mathbf{java.io.PrintWriter}} \; ;
    import java.net.Socket;
    import java.net.UnknownHostException;
    public class exampleTCPClient {
9
10
         // connect to localhost (this machine) on port 2251
11
         static final int port = 2251;
12
         static final String ip = "127.0.0.1";
13
14
         public static void main(String[] args) throws UnknownHostException
             → , IOException {
// Create a socket and implicitly connect.
15
16
             Socket socket = new Socket(ip, port);
17
18
              // create reader and writer for sending and receiving
             BufferedReader receive = new BufferedReader (new
19
                 → InputStreamReader(socket.getInputStream()));
20
              PrintWriter send = new PrintWriter(new OutputStreamWriter(

→ socket.getOutputStream()), true);
21
22
             // send a message from console input
23
             send.println(System.console().readLine());
24
              // print a received message from the socket to the console
25
26
             System.out.println(receive.readLine());
27
28
             // close the socket
29
             socket.close();
30
31
    }
```

#### Example: Simple Java Web Server

```
import java.io.BufferedReader;
    import java.io.IOException;
    import java.io.InputStreamReader;
    {\bf import \ java.io.Output Stream Writer};\\
4
    import java.io.PrintWriter;
    import java.net.ServerSocket;
    import java.net.Socket;
9
    public class exampleTCPServer {
10
        static final int port = 2251;
11
        public static void main(String[] args) throws IOException {
12
13
            // Bind and set socket to listen
14
            ServerSocket serverSocket = new ServerSocket(port);
15
16
             // status message
17
            System.out.println("Started listening on port" + port);
18
19
            while (true) {
                // accept a new connection and create socket to handle
20
                     \hookrightarrow connection.
21
                Socket socket = serverSocket.accept();
22
23
                   create reader and writer for sending and receiving
                 BufferedReader receive = new BufferedReader (new
24
                     → InputStreamReader(socket.getInputStream()));
25
                 PrintWriter send = new PrintWriter(new OutputStreamWriter(
                     → socket.getOutputStream()), true);
26
27
                 // send a message from console input
28
                 send.println(System.console().readLine());
29
30
                 // print a received message from the socket to the console
31
                System.out.println(receive.readLine());
32
33
                 // close the socket
34
                 socket.close();
35
            }
36
        }
37
```

To handle many clients, a thread must be created per client, rather than the basic forever loop as above.

#### **Segments**

# Definition: TCP Segment

A wrapper for  $\mathbf{TCP}$  data, transmitted within the Network Layer protocol (e.g  $\mathbf{IPv4}$  or  $\mathbf{IPv6}$ )

### Definition: Maximum Segment Size (MSS)

The maximum amount of application data transmitted in a single segment (header size is not included).

Usually related to the MTU of the connection to avoid network level fragmentation (splitting segments in the network layer into multiple packets).


### Definition: Maximum Transmission Unit (MTU)

The largest link layer frame available to the sender. Consider it as the largest unit of data that can be transmitted through all links to the receiver without requiring it to be split.

Path MTU Discovery determines the largest frame that can be sent on all links from the sender to receiver.

#### TCP Header

From the NMap book:



#### Points of note:

- Source and destination ports are 16 bit identifiers.
- Sequence number and Acknowledgement Number (32 bits) is used for reliable data transfer (identifies a segment, so any segments missing in the sequence can be detected)
- Receive window (16 bits), the amount of data that can be sent before an acknowledgement is received (if the receiver cannot process data as fast as it arrives, it will ask to reduce the TCP window), more here.
- Header length determines the size of the TCP header in 32 bit words.

• The optional/variable length field is used to negotiate protocol parameters such as window scale, or **maximum segment size**.


There are several header Fields:

$\mathbf{Field}$	$\mathbf{Bits}$	Description
URG	1	Signals the data as urgent, location of urgent data marked by urgent
		data pointer field. Note that some software will ignore it.
$\mathbf{ACK}$	1	Signals that the acknowledgement number is a valid acknowledgement.
PSH	1	Push flag, asks the receiver to push data to the application immedi-
		ately.
RST	1	Resets the connection, often used to shutdown a connection when some
		unexpected error occurs.
SYN	1	Synchronisation flag, used as part of the handshake.
FIN	1	Signals connection to finish/shutdown.
Checksum	16	Used for error detection.

### Definition: Sequence Number

Each byte in the data stream has a sequence number (byte, **not** segment).

The sequence number in a **TCP segment** indicates the position of the first byte carried by that segment.




When the **TCP** connection is setup, a random **Initial Sequence Number** is decided upon to avoid any leftover segments being received by mistake.

Hence when creating a new connections, even with the same data the sequence numbers will be different.

### Definition: Acknowledgement Number

An acknowledgedment number represents the end of the data received, or the first sequence number of the data waiting to be received.


- TCP acknowledgements can be cumulative (recieve segments 1, 2, 3, ackenowledge (wait for) 4).
- Typically acknowledge every other packet.



• As **TCP** is full duplex, multiple streams/sequences can be received, and acknowledged at the same time.

### 3-Way Handshake

- 1. Client sends a **TCP segment** with the **SYN** flag set to **true**, and the **initial sequence number**.
- 2. Server responds with another SYN TCP segment which also has ACK as true and the first unseen client Sequence number.
- 3. Client responds with an **ACK** with first unseen server **sequence number**, and a new **sequence number**.



Connection termination is similar, but uses **FIN**.

### **UDP**

### Definition: User Datagram Protocol (UDP)

A connection-less transport layer protocol.

- Data is split into **datagrams** (think like telegrams).
- **Datagrams** cannot be larger than 65,507 bytes (20B IP Header + 8B UDP Header + 65,507B = 65,535B which is the maximum IP packet size).
- In practice smaller  $500B \rightarrow 1KB$  datagrams are used to increase the proportion of packets that are intact (any small error only effects a small datagram, does not invalidate a large datagram).
- Application identification is provided (multiplexing/demultiplexing).
- Integrity of data is checked by a CRC-type checksum.

#### **UDP** is very simple:

- no flow Control
- no error Control
- no retransmissions


#### Why use **UDP**?

- Finer level of application layer control over when and what data is sent (e.g real-time such as skype).
- No connection needs to be established (faster than TCP).
- No connection state needs to be stored.
- Very small packet overhead (only a small bit of the packet is not payload).

It is also very useful in **client-server** interactions.

A client can send a short message to a server, and get a quick response, on failure can time out or try again. The resulting code is simple and fewer messages are needed (no connection setup/teardown).

### **UDP** Header



#### Example: Simple Java Web Client

```
import java.io.IOException;
    import java.net.DatagramPacket;
    import java.net.DatagramSocket;
    import java.net.InetAddress;
4
5
    public class exampleUDPClient {
        // connect to localhost (this machine) on port 2251
 7
        static final int port = 2251;
8
        static final String ip = "127.0.0.1";
9
10
        public static void main(String[] args) throws IOException {
11
            // Create a buffer to store data to send & receive, place
12
                13
            // the console.
14
            byte buffer [] = System.console().readLine().getBytes();
15
            // Create a new packet sourced from the buffer to the target
16
                → ip and port.
17
            {\tt DatagramPacket\ packet\ =\ new\ DatagramPacket\ (buffer\ ,\ buffer\ .}
                → length , InetAddress.getByName(ip) , port);
18
19
            // Create a datagram socket to send & receive packets
20
            DatagramSocket socket = new DatagramSocket();
21
22
            // send the packet, the ip and port and inside the packet.
23
            socket.send(packet);
24
            // reallocate the buffer to take the response packet
25
26
            buffer = new byte[256];
27
28
            // take the response from the socket and store in buffer.
29
            packet = new DatagramPacket(buffer, buffer.length);
30
            socket.receive(packet);
31
32
            // print the received data to the console.
33
            System.out.println(new String(packet.getData()));
34
35
            // Socket no longer used, so close.
36
            socket.close();
37
   }
38
```

```
import java.io.IOException;
1
    import java.net.DatagramPacket;
3
    import java.net.DatagramSocket;
4
    import java.net.InetAddress;
5
    public class exampleUDPServer {
        static final int port = 2251;
 7
8
        public static void main(String[] args) throws IOException {
9
10
             / Create a socket to receive datagrams on.
11
            DatagramSocket socket = new DatagramSocket(port);
12
            // Server runs in forever loop to deal with packets.
13
14
            while (true) {
                // Allocate a buffer to store packet data
15
16
                byte buffer [] = new byte [256];
17
                // Create a packet to use buffer.
18
19
                {\tt DatagramPacket\ packet\ =\ new\ DatagramPacket(buffer\ ,\ buffer\ .}
                    → length);
20
21
                // Receive data, write to buffer.
22
                socket.receive(packet);
23
                // Print the data received to the console.
24
25
                System.out.println(new String(packet.getData(), 0, packet.

    getLength());

26
                // Take response from standard input.
27
28
                buffer = System.console().readLine().getBytes();
29
30
                // Get the address of the sender from the received packet.
                InetAddress clientAddress = packet.getAddress();
31
                int clientPort = packet.getPort();
32
33
34
                // Create a new packet from the buffer.
                packet = new DatagramPacket (buffer, buffer.length,
35
                    36
37
                // Send the response.
                socket.send(packet);
38
39
            }
40
        }
   }
41
```

### TCP vs UDP

• (UDP) - A PvP Game sending short bursts of data to players

Data transmission is time critical, if a message is lost, we can simply recover our own way (e.g list of messages, retry).

We get to control the implementation. While we may mimic TCP in some error recovery, we can decide what features we want and don't for the best experience.

• (TCP) - An online card game

Speed is not a concern, **TCP** is just fine.

• (TCP) - Movie player application

We want it to be fast, however we do not want to drop frames.

- Pre-Buffer the video, and constantly use connection to get next few seconds as the movie plays. - TCP manages errors to reduce dropped frames.

### **Data Transfer**

### Lecture Recording

Lecture recording is available here

### Definition: (FSM) Finite State Machine

A mathematical abstraction used among other uses, to describe network protocols.


FSMFinite State Machine

FSA Finite State Automata


DFA Deterministic finite-state automaton

NFA None-deterministic finite state automaton

We can describe transitions between states for a protocol by the event and action.



### TCP FSM



### View TCP states on your device


On windows can use the **netstat -a** commend, topview or currPorts.

On linux there is htop and iptraf.

#### Data Transfer FSM

TCP provides mechanisms to ensure reliability in data transfer. While IP in the Network Layer is a best-effort protocol and is unreliable, by going through TCP we can create a reliable connection.

we can generalise this as:



#### **Error Detection**

Bits may be flipped in transmission (due to noise/interference and imperfect physical hardware).

Error Detection Receiver must be able to check if packet is corrupted.

Receiver Feedback Receiver must be able to tell sender the packet sent was corrupted.

### Definition: Parity Bit


A very simple type of error dectection code, where a single bit is set based on the parity of the rest of the packet. Typically this is the **XOR** of all the bits.

 $\begin{array}{ccc} 1001 & \rightarrow & 1001 \ 0 \\ 1101 & \rightarrow & 1101 \ 1 \end{array}$ 

### Stop and Wait with Error detection

We can express the data transfer **FSM** to include error detection. In this setup the protocol is synchronous, meaning for each segment the sender must receive back an acknowledgement before the next segment is sent.

# Sender



# Receiver



The main issue with this approach, is that **ACK**s and **NACK**s can also get corrupted. If we use the same scheme to reliably transfer the **ACK**s and **NACK**s we end up with potentially no termination (sender and receiver stuck in a loop of replying with **NACK**s at each other, that the other does not receive uncorrupted on a noisy channel).

#### Assume NACK and retransmit

We can add a sequence number to each packet, so that packets can be retransmitted, and the receiver knows which packets are retransmissions.

If we use **stop and wait** we only need 1 bit for the sequence number, as 0 is original, 1 is retransmission.

#### Use Sequence Numbers instead of NACKs

We can instead use sequence numbers. If the packet is not acknowledged then an **ACK** is not sent. **ACK** is sent for the last good packet, hence the receiver can use a lack of **ACK**s to determine that it must retransmit some data.

Note that with TCP the ACK contains the start of the packet to be sent (or resent) next/ the end byte sequence number of the data received.

#### Out of Order Sequence Numbers

Rather than use stop and wait, a sender may send many packets.

#### • Delayed ACK

The receiver only accepts in order, so ignores any packets sent out of order. After receiving a packet in order, it waits some time (e.g 500ms) before sending the **ACK**, allowing for more in order-packets to be received in this time (resetting the wait).

- 1. Received 0, start wait
- 2. Wait interrupted, received 1, start wait again
- 3. Wait interrupted, received 2, start wait again
- 4. Received 7, ignored
- 5. Received 6, ignored
- 6. Wait from (3.) over, send  $\mathbf{ACK}$  (have recieved up to 2, please send me 3)

. . .

#### • Cumulative ACK

Received an in-order segment with the expected number, waiting on the next segment.

Immediately send a cumulative **ACK**.

#### • Duplicate ACK

Send an **ACK** for the next segment. Then an out-of-order segment arrived with a higher than expected sequence number, there is a gap.

Immediately send another (duplicate) **ACK**.

#### • Immediate ACK

A segment received partially or completely fills a gap in the received data.

Immediately send an **ACK** for the lower end of the gap (to fill).

#### **Timeouts**

We can set a timeout for receiving **ACK**s. When the sender does not receive an acknowledgment within the time, it assumes the packet was not received and can try again (retransmit).

- If the timeout is too long, when packets are lost retransmission will have to wait a long time and hence slow down the connection.
- If the timeout is too short, packets may be needlessly retransmitted.

#### TCP & Checksums

Used by **TCP**. A checksum is calculated from the payload data.

- When received, if the checksum does not match the recalculated checksum, then corruption
  has occurred.
- Retransmission allows for error recovery.
- ACKs and NACKs are also protected by error detection code.
- Corrupted **ACK**s are used as **NACK**s
- Sequence numbers allow the receiver to ignore duplicate segments.

### **Network Simulation**

We can use network simulation to check, test and optimise parameters for protocols and network designs.

- Cisco Packet Tracer
  - Packet tracer is a lightweight network simulator with a user friendly GUI.
- GNS3 Network Emulator
  - GNS3 is network simulation tool available for free.
- Opnet Modeler
  - Opnet (now riverbed) modeller is a commercial (paid for) network simulation tool.

## **Detecting Congestion**

### Lecture Recording

Lecture recording is available here

### Definition: Congestion

So far we have roughly described the **TCP Reno** protocol. However there are many other variants to deal with congestion control.

Routers have a limit to how many packets they can route. Packets are held in a queue.

If too many packets are sent to one of the routers between a sender and reciever, its queue will overflow, resulting in some segments being dropped.

Hence the server assumes the network is congested when it detects segment loss from:

- timeouts (no **ACK** received)
- multiple **ACK**s (or equivalent acknowledgements) can be considered a **NACK**

There are many different congestion control algorithms:

Algorithm	Affects	
TFRC	Sender, Receiver	• Linux
RED	Router	Usually CUBIC, but can be found at /proc/sys/net
CLAMP	Router, Receiver	$\hookrightarrow$ /ipv4/tcp_congestion_control.
XCP	Sender, Router, Receiver	XX7* 1
VCP	Sender, Router, Receiver	• Windows
MaxNet	Sender, Router, Receiver	Can be found at netsh interface tcp>sh gl, if noth-
$\operatorname{JetMax}$	Sender, Router, Receiver	ing then it is using the windows default.
ECN	Sender, Router, Receiver	• Custom
Vegas	Sender	It is possible to force any socket to use any variant
High Speed	Sender	to the proposition to force only becomes to the only realizable
BIC	Sender	• Characteristics
CUBIC	Sender	Most have variable characteristics combined. For
H-TCP	Sender	example:
FAST	Sender	
Compound TCP	Sender	Tahoe Slow start, AIMD, Fast Retransmit
Westwood	Sender	Reno Fast Recovery
Jersey	Sender	Vegas Congestion Avoidance
BBR	Sender	

# Definition: TCP Vegas

A popular  $\mathbf{TCP}$  implementation.

- Attempts to detect congestion before losses occur.
- Predicts packet loss using **RTT** (round trip time)
- Larger  $\overrightarrow{RTT} \Rightarrow$  greater congestion

# Definition: TCP CUBIC

Used by linux as the standard.

In order to avoid advantaging smaller RTTs (as can happen with TCP Reno), grows window as a function of time rather than RTT

# Definition: Congestion Window



The **congestion window** is the number of bytes that can be sent before blocking to wait for acknowledgements.


Both the sender and receiver can define the window size, the size used is the minimum of both.


W = min(Congestion Window, Receiver Window)

Hence with a given RTT and window size W:

$$\text{maximum rate } \ \lambda \approx \frac{W}{RTT}$$


### Congestion Methods





- 1. Set initial window size to  $\mathbf{MSS}$  (maximum segment size) (quite small for high-speed networks).
- 2. For every good acknowledgement, increase the window size by the size of data acknowledged (meaning window size is roughly doubled every **RTT**).
- 3. Continue this exponential increase until window size reaches the **ssthresh** (segment size threshold).
- 4. The use Congestion Avoidance.

# Definition: Congestion Avoidance




The window size is increased roughly linearly ( $\approx 1~MSS$  per RTT).

For each good acknowledgement:

$$W = W + \frac{MSS^2}{W}$$

When congestion is detected (packet loss) switch to a different strategy.

### Definition: (AIMD) Additive Increase / Multiplicative Decrease



Acknowledgement No

- For every good acknoled gement:  $W = W + \frac{MSS^2}{W}$
- For every packet loss event:  $W = \frac{W}{2}$

### Definition: timeout

We need to detect packet loss, when no **ACK** is send back.

- timeout interval T must be larger than the RTT otherwise we will retransmit data unnecessarily.
- T cannot be too large, otherwise it will be slow to retransmit.
- $\bullet$  **TCP** continuously estimates the RTT.
- TCP sets T using the smoothed RTT (SRTT) and the RTT Variation RTTVAR(exact computation can be found in section 2.2 & 2.3 here.)

$$T = SRTT + 4 \times RTTVAR$$

### Definition: Fast Retransmission

Three duplicate ACKs are interpreted as a NACK. The number 3 is agreed upon in section 3 here as a tradeoff between fast retransmission and unnecessary premature retransmission.

- timeout suggests congestion
- 3 duplicate **ACK**s suggests the network can still transmit,

# Definition: Fast Recovery

Given the current window size is  $\overline{W}$ :

If timeout occurs:


- 1. W=MSS2. Run slow start until  $W=\frac{\overline{W}}{2}=ssthresh.$ 3. Switch to collision avoidance.

If it is 3 duplicate **ACK**s (a **NACK**) then run **Fast Recovery**:

- 1.  $W = \frac{\overline{W}}{2}$ 2. Switch to collision avoidance.

Fast recovery is fast as the window size is not reset all the way back to MSS, so can ramp up the window size more quickly.

## Window Strategies



### Definition: Sliding Window - Selective Repeat

Sender only re-transmits those segments it suspects were dropped or corrupted.

- Sender keeps a list/vector of acknowledgements.
- Receiver keeps a list/vector of acknowledged segments.
- When segments received out of order, they are kept to be added into the data once the missing/gap segments arrive.
- Sender keeps a timer for each segment it is waiting for acknowledgement of, resending only when the timer expires.
- Sender slides the window when the lowest pending segment is acknowledged.

### Definition: Flow Control

Flow control attempts to prevent the receiver from being overwhelmed/overflowing (rate of sending is too high for it to cope).

- The receiver sends the **RecieverWindow** size along with acknowledgements.
- This typically is the size of buffer left to fill.
- When a buffer is full and the receiver can take no more, it sends an acknowledgement with **RecieverWindow** set to 0, and repeats a 1-byte ping to the sender to indicate it is not down or deadlocked, but rather just processing.

### Wireless TCP

TCP was designed before the popularisation of wireless networks.

Wired Network

Wireless Network

When packets are lost, this indicated congestion.

When packets are lost, this is most likely a channel reliability issue.

We

- Reduce packets sent.
- Use congestion avoidance and recovery strategies.

• Resend packets as much as possible.

• Gives best chance of one getting received correctly.

can fix these conflicting requirements in two ways:

- **Split TCP Connections** If we use separate connections for wired and wireless we can distinguish between the two and hence use different algorithms for congestion avoidance.
- Use Base Station Have the wired base station do some retransmissions without informing the wireless source.

Here the base station tries to improve wireless IP reliability using TCP.

# Network Usage

 $\label{eq:utilisation} \text{Utilisation Factor} = \frac{\text{network use}}{\text{maximum theoretical usage}}$ 

When we have the RTT, packet size L and transmission rate R, we can also use the time on the connection used out of the possible time length:

$$d_{trans} = \frac{L}{R}$$

$$\text{Utilisation Factor} = \frac{d_{trans}}{RTT + d_{trans}}$$