
The Standard C++ Library

Version 1: Dr. Ofir Pele

Version 2: Dr. Erel Segal-Halevi

Main Components





Fixed size: pair, tuple, array

Sequence containers:

forward_list, list, vector, deque

Associative containers:

- set, multiset, map, multimap
- unordered_set, unordered_multiset, unordered_map, unordered_multimap

Container adaptors:

stack, queue, priority_queue

- Can hold a fixed number of elements of various types.
- Particularly useful in a return statement, to let your function return several values.
- Shortest (most automated) version:

```
auto f () {
  return tuple(5, 'a', "hello");
}
// in main:
auto [ii,cc,ss] = f();
```

Longer versions in folder 0.

Sequential Containers

Objects are ordered by the user

	insert first	insert middle	insert last	random access	iterate forward	iterate back	find	storage
forward_ list	fast	fast	fast	slow	fast	slow	slow	heap
list	fast	fast	fast	slow	fast	fast	slow	heap
vector	slow	slow	fast	fast	fast	fast	slow	heap
deque	fast	~slow	fast	~fast	fast	fast	slow	heap
array	-	-	-	fast	fast	fast	slow	stack

Associative Containers

Ordered: Objects are ordered by "<".
Insertion, deletion, find: O(log n).

set: Unique keys.

map: Associate unique keys to values.

multiset: Allows multiple keys.

multimap: Associate keys to multiple values.

Unordered: Insertion, deletion, find: O(1).

unordered_set: Unique keys.

unordered_map: Associate keys to values.

unordered_multiset: Allows multiple keys.

unordered_multimap: Associate keys to multiple values.

Container Adaptors

Take any sequential container; return a container with a given interface:

- stack: last in first out;
- queue: first in first out;
- **priority_queue**: best in first out.

Containers -General Rules

- Holds copies of elements.
- Assumes elements have:
 Copy Ctor & operator =

Assignable types with operator=
and copy Ctor

STL: Sequential Containers

vector<T>

- Contiguous array of elements of type T
- Random access
- Can grow on as needed basis
- Most useful in practice

```
std::vector<int> v(200);
v[0]= 45;
v[100]= 32;
v.emplace_back(60); //C++11
```


Vectors of ints

```
1)Creating an empty vector and filling it:
 std::vector<int> vec;
 vec.push back(42);
 vec.emplace back(42); // equivalent
2) Creating a vector with 10 ints with value 42:
 std::vector<int> vec(10,42);
 std::vector<int> vec(10); // default is 0
3)Initializing a vector like an array:
 std::vector<int> vec { 42, 52, 62 };
4)Initializing a vector from iterators:
 std::vector<int> v2(vec.begin(),vec.end());
```

Vectors of objects (folder 1)

```
1)Creating an empty vector and filling it:
 std::vector<MyClass> vec;
 vec.push back(MyClass{42,43});
 vec.emplace back(42,43); // more efficient
2) Creating a vector with 10 objs:
 std::vector<MyClass> vec(10,MyClass{42,43});
 std::vector<MyClass> vec(10); // default ctor
3)Initializing a vector like an array (calls ctor):
 std::vector<MyClass> vec { {42,43}, {52}, {62,72} };
4)Initializing a vector from iterators:
 std::vector<MyClass> v2(vec.begin(),vec.end());
```

size and capacity



- The first "size" elements are constructed (initialized)
- The last "capacity size" elements are uninitialized
- push_back / emplace_back use the uninitialized elements until they are full; then, they multiply the vector size by 2.


emplace_back / push_back Average Time Complexity

If we inserted **n** elements we paid:

$$1+2+1+4+1+1+1+8+...+n =$$
 $O(n) + 1+2+4+...+n =$
 $O(n)$

On average an each insertion cost O(1)

size and capacity methods



uint size() const;
uint capacity() const;
void reserve(uint new_capacity);
// ensure that the capacity is
// at least "new capacity".

vector<T> v

Accessing elements

Without boundary checking:

- reference operator[](size_type n)
- const_reference operator[](size_type n) const

With boundary checking:

- reference at(size_type n)
- const_reference at(size_type n) const

Associated types in vector

vector<typename T>::

- value_type The type of object, T, stored
- reference Reference to T
- const_reference const Reference to T
- iterator Iterator used to iterate through a vector (how would you write it?)

vectors: C++ vs. Java

- Look at cplusplus documentation of vector.
- Look at Java documentation of Vector.
- Differences:
 - Simple class vs. interface and vtable.
 - Simple elements vs. class elements.
 - Two accessors (with and without range check) vs. a single accessor

deque

- More efficient insertion at start and middle;
- Less efficient deallocation.
- How do we know? performance tests:
- https://www.codeproject.com/Articles/5425/A n-In-Depth-Study-of-the-STL-Deque-Contain er
- Implementation non contiguous blocks: https://stackoverflow.com/a/6292437/82792
 7

STL: Associative Containers

Associative Containers

Supports efficient retrieval of elements (values) based on keys.

(Typical) Implementation:

- red-black binary trees
- hash-table


Sorted Associative Containers

set

- A set of unique keys ordered by
 map
- Associate a value to key (associative array)
- Unique value of each key, ordered by
 multiset, multimap
- Same, but allow multiple values unordered_set, unordered_map
- Same, but without order (faster).

Sorted Associative Containers & Order

- Sorted associative containers assume that their elements are LessThanComparable.
- They use operator< as default order.
- We can control order using our own comparison function.
- We need to use a functor.



A functor in C++ is an object with an operator(). Examples:

- Pointer to function (like in C);
- A class that implements operator();
- Lambda [] expressions.

Example (see also folder 2)

```
class c str less {
public:
  bool operator()(const char* s1,
                  const char* s2) {
    return (strcmp(s1,s2) < 0);
c str less cmp; // declare an object
if(cmp("aa", "ab"))
                    Creates temporary objects, and
                      then call operator()
if( c str less()("a","b") )
```

Template comparator example

```
template<typename T>
class less {
public:
 bool operator()(const T& lhs, const T& rhs)
 { return lhs < rhs; }
 less<int> cmp; // declare an object
 if (cmp(1,2))
                    Creates temporary objects,
                    and then call operator()
 if( less<int>()(1,2) )
```

Using Comparators

```
// ascending order
// uses operator < for comparison</pre>
set<int> s1;
set<int,less<int>> s1; // same
// descending order
// uses operator > for comparison
set<int, greater<int>> s2;
```

Using Comparators


```
Creates a default constructed
set<int,MyComp> s3,
                          MyComp object.
MyComp cmp (42);
set<int,MyComp> s4(cmp);
                  Use given MyComp object.
```

Why should we use classes as functors?

So that we get the "power" of classes:

- Inheritance.
- Parameterize our functions in run time. (folder 2).
- Accumulate information.

How to choose a container?



Mikael Persson https://stackoverflow.com/a/22671607/827927