

High Speed Vendor Feed

SOLA HSVF UDP Multicast Specifications Guide for BOX

Confidential

HSVF-BX-002E Document Revision: 1.8 Protocol Version: C7

Date of Issue: 2023-10-17

Copyright

©BOX Technology Canada Inc, 2020

This document and all information contained herein is and will remain at all times proprietary and confidential information of BOX Technology Canada Inc.

No part of this document may be photocopied, reproduced, stored on retrieval system, or transmitted, in any form or by any means whether, electronic, mechanical, or otherwise without the prior written consent of BOX Technology Canada Inc

The information included in this document is believed to be accurate. BOX Technology Canada Inc does not guarantee the completeness or accuracy of any information included herein. This document is produced with the understanding that BOX Technology Canada Inc. is providing information and not in any way providing engineering or other professional services.

BOX Technology Canada Inc reserves the right to change details in this publication without notice.

SOLA® is a registered trademark of the BOX Technology Canada Inc.

HSVF-BX-002E, Document Version 1.8

VERSION	DATE	CHANGE DESCRIPTION			
1.0	2015-03-17	First release of HSVF UDP Multicast Specifications.			
1.1	2015-06-12	Section 2.6- Addition of Notes			
1.2	2016-12-20	Sections 3.4.23 and 3.4.24 Updated O and OS messages: added 2 fields (FirmId and CMTA) (Protocol version C6)			
1.3	2017-01-10	Section 3.4.6: Update of Message GC (added ScheduleTime field) Grouped field descriptions contained in sections 4, 5, 6 under Section 4- Fields Description.			
	2018-07-26	Section 3.4.14 Update of Message JS Section 3.4.17 Update of Message NS			
	2018-09-20	 Protocol version C7 Section 3.2.1: Strike Price Code replaced by filler Section 3.3.8: Update of Message Type RT Section 3.4.6: Update of Message Type GC Section 3.4.21: Update of Message Type M Sections 3.4.25 and 3.4.26: Update of Messages T and TS Sections 3.4.2, 3.4.5, 3.4.9, 3.4.10, 3.4.12. 3.4.14, 3.4.22, 3.4.24 (Messages CS, FS, H, HS, IS, JS, MS, OS): Update of Instrument Description field Section 4.9 Option Price Strike Codes removed 			
1.4	2020-06-29	This document version has been rolled-back. Please refer to Version 1.5 below. Protocol Version C8 Updated section 4.4 Price Indicator Markets			
1.5	2021-02-02	 Roll-back of Protocol C8 As of this version, HSVF latest protocol is C7 Sequence Number roll-over 1 billion messages (Table 2 – Message Header) Note on Retransmission after 1 billion message sequence (section 3.3.8) Added new section 4.8 – Complex Order (Strategy) Instrument Month Code 			
1.6	2021-03-12	Added Section 2.5.1 - Retransmission before and after the billion-message mark			

VERSION	DATE	CHANGE DESCRIPTION
1.7	2022-06-06	Section 3.4.14 – Message Type JS – Complex Order Instrument Keys - Support of 16 legs
1.8	2023-10-17	Section 3.2.1 – Instrument Description Added FLEX Symbology for American and European FLEX Options, Physical-Settled
		Section 4.9 – Market Feed Indicators Added new value 'F' as 1st letter of Market Feed Indicator to indicate a FLEX Option

Table of Contents

Section 1	Table of Co	ontents	i
2.1 Interface 2.2 HSVF Feed Schedule of a Typical Day 2.3 Transmission Format 2.4 Data Format 2.5 TCP Retransmission Defore and after the billion message-mark 3.1 Retransmission before and after the billion message-mark 3.1 Messages 3.1 Message Types 3.1.1 Technical Messages 3.2 Conventions 3.2.1 Instrument Description – 20 Bytes 3.3 Technical Messages 3.3.1 Message Type ER – Error Message – 95 Bytes 3.3.1 Message Type ER – Error Message – 95 Bytes 3.3.2 Message Type KO – Logout Acknowledgement (TCP Retransmission Mode) – 11 Bytes 17 3.3.3 Message Type LI – Login (TCP Retransmission Mode) – 51 Bytes 3.3.4 Message Type LI – Login (TCP Retransmission Mode) – 51 Bytes 3.3.5 Message Type RB – Retransmission Begin (TCP Retransmission Mode) – 11 Bytes 3.3.5	1.1 1.2	Objective	6
2.1 Interface 2.2 HSVF Feed Schedule of a Typical Day 2.3 Transmission Format 2.4 Data Format 2.5 TCP Retransmission Defore and after the billion message-mark 3.1 Retransmission before and after the billion message-mark 3.1 Messages 3.1 Message Types 3.1.1 Technical Messages 3.2 Conventions 3.2.1 Instrument Description – 20 Bytes 3.3 Technical Messages 3.3.1 Message Type ER – Error Message – 95 Bytes 3.3.1 Message Type ER – Error Message – 95 Bytes 3.3.2 Message Type KO – Logout Acknowledgement (TCP Retransmission Mode) – 11 Bytes 17 3.3.3 Message Type LI – Login (TCP Retransmission Mode) – 51 Bytes 3.3.4 Message Type LI – Login (TCP Retransmission Mode) – 51 Bytes 3.3.5 Message Type RB – Retransmission Begin (TCP Retransmission Mode) – 11 Bytes 3.3.5	Section 2	Trading Overview	-
2.2 HSVF Feed Schedule of a Typical Day 2.3 Transmission Format 2.4 Data Format 2.5 TCP Retransmission Defore and after the billion message-mark 1 Section 3 Messages 3.1 Message Types 3.1.1 Technical Messages 3.2.2 Conventions 3.2.1 Instrument Description – 20 Bytes 3.3.1 Message Type ER – Error Message – 95 Bytes 3.3.1 Message Type ER – Error Message – 95 Bytes 3.3.2 Message Type EN – Login Acknowledgement (TCP Retransmission Mode) – 11 Bytes 3.3.3 Message Type KO – Logout Acknowledgement (TCP Retransmission Mode) – 11 Bytes 3.3.4 Message Type LO – Logout (TCP Retransmission Mode) – 51 Bytes 3.3.5 Message Type RB – Retransmission Begin (TCP Retransmission Mode) – 11 Bytes 3.3.6 Message Type RB – Retransmission End (TCP Retransmission Mode) – 11 Bytes 3.3.7 Message Type RF – Retransmission Request – 31 Bytes 3.3.9 Mes		-	
2.3 Transmission Format .9 2.4 Data Format .9 2.5 TCP Retransmission Capability .1 2.5.1 Retransmission before and after the billion message-mark .1 3.1 Messages .1 3.1.1 Technical Messages .1 3.1.2 Business Messages .1 3.2.1 Instrument Description – 20 Bytes .1 3.3.1 Message Type ER – Error Message – 95 Bytes .1 3.3.1 Message Type ER – Error Message – 95 Bytes .1 3.3.1 Message Type KI – Login Acknowledgement (TCP Retransmission Mode) – 11 Bytes 17 3.3.3 Message Type KO – Logout Acknowledgement (TCP Retransmission Mode) – 11 Bytes 17 3.3.3 Message Type LI – Login (TCP Retransmission Mode) – 51 Bytes .1 3.3.4 Message Type LI – Login (TCP Retransmission Mode) – 51 Bytes .1 3.3.5 Message Type RB – Retransmission Begin (TCP Retransmission Mode) – 11 Bytes .1 3.3.6 Message Type RB – Retransmission Request – 31 Bytes .1 3.3.7 Message Type RF – Retransmission Request – 31 Bytes .1 3.3.8			
2.4 Data Format .9 2.5 TCP Retransmission Capability .10 2.5.1 Retransmission before and after the billion message-mark .11 Section 3 Messages .12 3.1 Message Types .12 3.1.2 Business Messages .12 3.1.2 Conventions .18 3.2 Conventions .18 3.3.1 Instrument Description – 20 Bytes .18 3.3.2 Instrument Description – 20 Bytes .11 3.3.2 Message Type ER – Error Message – 95 Bytes .11 3.3.2 Message Type KI – Login Acknowledgement (TCP Retransmission Mode) – 11 Bytes 17 3.3.3 Message Type KO – Logout Acknowledgement (TCP Retransmission Mode) – 11 Bytes 17 3.3.4 Message Type LO – Logout (TCP Retransmission Mode) – 51 Bytes .11 3.3.5 Message Type LO – Logout (TCP Retransmission Mode) – 51 Bytes .11 3.3.6 Message Type RB – Retransmission Begin (TCP Retransmission Mode) – 11 Bytes .12 3.3.5 Message Type RB – Retrans			
2.5 TCP Retransmission before and after the billion message-mark 11 2.5.1 Retransmission before and after the billion message-mark 12 3.1 Message Types 13 3.1.1 Technical Messages 13 3.1.2 Business Messages 15 3.2.1 Instrument Description – 20 Bytes 18 3.3.1 Instrument Description – 20 Bytes 18 3.3.1 Message Type ER – Error Message – 95 Bytes 16 3.3.1 Message Type KI – Login Acknowledgement (TCP Retransmission Mode) – 11 Bytes 17 3.3.3 Message Type KO – Logout Acknowledgement (TCP Retransmission Mode) – 11 Bytes 18 Message Type LO – Logout (TCP Retransmission Mode) – 51 Bytes 17 3.3.4 Message Type LO – Logout (TCP Retransmission Mode) – 11 Bytes 17 3.3.5 Message Type RB – Retransmission Begin (TCP Retransmission Mode) – 11 Bytes 17 3.3.7 Message Type RF - Retransmission End (TCP Retransmission Mode) – 11 Bytes 18 3.3.9 Message Type RF - Retransmission Request – 31 Bytes 18 3.3.9 Message Type C - Option Trade – 17 Bytes			
2.5.1 Retransmission before and after the billion message-mark			
3.1 Message Types 12 3.1.1 Technical Messages 11 3.2 Conventions 15 3.2.1 Instrument Description – 20 Bytes 16 3.3 Technical Messages 16 3.3.1 Message Type ER – Error Message – 95 Bytes 17 3.3.2 Message Type KI – Login Acknowledgement (TCP Retransmission Mode) – 11 Bytes 17 3.3.3 Message Type KO – Logout Acknowledgement (TCP Retransmission Mode) – 11 Bytes 1.3.4 Message Type LI – Login (TCP Retransmission Mode) – 51 Bytes 17 3.3.5 Message Type LO – Logout (TCP Retransmission Mode) – 11 Bytes 17 3.3.6 Message Type RB – Retransmission Begin (TCP Retransmission Mode) – 11 Bytes 17 3.3.7 Message Type RF – Retransmission End (TCP Retransmission Mode) – 11 Bytes 17 3.3.7 Message Type RF – Retransmission Far Bytes 18 3.3.8 Message Type RF – Retransmission Far Bytes 18 3.3.9 Message Type V – Circuit Assurance – 17 Bytes 18 3.3.1 Message Type V – Circuit Assurance – 17 Bytes 18 3.4.1 Message Type C – Option Trade – 76 Bytes <td></td> <td></td> <td></td>			
3.1.1 Technical Messages 12 3.1.2 Business Messages 11 3.2.1 Instrument Description – 20 Bytes 15 3.3 Technical Messages 16 3.3.1 Message Type ER – Error Message – 95 Bytes 17 3.3.2 Message Type KI – Login Acknowledgement (TCP Retransmission Mode) – 11 Bytes 17 3.3.3 Message Type KO – Logout Acknowledgement (TCP Retransmission Mode) – 11 Bytes 13.3.4 Message Type LI – Login (TCP Retransmission Mode) – 51 Bytes 17 3.3.5 Message Type LO – Logout (TCP Retransmission Mode) – 11 Bytes 17 3.3.6 Message Type RB – Retransmission Begin (TCP Retransmission Mode) – 11 Bytes 18 3.3.7 Message Type RF - Retransmission End (TCP Retransmission Mode) – 11 Bytes 18 3.3.8 Message Type RF - Retransmission Request – 31 Bytes 18 3.3.9 Message Type V – Circuit Assurance – 17 Bytes 18 3.3.10 Message Type V – Circuit Assurance – 17 Bytes 18 3.3.11 Message Type C – Option Trade – 76 Bytes 19 3.4.1 Message Type CS – Strategy Trade – 79 Bytes 19 3.4.2 Message Type CS – Strat	Section 3	Messages	12
3.1.2 Business Messages 13 3.2 Conventions 15 3.2.1 Instrument Description – 20 Bytes 15 3.3 Technical Messages 16 3.3.1 Message Type ER – Error Message – 95 Bytes 17 3.3.2 Message Type KI – Login Acknowledgement (TCP Retransmission Mode) – 11 18 Bytes 17 3.3.3 Message Type KO – Logout Acknowledgement (TCP Retransmission Mode) – 11 18 3.3.4 Message Type LO – Logout (TCP Retransmission Mode) – 51 Bytes 17 3.3.5 Message Type LO – Logout (TCP Retransmission Mode) – 11 Bytes 17 3.3.6 Message Type RB – Retransmission Begin (TCP Retransmission Mode) – 11 Bytes 18 3.3.7 Message Type RF - Retransmission End (TCP Retransmission Mode) – 11 Bytes 18 3.3.8 Message Type RF - Retransmission Request – 31 Bytes 18 3.3.9 Message Type U – End of Transmission – 18 Bytes 18 3.3.10 Message Type V – Circuit Assurance – 17 Bytes 18 3.4.1 Message Type Z – System Time Stamp – 20 Bytes 18 3.4.2 Message Type C – Option Trade – 76 Bytes 15 3.4.3 Message Type D	3.1	Message Types	12
3.2 Conventions 15 3.2.1 Instrument Description – 20 Bytes 16 3.3 Technical Messages 16 3.3.1 Message Type KI – Login Acknowledgement (TCP Retransmission Mode) – 11 11 3.3.2 Message Type KI – Login Acknowledgement (TCP Retransmission Mode) – 11 11 3.3.3 Message Type KO – Logout Acknowledgement (TCP Retransmission Mode) – 11 11 3.3.4 Message Type LI – Login (TCP Retransmission Mode) – 51 Bytes 3.3.5 Message Type RB – Retransmission Begin (TCP Retransmission Mode) – 11 Bytes 3.3.6 Message Type RB – Retransmission Begin (TCP Retransmission Mode) – 11 Bytes 3.3.7 Message Type RF - Retransmission End (TCP Retransmission Mode) – 11 Bytes 3.3.8 Message Type U – End of Transmission Request – 31 Bytes 18 3.3.10 Message Type V – Circuit Assurance – 17 Bytes 18 3.3.11 Message Type Z – System Time Stamp – 20 Bytes 18 3.4.1 Message Type C – Option Trade – 76 Bytes 18 3.4.2 Message Type C – Option Request for Quote (RFQ) – 40 Bytes 22 3.4.3 Message Type F – Option Quote – 68 Byte	3.1.1	Technical Messages	12
3.2.1 Instrument Description – 20 Bytes	3.1.2		
3.3.1 Message Type ER – Error Message – 95 Bytes	3.2		
3.3.1 Message Type ER – Error Message – 95 Bytes			
3.3.2 Message Type KI – Login Acknowledgement (TCP Retransmission Mode) – 11 Bytes 17 3.3.3 Message Type KO – Logout Acknowledgement (TCP Retransmission Mode) – 11 Bytes 17 3.3.4 Message Type LI – Login (TCP Retransmission Mode) – 51 Bytes 17 3.3.5 Message Type LO – Logout (TCP Retransmission Mode) – 11 Bytes 17 3.3.6 Message Type RB – Retransmission Begin (TCP Retransmission Mode) – 11 Bytes 17 3.3.7 Message Type RE - Retransmission End (TCP Retransmission Mode) – 11 Bytes 18 3.3.8 Message Type RT- Retransmission Request – 31 Bytes 18 3.3.9 Message Type U – End of Transmission – 18 Bytes 18 3.3.10 Message Type V – Circuit Assurance – 17 Bytes 18 3.3.11 Message Type Z – System Time Stamp – 20 Bytes 19 3.4.1 Message Type C – Option Trade – 76 Bytes 19 3.4.2 Message Type C – Option Request for Quote (RFQ) – 40 Bytes 19 3.4.3 Message Type F – Option Quote – 68 Bytes 19 3.4.4 Message Type F – Option Quote – 68 Bytes 19 3.4.5 Message Type F – Option Quote – 68 Bytes 19 3.4.6 Message Type F – Option Quote – 68 Bytes 19 3.4.7 Message Type G – Group Opening Time – 25 Bytes 19 3.4.8 Message Type G – Group Status – 19 Bytes 19 3.4.9 Message Type G – Group Status – 19 Bytes 19 3.4.10 Message Type G – Group Status – 19 Bytes 19 3.4.11 Message Type G – Complex Order Market Depth – up to 230 Bytes 19 3.4.11 Message Type H – Option Market Depth – up to 208 Bytes 19 3.4.11 Message Type H – Option Market Depth – up to 230 Bytes 19 3.4.12 Message Type I – Option Instrument Keys – 119 Bytes 19 3.4.13 Message Type J – Option Instrument Keys – 119 Bytes 19 3.4.14 Message Type J – Option Instrument Keys – 119 Bytes 19 3.4.14 Message Type J – Option Instrument Keys – Up to 591 Bytes 19			
Bytes 17 3.3.3 Message Type KO – Logout Acknowledgement (TCP Retransmission Mode) – 11 Bytes 17 3.3.4 Message Type LI – Login (TCP Retransmission Mode) – 51 Bytes 17 3.3.5 Message Type LO – Logout (TCP Retransmission Mode) – 11 Bytes 17 3.3.6 Message Type RB – Retransmission Begin (TCP Retransmission Mode) – 11 Bytes 17 3.3.7 Message Type RE - Retransmission End (TCP Retransmission Mode) – 11 Bytes 18 3.3.8 Message Type RT- Retransmission Request – 31 Bytes 18 3.3.9 Message Type U – End of Transmission – 18 Bytes 18 3.3.10 Message Type V – Circuit Assurance – 17 Bytes 18 3.3.11 Message Type Z – System Time Stamp – 20 Bytes 19 3.4.1 Message Type C – Option Trade – 76 Bytes 19 3.4.2 Message Type CS – Strategy Trade – 79 Bytes 20 3.4.3 Message Type D – Option Request for Quote (RFQ) – 40 Bytes 22 3.4.5 Message Type F – Option Quote – 68 Bytes 22 3.4.5 Message Type FS – Complex Order Quote – 79 Bytes 22 3.4.6 Message Type GS – Group Opening Time – 25 Bytes 22 3.4.7 Message Type GS – Group Status – 19 Bytes 25 3.4.9 Message Type GS – Group Status (Strategies) – 15 Bytes 26 3.4.10 Message Type GS – Group Status (Strategies) – 15 Bytes 25 3.4.11 Message Type HS – Complex Order Market Depth – up to 208 Bytes 25 3.4.11 Message Type HS – Complex Order Market Depth – up to 230 Bytes 26 3.4.11 Message Type JS – Strategy Trade Cancellation – 71 Bytes 33 3.4.11 Message Type JS – Strategy Trade Cancellation – 71 Bytes 33 3.4.11 Message Type JS – Strategy Trade Cancellation – 71 Bytes 33 3.4.11 Message Type JS – Complex Order Instrument Keys – Up to 591 Bytes 36 3.4.11 Message Type JS – Complex Order Instrument Keys – Up to 591 Bytes 36 3.4.11 Message Type JS – Complex Order Instrument Keys – Up to 591 Bytes 36 3.4.11 Message Type JS – Complex Order Instrument Keys – Up to 591 Bytes 36 3.4.11 Message Type JS – Complex Order Instrument Keys – Up to 591 Byte		Message Type ER – Error Message – 95 Bytes	17
3.3.3 Message Type KO – Logout Acknowledgement (TCP Retransmission Mode) – 11 Bytes			11
11 Bytes	•		
3.3.4 Message Type LI – Login (TCP Retransmission Mode) – 51 Bytes			
3.3.5 Message Type LO – Logout (TCP Retransmission Mode) – 11 Bytes			
3.3.6 Message Type RB – Retransmission Begin (TCP Retransmission Mode) – 11 Bytes 17 3.3.7 Message Type RE - Retransmission End (TCP Retransmission Mode) – 11 Bytes 18 3.3.8 Message Type RT- Retransmission Request – 31 Bytes			
Bytes 17 3.3.7 Message Type RE - Retransmission End (TCP Retransmission Mode) – 11 Bytes 18 3.3.8 Message Type RT- Retransmission Request – 31 Bytes			
3.3.7 Message Type RE - Retransmission End (TCP Retransmission Mode) – 11 Bytes 18 3.3.8 Message Type RT- Retransmission Request – 31 Bytes		- · · · · · · · · · · · · · · · · · · ·	1
18 3.3.8 Message Type RT- Retransmission Request – 31 Bytes 18 3.3.9 Message Type U – End of Transmission – 18 Bytes 18 3.3.10 Message Type V – Circuit Assurance – 17 Bytes 18 3.3.11 Message Type Z – System Time Stamp – 20 Bytes 19 3.4 Business Messages 19 3.4.1 Message Type C – Option Trade – 76 Bytes 19 3.4.2 Message Type CS – Strategy Trade – 79 Bytes 20 3.4.3 Message Type D – Option Request for Quote (RFQ) – 40 Bytes 22 3.4.4 Message Type F – Option Quote – 68 Bytes 22 3.4.5 Message Type FS – Complex Order Quote – 79 Bytes 22 3.4.6 Message Type GC – Group Opening Time – 25 Bytes 24 3.4.7 Message Type GS – Group Status (Strategies) – 15 Bytes 24 3.4.8 Message Type GS – Group Status (Strategies) – 15 Bytes 25 3.4.10 Message Type HS – Complex Order Market Depth – up to 230 Bytes 25 3.4.11 Message Type I – Option Trade Cancellation – 68 Bytes 25 3.4.12 Message Type IS – Strategy Trade Cancellation – 71 Bytes 36 3.4.13 Message Ty			Bytes
3.3.8 Message Type RT- Retransmission Request – 31 Bytes 18 3.3.9 Message Type U – End of Transmission – 18 Bytes 18 3.3.10 Message Type V – Circuit Assurance – 17 Bytes 18 3.3.11 Message Type Z – System Time Stamp – 20 Bytes 19 3.4 Business Messages 19 3.4.1 Message Type C – Option Trade – 76 Bytes 19 3.4.2 Message Type CS – Strategy Trade – 79 Bytes 20 3.4.3 Message Type D – Option Request for Quote (RFQ) – 40 Bytes 22 3.4.4 Message Type F – Option Quote – 68 Bytes 22 3.4.5 Message Type FS – Complex Order Quote – 79 Bytes 23 3.4.6 Message Type GC – Group Opening Time – 25 Bytes 26 3.4.7 Message Type GR – Group Status – 19 Bytes 24 3.4.8 Message Type GS – Group Status (Strategies) – 15 Bytes 25 3.4.9 Message Type HS – Complex Order Market Depth – up to 230 Bytes 25 3.4.10 Message Type I – Option Trade Cancellation – 68 Bytes 26 3.4.11 Message Type IS – Strategy Trade Cancellation – 71 Bytes 36 3.4.13 Message Type JS – Complex Order Instrument Keys – 119 Bytes </td <td>0.0.7</td> <td></td> <td>Dy (0)</td>	0.0.7		D y (0)
3.3.9 Message Type U – End of Transmission – 18 Bytes	3.3.8	• •	18
3.3.10 Message Type V – Circuit Assurance – 17 Bytes			
3.3.11 Message Type Z – System Time Stamp – 20 Bytes			
3.4.1 Message Type C – Option Trade – 76 Bytes	3.3.11		
3.4.2 Message Type CS – Strategy Trade – 79 Bytes	3.4		
3.4.3 Message Type D – Option Request for Quote (RFQ) – 40 Bytes	3.4.1	Message Type C – Option Trade – 76 Bytes	19
3.4.4 Message Type F – Option Quote – 68 Bytes	3.4.2		
3.4.5 Message Type FS – Complex Order Quote – 79 Bytes			
3.4.6 Message Type GC – Group Opening Time – 25 Bytes			
3.4.7 Message Type GR – Group Status – 19 Bytes			
3.4.8 Message Type GS – Group Status (Strategies) – 15 Bytes			
3.4.9 Message Type H – Option Market Depth – up to 208 Bytes			
3.4.10 Message Type HS – Complex Order Market Depth – up to 230 Bytes			
3.4.11 Message Type I – Option Trade Cancellation – 68 Bytes			
3.4.12 Message Type IS – Strategy Trade Cancellation – 71 Bytes			
3.4.13 Message Type J – Option Instrument Keys – 119 Bytes			
3.4.14 Message Type JS – Complex Order Instrument Keys – Up to 591 Bytes 32			

3.4.16	Message Type N – Option Summary – 127 Bytes	. 35
3.4.17	Message Type NS – Complex Order Summary – 116 bytes	. 37
3.4.18	Message Type Q – Beginning of Options Summary – 12 Bytes	
3.4.19	Message Type QS – Beginning of Complex Order Summary – 12 Bytes	. 39
3.4.20	Message Type S – End of Sales – 18 Bytes	.40
3.4.21	Message Type M – Improvement Process Beginning Message (Option) – 84	
Bytes	40	
3.4.22	Message Type MS – Improvement Process Beginning Message (Complex	
Order)	– 94 Bytes	.42
3.4.23	Message Type O – Market Sheet Initial and Improvement Order (Options) /	
Expose	ed Order (Options) – 80 Bytes	.43
3.4.24	Message Type OS – Market Sheet Initial and Improvement Order (Complex	
Order)	/ Exposed Order (Complex Order) – 91 Bytes	. 44
3.4.25	Message Type T – Initial and Improvement Order (Options) / Exposed Order	
	s) – 47 Bytes	
3.4.26	Message Type TS —Initial and Improvement Order (Complex Order) / Expose	ed
Order (Complex Order) – 57 Bytes	47
	, ,	. 71
Section 4	, , , ,	
Section 4 4.1	Fields Description Price and Fraction Indicator Code	. 48
	Fields Description	. 48 . 48
4.1	Fields Description	. 48 . 48 . 49
4.1 4.2	Fields Description	. 48 . 48 . 49 . 51
4.1 4.2 4.3	Fields Description	. 48 . 49 . 51
4.1 4.2 4.3 4.4	Fields Description	. 48 . 49 . 51 . 52 . 53
4.1 4.2 4.3 4.4 4.5	Fields Description	. 48 . 49 . 51 . 52 . 53
4.1 4.2 4.3 4.4 4.5 4.6	Fields Description Price and Fraction Indicator Code Markers for Options Status Markers Price Indicator Markers Indicator Code Strike Price Currency Codes	. 48 . 49 . 51 . 52 . 53 . 53
4.1 4.2 4.3 4.4 4.5 4.6 4.7	Fields Description Price and Fraction Indicator Code Markers for Options Status Markers Price Indicator Markers Indicator Code Strike Price Currency Codes Month Codes for Options	. 48 . 49 . 51 . 52 . 53 . 54 . 54

Section 1 Introduction

The BOX Exchange-High Speed Vendor Feed (HSVF) User Datagram Protocol (UDP) Multicast was developed by the Information Technology (IT) division of the Montréal Exchange Inc. (MX), a member of the TMX Group Inc.

The HSVF UDP Multicast is comprised of Trades, Quotes, Market Depth, Strategies, Bulletins, Summaries and other Statistics. Information is provided on all BOX listings.

The UDP provides to the HSVF Participant a faster dissemination flow of messages. HSVF Participants are to use UDP lines to obtain the Market Dissemination flow from HSVF Repeaters; each UDP line contains a specific Market, a specific Market Depth, and a specific protocol version.

The current Protocol version is C7.

1.1 Objective

The main objective of the Specifications Guide is to provide information to HSVF Participant in the functional design of their application intended to receive the HSVF feed.

1.2 Scope

This Specifications Guide defines the communications interface and message formats for the high-speed transmission which broadcasts real-time trading and statistical information from BOX.

1.3 BOX Contact

Market Operation Center Support / Technical Help Desk Toll Free: 1-866-768- 8845 boxmoc@boxoptions.com

Section 2 Trading Overview

All messages which comprise the BOX-HSVF are transmitted to the user on a dedicated line. Each message type is fixed in format. Re-transmission of any data is available on the transmission line.

2.1 Interface

Boston Exchange broadcasts the HSVF feed using both the UDP and TCP/IP broadcast interface as follows:

- Real-time Market Dissemination Flow is broadcasted according to a defined timeline using the UDP interface to allow Participants to connect.
- The TCP interface retransmission can be used by Participants to perform queries of missing messages of the UDP Feed.

2.2 HSVF Feed Schedule of a Typical Day

During a typical day, all messages that comprise the BOX-HSVF are transmitted following the schedule illustrated below.

Participants can connect at 1:15 a.m., which is when the broadcast starts, the dictionary is sent at 1:30 a.m. Until the opening of the market, information regarding the instrument keys, summaries, quote/market depth is broadcasted. The connection ends at 5:55 p.m. after the market closure.

Table 1: HSVF Schedule – Information broadcasted at each trading phase

TRADING PHASES/ INFORMATION BROADCASTED		OTHER MESSAGES	INSTRUMENT KEYS	SUMMARY	QUOTE/MARKET DEРТН
START OF CONNECTION	1:15 a.m.	Х			
DICTIONARY	1:35 a.m.	х	X	Х	X
INSTRUMENT OPEN INTEREST FOR THE DAY	5:00 a.m.			Х	
PRE-OPENING	7:00 a.m.	Х			Х
OPENING/TRADING	9:30 a.m.	x			
CLOSING ON EQUITY OPTIONS	4:00 p.m.	X			
CLOSING ON ETF AND INDEX OPTIONS	4:15 p.m.	Х			
END OF DAY SUMMARIES	4:40 p.m.	Х	Х	Х	
END OF DAY FOR HSVF	4:40 p.m.	Х			
END OF CONNECTION	5:55 p.m.	Х			

2.3 Transmission Format

A UDP packet can contain multiple HSVF messages. The UDP packet is built as follows:

UDP Packet			
HSVF Message 1	HSVF Message 2		HSVF Message N

A packet can have a maximum of 1000 characters.

Each message is framed by an STX and an ETX character. The format used is:

HSVF Message			
STX	Message Header	Message Body	ETX

STX and ETX indicate the beginning and the end of the record being transmitted.

2.4 Data Format

Each message consists of a standard message header followed by the message body, which varies in format according to the message type.

The standard message header attached to all messages has the following format.

Table 2: Message Header

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
			Each message is assigned a sequence number starting at '000000001' every day and incremented by 1 for each message sent.
			Note: Message sequencing is per Line. There is no validation of message sequence for incoming messages.
Sequence Number	9 N	N	The sequence numbers will range from 000000001 to 99999999 (decimal, ASCII).
			Retransmitted messages will contain the original sequence numbers.
		Sequence Number greater than 999999999 (decimal, ASCII) will be reset back and re-start at Sequence Number 000000000 and increment by 1 for each new message sent.	
Message Type	2	Х	Identifies the type of message being sent. Format is left-aligned, right 'blank' filled (if necessary).

2.5 TCP Retransmission Capability

ACTION	Particulars
Normal UDP Connection (Start of Day @ 1:35 a.m. EST)	 Participant connects to specific IP address and UDP port; 8 slices are available, each representing a subset of BOX traded instruments; on each slice, 3 different Feeds are available. Exchange sends data to Participant starting with the next available message. First message of the day has sequence number 000000001. Message types receive depend on the feed selected.
	Participant connects to specific IP address and TCP port.
	Participant sends a LI (Login) message type. BOX sends back a KI (Login Ack) message type.
	Participant sends a RT (Retransmission Request) message specifying the feed id and the message range to retransmit.
Retransmission	BOX sends a RB (Retransmission Begins) message.
(From a specific Sequence	5. BOX sends all requested messages.
number of a specific interval of messages)	BOX sends a RE (Retransmission Ends) message indicating that all requested messages have been retransmitted.
	Note: If the Exchange sequence (i.e. last sequence number of HSVF disseminated by the Exchange) is lower than the Start sequence number below 1 billion messages, the transmission request is rejected (ER message).
Disconnection	Participant disconnects from the UDP port. Participant sends a LO (Logout) message to terminate their TCP Retransmission connection.

2.5.1 Retransmission before and after the billion message-mark

When requesting a retransmission of messages, the following will happen depending on the number of messages sent for that day as specified by the examples below:

Total number of messages less than 1 billion

Retransmission Request RT		
Start	End	Outcome
200 000 000	300 000 000	Messages sequences from 200 000 000 to 300 000 000 will be re-transmitted
400 000 000	350 000 000	The RT is rejected because the billion message-mark has not been surpassed, and the End Sequence Number must be greater than the Start Sequence Number

Total number of messages greater than 1 billion

Retransmission Requ	iest RT	
Start	End	Outcome
200 000 000	300 000 000	Since the number of messages has passed a billion, the End Sequence will be interpreted as (1B + End Sequence = 1.3B)
		In this case, HSVF will return message sequences from 200 000 000 to 999 999 999, roll-over to 000 000 000, and continue to 300 000 000, with the last 300 000 000 messages corresponding to messages after the 1 billion message-mark
999 999 900	100 000 000	Since the number of messages has passed a billion, the End Sequence will be interpreted as (1B + End Sequence = 1.1B)
		In this case, HSVF will return message sequences from 999 999 900 to 999 999 999, roll-over to 000000000, and continue to 100 000 000, with the last 100 000 000 messages corresponding to messages after the 1 billion message-mark
999 999 999	999 999 999	Similarly, in this case, HSVF will return message sequences from 999 999 999, roll-over to 000 000 000, and continue to 999 999 999, with the last 999 999 999 messages corresponding to messages after the billion message-mark

Limitations

The highest start sequence is limited to 999 999 999. Therefore, it is not possible to request a range of messages starting above 1 billion. For instance, to obtain messages from 1.2 billion to 1.3 billion, the subscriber would need to request 999 999 to 300 000 000.

Section 3 Messages

3.1 Message Types

This section lists a summary of all HSVF message types.

Note:

HSVF users must have the ability to skip and ignore any message that is not defined below. Because new message types may be defined in future versions of the protocol, anyone using this version of the HSVF protocol must be able to avoid impact of undefined new messages types they may receive.

3.1.1 Technical Messages

	TCP RETRANSMISSION MESSAGES						
LI	Login 3.3.4						
LO	Logout 3.3.5						
кі	Login Acknowledgement	3.3.2					
ко	Logout Acknowledgement	3.3.3					
ER	Error Message 3.3.1						
RT	Retransmission Request 3.3.8						
RB	Retransmission Begins 3.3.6						
RE	Retransmission Ends 3.3.7						
	OTHER MESSAGES						
U	End of Transmission	3.3.9					
V	Circuit Assurance 3.3.10						
Z	System Time Stamp	3.3.11					

3.1.2 Business Messages

TRADE MESSAGES								
С	Option Trade	3.4.1						
cs	Complex Order Instrument Trade	3.4.2						
	REQUEST FOR QUOTES MESSAGES (RFQ)							
D	Option Request for Quote (RFQ)	3.4.3						
	QUOTE MESSAGES							
F	Option Quote	3.4.4						
FS	Complex Order	3.4.5						
	MARKET DEPTH MESSAGES							
н	Option Market Depth 3.4.9							
HS	HS Complex Order Market Depth 3.4.10							
	Trade Cancellation Messages							
ı	Option Trade Cancellation	3.4.11						
IS	Complex Order Trade Cancellation 3.4.12							
	INSTRUMENT KEYS MESSAGES							
J	Option Instrument Keys 3.4.							
JS Complex Order Instrument Keys 3.4.14								
	SUMMARY MESSAGES							
N	Option Summary	3.4.16						
NS	Complex Order Summary	3.4.17						

BEGINNING OF SUMMARY MESSAGES								
Q	Beginning of Options Summary	3.4.18						
QS	Beginning of Complex Order Summary	3.4.19						
	GROUP MESSAGES							
GC	Group Opening Time	3.4.6						
GR	Group Status	3.4.7						
GS	Complex Order Group Status	3.4.8						
	OTHER MESSAGES							
L	Bulletins	3.4.15						
s	End of Sales	3.4.20						
	IMPROVEMENT MESSAGES							
M	Improvement Process Beginning Message	3.4.21						
MS	Improvement Process Beginning Message (Complex Order)	3.4.22						
0	Market Sheet Initial and Improvement Order (Options)/Exposed Order (Options) 3.4.23							
os	Market Sheet Initial and Improvement Order (Complex Order)/Exposed Order (Complex Order) 3.4.24							
Т	Initial and Improvement Order (Options)/Exposed Order (Options) 3.4.25							
TS	Initial and Improvement Order (Complex Order)/Exposed Order (Complex Order)	3.4.26						

3.2 Conventions

In the following tables, the L column represents the length in bytes of the described field, and the T column ('Data Type') will be represented by the following characters: A = Alphabetic, N = Numeric, X = Alphanumeric.

- Whenever a field is indicated as being blank, it contains the ASCII space character (hex 20).
- Alphabetic fields A: letters (A to Z) left justified, blank filled unless stated otherwise.
- Numeric fields N: numbers (0 to 9), right justified, zero filled with a possibility to see a '.' (ASCII character hex 2).
- **Alphanumeric fields X**: all characters possible (numbers, letters, others), right justified, zero filled, with the exception of the following fields, which are left justified, and blank filled:
 - Instrument External Code
 - Root Symbol (Options related messages)
 - Symbol (Strategy related messages)
- The 'Filler' field can have any format; numeric, alphanumeric, ASCII space character (hex 20).

3.2.1 Instrument Description – 20 Bytes

The Instrument is identified when needed by the following fields.

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Root Symbol	6	Х	Symbol for the Option series FLEX Symbology: Root Symbol is prefixed by '1' (American FLEX Option, Physical-Settled) or '2' (European FLEX Option, Physical-Settled)
Expiry Month Code	1	А	Delivery month for the contract
Filler	1		Filler
Strike Price	7	Ν	Strike Price of the option in full
Strike Price Fraction Indicator	1	Х	Defines the number of decimal places or fraction positions
Expiry Year	2	Ν	Last 2 digits of the option expiry year
Expiry Day	2	N	Delivery day for the contract

3.3 Technical Messages

Technical messages are listed in alphabetical order within every sub-section.

3.3.1 Message Type ER – Error Message – 95 Bytes

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
ErrorCode	4	N	Send back when a LI, LO or RT message receive is invalid or rejected
ErrorMsg	80	Х	Error Message

3.3.2 Message Type KI – Login Acknowledgement (TCP Retransmission Mode) – 11 Bytes

FIELD NAME	L	T	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header

3.3.3 Message Type KO – Logout Acknowledgement (TCP Retransmission Mode) – 11 Bytes

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header

3.3.4 Message Type LI – Login (TCP Retransmission Mode) – 51 Bytes

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
User	16	Х	As provided by BOX
Pwd	16	Х	As provided by BOX
TimeStamp	6	N	Format HHMMSS
Protocol Version	2	Х	HSVF Protocol version (C7)

3.3.5 Message Type LO – Logout (TCP Retransmission Mode) – 11 Bytes

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header

3.3.6 Message Type RB – Retransmission Begin (TCP Retransmission Mode) – 11 Bytes

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	X	Refer to Message Header

3.3.7 Message Type RE - Retransmission End (TCP Retransmission Mode) – 11 Bytes

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header

3.3.8 Message Type RT- Retransmission Request – 31 Bytes

FIELD NAME	L	T	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Line	2	Х	Specific line name on which market is disseminated Refer to Network Access Specifications for more information regarding available lines.
Start	9	Ν	Starting message number
End	9	N	Ending message number

3.3.9 Message Type U – End of Transmission – 18 Bytes

This message will be sent to indicate that the day's transmission is complete. This message will be sent at approximately 5:15 p.m. daily. After this hour, no HSVF messages will be transmitted. Transmission will resume the following day at 1:00 a.m.

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	Α	Q by default
Time	6	N	Time at which the message is transmitted HHMMSS

3.3.10 Message Type V – Circuit Assurance – 17 Bytes

This message is sent out if no messages are sent by BOX for more than one minute after the broadcast has started (i.e. at the termination of the Test Loop message). This will be an assurance that the line is up.

This message will continue to be sent until the End of Transmission message (type U) is sent. The Circuit Assurance message will repeat the sequence number of the previous record transmitted (except if it is a re-transmit message) i.e. it will not increase the sequence number.

Note: These messages will be rarely be sent; at the beginning or at the end of the day.

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Time	6	N	Time at which the message is transmitted HHMMSS

3.3.11 Message Type Z – System Time Stamp – 20 Bytes

This message is sent out every second and contains the time stamp when it was originally transmitted by the trading engine. Broadcast starts during the pre-opening and continues until the end of day disconnection of all clients (currently 5:55 p.m. EST). The sequence number in the message header is incremented by 1 for each message sent.

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Χ	Refer to Message Header
Trading Engine TIme Stamp	9	N	Time stamp generated by the SOLA® Trading Engine (HHMMSSmmm)

3.4 Business Messages

3.4.1 Message Type C – Option Trade – 76 Bytes

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	А	Exchange on which the trade occurred Q by default
Instrument Description	20	Х	Refer to Instrument Description – 20 Bytes
Volume	8	N	Number of contracts for the trade Refer to Indicator Code
Trade Price	6	N	Price at which the transaction took place
Trade Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
			Refer to Price and Fraction Indicator Code
Net Change Sign +/-	1	Х	For the net change field
Net Change	6	N	Net change = last trade price - previous close
Net Change Fraction Indicator	1	Х	Fraction indicator for the net change price Refer to Price and Fraction Indicator Code
Filler	6	N	Filler
Timestamp	6	N	Time of transaction HHMMSS
Open Interest	7	N	This field contains the outstanding number of contracts in the series Updated on a trade by trade basis Refer to Indicator Code
Filler	1		Filler
Price Indicator Marker	1	А	Identifies the type of transaction Refer to Price Indicator Markers

3.4.2 Message Type CS – Strategy Trade – 79 Bytes

FIELD NAME	L	T	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	А	Exchange on which the trade occurred Q by default
Instrument Description	30	Х	Complex Order Instrument symbol. The individual legs are defined in message type JS.
Volume	8	N	Total number of contracts traded Refer to Indicator Code
Trade Price Sign +/-	1	Х	For Trade Price field (sign)
Trade Price	6	N	Price at which the transaction took place

Trade Price Fraction Indicator	1	x	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Net Change Sign	1	Х	+ or - sign
Net Change	6	N	Net change = last trade price - previous close
Net Change Fraction Indicator	1	х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Filler	6		Filler
Timestamp	6	N	Time of transaction HHMMSS
Price Indicator Marker	1	Х	Identifies type of transaction Refer to Price Indicator Markers

3.4.3 Message Type D – Option Request for Quote (RFQ) – 40 Bytes

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11		Refer to Message Header
Exchange ID	1	А	Exchange on which the quote occurred Q by default
Instrument Description	20	Х	Refer to Instrument Description – 20 Bytes
Requested Size	8	Х	Size of the market requested Refer to Indicator Code

3.4.4 Message Type F – Option Quote – 68 Bytes

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	А	Exchange on which the quote occurred Q by default
Instrument Description	20	Х	Refer to Instrument Description – 20 Bytes
Bid Price	6	Х	Bid price for the option series
Bid Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Bid Size	5	x	Number of option contracts represented by the Bid Price If size is greater than 99999, the 5th character becomes an exponent Refer to Indicator Code
Ask Price	6	Х	Ask price for the option series
Ask Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Ask Size	5	x	Number of option contracts represented by the Ask Price If size is greater than 99999, the 5th character becomes an exponent Refer to Indicator Code
Filler	1	Х	Filler

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Instrument Status Marker	1	Α	Indicates instrument status Refer to Status Markers
Public Customer Bid Size	5	Х	Number of option contracts represented by Public Customer orders on the bid side Refer to Indicator Code
Public Customer Ask Size	5	Х	Number of option contracts represented by Public Customer orders on the ask side Refer to Indicator Code

3.4.5 Message Type FS – Complex Order Quote – 79 Bytes

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	А	Exchange on which the quote occurred Q by default
Instrument Description	30	Х	Complex Order Instrument symbol The legs (underlying) are defined in message type JS
Bid Price Sign	1	Х	+ or - sign
Bid Price	6	Х	Bid price for the option series
Bid Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Bid Size	5	x	Number of futures contracts represented by the Bid Price If size is greater than 99999, the 5th character becomes an exponent Refer to Indicator Code
Ask Price sign	1	Х	+ or – sign
Ask Price	6	Х	Ask price for the option series
Ask Price Fraction Indicator	1	N	Defines number of decimal places or fraction positions. Refer to Price and Fraction Indicator Code

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Ask Size	5	X	The number of option contracts represented by the Ask Price If size is greater than 99999, the 5th character becomes an exponent Refer to Indicator Code
Instrument Status Marker	1	Х	Indicates instrument status Refer to Status Markers
Public Customer Bid Size	5	Х	Number of option contracts represented by Public Customer orders on the bid side Refer to Indicator Code
Public Customer Ask Size	5	Х	Number of option contracts represented by Public Customer orders on the ask side Refer to Indicator Code

3.4.6 Message Type GC – Group Opening Time – 25 Bytes

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	А	Exchange on which the quote occurred Q by default
Root Symbol	6	Х	Root of the instrument group
Group Status	1	Α	Value is O
Schedule Time	6	N	Opening time of the instrument group (HHMMSS format)

3.4.7 Message Type GR – Group Status – 19 Bytes

This message will be sent when a group of trading instruments enters a new status. Refer to BOX Website (http://www.bostonoptions.com/) for a complete list of the trading hours schedule for BOX products

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	А	Exchange on which the quote occurred Q by default

Root Symbol	6	Х	Root of the instrument group
Group Status	1	Α	Group status of the trading instrument Refer to Status Markers

3.4.8 Message Type GS – Group Status (Strategies) – 15 Bytes

This message will be sent when a Strategy group of trading instruments enters a new status. All strategies have a predetermined group that can be found in the JS message (Strategy Instrument Keys message).

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	А	Exchange on which the quote occurred Q by default
Group of the Complex Order Instrument	2	Х	Group of the Complex Order Instrument
Group Status	1	Α	Group status of the trading instrument Refer to Status Markers

3.4.9 Message Type H – Option Market Depth – up to 208 Bytes

ı	FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Messa	ige Header	11	Х	Refer to Message Header
Excha	nge ID	1	A	Exchange on which the quote occurred Q by default
Instrur	ment Description	20	Х	Refer to Instrument Description – 20 Bytes
Instrur Marke	ment Status r	1	А	Instrument status Refer to Status Markers
Numb	er of Levels	1	N	Number of levels for the trading instrument 1 to 6
Up to 6 times	Level of Market Depth	1	х	Level of market depth 1 to 6 = Regular market depth A = Implied prices P = Public Customer volume

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Bid Price	6	Х	Bid price for the option series For Implied, it represents the best (1st limit) indicative implied bid price
Bid Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Bid Size	5	Х	Number of option contracts represented by the Bid Price For Implied, represents the indicative quantity at the best (1st limit) implied bid price If size is greater than 99999, the 5th character becomes an exponent
Number of Bid Orders	2	x	Number of bid orders, present at a given moment, in the order book For Implied, represents the indicative number of implied bid orders making up the implied bid size at that implied bid price If greater than 99-> the 2nd character becomes an exponent Refer to Indicator Code
Ask Price	6	Х	Ask price for the option series For Implied, represents the best (1st limit) indicative implied ask price
Ask Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Ask Size	5	x	Number of option contracts represented by the Ask Price If size is greater than 99999, the 5 th character becomes an exponent Refer to Indicator Code
Number of Ask Orders	2	X	Number of Ask Orders, present at a given moment, in the order book If greater than 99-> the 2 nd character becomes an exponent Refer to Indicator Code

3.4.10 Message Type HS – Complex Order Market Depth – up to 230 Bytes

	FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Messa	age Header	11	Х	Refer to Message Header
Excha	inge ID	1	А	Exchange on which the quote occurred Q by default
Instru	ment Description	30	Х	Complex Order Instrument symbol. Individual legs are defined in message type JS.
Instrui Marke	ment Status er	1	А	Instrument status Refer to Status Markers
Numb	er of Levels	1	N	Number of levels for the trading instrument 1 - 6
	Level of Market Depth	1	х	Level of market depth 1 to 6 = regular market depth A = Implied prices P = Public Customer volume
	Bid Price Sign	1	Х	+ or - sign
	Bid Price	6	Х	Bid price for option series
	Bid Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Up to 6 times	Bid Size	5	Х	Number of strategy units represented by the Bid Price For Implied, it represents the indicative quantity at the best (1st limit) implied bid price If size is greater than 99999, the 5th character becomes an exponent Refer to Indicator Code
	Number of Bid Orders	2	Х	Number of Bid Orders, present at a given moment, in the order book If greater than 99-> the 2 nd character becomes an exponent Refer to Indicator Code
	Ask Price Sign	1	Х	+ or – sign
	Ask Price	6	Х	Ask price for the option series

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Ask Price Fraction Indicator	1	N	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Ask Size	5	x	The number of strategy units represented by the Ask Price If size is greater than 99999, the 5 th character becomes an exponent Refer to Indicator Code
Number of Ask Orders	2	x	Number of Ask Orders, present at a given moment, in the order book If greater than 99-> the 2 nd character becomes an exponent Refer to Indicator Code

3.4.11 Message Type I – Option Trade Cancellation – 68 Bytes

A cancellation will reduce the total volume, value and transactions by the amount of the cancelled trade. A cancellation message is followed by an Option Summary message (message type N) which will reflect the corrected market.

FIELD NAME	L	T	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	А	Exchange on which the trade occurred Q by default
Instrument Description	20	Х	Refer to Instrument Description – 20 Bytes
Volume	8	N	Number of contracts being cancelled Refer to Indicator Code
Trade Price	6	N	Price at which the transaction took place
Trade Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Filler	6		Filler
Timestamp	6	N	Time of cancellation transaction HHMMSS
Open Interest	7	N	Open long position of the option series, as of the trade Refer to Indicator Code
Filler	1		Filler
Price Indicator Marker	1	А	Identifies the type of transaction Refer to
			Price Indicator Markers

3.4.12 Message Type IS – Strategy Trade Cancellation – 71 Bytes

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	А	Exchange on which the trade occurred Q by default
Instrument Description	30	Х	Complex Order Instrument symbol. The individual legs are defined in message type JS.
Volume	8	Х	Number of contracts being cancelled Refer to Indicator Code
Trade Price sign	1	Х	+ or - sign
Trade Price	6	N	Estimated price at which the transaction took place
Trade Price Fraction Indicator	1	Х	Defines the number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Filler	6		Filler
Timestamp	6	N	Time of cancellation transaction HHMMSS
Price Indicator Marker	1	А	Identifies the type of transaction Refer to Price Indicator Markers

3.4.13 Message Type J – Option Instrument Keys – 119 Bytes

Option Instrument Keys messages will be sent:

- At the beginning and the end of the day with associate Summary message
- Anytime during the day if a threshold limit was changed for an instrument

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	А	Exchange on which the trade occurred Q by default
Instrument Description	20	Х	Refer to Instrument Description – 20 Bytes
Strike Price Currency	3	Х	Currency used for the Option Strike Price Refer to Strike Price Currency Codes
Maximum Number of Contracts per Order	6	N	Maximum authorized number of contract per order Refer to Indicator Code
Minimum Number of Contracts per Order	6	N	Minimum authorized number of contract per order Refer to Indicator Code
Maximum Threshold Price	6	N	Maximum threshold price authorized for an option contract Refer to Indicator Code
Maximum Threshold Price Fraction Indicator	1	x	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Minimum Threshold Price	6	N	Minimum threshold price authorized for an option contract Refer to Indicator Code
Minimum Threshold Price Fraction Indicator	1	x	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Tick Increment	6	X	Precision with which the price of an order limit can be expressed Refer to Tick Table
Tick Increment Fraction Indicator	1	N	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Option Type	1	N	Type of option A = American E = European

FIELD NAME	L	T	DEFINITION / VALIDATION RULES
Market Flow Indicator	2	X	Defines the type of instruments Refer to Market Feed Indicators
Group Instrument	2	Х	Group of the instrument
Instrument	4	Х	Instrument
Instrument External Code	30	Х	External identifier used by traders when entering an order
Option Marker	2	Α	Refer to Markers for Options
Underlying Symbol Root	10	Х	Symbol root for the underlying security

3.4.14 Message Type JS – Complex Order Instrument Keys – Up to 591 Bytes

Complex Order Instrument Keys messages will be sent:

- At the beginning and the end of the day with his associate Summary message;
- Also when a Complex Order instrument is created during trading hours.

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	Α	Q by default
Instrument Description	30	Х	Complex Order Instrument symbol. The individual legs are defined in this message.
Expiry Year	2	N	Expiration year of the leg of the Complex Order Instrument expiring first (format is YY)
Delivery Month	1	Α	Delivery month code of the leg of the Complex Order Instrument expiring first Refer to Month Codes
Expiry Day	2	N	Expiry day of the leg of the Complex Order Instrument expiring first
Max Number of Contracts per Order	6	Х	Maximum authorized number of contract per order Refer to Indicator Code
Min Number of Contracts per Order	6	Х	Minimum authorized number of contract per order Refer to Indicator Code
Max Threshold Price Sign	1	Х	+ or - sign

	FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Max T	hreshold Price	6	Х	Maximum threshold price authorized for an option contract Refer to Indicator Code
	hreshold Price on Indicator	1	Х	Number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Min Th	nreshold Price Sign	1	Х	+ or - sign
Min Th	nreshold Price	6	Х	Minimum threshold price authorized for an option contract Refer to Indicator Code
	nreshold Price on Indicator	1	Х	Number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Tick Ir	ncrement	6	Х	Precision used when expressing the price of an order limit Refer to Tick Table (Price Fraction rules)
Tick In	acrement Fraction tor	1	N	Defines the number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Filler		2	Х	Filler
Group		2	Х	Group of the instrument
Instrument		4	Х	Code identifying the instrument
Instrur Extern	ment al Code	30	Х	External identifier used by traders when entering an order
Complex Order Instrument Allow Implied		1	А	Complex Order Instrument support of Implied Price. N = No C = Continuous Implied S = Snapshot Implied
Numb	er of Legs	2	N	Number of legs in the Complex Order Instrument 2 to 16
From 2 to 16 times	Leg Ratio Sign	1	Х	+ = Buy the leg - = Sell the leg
	Leg Ratio	8	N	Quantity (bought or sold) 1 to 99999999
Fro	Leg Symbol	30	Х	Trading symbol of the leg

3.4.15 Message Type L – Bulletins – 93 Bytes

Bulletins will be sent throughout the trading day. More than one message will be used if the bulletin is longer than 79 characters. The continuation character "0" indicates that the bulletin continues to the next record.

When a Trading instrument has been halted by BOX, a Bulletin Message explaining the reason for the halt will be transmitted. When the trading instrument is reinstated, another Bulletin Message explaining the news that accompanied the reinstatement will be transmitted.

All records that make up a particular bulletin will be sent out together. No other message will be interspersed among the records that make up a complete bulletin.

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Filler	1	Х	
Bulletin Type	1	Х	1 = Regular text bulletin 2 = Special text bulletin
Bulletin Contents	79	Х	Bulletin in textual format. Left justified and blank filled
Continue Marker	1	N	0 = Bulletin continues in next record 1 = Bulletin ended

3.4.16 Message Type N – Option Summary – 127 Bytes

Option Summary messages are sent:

- At the beginning of the day. The first Option Summary message sent defines the
 instruments traded on that day, and contain the closing/reference price in the
 'Last Price' field. All other price fields, with the exception of open interest, contain
 zero values. Any other message sent during the day contain details of the last
 trade.
- Any option summary sent after the BEGINNING OF OPTIONS SUMMARY
 message (Message Type = Q) contains the list of trading instruments for the day
 (sent prior to market opening) or the summaries after the close of the market for
 BOX options (sent at 5:10 p.m. EST).
- After a trade cancellation if extreme values have been changed (Open/High/Low/Last).
- At the end of the day with relevant data such as the Open/High/Low/Last/Volume
- During the day when new instruments are added.

FIELD NAME	L	T	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	А	Identifies the exchange for the option Q by default
Instrument Description	20	Х	Option Instrument symbol
Bid Price	6	N	Closing or most recent bid price
Bid Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Bid Size	5	X	Number of contracts represented by the Bid Price If size is greater than 99999, the 5 th character becomes an exponent Refer to Indicator Code
Ask Price	6	N	Closing or most recent ask price
Ask Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Ask Size	5	Х	Number of contracts represented by the Ask Price If size is greater than 99999, the 5 th character becomes an exponent Refer to Indicator Code

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Last Price	6	N	Closing or most recent trade price
Last Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Open Interest	7	N	This field contains current outstanding number of contracts in the series. Updated on a trade by trade basis. Refer to Indicator Code
Tick	1	Х	Determined by the difference between last price and the previous different trade price '+' = uptick '-' = downtick
Volume	8	N	Total number of contracts traded or current volume if sent after a cancellation
Net Change Sign +/-	1	Х	For net change field
Net Change	6	N	Net change = last trade price - previous close Net change will be zero if the option did not trade on the last business day or did not trade today
Net Change Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Open Price	6	N	Price of the first trade of the day
Open Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
High Price	6	N	Highest trade price of the day or current high price if sent after a cancellation
High Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Low Price	6	N	Lowest trade price of the day or current low price if sent after a cancellation
Low Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Option Marker	2	Α	Refer to Markers for Options

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Underlying Symbol	10	Х	Symbol root for the underlying security
Reference Price	6	N	Reference Price of the Option
Reference Price Fraction Indicator	1	Х	Number of decimal places or fraction positions Refer to Price and Fraction Indicator Code

3.4.17 Message Type NS – Complex Order Summary – 116 bytes

Complex Order Summary messages will be sent:

- At the beginning of the day. The first Complex Order Summary message sent defines the instruments traded on that day, and contain the closing price in the 'Last Price' field. All other price fields contain zero values. Any other message sent during the day contain details of the last trade.
- Any Complex Order Summary sent after the BEGINNING OF COMPLEX
 ORDER SUMMARY message (Message Type = QS) contains the list of trading
 Complex Order instruments for the day (sent prior to market opening) or the
 summaries after the close of the market for BOX options (sent at 5:10 p.m. EST).
- After a trade cancellation if extreme values have been changed (Open/High/Low/Last).
- At the end of the day with relevant data such as the Open/High/Low/Last/Volume
- During the day when new instruments are added.

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	А	Identification of the exchange for the future Q by default
Instrument Description	30	Х	Complex Order Instrument symbol
Bid Price sign	1	Х	+ or - sign
Bid Price	6	N	Closing bid or most recent bid
Bid Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Bid Size	5	Х	Number of contracts represented by the Bid Price. Refer to Indicator Code
Ask Price Sign	1	Х	+ or - sign
Ask Price	6	N	Closing ask or most recent ask

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Ask Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Ask Size	5	Х	Number of contracts represented by the Ask Price.
Last Price Sign +/-	1	Х	For the Last Price field
Last Price	6	N	Last Trade Price for the contract or the current price if sent after a cancellation
Last Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Open Price Sign	1	Х	+ or - sign
Open Price	6	N	Price of the first trade of the day
Open Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
High Price Sign	1	Х	+ or – sign
High Price	6	N	Highest trade price of the day or current high price if sent after a cancellation
High Price Fraction Indicator	1	Х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code
Low Price Sign	1	Х	+ or - sign
Low Price	6	N	Lowest Trade Price of the day or current low price if sent after a cancellation
Low Price Fraction Indicator	1	Х	Defines number of decimal or fraction positions Refer to Price and Fraction Indicator Code
Net Change Sign	1	Х	+ or – sign
Net Change	6	N	Net change = last trade price - previous close Net change will be zero if the option did not trade on the last business day or did not trade today.
Net Change Fraction Indicator	1	х	Defines number of decimal places or fraction positions Refer to Price and Fraction Indicator Code

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Volume	8	N	Total number of contracts traded or current volume if sent after cancellation Refer to Indicator Code

3.4.18 Message Type Q – Beginning of Options Summary – 12 Bytes

This message indicates that the beginning and the end of day option summaries (message type N) are to follow. Other messages (such as bulletins) can be interspersed with the summaries.

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	А	Identifies the exchange Q by default

3.4.19 Message Type QS – Beginning of Complex Order Summary – 12 Bytes

This message indicates that the beginning or the end of day Complex Order summaries (message type NS) are to follow. Other messages can be interspersed with the summaries.

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	А	Identifies the exchange Q by default

3.4.20 Message Type S – End of Sales – 18 Bytes

This message will be sent when there is no more trading activity to be transmitted. This will occur after the closing of the market.

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Reserved	1	А	Reserved for future use
Time	6	N	Time at which the message is transmitted HHMMSS

3.4.21 Message Type M – Improvement Process Beginning Message (Option) – 84 Bytes

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	Α	Q by default
Instrument Description	20	Х	Refer to Instrument Description – 20 Bytes
Improvement Phase Sequential Number	6	N	Indicates the number of an Improvement Phase. Sequential number unique per Instrument and per trading day
Initial Order Price	6	N	Indicates the price of the Initial Order
Initial Order Price Fraction Indicator	1	Х	Refer to Price and Fraction Indicator Code
Initial Order Quantity	8	Х	Indicates the quantity of the Initial Order
Initial Order Side	1	А	Indicates the dealer side of the Initial Order B = Buy S = Sell
Improvement Phase Expiry Time	8	А	Indicates the expiry time of the Improvement Phase (value is in HHMMSSCC)
Improvement Process Expiry Duration	4	N	Indicates the expiry duration of the Improvement Phase (value is in SSCC)
Minimum Quantity for Improvement Order	8	Х	Enables market makers to know the minimum quantity for an Improvement Order during the Improvement Phase

FIELD NAME	L	T	DEFINITION / VALIDATION RULES
Percentage Assured to Initial Order	8	X	Indicates the quantity of the Initial Order assured to the dealer side of the IO in case of the Initial Order price is the best limit Ex: 00040.00 stands for 40.00 %
Auction Type	1	X	Indicating the auction type G = Regular PIP B = Solicitation C = Facilitation
Filler	1	А	Default value space

3.4.22 Message Type MS – Improvement Process Beginning Message (Complex Order) – 94 Bytes

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
Message Header	11	Х	Refer to Message Header
Exchange ID	1	А	Q by default
Instrument Description	30	Х	Complex Order Instrument symbol. The individual legs are defined in message type JS.
Improvement Phase Sequential Number	6	N	Indicates the number of an Improvement Phase. Sequential number unique per Instrument and per trading day
Initial Order Price Sign	1	Х	+ or - sign
Intial Order Price	6	N	Indicates the price of the Initial Order
Initial Order Price Fraction Indicator	1	Х	Refer to Indicator Code
Initial Order Quantity	8	Х	Indicates the quantity of the Initial Order
Initial Order Side	1	А	Indicates the dealer side of the Initial Order B = Buy S = Sell
Improvement Phase Expiry Time	8	А	Indicates the expiry time of the Improvement Phase (value is in HHMMSSCC)
Improvement Process Expiry Duration	4	N	Indicates the expiry duration of the Improvement Phase (value is in SSCC)
Minimum Quantity for Improvement Order	8	Х	Enables market makers to know the minimum quantity for an Improvement Order during the Improvement Phase
Percentage Assured to Initial Order	8	Х	Indicates the quantity of the Initial Order assured to the dealer side of the IO in case of the Initial Order price is the best limit Ex: 00040.00 stands for 40.00 %
Auction Type	1	Х	Indicating the auction type G =Regular PIP B = Solicitation C = Facilitation

3.4.23 Message Type O – Market Sheet Initial and Improvement Order (Options) / Exposed Order (Options) – 80 Bytes

This message type is not broadcasted for Improvement orders related to Solicitation and Facilitation auction types.

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES	
Message Header	11	Х	Refer to Message Header	
Exchange ID	1	А	Q by default	
Instrument Description	20	Х	Refer to Instrument Description – 20 Bytes	
Order Side	1	Х	The "must be filled" side ("B" for Buy, "S" for Sell)	
Type of Order	1	Х	Type of limit entered A: Initial Order P: Exposed Order	
Limit Entered for an Order	6	x	For a buy order, represents the highest price that the order issuer is willing to pay For a sell order, represents the lowest price at which the order issuer is willing to sell	
Limit Fraction Indicator	1	Х	Refer to Price and Fraction Indicator Code	
Order Quantity	8	Х	Refer to Indicator Code	
Order Sequence Number	6	N	Allocated by the Central trading engine at each valid order entry	
Improvement Phase Sequential Number	6	N	Indicates the number of an Improvement Phase. Not relevant when the message refers to an Exposed Order. Sequential number unique per instrument and per trading day	
Type of Clearing Account for Member that Owns the Order	1	X	Indicates the account type for which an order was entered using the clearing house member's account typology. When "Type of Order" is equal to "A", the Account Type is for the InitO (Auction initiator or dealer side). 6 = Public Customer 7 = Broker Dealer 8 = Market Maker T = Professional Customer W = Broker Dealer cleared as Customer X = Away Market Maker	
Filler	1	Α	Default value space	

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES
End of the Exposition	8	Ν	HHMMSSCC - '0' filled for PIP messages
Auction Type	1	Х	Indicates the auction type G = Regular PIP F = Exposed Order
FirmId	4	Х	Indicates the FirmId
СМТА	4	Х	Indicates the CMTA

3.4.24 Message Type OS – Market Sheet Initial and Improvement Order (Complex Order) / Exposed Order (Complex Order) – 91 Bytes

This message type is not broadcasted for Improvement orders related to Solicitation and Facilitation auction types.

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES	
Message Header	11	Х	Refer to Message Header	
Exchange ID	1	Α	Q by default	
Instrument Description	30	Х	Complex Order Instrument symbol. The individual legs are defined in message type JS.	
Order Side	1	Х	The "must be filled" side ("B" for Buy, "S" for Sell)	
Type of Order	1	Х	Type of limit entered A = Initial Order P = Exposed Order	
Limit Entered for an Order sign	1	х	+ or - sign	
Limit Entered for an Order	6	N	For a buy order, represents the highest price that the order issuer is willing to pay For a sell order, represents the lowest price at which the order issuer is willing to sell	
Limit Fraction Indicator	1	Х	Refer to Price and Fraction Indicator Code	
Order Quantity	8	Х	Refer to Indicator Code	
Order Sequence Number	6	N	Allocated by the Central trading engine at each valid order entry	

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES	
Improvement Phase Sequential Number	6	N	Indicates the number of an Improvement Phase. Not relevant when the message refers to an Exposed Order. Sequential number unique per instrument and per trading day	
Type of Clearing Account for Member that Owns the Order	1	X	Indicates the account type for which an order was entered using the clearing house member's account typology. When "Type of Order" is equa "A", the Account Type is for the InitO (Auction initiator or dealer side). 6 = Public Customer 7 = Broker Dealer 8 = Market Maker T = Professional Customer W = Broker Dealer cleared as Customer X = Away Market Maker	
Filler	1	А	Default value space	
End of the Exposition	8	N	HHMMSSCC - '0' filled for PIP messages	
Auction Type 1		Х	Indicating the auction type G = Regular PIP F = Exposed Order	
FirmId	4	Х	Indicates the FirmId	
СМТА	4	Х	Indicates the CMTA	

3.4.25 Message Type T – Initial and Improvement Order (Options) / Exposed Order (Options) – 47 Bytes

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES	
Message Header	11	Х	Refer to Message Header	
Exchange ID	1	А	Q by default	
Instrument Description	20	Х	Options Instrument symbol	
Deletion Type	1	N	1 = Deletion of a precise order 2 = Deletion of all previous orders in the specified side 3 = Deletion of all orders	
Order Sequence Number	6	N	Allocated by the Central trading engine at each valid order entry	
Order Side	1	Х	B = Buy S = Sell <blank> = all</blank>	
Improvement Phase Sequential Number	6	N	Number of an Improvement Phase. Not relevant when the message refers to an Exposed Order. Sequential number unique per Instrument and per trading day	
Auction Type	1	Х	Auction type or if the message is related to an exposed order. G = Regular PIP B = Solicitation C = Facilitation F = Exposed Order	

3.4.26 Message Type TS —Initial and Improvement Order (Complex Order) / Exposed Order (Complex Order) – 57 Bytes

FIELD NAME	L	Т	DEFINITION / VALIDATION RULES	
Message Header	11	Х	Refer to Message Header	
Exchange ID	1	Α	Q by default	
Instrument Description	30	Х	Complex Order Instrument symbol	
Deletion Type	1	N	 1 = Deletion of a precise order 2 = Deletion of all previous orders in the specified side 3 = Deletion of all orders 	
Order Sequence Number	6	Ν	Allocated by the Central trading engine at each valid order entry	
Order Side	1	Х	B = Buy S = Sell <blank> = all</blank>	
Improvement Phase Sequential Number	6	N	Number of an Improvement Phase. Not relevant when the message refers to an Exposed Order. Sequential number unique per Instrument and per trading day	
Auction Type	1	Х	Auction type or if the message is related to an exposed order G = Regular PIP B = Solicitation C = Facilitation F = Exposed Order	

Section 4 Fields Description

4.1 Price and Fraction Indicator Code

The Price field is a six-character numeric field.

Note:

The exception to the above is for MarketOnOpen (MOO) orders, where the Price field contains '000OUV' with a Fraction Indicator Code of '0'. '000OUV' stands for 'Opening Price' as calculated by the trading engine during the pre-opening phase.

The delineation of the whole number portion of the price and the decimal/fractional portion of the price will be defined by the Fraction Indicator (FI) Code. Furthermore, the FI indicates the manner in which the price is displayed visually. This implies that all zero fractions may be sent in order to maintain consistency in the visual alignment of the implied decimal places. The all zero fraction is replaced by spaces for visual display.

No truncation of price data is permitted by this Specification, except for high-order zeros for products that trade in fractions of 1/10,000,000 or smaller. Should such a truncation be necessary, then it is implicit from the FI, which is 7, 8, or 9.

All fractions are expressed as fractions or in decimals as defined by the price fraction rules of the particular product (section Tick Table). The **Fraction Indicator Code** is one alphanumeric character as shown.

FRACTION	CODE	FRACTION	CODE
1/1	0	-1/1	Α
1/10	1	-1/10	В
1/100	2	-1/100	С
1/1,000	3	-1/1,000	D
1/10,000	4	-1/10,000	E
1/100,000	5	-1/100,000	F
1/1,000,000	6	-1/1,000,000	G
1/10,000,000	7		
1/100,000,000	8		
1/1,000,000,000	9		

Tick Table (Price Fraction rules)

PRICE RANGE	TICK INCREMENT FIELD VALUE	FRACTION INDICATOR (F.I.)	MINIMUM TICK INCREMENT
Order Price below \$3.00	0000T1	2	\$0.05
Order Price equal or above \$3.00	0000T1	2	\$0.10
All PIP, Facilitation and Solicitation orders, at any price	0000T1	2	\$0.01

4.2 Markers for Options

FIRST LETTER (CURRENCY OR TYPE OF MARKET)			
Marker	Description		
B Trading in British Pound			
С	Trading in Canadian Dollar		
D	Danish Krone		
E	Trading in Swiss Franc		
F	Trading in Euro		

U	Trading in US Dollar	
Υ	Trading in Japanese Yen	
2ND L	ETTER (TYPE OF OPTIONS)	
Marker	Description	
	Regular Options	

4.3 Status Markers

	STATUS	Usi	ED IN
MARKER	DESCRIPTION	GROUP MESSAGES	Instrument Messages
Υ	Pre-opening phase	Х	Х
0	Opening phase	Х	Х
Т	Opened for Trading	Х	Х
F	Forbidden phase	Х	Х
Н	Trading Halted	Х	Х
R	Reserved phase (goes into a state as pre-opening where orders can be sent, modified, or canceled)		Х
S	Suspended phase (goes into a state as pre-opening where orders can be sent, modified, or cancelled)		Х
Z	Frozen		Х
А	Surveillance Intervention phase (Consultation phase)	Х	Х
С	Closed	Х	Х
В	Beginning of day inquiries	Х	Х
BLANK	If not used		

4.4 Price Indicator Markers

PRICE INDICATOR			WILL I	мраст Тне		
MARKER	DESCRIPTION	OPENING PRICE	HIGH PRICE	Low PRICE	LAST PRICE	VOLUME
Α	As-Of trades					Х
С	Trades performed at the end of a PIP allocation phase	Х	Х	Х	Х	х
L	Late trade (Transaction is being reported late and is out of sequence)					Х
0	Trades performed during the opening	Х	X	Х	Х	Х
S	Reference price (volume field zero filled)					
W	Trades resulting from the transmission of an ISO Inbound order	Х	X	X	X	Х
X	Trades performed when the market is crossed					х
G	Contingent Trade, price of the trade was not controlled against the NBBO	Х	Х	Х	X	Х
I	Trade involving an implied order or Leg Trade of a Complex Order instrument	Х	X	Х	Х	Х
Р	Trade done on a Complex Order Instrument					Х
BLANK	Actual transaction took place	Х	Х	Х	Х	Х

4.5 Indicator Code

This code is used for Bid/Ask Size, Volume, and Open Interest.

MARKER	DESCRIPTION (THE SIZE OF THE BID/ASK FIELD IS IN)		
С	100	(Hundreds)	
D	1,000	(Thousands)	
E	10,000	(Ten-Thousands)	
F	100,000	(Hundred-Thousands)	
G	1,000,000	(Millions)	
Н	10,000,000	(Ten-Millions)	
I	100,000,000	(Hundred-Millions)	
J	1,000,000,000	(Billions)	

DATA	MESSAGE SENT	PARTICIPANT SHOULD DISPLAY	
Bid size of 120575	Size field will indicate 1205C	120500	
Volume of 258,487,797	Volume will indicate 2584877C	258,487,700	

4.6 Strike Price Currency Codes

Currency			
Marker	DESCRIPTION		
USD	US\$		
CAD	Canadian \$		
Blank	Not provided		

4.7 Month Codes for Options

CALL OPTIONS					
A – January	E – May	I – September			
B – February	F – June	J – October			
C – March	G – July	K – November			
D – April	H – August L – December				
Put Options					
M – January	Q – May	U – September			
N – February	R – June	V – October			
O – March	S – July	W – November			
P – April	T – August	X – December			

4.8 Complex Order Instrument (Strategy) month code

The rule for determining the Month Code of Complex Order Instrument in the JS – Complex Order Instrument is determined from the <u>closest</u> expiry leg(s) as follows:

- If the closest expiry leg(s) have the <u>same</u> option type i.e either all legs are Call Options or all legs are Put Options then the Strategy Month Code is the corresponding month code of any of the leg as defined in the above table (section 4.7)
- If the closest expiry legs have <u>different</u> option type i.e some leg(s) are Call Option and the other leg(s) are Put Options, then the Strategy Month Code is chosen as the month code of the Call Option Leg as defined in the above table (section 4.7)

4.9 Market Feed Indicators

FIRST LETTER	TYPE OF INSTRUMENT	SECOND LETTER	TYPE OF UNDERLYING
0	Options	X	Index
L	Long Term	Е	Equities
F	FLEX Option	E	Equities



BOX Technology Canada Inc. 2000 Mansfield, Suite 510 Montréal, Quebec, H3B 0G7 Canada