# Smallworld 5 Magik debugger

Copyright Information

© 2018 General Electric Company or its Affiliates

Licensed under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at

http://www.apache.org/licenses/LICENSE-2.0

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

The information contained in this document is subject to change without notice.

The software described in this document is supplied under licence and may be used or copied only in accordance with the terms of such licence.

Date	28/02/2019	
Version	0.8	
Author	GE Smallworld	

## Contents

Installing and starting the debugger

Components of the debugger

Starting a session with the debug agent running

Windows

Linux

Starting the debug client in node.js

Starting the web GUI

Using the Magik debugger

Functions available in the debugger web GUI

Screenshots

Debugger Web GUI

List of threads

Thread stack trace

#### Limitations

# Installing and starting the debugger

## Components of the debugger

There are 3 components.

Item	Description	Prerequisites
Debug agent	This is shipped as a DLL (Windows: <i>mda.dll</i> ) or shared library (Linux & Solaris: <i>libmda.so</i> )	Smallworld 515 or later
Debug client running in node.js	Available from https://github.com/OpenSmallworld/magik-debugger. Clone or download the zip file and put in folder such as c:\magik-debugger	Minimum of node.js v8 required.
Web-based GUI	Browser based	Chrome or FireFox browsers. Internet Explorer not recommended

Note that the components can be co-located on the same host, or run from different hosts.

Note that source code is not a prerequisite for all functions of the debugger. It is possible to set breakpoints and inspect running threads without this.

Information in this document is based on the following component versions

Component	Version	Comments
Smallword	519	
Magik debug agent	14	
Magik debug client	"version": "0.1.1"	2018-05-25
Node.js	10.15.1	LTS stream

# Starting a Smallworld session with the debug agent running

The additional Java argument **-agentpath** is passed to the Magik session with the full path to the agent library as a parameter.

Examples

## Windows

runalias.exe **-j -agentpath:%SMALLWORLD\_GIS%\core\bin\x86\mda.dll** -a %SMALLWORLD\_GIS%..\cambridge\_db\config\gis\_aliases cambridge\_db\_open\_no\_auth

# Linux

/opt/smallworld/core/bin/share/runalias -i -

agentpath:/opt/smallworld/core/bin/Linux.x86/libmda.so -a

/opt/smallworld/cambridge\_db/config/gis\_aliases cambridge\_db\_open\_no\_auth

Alternatively, this can be added to an alias using environment variable SW\_LAUNCH\_JAVA\_ARGS:

```
eo_suite_open_dbg: title = Start Smallworld Electric Office Product Suite
session = sw_electric_office:eo_suite_open
SW_ACE_DB_DIR = %SMALLWORLD_GIS%/../electric_office/example_db/ds/ds_admin
SW_CONSTRUCTION_PACK_DIR= C:/Temp
SW_LAYOUT_DOCUMENT_DIR = C:/Temp
splash_screen =
%SMALLWORLD_GIS%/../electric_office/resources/base/bitmaps/smallworld_electric_splash.png
product = sw_electric_office
args = -cli
SW_LAUNCH_JAVA_MEMORY = -Xmx1500m
SW_LAUNCH_JAVA_ARGS = %SW_LAUNCH_JAVA_ARGS% -
agentpath:%SMALLWORLD_GIS%\bin\x86\mda.dll
```

Starting the session for debugging then becomes:

```
%SMALLWORLD_GIS%\core\bin\x86\runalias.exe -a
%SMALLWORLD_GIS%\electric_office\config\gis_aliases eo_suite_open_dbg
```

A magik session can be started with the debug agent enabled. The debugger is then connected when required. In-house testing shows that there appears to be little overhead in the Magik process when this is run.

**IMPORTANT** A debugger session should NOT be left unattended in a production environment, as this poses a serious security risk.

Note that **-agentpath** also accepts an additional argument to specify the port for the client. This is useful if multiple instances of the debugger need to be run:

#### Example:

```
%SMALLWORLD_GIS%\core\bin\x86\runalias.exe -j -
agentpath:%SMALLWORLD_GIS%\core\bin\x86\mda.dll=socket:20001 -a
%SMALLWORLD_GIS%\electric_office\config\gis_aliases eo_suite_open
```

# Starting the debug client in node.js

In order for the source code to be located, environment variables have to be defined for the session running the node.js Magik debugger client, to point to the locations of source.

Product	Variable name
Core product	SMALLWORLD_GIS
Other products	These are in the format <uppercase name="" product="">_DIR</uppercase>

Examples: PNI\_DIR PNI\_FTTH\_DIR SW\_DM\_DIR SCHEMATICS\_DIR SW\_COMMON\_OFFICE\_DIR SW\_ELECTRIC\_OFFICE\_DIR SW\_ELECTRIC\_OFFICE\_LP\_DIR SW\_GAS\_DIST\_OFFICE\_DIR

Assuming that the Debug client source is in c:\magik-debugger, as in the install example above

```
cd c:\magik-debugger
c:\magik-debugger >npm start localhost:32000
> magik.debugger@0.1.1 start c:\magik-debugger
> node server.js "localhost:32000"
Listening on port 4123
Connected to agent version 14
```

The Debug Agent communicates with the Debug Client using a TCP/IP connection which by default has a port number of **32000**. This can be specified when starting up the debug client, as described in the previous section.


The port for the Web GUI defaults to **4123** but is configurable using environment variable **PORT.** This is useful if multiple debugger sessions need to be run on the same host.

# Starting the web GUI

Assuming the port shown was as in the example above (4123):

Start your web browser, and enter localhost:4123

You should see a display similar to this:



# Using the Magik debugger

Functions available in the debugger web GUI

#### 1.Threads

Suspend and resume threads

• Look at the stack frame for a thread.

#### 2.Breakpoints

- Set breakpoints on method entry using the breakpoint tab
- Set breakpoints in methods at a specific source file location. Once the GUI knows about a source file
  one can single click on a source line to set a breakpoint. Note that this currently only works for
  methods.

#### 3. Variables

- Examine local variables and object slots in a suspended thread.
- Evaluate arbitrary Magik expressions in a given stack frame on a thread (click on the ">\_" button on the stack frame)

#### 4.Step execution.


- GUI Line step: steps to the next line of Magik source whether it is the current method or not.
- **GUI Over**: steps to the next Magik line in the current method or its caller.
- **GUI Out**: steps until control is returned to the next Magik line executed in a method calling this one. To stop execution stepping, suspend the thread.

#### Screenshots


# Scenario:

- List threads
- Set breakpoint in sw\_task\_runner.get\_next\_task()
- On break, jump to source


#### Thread tab (List of threads)




### Thread tab (Selected thread stack trace)



### **Breakpoint tab**



### Thread tab (Jumping to source)



This also shows the variable list for the stack execution stage when expanded.

# Limitations

Item	Limitation	Notes
Line Numbers	Sending magik code from emacs to the Magik session will lead to a mismatch in line numbers between the original code and what is compiled. Hence the debugger will not have accurate line number information.	The emacs lisp magik customization sends three extra source lines at the start of the file.
Breakpoints	Cannot set breakpoints when entering a Magik _proc	
	Cannot set breakpoints on Java methods	
Stepping	Stepping of execution can be very slow.	Line steps are generally not too slow.
	If the <b>Over</b> functionality has to step over a method invocation which does a lot of processing, then the time to run the step can be extremely large.	
	Similarly, the time take to execute <b>GUI Out</b> functionality can be large.	
Variables  F S V	The structure of the Magik code matches what is generated by the compiler not the source code.	This is a side- effect of cross- compilation.
	For example, the body of a loop appears as a separate method on the stack frame. As this has its own variable scope, the <b>_local</b> variables viewed in the loop body only be those used in the loop body. <b>_local</b> variables defined in the enclosing method and loop bodies but which are not used in the loop body will not be visible. In the example, when debugging the loop, variable <b>a</b> will not be visible, but variables <b>i</b> , <b>var_b</b> will be visible	See Example 1
	Similar, but slightly different:	For example, the debugger will not see the _local a in Example 2
	<b>_local</b> variables defined in a method but only set inside loops nested in the method might not be picked up by the debugger.	
	The debugger cannot access <b>_dynamic</b> variables.	

Item	Limitation	Notes
Evaluate function	Evaluating an expression can set <b>_global</b> variables. It cannot set <b>_local</b> variables.	
	When evaluating an expression _self is transformed into a different form of variable lookup.Accessing private methods and slots has to be done with sys!perform() and sys!slot() respectively.	
	Evaluation of the expression <b>quit()</b> will not have the expected effect.	quit() is effectively disabled in the evaluation mechanism
Various	Viewing the source code for a <b>_loopbody</b> does not work. The GUI cannot translate the stack frame for a <b>_loopbody</b> into a meaningful method name to look up in the source	This is a consequence of the cross-compilation from Magik to Java.Changing this would be a major piece of work

## **Example 1**

```
_method thing.test(a, b)
    a << 0
_for j _over a.elements()
_loop
    var_b << 99
    _for i _over b.elements()
    _loop
        var_b +<< i.operate(j)
    _endloop
_endloop
>> a
_endmethod
$
```

### Example 2

```
_method thing.test(a, b)
    a << 0
    _for j _over a.elements()
    _loop</pre>
```