Geometric Tools Engine Version 3.13 Installation Manual and Release Notes

David Eberly, Geometric Tools Document Version 3.13.0 June 7, 2018

Contents

1	Introduction		
	1.1	License	4
	1.2	Copying the Distribution to Your Machine	5
2	Development on Microsoft Windows		
	2.1	Environment Variables	6
	2.2	Compiling the Source Code	6
	2.3	Support for OpenGL	7
	2.4	Automatic Generation of Project and Solution Files	7
	2.5	Running the Samples	7
	2.6	Microsoft Visual Studio Custom Visualizers	8
	2.7	Falling Back to Direct3D 10	8
	2.8	Falling Back to Direct3D 9	9
	2.9	No Support Yet for Dynamic Libraries for GTEngine	9
	2.10	Managed Wrapper to Access GTEngine Code from C#	9
3	Dev	velopment on Linux	9
	3.1	Environment Variables	9
	3.2	Dependencies on Other Packages	10
	3.3	Compiling the Source Code	10
	3.4	Support for OpenGL via Proprietary Drivers	10
	3.5	Running the Samples	10
1	Sun	aport for Macintosh OS X is Discontinued	11

5	Accessing the OpenGL Driver Information	11
6	Automatic Generation of a Wrapper for OpenGL	11

1 Introduction

You are about to install Geometric Tools Engine 3.13. Version 1.0 source code was the companion to the book GPGPU Programming for Games and Science and was developed on Microsoft Windows 8.1 using Microsoft Visual Studio 2013, C++ 11 and Direct3D 11.1. Version 3.x is close enough to what is in the book that you should have no problem navigating the code as you read the book. The source code has been reorganized using subfolders of Source and Include and the header includes are now slightly different.

Version 3.x has a graphics engine that requires minimally OpenGL 4.3 (or later) and GLSL 4.3 (or later) in order to support compute shaders and GLSL introspection, and it runs on both Microsoft Windows (WGL) and Linux (GLX). Please observe that the engine and sample applications require OpenGL 4.3 (or later) and GLSL 4.3 (or later). If your graphics driver does not support this, the applications will gracefully terminate with a message to the console window: OpenGL 4.3 is required. In particular, the Nouveau Open Source graphics drivers that ship with the various flavors of Linux might not support OpenGL 4.3 (or later) or GLSL 4.3 (or later). You must install the graphics card manufacturer's proprietary driver in order to use the graphics engine.

A Direct3D 12 engine is in development, but given that the programming model is significantly different from Direct3D 11, the graphics subsystem of GTEngine needs to be redesigned. The plan is to factor GTEngine into smaller projects, each graphics API having its own project and corresponding application support. The mathematics library will also be factored into a stand-alone project to allow developers to use the code without having to depend on all other parts of the library.

Visit the Geometric Tools website for updates, bug fixes, known problems, new features and other materials.

1.1 License

The Geometric Tools Engine uses the Boost License, listed next.

Boost Software License - Version 1.0 - August 17th, 2003

Permission is hereby granted, free of charge, to any person or organization obtaining a copy of the software and accompanying documentation covered by this license (the Software) to use, reproduce, display, distribute, execute, and transmit the Software, and to prepare derivative works of the Software, and to permit third-parties to whom the Software is furnished to do so, all subject to the following:

The copyright notices in the Software and this entire statement, including the above license grant, this restriction and the following disclaimer, must be included in all copies of the Software, in whole or in part, and all derivative works of the Software, unless such copies or derivative works are solely in the form of machine-executable object code generated by a source language processor.

THE SOFTWARE IS PROVIDED ''AS IS'', WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, TITLE AND NON-INFRINGEMENT. IN NO EVENT SHALL THE COPYRIGHT HOLDERS OR ANYONE DISTRIBUTING THE SOFTWARE BE LIABLE FOR ANY DAMAGES OR OTHER LIABILITY, WHETHER IN CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

1.2 Copying the Distribution to Your Machine

You may unzip the distribution to a folder of your choice. The top-level folder of the distribution is GeometricTools and the subfolder for the distribution is named GTEngine. Some of the folder hierarchy is shown next. The Include and Source folders contain all the code for the engine.

```
GeometricTools
                                 Root folder for Geometric Tools Engine, set GTE_PATH to here.
 GTEngine
   Include
                                  Location for *.h files
        Applications
                                  Platform-independent classes
                                  Support for Linux GLX applications
           GLX
                                  Support for Microsoft Windows applications.
           MSW
                DX11
                                  Support for Direct3D 11 applications.
                                  Support for WGL applications
                WGL
        Graphics
                                  Platform-independent\ graphics\ files\ .
           DX11
                                 DX11-specific graphics files
                                  Platform—independent OpenGL—specific graphics files.
            GL4
                                  Linux GLX graphics files
                GI X
                                 WGL graphics files
                WGL
        Imagics
                                 Image processing files
                                  Several low-level utility files
        LowLevel
                                  Microsoft Windows-specific files
         MSW
                                  The bulk of the engine consists of mathematics support.
        Mathematics
                                  Microsoft Windows-specific files
         MSW
                                  Some physics support, not all WM5 physics code has been ported
        Physics
                                  Location for *.cpp files
    Source
        Applications
                                  Platform-independent\ classes
                                  Support for Linux GLX applications
           GI X
           MSW
                                  Support for Microsoft Windows applications.
                DX11
                                  Support for Direct3D 11 applications
                WGL
                                  Support for WGL applications
        Graphics
                                 Platform-independent graphics files
            DX11
                                 DX11-specific graphics files
            GL4
                                  Platform-independent OpenGL-specific graphics files.
                                  Linux GLX graphics files
                GLX
                WGI
                                 WGL graphics files
        Imagics
                                 Image processing files
                                  Several low-level utility files
        LowLevel
         MSW
                                  Microsoft Windows-specific files
        Mathematics
                                  The bulk of the engine consists of mathematics support.
         MSW
                                  Microsoft Windows-specific files
                                  Some physics support, not all WM5 physics code has been ported.
        Physics
    Samples
                                  Sample applications, many discussed in the GPGPU book.
      Data
                                 A small number of data files for the samples.
      Basics
                                  Basic tutorials for several HLSL concepts
                                  Sample application with libraries to call C++ code from C#.
      \mathsf{CSharpCppManaged}
      Geometrics
                                  Samples for computational geometry.
      Graphics
                                  Samples for graphics and video streams (parallel copy).
                                  Samples for 2D and 3D image processing
      Imagics
      Mathematics
                                  Samples for mathematical algorithms and numerical methods.
                                  Samples for 2D and 3D physics
      Physics
     DX11
                                  Samples specifically for Direct3D 11.
    Shaders
                                  HLSL/GLSL shader files (embedded versions are in the engine source).
    Tools
                                  Several convenient tools.
                                  Generate .h/.cpp file to represent a graphics font.
      {\sf BitmapFontCreator}
      GenerateApproximations
                                  Used to generate the minimax approximations for common functions
                                  Source-code generator for gl* wrappers driven by glcorearb.h.
      GenerateOpenGLWrapper
                                  Generate MSVS 2013/2015 vcxproj, sln, h and cpp for applications.
      GenerateProject
      Precision Calculator
                                  Determine bits of precision needed exact-arithmetic algorithms.
```


The Samples subfolders are many. Listing them here would make the displayed hierarchy difficult to read. The projects all use paths relative to GTEngine and they do not rely on the top-level directory being located at the root of a hard drive. An environment variable GTE_PATH is used to locate data files required by the application. How you set an environment variable depends on the operating system and/or shell you are using.

2 Development on Microsoft Windows

The code is maintained currently on an Intel-based computer with Microsoft Windows 10, Version 1607 (OS Build 14393.969). If you develop on Microsoft Windows 7 or 8.x and encounter problems with the code, contact us via the email address listed at the Geometric Tools website.

2.1 Environment Variables

Create an environment variable named GTE_PATH that stores the absolute directory path to the folder GeometricTools/GTEngine. For example, if you unzipped the distribution to the root of the C drive, you would set GTE_PATH to C:/GeometricTools/GTEngine. You can set environment variables via System | Advanced system settings, which launches the System Properties dialog with a button for Environment Variables.



2.2 Compiling the Source Code

Microsoft Visual Studio 2013 uses Version 12 (Platform Toolset v120) of the compiler, Microsoft Visual Studio 2015 uses Version 14 (Platform Toolset v140) of the compiler and Microsoft Visual Studio 2017 uses Version 15 (Platform Toolset v141). The project and solution names have embedded in them v12, v14 or v15; that is, all three versions of the compiler are supported. The engine solutions are in the root folder GeometricTools/GTEngine and are named GTEngine.v12.sln, GTEngine.v14.sln and GTEngine.v15.sln. Each sample

application or tool has its own solution with all dependencies listed, so it is possible to open a sample application and compile and run it without explicitly building the engine solution first. The root folder also contains the solutions GTBuildAll.v12.sln, GTBuildAll.v14.sln, and GTBuildAll.v15.sln if you want to build the engine, samples and tools at the same time rather than building the projects separately.

2.3 Support for OpenGL

All the Microsoft Visual Studio projects have configurations Debug and Release that include compiling the Direct3D 11 source code. The configurations DebugGL4 and ReleaseGL4 include compiling the OpenGL source code. Although it is possible to have an application that creates both a Direct3D 11 engine and an OpenGL engine, the current project design does not allow this. If you have such a need, you must create your own GTEngine project that enables both sets of graphics code. For example, you might have an application that uses OpenGL for rendering but uses Direct3D 11 for compute shaders (for GPGPU).

2.4 Automatic Generation of Project and Solution Files

Creating a new Microsoft Visual Studio project and manually setting its properties to match those of the current sample applications is tedious. A tool is provided to generate a skeleton project, solution and source files, namely, GeometricTools/GTEngine/Tools/GenerateProject. As an example of how to use the tool, suppose you want to create a new project in the folder, GeometricTools/GTEngine/Samples/Graphics/MySample for a sample application. Copy GenerateProject.exe to that folder, and in a command window opened in that folder, execute

GenerateProject 3 MySample

The number 3 indicates the nesting of the MySample folder relative to the GTEngine folder. The tool creates the files MySample.v12.sln, MySample.v12.vcxproj, MySample.v12.vcxproj, filters, MySample.v14.sln, MySample.v14.vcxproj, MySample.v15.sln, MySample.v15.vcxproj, MySample.v15.vcxproj, filters, MySample.v15.sln, MySample.v15.vcxproj, MySample.v15.vcxproj, filters, MySample.v16.vcxproj, filters, MySample.v16.vcxproj, filters, MySample.v16.vcxproj, MySample.v17.vcxproj, filters, filters,

If you want the generated files to live in a folder outside the GTEngine hierarchy, you will need to modify the include path in the projects to \$(GTE_PATH)/Include. You will also need to delete the GTEngine project from the Required folder of the solution and re-add it so that the correct path occurs. This is necessary because the Microsoft Visual Studio reference system is used to link in the GTEngine library.

Also, it is not necessary to copy GenerateProject.exe to the project folder. If the executable can be found via the PATH statement, just execute it in any folder of your choosing and then copy the generated files to your project folder.

2.5 Running the Samples

You can run the samples from within the Microsoft Visual Studio development environment. Samples that access data files use the GTE_PATH environment variable to locate those files; code is in place to assert when the environment variable is not set. If you run from Microsoft Windows, presumably double-clicking an executable via Windows Explorer, the environment variable is still necessary.

Many of the samples compile HLSL shaders at run time. This requires having D3Dcompiler_*.dll in your path, where * is the version number of the shader compiler. You might have to modify your PATH environment variable to include the path. With latest Windows, the DLL should be in a Windows Kit bin folder.

2.6 Microsoft Visual Studio Custom Visualizers

A new file has been added, GeometricTools/GTEngine/gtengine.natvis, that provides a native visualizer for the Vector and Matrix classes. Copy this to C:/Users/YOURLOGIN/Documents/Visual Studio 2015/Visualizers. More visualizers will be added over time. Feel free to suggest GTEngine classes for which you want specialized visualization during debugging.

2.7 Falling Back to Direct3D 10

For Microsoft Windows machines, the default settings for GTEngine are to use Direct3D 11.0 or later for rendering and to compile the shaders for the built-in effects (such as Texture2Effect and VertexColorEffect) using Shader Model 5. These settings are also used when compiling shaders that are part of the sample application or those you write yourself. If you do not have graphics hardware recent enough to support the default configuration, it is possible to modify the start-up code in the sample applications to fall back to Direct3D 10.0 (Shader Model 4.0) or Direct3D 10.1 (Shader Model 4.1).

Open the graphics sample named VertexColoring. The main function has the block of code

```
Window:: Parameters parameters (L" VertexColoringWindow", 0, 0, 512, 512); auto window = TheWindowSystem. Create < VertexColoringWindow > (parameters); TheWindowSystem. MessagePump (window, TheWindowSystem. DEFAULT_ACTION); TheWindowSystem. Destroy < VertexColoringWindow > (window);
```

All the 2D and 3D windowed applications have similar blocks of code. The Window::Parameters structure has a member named featureLevel that defaults to D3D_FEATURE_LEVEL_11_0. The general list of values from which you can choose is

```
enum D3D_FEATURE_LEVEL
     D3D_FEATURE_LEVEL_9_1
                                 = 0 \times 9100,
                                                   / 4_0_level_9_1
    D3D_FEATURE_LEVEL_9_2
                                 = 0 \times 9200
                                                    4_0_level_9_1
    D3D_FEATURE_LEVEL_9_3
                                 = 0 \times 9300,
                                                 // 4_0_level_9_3
                                                 // 4_0
// 4_1
    D3D_FEATURE_LEVEL_10_0
                                 = 0 \times a000.
    D3D_FEATURE_LEVEL_10_1
                                 = 0 \times a100,
    D3D_FEATURE_LEVEL_11_0
                                                   / 5_0
                                 = 0 \times b000
    D3D_FEATURE_LEVEL_11_1
                                 = 0 \times b100
D3D_FEATURE_LEVEL;
```

The enumeration is found in d3dcommon.h. If you have a graphics card that supports at most Direct3D 10.0, then modify the main code to

```
Window:: Parameters parameters (L" VertexColoringWindow", 0, 0, 512, 512);
#if !defined (GTE_DEV_OPENGL)
    parameters . featureLevel = D3D_FEATURE_LEVEL_10_0;
    HLSLProgramFactory:: defaultVersion = "4_0";
#endif
    auto window = TheWindowSystem . Create < VertexColoringWindow > (parameters);
    TheWindowSystem . MessagePump (window, TheWindowSystem . DEFAULT_ACTION);
    TheWindowSystem . Destroy < VertexColoringWindow > (window);
```

Comments were added after the enumerates to indicate what to assign to HLSLProgramFactory::defaultVersion.

For non-windowed applications, the DX11Engine constructors allow you to specify directly the feature level.

2.8 Falling Back to Direct3D 9

This is not really possible, because GTEngine uses constant buffers and other concepts without equivalent DX9 representations. The best you can do is specify one of the feature levels mentioned in the previous section for which LEVEL_9 is part of the name. Note that there is no shader profile with name 4_0_level_9_2. If you set the version string to "3_0", the D3DReflect call will fail with HRESULT 0x8876086C, which is not listed in winerror.h. This is the code for the obsolete D3DERR_INVALIDCALL. The HLSL assembly instructions for Shader Model 3 do not contain constant buffer register assignments (because they did not exist then).

2.9 No Support Yet for Dynamic Libraries for GTEngine

Currently, the engine solution generates static libraries. The hooks are in place for dynamic libraries, but the build configurations have not yet been added to the projects.

2.10 Managed Wrapper to Access GTEngine Code from C#

There is a new project

GeometricTools/GTEngine/Samples/CSharpCppManaged

that shows how to wrap GTEngine code using a managed wrapper (C++/CLI) that can be called from C# code.

3 Development on Linux

The GTEngine source code and sample applications have been tested on five flavors of Linux: Fedora 24, Debian 8.5.0, Ubuntu 16.04, Open SUSE Leap 42.2 and Linux Mint 18 (MATE). As mentioned previously, your graphics driver must be capable of OpenGL 4.3 (or later) and GLSL 4.3 (or later).

3.1 Environment Variables

Create an environment variable named GTE_PATH that stores the absolute directory path to the folder GeometricTools/GTEngine. For example, if you use a bash shell, you would define the environment variable in the file .bashrc by adding the line

 ${\tt GTE_PATH=/home/YOURLOGIN/GeometricTools/GTEngine} \ \ ; \ \ {\tt export} \ \ {\tt GTE_PATH}$

The actual path depends on YOURLOGIN and where you copied the GTEngine distribution. The .bashrc file is processed when you login; however, if you modify it after logging in, you may process it by executing

```
source .bashrc
```

from a terminal window whose active directory is your home folder. For other versions of Linux or other shells, consult your user's guide on how to create an environment variable.

3.2 Dependencies on Other Packages

Each of the five supported flavors of Linux was installed from Live distributions. GTEngine depends on development packages for X11, OpenGL, GLX and libpng. The latter package is used for a simple reader/writer of PNG files for the sample applications. Use the package manager for your Linux distribution to install the aforementioned dependencies.

3.3 Compiling the Source Code

The makefile to build the GTEngine library is GeometricTools/GTEngine/makeengine.gte where both static and shared library builds are supported. From a terminal window execute

```
make CFG=configuration -f makeengine.gte
```

where configuration is Debug or Release for static libraries abd is DebugDynamic or ReleaseDynamic for shared libraries.

You can build all samples by changing directory to GeometricTools/GTEngine/Samples and executing make CFG=configuration -f makeallsamples.gte

If you want to build a single sample application, change directory to the sample folder. For example, change directory to GeometricTools/GTEngine/Samples/Graphics/VertexColoring and execute

```
make CFG=configuration APP=VertexColoring -f ... / makesample.gte
```

3.4 Support for OpenGL via Proprietary Drivers

Many of the Linux distributions ship with Nouveau as the default graphics driver. If the driver does not support OpenGL 4.3 or later, the sample applications will terminate with a message *OpenGL 4.3 is required*. To execute the samples, You should install the NVIDIA proprietary drivers. How you install these drivers depends on the Linux distribution.

GTEngine uses a minimum of GLX functions in order to create windows that allow OpenGL accelerated rendering. All functions are included in the GLX packages for Linux, so there is no need for GLX extensions.

3.5 Running the Samples

For the static library builds, you can simply open a terminal window and change directory to the project directory. For example, if you built the static release library and the Graphics/BlendedTerrain sample application, the application can be launched by executing ./BlendedTerrain.Release

For shared library builds, the libraries are stored in GeometricTools/GTEngine/lib. A simple way to launch the application is the following. Suppose you have a terminal window open and you have changed directory to Samples/Graphics/BlendedTerrain and that you have built the shared release versions of the engine and application. Execute the following

 $LD_LIBRARY_PATH = \$GTE_PATH / \ lib / ReleaseDynamic . / BlendedTerrain . . / Bl$

4 Support for Macintosh OS X is Discontinued

Development on Macintosh OS X has evolved significantly, veering away from standard windowing and graphics support. I do not program in Objective C or Swift, and Metal and OpenCL are preferred over third-party OpenGL. My test machine for Macintosh has been a Mac Mini, and the latest OS X cannot be installed on it. Apple and Macintosh products seem to be designed mainly for consumers, not for scientific computing or graphics. I no longer have the time (or desire) to support the Macintosh.

That said, if you want to use the non-graphics code on a Macintosh, feel free to grab that code and create your own Xcode projects. If you get compiler warnings or errors for the code, send me an email and I will do my best to modify the code to fix those problems. The effort on your part will be to test my changes and let me know whether they worked, in which case I will update the source code accordingly in the distribution.

5 Accessing the OpenGL Driver Information

This section is applicable both to Microsoft Windows and to Linux.

The GL4Engine code is designed to allow you to write to disk information about the OpenGL driver. Extending the example for VertexColoring described in the previous sections, modify the main code

```
\label{eq:window:parameters} Window:: Parameters parameters (L"VertexColoringWindow", 0, 0, 512, 512); \\ \mbox{\#if} & defined (GTE\_DEV\_OPENGL) \\ & parameters . deviceCreationFlags = 1; \\ \mbox{\#endif} & \mbox{auto} & window = TheWindowSystem . Create < VertexColoringWindow > (parameters); \\ & TheWindowSystem . MessagePump (window, TheWindowSystem . DEFAULT\_ACTION); \\ & TheWindowSystem . Destroy < VertexColoringWindow > (window); \\ \mbox{\coloringWindow} & \mbox{\co
```

For now the only device creation flags for OpenGL are the default 0 or 1, the latter causing the OpenGL driver information to be written to a file named OpenGLDriverInfo.txt. The first several lines of the file show the vendor, the renderer (graphics card model and related) and the OpenGL version supported by the driver. The remaining lines list supported OpenGL extensions.

6 Automatic Generation of a Wrapper for OpenGL

Several packages may be found online that provide wrappers that query for OpenGL function pointers and that encapsulate many of the gory details in using the OpenGL API. As an alternative, GTEngine ships with a tool to build a wrapper, GeometricTools/GTEngine/Tools/GenerateOpenGLWrapper. The file GteOpenGL.h was written manually—do not modify it. The file GteOpenGL.cpp is generated by parsing glcorearb.h, a file that is available from the OpenGL Registry. This file is introduced in the OpenGL 4.3 Specification.

If the file is updated or if you want to use a previous version, you can copy your file to the tool's project folder and then use the wrapper tool to regenerate GteOpenGL.cpp and copy it to

GeometricTools/GTEngine/Source/Graphics/GL4/GteOpenGL.cpp

You must also copy your version of glcorearb.h to

Geometric Tools/GTEngine/Include/Graphics/GL4/GL/glcorearb.h

The extension files from the OpenGL Registry were also copied to the same folder as glcorearb.h. These include glext.h, glxext.h and wglext.h. The first two are not used by the engine, but the last one is used by the WGL OpenGL engine.

The GenerateOpenGLWrapper tool has projects for Microsoft Visual Studio. To build this on Linux,

and then execute the program in the project folder.