CS 211 Cheat Sheet

Base Arithmetic and Conversions

To convert **decimal to binary**, divide by 2 and if remainder is even the binary remainder is 0, else 1. Take the first digit and work up to the last.

Hex arithmetic is done by adding normally and converting to base 16, i.e. 17 + A7 becomes 7 + 7 = 14 = E, and then

1 + A = 11 = B so we get BE

Hex multiplication is the same as base-10, except we end up subtracting by 16 when we get the sum.

 $21 \times 2 = (2 \times 1) + (20 \times 2) = 42$

Hex	Binary	Decimal	Hex	Binary	Decimal
0	0000	0	8	1000	8
1	0001	1	9	1001	9
2	0010	2	A	1010	10
3	0011	3	В	1011	11
4	0100	4	С	1100	12
5	0101	5	D	1101	13
6	0110	6	E	1110	14
7	0111	7	F	1111	15

De Morgan's Law

_	(A	\wedge	B)	=	(¬	A)	V	(¬	(B)
F	Т	Т	T	Т	F	Т	F	F	T
Т	T	F	F	T	F	T	T	T	F
Т	F	F	Т	Т	T	F	Т	F	T
Т	F	F	F	Т	Т	F	Т	Т	F

Pipelining

Instr. No.	Pipeline Stage						
1	느	ID	EX	MEM	WB		
2		IF	ID	EX	MEM	WB	
3			IF	ID	EX	MEM	WB
4				IF	ID	EX	MEM
5					IF	ID	EX
Clock Cycle	1	2	3	4	5	6	7

The process of taking multiple instances of one process and streamlining it. By pipelining, you shorten the total amount of time for things to be done, but often have to make a certain step of the process take longer. Without pipelining, instance one would go A to B to C and instance two would start when it completes. With pipelining, instance one finishes A, stores that value in a register, begins instance B and as it begins B instance 2 begins A, etc until it is completed.

General Pipelining is the idea that there is no reason to ever have idle hardware in a computer. INSTRUCTION

Pipelining is when each instruction step is split up and consecutive instructions are executed at the same time. IN **Order**: Instruction Fetch, instruction Decode, Execute, Memory access, register write back.

Data dependency: the output of one instruction is an input to another.

Control dependency: some instruction determines the location of the instruction to execute call, return jump

Dealing by Stalling: prevent the execution of an instruction until the outputs of the previous instructions(use no-ops to stall)

Dealing by Forwarding: make output values available to earlier instructions. Just keep executing instructions, look at pending values instead of current value and get it.

Structural hazards commonly occurs when two activites require the same resource. Solution: We stall the pipeline when if it occurs. A Control hazard are a type of hazard that occur from an uncertain execution path, either a possible branch or a branch not taken. Solution: A stall, or by delaying the branch. Data hazards occur when the pipeline changes the order of read/write access, or when some instruction is dependant on the outcome of a previous instruction not yet completed. Solution: Internal forwarding.

Random Access Memory

RAM is the primary means for a computer to run programs in real time. RAM is designed to be fast and dense, but most RAM is also volatile, meaning that information is lost quickly when there is no power provided to the chip.

Static

SRAM is more expensive because it takes several transistors and capacitors per each bit of memory, making it naturally less dense. The advantages for SRAM are as follows: It is faster, and it has constant-time direct address access. It also, depending on the implementation, can be much less power dependent.

Dynamic

DRAM is the simplest form of storage available, each bit is just one capacitor that either has a charge or does not have a charge. This makes DRAM extremely memory dense, and very very very cheap. The problem is that, because capacitors lose charge quickly, each address has to be "refreshed" (re-charged) periodically to avoid loss of information. This makes it slow and power inefficient.

Why is DRAM so slow?

DRAM is slow, relative to SRAM, because so much effort is expended to make sure that the information you are accessing is the information that you want and not some corruption due to loss of charge.

Furthermore, **DRAM** is arranged as a 2D array, and this is why it is slower to access. We must go row then column, or column then row. These are known as **Row Access Strobe** and **Column Access Strobe requests**.

DRAM requires data to be refreshed from time to time in order to keep the data SRAM does not need to be refreshed, since the transistors inside continue to hold the data as long as power supply is on. DRAM contains more circuitry, and requires more timing for the refresh, creating complications that make it slower than SRAM (higher power requirement is such a complication) SRAM is simpler compared to DRAM, but need more transistors than DRAM. DRAM generally need a single transistor for each bit of data, but SRAM need 6 (this is why DRAM is cheaper and larger)

Caches

Block: a fixed chunk of data that moves back and forth between cache and main memory.

Set: collection of lines.

Working Set: set of blocks we are using now, changes through execution.

Capacity: total number of bytes that it can hold. Obtained by the number of blocks multiplied by the size, where the blocks is the number of sets multiplied by the number of lines per set.

Cold Miss: occurs when memory location is accessed for the first time.

Conflict Miss: occurs when the level cache is large enough, but multiple data items all map to the same k block.

Cache Hit: when we look for something and it is there.

Fully associative: allowed to choose any entry

Set associative: more than one line per set, powers of 2. All must have same amount.

Direct-mapped cached: simplest kind, one line per set.

Endianness

Two forms of Endian-ness (big endian, little endian), which refer to the ordering of bytes stored in memory, determined by significance of byte. Little endian store least significant byte first, at lowest byte address (most machines) and big endian store most significant byte first at lowest byte address.

Two kinds, Big endian and Little endian. Big endian is MSB first, decreasing numeric significance as byte address increases. Little endian is LSB first, with an increasing numeric significance as the address increases (Intel uses this). For example, storing OAOBOCOD: Big Endian - OA OB OC OD; Little Endian OD OC OB OA

LRU and LFU algorithms

Least Recently Used (LRU): discards the least recently used items first. This algorithm requires keeping track of what was used when, which is expensive if one wants to make sure the algorithm always discards the least recently used item.

Least recently used works by using system clock to determine when cache was used recently. Caches that were used a long time ago are evicted first

We always increment global counter by one for any block. If the block we are looking for is already in the cache, we set the counter for the block to the global access counter. If it is not in the cache, we get the block, put it in the cache, and set its count equal to the global counter. You put an "event time" on the block. Event timer is another step forward in timekeep accessing the same block, they they move forward. The block we used furthest in past gets evicted.

Least Frequently Used (LFU): LFU counts how often an item is needed. Those that are used least often are discarded first. The simplest method to employing an LFU algorithm is to assign a counter to every block that is loaded into the cache. Each time a reference is made to that block the counter is increased by one. When the cache reaches capacity and has a new block waiting to be inserted the system will search for the block with the lowest counter and remove it from the cache.

Least frequently used works by using hardware flags to determine how many times something is used. Least frequently used cache is evicted (duh). There's some problems with this since something can be used a lot at the beginning and then not be used at all afterward. Every block as an integer usage counter, initialized to one. Every time a block in cache is accessed, increment it. When it comes time to evict, select the block with the lowest counter value. Read in a new block and the counter is set to one (because of locality, we increment it).

Limitations: if we use a block a lot and stop using it, it won't be evicted even though it is not being currently used a lot.

$$T = m * T_m + T_h + E$$

T =average memory reference time

m = miss ratio = 1 - (hit ratio)

 T_m = time to make a main memory access when there is a miss (or, with multi-level cache, average memory reference time for the next-lower cache)

 $T_h=$ the latency: the time to reference the cache when there is a hit

 $E={\rm various}$ secondary effects, such as queuing effects in multiprocessor systems

x86 Instructions

mov	copies data from the second operand to the
	first. Can not do memory to memory.
lea	places address of second operand into the reg-
	ister of the first.
add	adds two operands together, stored in the first
	operand.
sub	subtracts two operands together, stored in the
	first operand.
imul	multiplies two operands together and stores it
	in the first operand.
and,	applies the bitwise operator on two operands,
or, xor	stored in the first operand.
jumps	jumps to a label depending on location.
cmp	nondestructive subtraction.


Call Stack

Stack **grows downards** (high to low addresses). The top is the %esp register. The frame pointer, or %ebp serves a fixed location, such as the return address. The portion allocated for a single procedure is called a stack frame.


push: set the stack pointer to %esp = %esp (4 times the number
of registers)

pop: copy the data from the stack to the registers, then %esp =
%esp + 4(times the number of registers)

Having a frame pointer is convenient when a function is likely to move the stack pointer several times throughout the course of running the function.





Karnaugh Maps AB



Solving a Karnaugh Map: (1) Group rectangles that are touching; (2) Each rectangle is an or statement; (3) Remember that they can wrap from side to side.

Drawing a Circuit





Locality

Good locality allows a program to run faster than one with poor locality. Stride-k is sequential visiting pattern, for example visiting every space in an array is of stride 1, with every k th element being stride k.

Temporal Locality occurs when things occur over a short period of time next to each other.

memory that is referenced once is likely to be referenced again (the more you use one thing, the better). As an example, using the same variable in a summation for loop instead of using multiple variables.

Spatial Locality occurs when things are close together in memory/space. As stride increases, the spatial locality decreases. (keep memory that you use a lot close by to each other.)

For example, the elements in an array, arr will have spatial locality. Accessing i and arr[i] happen after each other, so they have temporal locality.

Writing Policies

Write-through: Every time you write something to a cached block, you write it through to whatever is below this block. If you write to L1, then you also write to L2. *Advantages*: easy with software and hardware, always consistent, good if reads is greater than writes. *Disadvantages*: if writes is greater than reads, lose a significant amount of speed

Write-back: Only when a page is evicted do you write it to the lower level. Usually the larger a block is, the more likely they are to be write-back. *Advantages*: faster, smaller number of downward block transfers; *Disadvantages*: harder to implement, greater possibility of data inconsistency

Writing to blocks not in cache:

Write-allocate: Puts the block in the cache, so subsequent writes also go to the cache. Advantages: takes advantage of spacial locality. Disadvantages: every miss requires a block transfer upwards, causing a block eviction

No-Write-Allocate: Does not take advantage of spacial locality (write-through is typically no-write-allocate)

Addressing Modes

Instruction (mov)	Result
eax, ebx	ebx = eax
(eax), ebx	ebx = mem[eax]
4(eax), ebx	ebx = mem[eax+4]
(eax, ecx), ebx	ebx = mem[eax + ecx]
4(eax, ecx), ebx	ebx = mem[eax + ecx + 4]
(eax, ecx, 2), ebx	ebx = mem[eax + ecx*2]
4(eax, ecx, 2), ebx	ebx = mem[eax + ecx*2 + 4]

Two's Complement

Gives us the ability to represent negative values. In binary, negative numbers start with a 1 and positive numbers start with a 0. For example, we will use 00002710. In order to find the twos complement form of a number, we do two steps: (1) Flip - we flip the bits to become FFFFD8EF. (2) Add One - we add one to the number, becoming FFFFD8F0.

Shifting

There are two types: Left Shift moves bytes to the left. Same as multiplying 2^n . Right Shift moves bytes to the left. Same as dividing 2^n .

Each has two forms: **Arithmetic** preserves sign. **Logical** means our new high bits are zero, including sign.

Floating points

First bit is the sign bit which determines if the number is positive or negative. The next are the exponent. The rest are fraction for the number.

Assembly to C

of a matrix is movl %ecx, array(, %rax,4).

Depending on syntax, addl r1,r2 becomes r2 = r1+r2. Jumps and conditions allow us to create loops. An auto array will be made by movl %edx, -48(%rbp,%rax,4) and scaled by 4 because it is an int array. Accessing a struct array is movl %edx, a+8(,%rax,4) where a is the name of the struct. Row major access