DKB Documentation

DKB team

CONTENTS:

	pyDKB package 1.1 Subpackages	1
2	Indices and tables	11
Ру	thon Module Index	13
In	dex	15

CHAPTER

ONE

PYDKB PACKAGE

Common library for Data Knowledge Base development.

1.1 Subpackages

1.1.1 pyDKB.common package

Common modules.

Submodules

pyDKB.common.Type module

```
Abstract class for type definitions.
class pyDKB.common.Type.Type(*args)
     Bases: object
     Abstract class for type definitions. Usage:
          myType = Type("Orange", "Apple")
          myType.add("Plum")
          t = myType.Orange
          if t == myType.Orange: # Oranges stuff
          elif t == myType.member("Apple"): # Apples stuff
          if not myType.hasMember(t): print "Wrong type!"
     add (name)
          Add new Type member.
     hasMember(val)
          Check if the member exists (by value).
     member (name)
          Check if the member exists (by name).
          Return member value or False.
```

```
memberName (val)
```

Return string name of the member.

pyDKB.common.custom_readline module

Custom_readline() separates content from a text file 'f' by delimiter 'newline' to distinct messages. The last line can be incomplete, if the input data flow is interrupted in the middle of data writing.

Keyword arguments: f – file/stream to read newline – custom delimiter

pyDKB.common.exceptions module

Definition of common modules exceptions

```
 \begin{array}{c} \textbf{exception} \\ \textbf{Bases:} \\ \textbf{exceptions.RuntimeError} \end{array}
```

Base Exception for HDFS module.

pyDKB.common.hdfs module

Utils to interact with HDFS.

```
pyDKB.common.hdfs.check_stderr(proc, timeout=None, max_lines=1)
```

Wait till the end of the subprocess and send its STDERR to STDERR.

Output only MAX_LINES of the STDERR to the current STDERR; if MAX_LINES == None, output all the STDERR.

Return value is the subprocess' return code.

```
pyDKB.common.hdfs.getfile(fname)
```

Download file from HDFS.

Return value: file name (without directory)

```
pyDKB.common.hdfs.listdir(dirname, mode='a')
```

List files and/or subdirectories of HDFS directory.

Parameters: dirname – directory to list mode – 'a': list all objects

'f': list files 'd': list subdirectories

```
pyDKB.common.hdfs.makedirs(dirname)
```

Try to create directory (with parents).

```
pyDKB.common.hdfs.putfile (fname, dest)
```

Upload file to HDFS.

pyDKB.common.json utils module

Utils to work with JSON (dict) objects.

```
pyDKB.common.json_utils.nestedKeys(key)
```

Transform STRING with nested keys into LIST.

Parameters:

STRING key – dot-separated list of nested keys. If a key contains dot itself, the key must be put between quotation marks.

```
pyDKB.common.json_utils.valueByKey(json_data, key)
```

Return value by a chain (list) of nested keys.

Parameters: DICT json_data – to search in STRING key – dot-separated list of nested keys

1.1.2 pyDKB.dataflow package

Dataflow organization utils.

Subpackages

pyDKB.dataflow.stage package

Stage submodule init file.

```
class pyDKB.dataflow.stage.JSONProcessorStage
    Bases: pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorStage
    JSON2JSON Processor Stage
    Input message: JSON Output message: JSON
    file_input (fd)
```

Override AbstractProcessorStage.file_input

file_nd_json(fd)

Read file as NDJSON file.

Raises ValueError if can't read the first line.

file_true_json(fd)

Read file as true JSON file.

```
class pyDKB.dataflow.stage.TTLProcessorStage
```

Bases: pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorStage

TTL2TTL Processor Stage

Input message: TTL Output message: TTL

output (message)

Put the (list of) message(s) to the output buffer.

```
class pyDKB.dataflow.stage.JSON2TTLProcessorStage
```

Bases: pyDKB.dataflow.stage.processors.JSONProcessorStage, pyDKB.dataflow.stage.processors.TTLProcessorStage

JSON2TTL Processor Stage

Input message: JSON Output message: TTL

input()

Override: Falls back to JSONProcessorStage.input

output (message)

Override: Falls back to TTLProcessorStage.output

1.1. Subpackages 3

Submodules

pyDKB.dataflow.stage.AbstractProcessorStage module

Definition of an abstract class for Dataflow Data Processing Stages.

```
USAGE: ProcessorStage [<options>] [<input files>]
```

OPTIONS:

```
-s, --source
                      {flslh} - where to get data from: local (f)iles, (s)tdin, (h)dfs
                      DIR - base directory for relative input file names (for local and
-i, --input-dir
                      HDFS sources). If <input files> not specified, all files from the
                      directory will be taken as the input.
-d, --dest
                      {flslh} - where to send data to: local (f)iles, (s)tdout, (h)dfs
                      DIR - base directory for output files (for local and HDFS
-o, --output-dir
                      sources)
--hdfs
                         • equivalent to "-source h -dest h"
-m, --mode
                      MODE - MODE: (f)ile = -source f
                           -dest f (can be
                             rewritten with 's' or 'h')
                      (s)tream = -source s (can be
                             rewritten with 'h')
                           -dest s
                      (m)apreduce = -source s (can be
                             rewritten with 'h')
                           -dest s
```

class pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorStage(description='DKB

Dataflow data pro-cess-ing stage.')

Bases: pyDKB.dataflow.stage.AbstractStage.AbstractStage

Abstract class to implement Processor stages

Processor stage – is a stage for data processing/transfornation.

Class/instance variable description: * Current processing file name:

```
current file full – full name with path current file – file name
```

- Iterable object for input data sources (file descriptors) __input
- Output messages buffer: __output_buffer
- Generator object for output file descriptor OR file descriptor (for (s)tream mode)

```
__output
```

• List of objects to be "stopped" __stoppable

```
clear buffer()
     Drop buffered output messages.
defaultArguments()
     Default parser configuration.
file flush()
     Flush message buffer into a file.
     By default writes to file as to a stream. To be implemented individually if needed.
file_input (fd)
     Generator for input messages.
     By default reads file just as stream. To be implemented individually for other cases.
flush_buffer()
     Flush message buffer to the output.
forward()
     Send EOPMessage in the streaming output mode.
input()
     Generator for input messages.
     Returns iterable object. Every iteration returns single input message to be processed.
input_message_class()
     Get input message class.
output (message)
     Put the (list of) message(s) to the output buffer.
output_message_class()
     Get output message class.
parseMessage (input_message)
     Verify and parse input message.
     Is called from input() method.
parse_args (args)
     Parse arguments and set dependant arguments if neeeded.
static process(stage, input_message)
     Transform input_message -> output_message.
     To be implemented individually for every stage. Takes the stage as first argument to allow calling output()
         from inside the function.
     Return value: True – processing successfully finished False – processing failed (skip the input message)
run()
     Run process() for every input() message.
stop()
     Finalize all the processes and prepare to exit.
```

1.1. Subpackages 5

stream_flush(fd=None)

Flush message buffer as a stream.

```
stream_input (fd)
          Generator for input messages.
          Read data from STDIN; Split stream into messages; Yield Message object.
pyDKB.dataflow.stage.AbstractStage module
Definition of an abstract class for Dataflow Stages.
class pyDKB.dataflow.stage.AbstractStage.AbstractStage (description='DKB Dataflow
                                                                     stage')
     Bases: object
     Class/instance variable description: * Argument parser (argparse.ArgumentParser)
          parser
        • Parsed arguments (argparse.Namespace) ARGS
     add_argument (*args, **kwargs)
          Add specific (not common) arguments.
     defaultArguments()
         Config argument parser with parameters common for all stages.
     parse_args (args)
          Parse arguments and set dependant arguments if needed.
     print_usage (fd=<open file '<stderr>', mode 'w'>)
          Print usage message.
     run()
          Run the stage.
pyDKB.dataflow.stage.processors module
Processor stages definitions (with predefined message type).
class pyDKB.dataflow.stage.processors.JSONProcessorStage
     Bases: pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorStage
     JSON2JSON Processor Stage
     Input message: JSON Output message: JSON
     file_input (fd)
          Override AbstractProcessorStage.file_input
     file_nd_json(fd)
          Read file as NDJSON file.
          Raises ValueError if can't read the first line.
     file\_true\_json(fd)
         Read file as true JSON file.
class pyDKB.dataflow.stage.processors.TTLProcessorStage
     Bases: pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorStage
     TTL2TTL Processor Stage
```

```
Input message: TTL Output message: TTL

output (message)
Put the (list of) message(s) to the output buffer.

class pyDKB.dataflow.stage.processors.JSON2TTLProcessorStage
Bases: pyDKB.dataflow.stage.processors.JSONProcessorStage, pyDKB.dataflow.stage.processorStage
JSON2TTL Processor Stage
Input message: JSON Output message: TTL

input ()
Override: Falls back to JSONProcessorStage.input

output (message)
Override: Falls back to TTLProcessorStage.output
```

Submodules

pyDKB.dataflow.cds module

Extended CDSInvenioConnector allowing us to login via Kerberos

pyDKB.dataflow.dkbID module

Utils to generate unique yet meaningful identifier for DKB objects.

```
pyDKB.dataflow.dkbID.dkbID (json_data, data_type)
Return unique identifier for object of TYPE based on DATA.
```

pyDKB.dataflow.exceptions module

```
Definition of DKB Dataflow exceptions
```

```
exception pyDKB.dataflow.exceptions.DataflowException
Bases: exceptions.Exception
Base Exception for Dataflow modules.
```

pyDKB.dataflow.messages module

```
Definition of abstract message class and specific message classes
```

```
class pyDKB.dataflow.messages.AbstractMessage(message=None)
    Bases: object
    Abstract message
    content()
        Return message content.

decode(code)
        Decode original from CODE to TYPE-specific format.
        Raises ValueError
    decoded = None
```

1.1. Subpackages 7

```
encode (code)
         Encode original message from TYPE-specific format to CODE.
         Raises ValueError
     encoded = None
     classmethod extension()
         Return file extension corresponding this message type.
     getOriginal()
         Return original message.
     msg_type = None
     native_types = []
     classmethod typeName()
         Return message type name as string.
exception pyDKB.dataflow.messages.DecodeUnknownType (code, cls)
     Bases: exceptions.NotImplementedError
     Exception to be thrown when message type is not decodable.
exception pyDKB.dataflow.messages.EncodeUnknownType (code, cls)
     Bases: exceptions.NotImplementedError
     Exception to be thrown when message type is not encodable.
class pyDKB.dataflow.messages.JSONMessage(message=None)
     Bases: pyDKB.dataflow.messages.AbstractMessage
     Message in JSON format.
     decode(code=1)
         Decode original data as JSON.
     encode (code=1)
         Encode JSON as CODE.
     msg\_type = 2
     native_types = [<type 'dict'>]
pyDKB.dataflow.messages.Message(msg type)
     Return class XXXMessage, where XXX is the passed type.
class pyDKB.dataflow.messages.TTLMessage(message=None)
     Bases: pyDKB.dataflow.messages.AbstractMessage
     Messages in TTL format
     Single message = single TTL statement
     decode(code=1)
         Decode original data as TTL.
         Currently takes text as it is. TODO: check some formal matter to confirm the string is TTL.
     encode(code=1)
         Encode JSON as CODE.
     msg_type = 3
     native_types = [<type 'str'>, <type 'unicode'>]
```

pyDKB.dataflow.types module

Type definitions for library objects.

1.1. Subpackages 9

CHAPTER

TWO

INDICES AND TABLES

- genindex
- modindex
- search

PYTHON MODULE INDEX

р

```
pyDKB, 1
pyDKB.common, 1
pyDKB.common.custom_readline, 2
pyDKB.common.exceptions, 2
pyDKB.common.hdfs, 2
pyDKB.common.json_utils,2
pyDKB.common.Type, 1
pyDKB.dataflow, 3
pyDKB.dataflow.cds,7
pyDKB.dataflow.dkbID,7
pyDKB.dataflow.exceptions, 7
pyDKB.dataflow.messages,7
pyDKB.dataflow.stage, 3
pyDKB.dataflow.stage.AbstractProcessorStage,
pyDKB.dataflow.stage.AbstractStage,6
pyDKB.dataflow.stage.processors,6
pyDKB.dataflow.types,9
```

14 Python Module Index

INDEX

A	encode() (pyDKB.dataflow.messages.JSONMessage
AbstractMessage (class in pyDKB.dataflow.messages), 7 AbstractProcessorStage (class in py- DKB.dataflow.stage.AbstractProcessorStage), 4 AbstractStage (class in py- DKB.dataflow.stage.AbstractStage), 6 add() (pyDKB.common.Type.Type method), 1 add_argument() (pyDKB.dataflow.stage.AbstractStage.Abs	
method), 5 content() (pyDKB.dataflow.messages.AbstractMessage method), 7 custom_readline() (in module py-DKB.common.custom_readline), 2 D DataflowException, 7 decode() (pyDKB.dataflow.messages.AbstractMessage method), 7 decode() (pyDKB.dataflow.messages.JSONMessage method), 8 decode() (pyDKB.dataflow.messages.TTLMessage method), 8 decoded (pyDKB.dataflow.messages.AbstractMessage attribute), 7 DecodeUnknownType, 8	file_flush() (pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcess method), 5 aftle_input() (pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcess method), 5 file_input() (pyDKB.dataflow.stage.JSONProcessorStage method), 3 file_input() (pyDKB.dataflow.stage.processors.JSONProcessorStage method), 6 file_nd_json() (pyDKB.dataflow.stage.JSONProcessorStage method), 3 file_nd_json() (pyDKB.dataflow.stage.processors.JSONProcessorStage method), 6 file_true_json() (pyDKB.dataflow.stage.JSONProcessorStage method), 3 file_true_json() (pyDKB.dataflow.stage.JSONProcessorStage method), 6 file_true_json() (pyDKB.dataflow.stage.processors.JSONProcessorStage method), 5 forward() (pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorMethod), 5 forward() (pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorMethod), 5
defaultArguments() (py- DKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorStage.AbstractProcessorStage.AbstractArguments() (py- DKB.dataflow.stage.AbstractStage.AbstractStage method), 6 dkbID() (in module pyDKB.dataflow.dkbID), 7	getfile() (in module pyDKB.common.hdfs), 2 getOriginal() (pyDKB.dataflow.messages.AbstractMessage
E encode() (pyDKB.dataflow.messages.AbstractMessage	hasMember() (pyDKB.common.Type.Type method), 1 HDFSException, 2
method), 7	

method), 7

1	output() (pyDKB.dataflow.stage.processors.TTLProcessorStage
input() (pyDKB.dataflow.stage.AbstractProcessorStage.Abs	stractProcessors(age 7
method), 5	output() (pyDKB.dataflow.stage.TTLProcessorStage
$input() \ (pyDKB. data flow. stage. JSON 2TTL Processor Stage$	method), 3
method), 3	output_message_class() (py-
input() (pyDKB.dataflow.stage.processors.JSON2TTLProcemethod), 7	essorStage DKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorSt method), 5
input_message_class() (py-	D
DKB. data flow. stage. Abstract Processor Stage. Abstract Processor Stage. Abstract Processor Stage and	
method), 5	parse_args() (pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcemethod), 5
J	$parse_args() (pyDKB. data flow. stage. Abstract Stage. Abstract Stage$
JSON2TTLProcessorStage (class in py-	method), 6
DKB.dataflow.stage), 3	parseMessage() (pyDKB.dataflow.stage.AbstractProcessorStage.AbstractPro
JSON2TTLProcessorStage (class in py-	method), 5
DKB.dataflow.stage.processors), 7	print_usage() (pyDKB.dataflow.stage.AbstractStage.AbstractStage
JSONMessage (class in pyDKB.dataflow.messages), 8	method), 6
JSONProcessorStage (class in pyDKB.dataflow.stage), 3	process() (pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcesso
JSONProcessorStage (class in py-	static method), 5 putfile() (in module pyDKB.common.hdfs), 2
DKB.dataflow.stage.processors), 6	pyDKB (module), 1
1	pyDKB.common (module), 1
	pyDKB.common.custom_readline (module), 2
listdir() (in module pyDKB.common.hdfs), 2	pyDKB.common.exceptions (module), 2
M	pyDKB.common.hdfs (module), 2
	pyDKB.common.json_utils (module), 2
makedirs() (in module pyDKB.common.hdfs), 2	pyDKB.common.Type (module), 1
member() (pyDKB.common.Type.Type method), 1	pyDKB.dataflow (module), 3
memberName() (pyDKB.common.Type.Type method), 1	pyDKB.dataflow.cds (module), 7
Message() (in module pyDKB.dataflow.messages), 8 msg_type (pyDKB.dataflow.messages.AbstractMessage	pyDKB.dataflow.dkbID (module), 7
attribute), 8	pyDKB.dataflow.exceptions (module), 7
msg_type (pyDKB.dataflow.messages.JSONMessage at-	pyDKB.dataflow.messages (module), 7
tribute), 8	pyDKB.dataflow.stage (module), 3
msg_type (pyDKB.dataflow.messages.TTLMessage at-	pyDKB.dataflow.stage.AbstractProcessorStage (module), 4
tribute), 8	pyDKB.dataflow.stage.AbstractStage (module), 6
	pyDKB.dataflow.stage.processors (module), 6
N	pyDKB.dataflow.types (module), 9
native_types (pyDKB.dataflow.messages.AbstractMessage	p) 2 12 (analy), y
attribute), 8	R
native_types (pyDKB.dataflow.messages.JSONMessage attribute), 8	run() (pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorStage.method), 5
native_types (pyDKB.dataflow.messages.TTLMessage attribute), 8	run() (pyDKB.dataflow.stage.AbstractStage.AbstractStage
nestedKeys() (in module pyDKB.common.json_utils), 2	method), 6
_	S
0	
output() (pyDKB.dataflow.stage.AbstractProcessorStage.Almethod), 5	
output() (pyDKB.dataflow.stage.JSON2TTLProcessorStage	stream_flush() (pyDKB.dataflow.stage.AbstractProcessorStage.Abstract
method), 3	incurous, 5
output() (pyDKB.dataflow.stage.processors.JSON2TTLPro	stream_input() (pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorStage.abstractProcessorStage), 5

16 Index

Τ

```
TTLMessage (class in pyDKB.dataflow.messages), 8
TTLProcessorStage (class in pyDKB.dataflow.stage), 3
TTLProcessorStage (class in py-
DKB.dataflow.stage.processors), 6
Type (class in pyDKB.common.Type), 1
typeName() (pyDKB.dataflow.messages.AbstractMessage class method), 8
```

V

valueByKey() (in module pyDKB.common.json_utils), 3

Index 17