DKB Documentation

DKB team

CONTENTS:

	pyDKB package 1.1 Subpackages	1
2	Indices and tables	11
Ру	thon Module Index	13
In	dex	15

CHAPTER

ONE

PYDKB PACKAGE

Common library for Data Knowledge Base development.

1.1 Subpackages

1.1.1 pyDKB.common package

Common modules.

Submodules

pyDKB.common.Type module

Abstract class for type definitions.

Usage:

```
>>> myType = Type("Orange", "Apple")
>>> myType.add("Plum")
>>> t = myType.Orange
>>> if t == myType.Orange:
...    print "Orange!"
... elif t == myType.member("Apple"):
...    print "Apple!"
...
Orange!
>>> if not myType.member("Walnut"):
...    print "Wrong type!"
...
Wrong type!
```

```
class pyDKB.common.Type.Type(*args)
    Bases: object
```

Abstract class for type definitions.

Member names (str) are passed to the constructor as positional arguments.

```
add (name)
Add member.
```

Parameters name (str) – name of the member to be added

hasMember (val)

Check if the member exists (by value).

Parameters val (*int*) – member to be checked

Returns True/False

Return type bool

member (name)

Check if the member exists (by name).

Parameters name (str) – name to be checked

Returns member value or False if member does not exist

Return type int, bool

memberName (val)

Return string name of the member.

Parameters val (*int*) – member to retrieve name for

Returns member name of False if member does not exist

Return type str, bool

pyDKB.common.custom_readline module

```
\verb"pyDKB.common.custom_readline.custom_readline" (f, newline)
```

Custom readline() function.

Custom_readline() separates content from a text file 'f' by delimiter 'newline' to distinct messages. The last line can be incomplete, if the input data flow is interrupted in the middle of data writing.

Keyword arguments: f - file/stream to read newline - custom delimiter

pyDKB.common.exceptions module

Definition of common modules exceptions

```
exception pyDKB.common.exceptions.HDFSException
```

Bases: exceptions.RuntimeError

Base Exception for HDFS module.

pyDKB.common.hdfs module

Utils to interact with HDFS.

```
pyDKB.common.hdfs.check_stderr(proc, timeout=None, max_lines=1)
```

Wait till the end of the subprocess and send its STDERR to STDERR.

Output only MAX_LINES of the STDERR to the current STDERR; if MAX_LINES == None, output all the STDERR.

Return value is the subprocess' return code.

```
pyDKB.common.hdfs.getfile(fname)
```

Download file from HDFS.

Return value: file name (without directory)

```
pyDKB.common.hdfs.listdir(dirname, mode='a')
List files and/or subdirectories of HDFS directory.

Parameters: dirname – directory to list mode – 'a': list all objects

'f': list files 'd': list subdirectories

pyDKB.common.hdfs.makedirs(dirname)
Try to create directory (with parents).

pyDKB.common.hdfs.putfile(fname, dest)
Upload file to HDFS.
```

pyDKB.common.json_utils module

Utils to work with JSON (dict) objects.

```
pyDKB.common.json_utils.nestedKeys(key)
```

Transform STRING with nested keys into LIST.

Parameters:

STRING key – dot-separated list of nested keys. If a key contains dot itself, the key must be put between quotation marks.

```
pyDKB.common.json_utils.valueByKey (json_data, key)
Return value by a chain (list) of nested keys.
```

Parameters: DICT json_data - to search in STRING key - dot-separated list of nested keys

1.1.2 pyDKB.dataflow package

Dataflow organization utils.

Subpackages

pyDKB.dataflow.stage package

Stage submodule init file.

```
class pyDKB.dataflow.stage.JSONProcessorStage
Bases: pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorStage
JSON2JSON Processor Stage
Input message: JSON Output message: JSON
file_input (fd)
    Override AbstractProcessorStage.file_input
file_nd_json (fd)
    Read file as NDJSON file.
    Raises ValueError if can't read the first line.
file_true_json (fd)
    Read file as true JSON file.
```

```
class pyDKB.dataflow.stage.TTLProcessorStage
    Bases: pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorStage
    TTL2TTL Processor Stage
    Input message: TTL Output message: TTL
    output (message)
         Put the (list of) message(s) to the output buffer.
class pyDKB.dataflow.stage.JSON2TTLProcessorStage
            pyDKB.dataflow.stage.processors.JSONProcessorStage, pyDKB.dataflow.
     stage.processors.TTLProcessorStage
    JSON2TTL Processor Stage
    Input message: JSON Output message: TTL
    input()
         Override: Falls back to JSONProcessorStage.input
    output (message)
         Override: Falls back to TTLProcessorStage.output
Submodules
pyDKB.dataflow.stage.AbstractProcessorStage module
Definition of an abstract class for Dataflow Data Processing Stages.
```

USAGE: ProcessorStage [<options>] [<input files>]

OPTIONS:

```
-s, --source
                       {flslh} - where to get data from: local (f)iles, (s)tdin, (h)dfs
-i, --input-dir
                      DIR - base directory for relative input file names (for local and
                      HDFS sources). If <input files> not specified, all files from the
                      directory will be taken as the input.
-d, --dest
                      {flslh} - where to send data to: local (f)iles, (s)tdout, (h)dfs
-o, --output-dir
                      DIR - base directory for output files (for local and HDFS
                      sources)
--hdfs
                         • equivalent to "-source h -dest h"
                      MODE - MODE: (f)ile = -source f
-m, --mode
                           -dest f (can be
                             rewritten with 's' or 'h')
                      (s)tream = -source s (can be
                             rewritten with 'h')
                           -dest s
                      (m)apreduce = -source s (can be
                             rewritten with 'h')
                           -dest s
```

```
class pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorStage (description='DKB
                                                                                                     Dataflow
                                                                                                     data
                                                                                                    pro-
                                                                                                    cess-
                                                                                                    ing
                                                                                                    stage.')
     Bases: pyDKB.dataflow.stage.AbstractStage.AbstractStage
     Abstract class to implement Processor stages
     Processor stage – is a stage for data processing/transfornation.
     Class/instance variable description: * Current processing file name:
          __current_file_full - full name with path __current_file - file name
        • Iterable object for input data sources (file descriptors) input
        • Output messages buffer: __output_buffer
        • Generator object for output file descriptor OR file descriptor (for (s)tream mode)
               output
        • List of objects to be "stopped" __stoppable
     clear_buffer()
          Drop buffered output messages.
     defaultArguments()
          Default parser configuration.
     file_flush()
          Flush message buffer into a file.
          By default writes to file as to a stream. To be implemented individually if needed.
     file input (fd)
          Generator for input messages.
          By default reads file just as stream. To be implemented individually for other cases.
     flush buffer()
          Flush message buffer to the output.
     forward()
          Send EOPMessage in the streaming output mode.
     input()
          Generator for input messages.
          Returns iterable object. Every iteration returns single input message to be processed.
     input_message_class()
          Get input message class.
     output (message)
          Put the (list of) message(s) to the output buffer.
     output_message_class()
          Get output message class.
```

```
parseMessage (input_message)
          Verify and parse input message.
          Is called from input() method.
     parse_args (args)
          Parse arguments and set dependant arguments if neeeded.
     static process(stage, input_message)
          Transform input_message -> output_message.
          To be implemented individually for every stage. Takes the stage as first argument to allow calling output()
               from inside the function.
          Return value: True – processing successfully finished False – processing failed (skip the input message)
     run()
          Run process() for every input() message.
     stop()
          Finalize all the processes and prepare to exit.
     stream_flush (fd=None)
          Flush message buffer as a stream.
     stream_input (fd)
          Generator for input messages.
          Read data from STDIN; Split stream into messages; Yield Message object.
pyDKB.dataflow.stage.AbstractStage module
Definition of an abstract class for Dataflow Stages.
class pyDKB.dataflow.stage.AbstractStage.AbstractStage (description='DKB Dataflow
                                                                           stage')
     Bases: object
     Class/instance variable description: * Argument parser (argparse.ArgumentParser)
          __parser

    Parsed arguments (argparse.Namespace) ARGS

     add_argument (*args, **kwargs)
          Add specific (not common) arguments.
     defaultArguments()
          Config argument parser with parameters common for all stages.
     parse_args (args)
          Parse arguments and set dependant arguments if needed.
     print_usage (fd=<open file '<stderr>', mode 'w'>)
          Print usage message.
     run()
          Run the stage.
```

pyDKB.dataflow.stage.processors module

```
Processor stages definitions (with predefined message type).
class pyDKB.dataflow.stage.processors.JSONProcessorStage
    Bases: pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorStage
    JSON2JSON Processor Stage
    Input message: JSON Output message: JSON
    file_input (fd)
         Override AbstractProcessorStage.file_input
    file_nd_json(fd)
         Read file as NDJSON file.
         Raises ValueError if can't read the first line.
    file_true_json(fd)
         Read file as true JSON file.
class pyDKB.dataflow.stage.processors.TTLProcessorStage
    Bases: pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorStage
    TTL2TTL Processor Stage
    Input message: TTL Output message: TTL
    output (message)
         Put the (list of) message(s) to the output buffer.
class pyDKB.dataflow.stage.processors.JSON2TTLProcessorStage
           pyDKB.dataflow.stage.processors.JSONProcessorStage, pyDKB.dataflow.
    stage.processors.TTLProcessorStage
    JSON2TTL Processor Stage
    Input message: JSON Output message: TTL
    input()
```

Submodules

pyDKB.dataflow.cds module

output (message)

Extended CDSInvenioConnector allowing us to login via Kerberos

Override: Falls back to JSONProcessorStage.input

Override: Falls back to TTLProcessorStage.output

pyDKB.dataflow.dkbID module

Utils to generate unique yet meaningful identifier for DKB objects.

```
pyDKB.dataflow.dkbID.dkbID (json_data, data_type)
Return unique identifier for object of TYPE based on DATA.
```

pyDKB.dataflow.exceptions module

```
Definition of DKB Dataflow exceptions
exception pyDKB.dataflow.exceptions.DataflowException
    Bases: exceptions. Exception
    Base Exception for Dataflow modules.
pyDKB.dataflow.messages module
```

```
Definition of abstract message class and specific message classes
class pyDKB.dataflow.messages.AbstractMessage(message=None)
     Bases: object
     Abstract message
     content()
         Return message content.
     decode (code)
         Decode original from CODE to TYPE-specific format.
         Raises ValueError
     decoded = None
     encode (code)
         Encode original message from TYPE-specific format to CODE.
         Raises ValueError
     encoded = None
     classmethod extension()
         Return file extension corresponding this message type.
     getOriginal()
         Return original message.
     msg_type = None
     native_types = []
     classmethod typeName()
         Return message type name as string.
exception pyDKB.dataflow.messages.DecodeUnknownType(code, cls)
     Bases: exceptions.NotImplementedError
     Exception to be thrown when message type is not decodable.
exception pyDKB.dataflow.messages.EncodeUnknownType (code, cls)
     Bases: exceptions.NotImplementedError
     Exception to be thrown when message type is not encodable.
class pyDKB.dataflow.messages.JSONMessage(message=None)
     Bases: pyDKB.dataflow.messages.AbstractMessage
     Message in JSON format.
     decode(code=1)
         Decode original data as JSON.
```

```
encode(code=1)
         Encode JSON as CODE.
    msg\_type = 2
    native_types = [<type 'dict'>]
pyDKB.dataflow.messages.Message(msg_type)
     Return class XXXMessage, where XXX is the passed type.
class pyDKB.dataflow.messages.TTLMessage(message=None)
     Bases: pyDKB.dataflow.messages.AbstractMessage
     Messages in TTL format
     Single message = single TTL statement
     decode(code=1)
         Decode original data as TTL.
         Currently takes text as it is. TODO: check some formal matter to confirm the string is TTL.
     encode(code=1)
         Encode JSON as CODE.
    msg\_type = 3
    native_types = [<type 'str'>, <type 'unicode'>]
```

pyDKB.dataflow.types module

Type definitions for library objects.

CHAPTER

TWO

INDICES AND TABLES

- genindex
- modindex
- search

PYTHON MODULE INDEX

р

```
pyDKB, 1
pyDKB.common, 1
pyDKB.common.custom_readline, 2
pyDKB.common.exceptions, 2
pyDKB.common.hdfs, 2
pyDKB.common.json_utils,3
pyDKB.common.Type, 1
pyDKB.dataflow, 3
pyDKB.dataflow.cds,7
pyDKB.dataflow.dkbID,7
pyDKB.dataflow.exceptions, 8
pyDKB.dataflow.messages, 8
pyDKB.dataflow.stage, 3
pyDKB.dataflow.stage.AbstractProcessorStage,
pyDKB.dataflow.stage.AbstractStage,6
pyDKB.dataflow.stage.processors,7
pyDKB.dataflow.types,9
```

14 Python Module Index

INDEX

AbstractMessage (class in pyDKB.dataflow.messages), 8 AbstractProcessorStage (class in pyDKB.dataflow.stage.AbstractProcessorStage) AbstractStage (class in pyDKB.dataflow.stage.AbstractStage), 6 add() (pyDKB.dataflow.stage.AbstractStage), 6 add() (pyDKB.dataflow.stage.AbstractStage), 6 add() (pyDKB.dataflow.stage.AbstractStage), 6 add() (pyDKB.dataflow.stage.AbstractStage), 6 add() (pyDKB.dataflow.stage.AbstractStage.AbstractStage.AbstractStage class method), 8 method), 6 C C Check_stderr() (in module pyDKB.common.hdfs), 2 clear_buffer() (pyDKB.dataflow.stage.AbstractMessage method), 5 content) (pyDKB.dataflow.messages.AbstractMessage method), 5 content) (pyDKB.dataflow.messages.AbstractMessage method), 8 custom_readline() (in module pKB.common.custom_readline), 2 D D DataflowException, 8 decode() (pyDKB.dataflow.messages.AbstractMessage method), 8 decode() (pyDKB.dataflow.messages.AbstractMessage method), 8 decode() (pyDKB.dataflow.messages.AbstractMessage method), 8 decode() (pyDKB.dataflow.messages.AbstractMessage method), 8 decode() (pyDKB.dataflow.messages.AbstractMessage at ribup), 8 DecodeUnknownType, 8 decode() (pyDKB.dataflow.stage.AbstractProcessorStage.AbstractPr	A	encode() (pyDKB.dataflow.messages.JSONMessage
method), 6 C file_flush() (pyDKB.dataflow.stage.AbstractProcessorSta	AbstractProcessorStage (class in py-DKB.dataflow.stage.AbstractProcessorStage), 4 AbstractStage (class in py-DKB.dataflow.stage.AbstractStage), 6 add() (pyDKB.common.Type.Type method), 1	encode() (pyDKB.dataflow.messages.TTLMessage method), 9 encoded (pyDKB.dataflow.messages.AbstractMessage attribute), 8 EncodeUnknownType, 8 extension() (pyDKB.dataflow.messages.AbstractMessage
C check_stderr() (in module pyDKB.common.hdfs), 2 clear_buffer() (pyDKB.dataflow.stage.AbstractProcessorStage method), 5 content() (pyDKB.dataflow.messages.AbstractMessage method), 5 file_input() (pyDKB.dataflow.stage.AbstractProcessorStage method), 5 file_input() (pyDKB.dataflow.stage.JSONProcessorStage method), 3 file_input() (pyDKB.dataflow.stage.JSONProcessorStage method), 5 forward() (pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProce		
DKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorStage method), 5 defaultArguments() DKB.dataflow.stage.AbstractStage.AbstractStage DKB.dataflow.stage.AbstractStage.AbstractStage method), 6 dkbID() (in module pyDKB.dataflow.dkbID), 7 H hasMember() (pyDKB.common.Type.Type method), 1 HDFSException, 2	check_stderr() (in module pyDKB.common.hdfs), 2 clear_buffer() (pyDKB.dataflow.stage.AbstractProcessorStamethod), 5 content() (pyDKB.dataflow.messages.AbstractMessage method), 8 custom_readline() (in module py-DKB.common.custom_readline), 2 D DataflowException, 8 decode() (pyDKB.dataflow.messages.AbstractMessage method), 8 decode() (pyDKB.dataflow.messages.JSONMessage method), 8 decode() (pyDKB.dataflow.messages.TTLMessage method), 9 decoded (pyDKB.dataflow.messages.AbstractMessage attribute), 8	method), 5 a file_input() (pyDKB_dataflow.stage.AbstractProcessorStage.AbstractProcess method), 5 file_input() (pyDKB.dataflow.stage.JSONProcessorStage method), 3 file_input() (pyDKB.dataflow.stage.processors.JSONProcessorStage method), 7 file_nd_json() (pyDKB.dataflow.stage.JSONProcessorStage method), 3 file_nd_json() (pyDKB.dataflow.stage.processors.JSONProcessorStage method), 7 file_true_json() (pyDKB.dataflow.stage.JSONProcessorStage method), 3 file_true_json() (pyDKB.dataflow.stage.JSONProcessorStage method), 3 file_true_json() (pyDKB.dataflow.stage.processors.JSONProcessorStage method), 7 flush_buffer() (pyDKB.dataflow.stage.AbstractProcessorStage.Abst
DKB.dataflow.stage.AbstractStage method), 8 method), 6 dkbID() (in module pyDKB.dataflow.dkbID), 7 HasMember() (pyDKB.common.Type.Type method), 1 HDFSException, 2	DKB.dataflow.stage.AbstractProcessorStage.Abs	getfile() (in module pyDKB.common.hdfs), 2
	DKB.dataflow.stage.AbstractStage.AbstractStage method), 6 dkbID() (in module pyDKB.dataflow.dkbID), 7	H hasMember() (pyDKB.common.Type.Type method), 1

1	output() (pyDKB.dataflow.stage.processors.TTLProcessorStage
$input() \ (pyDKB. data flow. stage. Abstract Processor Stage. Abstra$	
method), 5	output() (pyDKB.dataflow.stage.11LProcessorStage
input() (pyDKB.dataflow.stage.JSON2TTLProcessorStage	method), 4
method) 4	output_message_class() (py-
input() (pyDKB.dataflow.stage.processors.JSON2TTLProc method), 7	cessorStage DKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorSt method), 5
input_message_class() (py-	D
DKB.dataflow.stage.AbstractProcessorStage.Ab	stractProcessorStage
method), 5	parse_args() (pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcemethod), 6
J	parse_args() (pyDKB.dataflow.stage.AbstractStage.AbstractStage
	method), 6
JSON2TTLProcessorStage (class in py- DKB.dataflow.stage), 4	parseMessage() (pyDKB.dataflow.stage.AbstractProcessorStage.AbstractPro
JSON2TTLProcessorStage (class in py-	method), 5
DKB.dataflow.stage.processors), 7	print_usage() (pyDKB.dataflow.stage.AbstractStage.AbstractStage
JSONMessage (class in pyDKB.dataflow.messages), 8	method), 6
JSONProcessorStage (class in pyDKB.dataflow.stage), 3	process() (pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessor
JSONProcessorStage (class in py-	static method), 6
DKB.dataflow.stage.processors), 7	putfile() (in module pyDKB.common.hdfs), 3
8-1	pyDKB (module), 1
L	pyDKB.common (module), 1
listdir() (in module pyDKB.common.hdfs), 2	pyDKB.common.custom_readline (module), 2
instancy (in module py 2 112) common mais), 2	pyDKB.common.exceptions (module), 2
M	pyDKB.common.hdfs (module), 2
makedirs() (in module pyDKB.common.hdfs), 3	pyDKB.common.json_utils (module), 3
member() (pyDKB.common.Type.Type method), 2	pyDKB.common.Type (module), 1
memberName() (pyDKB.common.Type.Type method), 2	pyDKB.dataflow (module), 3
Message() (in module pyDKB.dataflow.messages), 9	pyDKB.dataflow.cds (module), 7
msg_type (pyDKB.dataflow.messages.AbstractMessage	pyDKB.dataflow.dkbID (module), 7
attribute), 8	pyDKB.dataflow.exceptions (module), 8
msg_type (pyDKB.dataflow.messages.JSONMessage at-	pyDKB.dataflow.messages (module), 8
tribute), 9	pyDKB.dataflow.stage (module), 3
msg_type (pyDKB.dataflow.messages.TTLMessage at-	pyDKB.dataflow.stage.AbstractProcessorStage (module), 4
tribute), 9	pyDKB.dataflow.stage.AbstractStage (module), 6
NI	pyDKB.dataflow.stage.processors (module), 7
N	pyDKB.dataflow.types (module), 9
native_types (pyDKB.dataflow.messages.AbstractMessage	
attribute), 8 native_types (pyDKB.dataflow.messages.JSONMessage	R
attribute), 9	run() (pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorStage.method), 6
$native_types \qquad (pyDKB.dataflow.messages.TTLMessage$	run() (pyDKB.dataflow.stage.AbstractStage.AbstractStage
attribute), 9	method), 6
nestedKeys() (in module pyDKB.common.json_utils), 3	
0	S
output() (pyDKB.dataflow.stage.AbstractProcessorStage.A	stop() (pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorStage.bstractProcessorStage.bstractProcessorStage.abstractProcessorStage.bstractProcessorStage.abstractProcessorSt
method), 5	stream_flush() (pvDKB_dataflow_stage_AbstractProcessorStage_AbstractPro
output() (pyDKB.dataflow.stage.JSON2TTLProcessorStag method), 4	method), 0
output() (nyDKR dataflow stage processors ISONOTTI De-	stream_input() (pyDKB.dataflow.stage.AbstractProcessorStage.AbstractProcessorStage, abstractProcessorStage, abstractProcessorS
method), 7	method), 6

16 Index

Τ

```
TTLMessage (class in pyDKB.dataflow.messages), 9
TTLProcessorStage (class in pyDKB.dataflow.stage), 3
TTLProcessorStage (class in py-
DKB.dataflow.stage.processors), 7
Type (class in pyDKB.common.Type), 1
typeName() (pyDKB.dataflow.messages.AbstractMessage class method), 8
```

V

valueByKey() (in module pyDKB.common.json_utils), 3

Index 17