1 Intro

Hi. I am Panteleimon Sarantos (You can call me Pantelis) and I made this list of commands for the Cisco Routers and Switches.

2 License

This work is licensed under the Creative Commons Attribution-NonCommercial-ShareAlike 4.0 International License. To view a copy of this license, visit http://creativecommons.org/licenses/by-nc-sa/4.0/ or send a letter to Creative Commons, PO Box 1866, Mountain View, CA 94042, USA.



3 Table of Contents

1	Intro	1
2	License	1
3	Table of Contents	1
4	Save Progress	3
5	Router	
	5.1 Security	3
	5.1.1 Management Security	
	5.1.1.1 Enable CLI Password	3
	5.1.1.2 Enable Password after enable – EXEC – Global Configuration	3
	5.1.1.3 Enable Telnet Password	
	5.1.1.4 SSH	
	5.1.1.4.1 SSH Configuration	
	5.1.1.4.2 More SSH Settings	
	5.1.2 Access Lists Security	4
	5.1.2.1 Standard ACLs	
	5.1.2.1.1 Numbered Standard ACLs	
	5.1.2.1.2 Named Standard ACLs	
	5.1.2.1.3 Modify Named ACLs	
	5.1.2.2 Extended ACLs	
	5.1.2.2.1 Numbered Extended ACLs	
	5.1.2.2.2 Named Extended ACLs	5

	5.1.2.2.3 Modify Numbered Extended ACLs	5
	5.1.2.2.4 Modify Named Extended ACLs	6
	5.1.2.3 Access Lists Info	6
	5.1.2.3.1 More SSH Settings	6
	5.2 IP	
	5.2.1 Assign IP to Interface	6
	5.2.1.1 IPv4	
	5.2.1.2 IPv6	
	5.3 Routing	
	5.3.1 OSPF	
	5.3.2 EIGRP	
	5.3.3 RIPv2	
	5.4 InterVLAN Routing	
	5.5 DHCP	
	5.6 NAT	
	5.6.1 Static NAT	
	5.6.1.1 Configuration	
	5.6.1.2 Assign NAT to Interfaces	
	5.6.2 Dynamic NAT	
	5.6.2.1 Configuration	
	5.6.3 PAT	
	5.6.4 General	
	5.6.4.1 Verify Configuration	
	5.6.4.2 Clear Static NAT	
	5.6.4.3 Clear Dynamic NAT	
	5.6.4.4 Remove the public NAT pool	
	5.6.4.5 Remove the NAT translation from inside source list to outside pool	
	5.7 General Settings	
	5.7.1 Date and Time Settings	
	5.7.2 Prevent unwanted DNS Lookups	
6	Switch	
Ü	6.1 Security	
	6.1.1 Management Security	
	6.1.1.1 Enable CLI Password	
	6.1.1.2 Enable Encrypted Password after enable – EXEC – Global Configuration	
	o2 Enable Enerypted rassword after enable 2/22 Globar coringaration	
	6.1.1.3 Enable Telnet Password	
	6.1.1.3.1 SSH	
	6.1.1.3.1.1 SSH Configuration	
	6.1.1.3.1.2 More SSH Settings	
	6.1.2 Port Security	
	6.1.2.1 Close unused physical ports	
	6.1.2.2 Configure Basic Port Security	
	6.2 VLAN	
	V: ← V ← II 1. 1. 1. 1. 1. 1. 1. 1. 1. 1. 1. 1. 1.	

6.2.1	Create a VLAN	11
6.2.2	Assign Physical Access Ports to VLAN	11
6.2.3	Set Physical Ports to Trunk	11
6.2.4	Set Physical Ports to Native Trunking	11
6.2.5	Assign IP to VLAN	11
6.2.6	Verify VLAN	12
6.3 IP		12
6.3.1	Prevent unwanted DNS Lookups	12
6.3.2	Default Gateway	12
6.4 Ger	neral Settings	12
6.4.1	Date and Time Settings	12
6.4.2	Log In Banner Message	12

4 Save Progress

To save the following commands to the startup-config run:

en

conf t

wr

#or

do wr

5 Router

5.1 Security

5.1.1 Management Security

5.1.1.1 Enable CLI Password

en

conf t

line con 0

password conpass

5.1.1.2 Enable Password after enable – EXEC – Global Configuration

en

conf t

enable secret password

5.1.1.3 Enable Telnet Password

en

conf t

line vty 0 15

password telnetpass login

5.1.1.4 SSH

5.1.1.4.1 SSH Configuration

en

conf t

ip domain-name isp.gr username admin privilege 15 secret sshpass line vty 0 15 transport input ssh login local exit

crypto key generate rsa end show ip ssh

5.1.1.4.2 More SSH Settings

en

conf t

ip ssh time-out 75 ip ssh authentication-retries 2

5.1.2 Access Lists Security

5.1.2.1 Standard ACLs

5.1.2.1.1 Numbered Standard ACLs

<u>en</u>

conf t

access-list 1 remark Allow R1 LANs Access access-list 1 permit 192.168.10.0 0.0.0.255 access-list 1 permit 192.168.20.0 0.0.0.255 access-list 1 deny any

en conf t interface g0/1 ip access-group 1 out

5.1.2.1.2 Named Standard ACLs

en

conf t

ip access-list standard BRANCH-OFFICE-POLICY permit host 192.168.30.3

permit 192.168.40.0 0.0.0.255 end

en

conf t

int g0/1

ip access-group BRANCH-OFFICE-POLICY out

5.1.2.1.3 Modify Named ACLs

en

conf t

ip access-list standard BRANCH-OFFICE-POLICY

30 permit 209.165.200.224 0.0.0.31

40 deny any

end

5.1.2.2 Extended ACLs

5.1.2.2.1 Numbered Extended ACLs

en

conf t

access-list 100 remark Allow Web & SSH Access access-list 100 permit tcp host 192.168.10.3 host 10.2.2.1 eq 22 access-list 100 permit tcp any any eq 80

en

conf t

interface g0/1

ip access-group 100 out

5.1.2.2.2 Named Extended ACLs

en

conf t

ip access-list extended WEB-POLICY

permit tcp 192.168.30.0 0.0.0.255 host 10.1.1.1 eq 80

permit tcp 192.168.30.0 0.0.0.255 209.165.200.224 0.0.0.31 eq 80

en

conf t

interface S0/0/1

ip access-group WEB-POLICY out

5.1.2.2.3 Modify Numbered Extended ACLs

en

conf t

ip access-list extended 100

30 permit ip 192.168.10.0 0.0.0.255 192.168.30.0 0.0.0.255 end

5.1.2.2.4 Modify Named Extended ACLs

en

conf t

ip access-list extended WEB-POLICY 30 permit ip 192.168.30.0 0.0.0.255 192.168.10.0 0.0.0.255 end

5.1.2.3 Access Lists Info

en

show access-lists

5.1.2.3.1 More SSH Settings

en

conf t

ip ssh time-out 75

ip ssh authentication-retries 2

5.2 IP

5.2.1 Assign IP to Interface

5.2.1.1 IPv4

En

conf t

int g0/0

ip add 192.168.1.1 255.255.255.0

no shut

5.2.1.2 IPv6

en

conf t

ipv6 unicast-routing

int g0/0

ipv6 add 2001:db8:1:1::1/64

ipv6 add fe80::1 link-local

no shut

5.3 Routing

5.3.1 OSPF

en

conf t

router ospf 1 network 192.168.1.0 0.0.0.255 area 0 network 10.0.0.0 0.0.0.3 area 0 network 10.1.1.0 0.0.0.3 area 0

5.3.2 EIGRP

en conf t router eigrp 1 network 200.200.200.0 0.0.0.3 network 100.100.100.0 0.0.0.255 auto-summary

5.3.3 RIPv2

en conf t router rip version 2 network 192.168.10.0 network 192.168.20.0 network 192.168.30.0 no auto-summary

5.4 InterVLAN Routing

interface g0/1.1
encapsulation dot1Q 1
ip add 192.168.1.1 255.255.255.0
interface g0/1.10
encapsulation dot1Q 10
ip add 192.168.10.1 255.255.255.0
interface g0/1.20
encapsulation dot1Q 20
ip add 192.168.20.1 255.255.255.0
exit
interface g0/1
no shut

5.5 DHCP

en conf t ip dhcp excluded-address 100.100.100.1 ip dhcp pool KATOSTARI

5.6 NAT

5.6.1 Static NAT

5.6.1.1 Configuration

en

conf t

ip nat inside source static <Private Address> <Public Address> ip nat inside source static 192.168.1.20 209.169.200.225

5.6.1.2 Assign NAT to Interfaces

en

conf t

int g0/1

ip nat inside

int s0/0/1

ip nat outside

5.6.2 Dynamic NAT

5.6.2.1 Configuration

en

conf t

access-list 1 permit 192.168.1.1 0.0.0.255

ip nat pool public_access 209.169.200.242 209.169.200.254 netmask 255.255.255.224 ip nat inside source list 1 pool public access

5.6.3 PAT

en

conf t

access-list 1 permit 192.168.1.1 0.0.0.255

ip nat inside source list 1 interface serial 0/0/1 overload

5.6.4 General

5.6.4.1 Verify Configuration

en

show ip nat translations show ip nat statistics

5.6.4.2 Clear Static NAT

en

conf t

no ip nat inside source static 192.168.1.20 209.169.200.225

5.6.4.3 Clear Dynamic NAT

en

clear ip nat translation * clear ip nat statistics

5.6.4.4 Remove the public NAT pool

en

conf t

no ip nat pool public_access 209.169.200.225 209.169.200.230 netmask 255.255.255.248

5.6.4.5 Remove the NAT translation from inside source list to outside pool

en

conf t

no ip nat inside source list 1 pool public_access overload

5.7 General Settings

5.7.1 Date and Time Settings

en

clock set 16:45:00 Dec 8 2016 show clock

5.7.2 Prevent unwanted DNS Lookups

en

conf t

no ip domain-lookup

6 Switch

6.1 Security

6.1.1 Management Security

6.1.1.1 Enable CLI Password

en

conf t

line con 0

password conpass

login logging synchronous

6.1.1.2 Enable Encrypted Password after enable – EXEC – Global Configuration

en

conf t

enable password-encryption

enable secret pass

6.1.1.3 Enable Telnet Password

en

conf t

line vty 0 15

password telnetpass

login

6.1.1.3.1 SSH

6.1.1.3.1.1 SSH Configuration

en

conf t

ip domain-name isp.gr

username admin privilege 15 secret sshpass

line vty 0 15

transport input ssh

login local

exit

crypto key generate rsa

end

show ip ssh

6.1.1.3.1.2 More SSH Settings

en

conf t

ip ssh time-out 75

ip ssh authentication-retries 2

6.1.2 Port Security

6.1.2.1 Close unused physical ports

en

conf t

int f0/0 | int range f0/0 - 4

shut

do sh ip interface brief

6.1.2.2 Configure Basic Port Security

en

conf t

int f0/5

shut

switchport mode access

switchport port-security

switchport port-security mac-address xxxx.xxxx.xxxx

(switchport port-security mac-address sticky)

no shut

end

sh port-security int f0/5

6.2 VLAN

6.2.1 Create a VLAN

en

conf t

vlan 10

name Students

exit

6.2.2 Assign Physical Access Ports to VLAN

en

conf t

int range f0/1 - 24, g0/1 - 2

switchport access vlan 10

6.2.3 Set Physical Ports to Trunk

en

conf t

int g0/1

switchport mode trunk

6.2.4 Set Physical Ports to Native Trunking

en

conf t

int g0/1

switchport mode trunk

switchport trunk native vlan 99

6.2.5 Assign IP to VLAN

int vlan99

ip add 192.168.1.2 255.255.255.0 no shut

6.2.6 Verify VLAN

en

sh vlan brief

6.3 IP

6.3.1 Prevent unwanted DNS Lookups

en

conf t

no ip domain-lookup

6.3.2 Default Gateway

en

conf t

ip default-gateway 192.168.1.1

6.4 General Settings

6.4.1 Date and Time Settings

show clock detail clock set 16:30:00 Mar 27 2017 do wr

6.4.2 Log In Banner Message

en

conf t

banner motd #

Some message #