

CS 5323 - OS II

Lecture 11 – Main and Virtual Memory Management



Logistics

- Quiz 4 posted and is due: Monday 03/14/2022 11:59 pm
- Assignment 3 posted. Due 03/27/2022 11:59 pm



Virtual Memory

Virtual memory




- Virtual memory separation of user logical memory from physical memory
 - Only part of the program needs to be in memory for execution
 - Logical address space can therefore be much larger than physical address space
 - Allows address spaces to be shared by several processes
 - Allows for more efficient process creation
 - More programs running concurrently
 - Less I/O needed to load or swap processes

Demand Paging



- Could bring entire process into memory at load time
- Or bring a page into memory only when it is needed
 - Less I/O needed, no unnecessary I/O
 - Less memory needed
 - Faster response
 - More users
- Similar to paging system with swapping (diagram on right)



Basic Concepts




- With swapping, pager guesses which pages will be used before swapping out again
- Instead, pager brings in only those pages into memory
- How to determine that set of pages?
 - Need new MMU functionality to implement demand paging
- If pages needed are already memory resident
 - No difference from non demand-paging
- If page needed and not memory resident
 - Need to detect and load the page into memory from storage
 - Without changing program behavior
 - Without programmer needing to change code

Valid-Invalid Bit




- With each page table entry a valid—invalid bit is associated
 (v ⇒ in-memory memory resident, i ⇒ not-in-memory)
- Initially valid—invalid bit is set to i on all entries
- Example of a page table snapshot:



 During MMU address translation, if valid—invalid bit in page table entry is i ⇒ page fault


Page Table When Some Pages Are Not in Main Memory





Steps in Handling a Page Fault (Cont.)





Performance of Demand Paging



- Three major activities
 - Service the interrupt careful coding means just several hundred instructions needed
 - Read the page lots of time
 - Restart the process again just a small amount of time
- Page Fault Rate $0 \le p \le 1$
 - if p = 0 no page faults
 - if p = 1, every reference is a fault
- Effective Access Time (EAT)

```
EAT = (1 - p) x memory access
+ p (page fault overhead
```

- + swap page out
- + swap page in)

Demand Paging Optimizations



- Swap space I/O faster than file system I/O even if on the same device
 - Swap allocated in larger chunks, less management needed than file system
- Copy entire process image to swap space at process load time
 - Then page in and out of swap space
 - Used in older BSD Unix
- Demand page in from program binary on disk, but discard rather than paging out when freeing frame
 - Used in Solaris and current BSD
 - Still need to write to swap space
 - Pages not associated with a file (like stack and heap) anonymous memory
 - Pages modified in memory but not yet written back to the file system
- Mobile systems
 - Typically don't support swapping
 - Instead, demand page from file system and reclaim read-only pages (such as code)


Copy-on-Write



- Copy-on-Write (COW) allows both parent and child processes to initially share the same pages in memory
 - If either process modifies a shared page, only then is the page copied
- COW allows more efficient process creation as only modified pages are copied
- In general, free pages are allocated from a pool of zero-fill-on-demand pages
 - Pool should always have free frames for fast demand page execution
 - Don't want to have to free a frame as well as other processing on page fault
 - Why zero-out a page before allocating it?
- vfork() variation on fork() system call has parent suspend and child using copy-on-write address space of parent
 - Designed to have child call exec ()
 - Very efficient


Before Process 1 Modifies Page C





After Process 1 Modifies Page C





What Happens if There is no Free Frame?



- Used up by process pages
- Also in demand from the kernel, I/O buffers, etc
- How much to allocate to each?
- Page replacement find some page in memory, but not really in use, page it out
 - Algorithm terminate? swap out? replace the page?
 - Performance want an algorithm which will result in minimum number of page faults
- Same page may be brought into memory several times


Page Replacement



- Prevent over-allocation of memory by modifying page-fault service routine to include page replacement
- Use modify (dirty) bit to reduce overhead of page transfers only modified pages are written to disk
- Page replacement completes separation between logical memory and physical memory – large virtual memory can be provided on a smaller physical memory


Need For Page Replacement





Page Replacement





Page and Frame Replacement Algorithms




- Frame-allocation algorithm determines
 - How many frames to give each process
 - Which frames to replace
- Page-replacement algorithm
 - Want lowest page-fault rate on both first access and re-access
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
 - String is just page numbers, not full addresses
 - Repeated access to the same page does not cause a page fault
 - Results depend on number of frames available
- In all our examples, the reference string of referenced page numbers is

7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1

First-In-First-Out (FIFO) Algorithm




- Reference string: 7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1
- 3 frames (3 pages can be in memory at a time per process)



First-In-First-Out (FIFO) Algorithm




- Reference string: 7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1
- 3 frames (3 pages can be in memory at a time per process)



• Can vary by reference string: consider 1,2,3,4,1,2,5,1,2,3,4,5

FIFO Illustrating Belady's Anomaly






First-In-First-Out (FIFO) Algorithm



- Reference string: 7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1
- 3 frames (3 pages can be in memory at a time per process)




- Can vary by reference string: consider 1,2,3,4,1,2,5,1,2,3,4,5
 - Adding more frames can cause more page faults!
 - Belady's Anomaly
- How to track ages of pages?
 - Just use a FIFO queue

Optimal Algorithm




- Replace page that will not be used for longest period of time
 - 9 is optimal for the example
- How do you know this?
 - Can't read the future
- Used for measuring how well your algorithm performs



Least Recently Used (LRU) Algorithm

- ■Use past knowledge rather than future
- ■Replace page that has not been used in the most amount of time
- Associate time of last use with each page



- ■12 faults better than FIFO but worse than OPT
- ■Generally good algorithm and frequently used
- ■But how to implement?

LRU Algorithm (Cont.)




- Counter implementation
 - Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter
 - When a page needs to be changed, look at the counters to find smallest value
 - Search through table needed
- Stack implementation
 - Keep a stack of page numbers in a double link form:
 - Page referenced:
 - move it to the top
 - requires 6 pointers to be changed
 - But each update more expensive
 - No search for replacement
- LRU and OPT are cases of stack algorithms that don't have Belady's Anomaly

Use Of A Stack to Record Most Recent Page References



reference string





Page replacement

Consider the following page reference strings:

- Assume demand paging with 3 frames, how many page faults will occur for:
 - LRU Page Replacement Algorithm
 - FIFO Page Replacement Algorithm
 - Optimal Page Replacement Algorithm



Page replacement

Consider the following page reference strings:

 Assume demand paging with 3 frames, how many page faults will occur for:

```
FIFO (17 page faults): 7; 7 2; 7 2 3; 1 2 3; 1 5 3; 1 5 4; 6 5 4; 6 7 4; 6 7 1; 0 7 1; 0 5 1; 0 5 4; 6 5 4; 6 2 4; 6 2 3; 0 2 3; 0 1 3

LRU (18 page faults): 7; 7 2; 7 2 3; 1 2 3; 1 2 5; 3 2 5; 3 4 5; 3 4 6; 7 4 6; 7 1 6; 7 1 0; 5 1 0; 5 4 0; 5 4 6; 2 4 6; 2 3 6; 2 3 0; 1 3 0

OPT (13 page faults): 7; 7 2; 7 2 3; 1 2 3; 1 5 3; 1 5 4; 1 5 6; 1 5 7; 1 5 0; 1 4 0; 1 6 0; 1 2 0; 1 3 0
```

LRU Approximation Algorithms



LRU needs special hardware and still slow

Reference bit


- With each page associate a bit, initially = 0
- When page is referenced bit set to 1
- Replace any with reference bit = 0 (if one exists)
 - We do not know the order, however

Second-chance algorithm

- Generally FIFO, plus hardware-provided reference bit
- Clock replacement
- If page to be replaced has
 - Reference bit = 0 -> replace it
 - reference bit = 1 then:
 - set reference bit 0, leave page in memory
 - replace next page, subject to same rules

Second-Chance (clock) Page-Replacement Algorithm





Allocation of Frames



- Each process needs *minimum* number of frames
- Example: IBM 370 6 pages to handle SS MOVE instruction:
 - instruction is 6 bytes, might span 2 pages
 - 2 pages to handle from
 - 2 pages to handle to
- Maximum of course is total frames in the system
- Two major allocation schemes
 - fixed allocation
 - priority allocation
- Many variations

Fixed Allocation



- Equal allocation For example, if there are 100 frames (after allocating frames for the OS) and 5 processes, give each process 20 frames
 - Keep some as free frame buffer pool
- Proportional allocation Allocate according to the size of process
 - Dynamic as degree of multiprogramming, process sizes change

$$m = 64$$
 $-s_i = \text{size of process } p_i$
 $s_1 = 10$
 $-S = \sum s_i$
 $s_2 = 127$
 $-m = \text{total number of frames}$
 $a_1 = \frac{10}{137} \times 62 \approx 4$
 $-a_i = \text{allocation for } p_i = \frac{s_i}{S} \times m$
 $a_2 = \frac{127}{137} \times 62 \approx 57$

Global vs. Local Allocation



- Global replacement process selects a replacement frame from the set of all frames; one process can take a frame from another
 - But then process execution time can vary greatly
 - But greater throughput so more common
- Local replacement each process selects from only its own set of allocated frames
 - More consistent per-process performance
 - But possibly underutilized memory

Thrashing




- If a process does not have "enough" pages, the page-fault rate is very high
 - Page fault to get page
 - Replace existing frame
 - But quickly need replaced frame back
 - This leads to:
 - Low CPU utilization
 - Operating system thinking that it needs to increase the degree of multiprogramming
 - Another process added to the system

Thrashing (Cont.)



 Thrashing. A process is busy swapping pages in and out



Demand Paging and Thrashing



Why does demand paging work?

Locality model

- Process migrates from one locality to another
- Localities may overlap
- Why does thrashing occur?

 Σ size of locality > total memory size

Limit effects by using local or priority page replacement

Working-Set Model




- Δ = working-set window = a fixed number of page references Example: 10,000 instructions
- WSS_i (working set of Process P_i) = total number of pages referenced in the most recent Δ (varies in time)
 - if Δ too small will not encompass entire locality
 - if Δ too large will encompass several localities
 - if $\Delta = \infty \Rightarrow$ will encompass entire program
- $D = \sum WSS_i \equiv \text{total demand frames}$
 - Approximation of locality

Working-Set Model (Cont.)



- D -> Demand for frames, m->available frames
- if $D > m \Rightarrow$ Thrashing
- Policy if *D* > m, then suspend or swap out one of the processes



Keeping Track of the Working Set



- Approximate with interval timer + a reference bit
- Example: $\Delta = 10,000$
 - Timer interrupts after every 5000 time units
 - Keep in memory 2 bits for each page
 - Whenever a timer interrupts copy and sets the values of all reference bits to 0
 - If one of the bits in memory = $1 \Rightarrow$ page in working set
- Why is this not completely accurate?
 - We cannot tell where the reference occurred.
- Improvement = 10 bits and interrupt every 1000 time units

Allocating Kernel Memory



- Treated differently from user memory
- Often allocated from a free-memory pool
 - Kernel requests memory for structures of varying sizes
 - Some kernel memory needs to be contiguous
 - I.e. for device I/O

Buddy System




- Allocates memory from fixed-size segment consisting of physicallycontiguous pages
- Memory allocated using power-of-2 allocator
 - Satisfies requests in units sized as power of 2
 - Request rounded up to next highest power of 2
 - When smaller allocation needed than is available, current chunk split into two buddies of next-lower power of 2
 - Continue until appropriate sized chunk available
- For example, assume 256KB chunk available, kernel requests 21KB
 - Split into A_{L and} A_R of 128KB each
 - One further divided into B_I and B_R of 64KB
 - One further into C_L and C_R of 32KB each one used to satisfy request
- Advantage quickly coalesce unused chunks into larger chunk
- Disadvantage fragmentation

Buddy System Allocator



physically contiguous pages



Slab Allocator



- Alternate strategy
- Slab is one or more physically contiguous pages
- Cache consists of one or more slabs
- Single cache for each unique kernel data structure
 - Each cache filled with objects instantiations of the data structure
- When cache created, filled with objects marked as **free**
- When structures stored, objects marked as used
- If slab is full of used objects, next object allocated from empty slab
 - If no empty slabs, new slab allocated
- Benefits include no fragmentation, fast memory request satisfaction

Slab Allocation



