# **Ultimate Starter Kit**

**Documentation** 

## Table of contents

| 1. Getting Started      | 4  |
|-------------------------|----|
| 1.1 Requirements        | 4  |
| 1.2 Installation        | 4  |
| 1.3 Plugin Content      | 4  |
| 2. Support the Project  | 5  |
| 3. Special Thanks       | 6  |
| 4. Console Codenames    | 7  |
| 4.1 Code names          |    |
| 4.2 Obfuscated code     | 7  |
| 5. Core Functionality   | 8  |
| 5.1 Input Devices       | 8  |
| 5.2 Game Instance       | ç  |
| 6. Logger               | 13 |
| 6.1 Introduction        | 13 |
| 6.2 Log Levels          | 13 |
| 6.3 Logging Methods     | 13 |
| 6.4 API Reference       | 14 |
| 6.5 Blueprint Usage     | 15 |
| 6.6 C++ Usage           | 15 |
| 7. Dialogue System      | 17 |
| 7.1 Dialogue System     | 17 |
| 7.2 Dialogue            | 18 |
| 7.3 Participant         | 19 |
| 7.4 Entry               | 20 |
| 7.5 Transition          | 22 |
| 7.6 Manager             | 24 |
| 7.7 Widget              | 26 |
| 8. Inventory            | 27 |
| 8.1 Inventory Component | 27 |
| 8.2 Inventory Data      | 29 |
| 8.3 Inventory Item      | 30 |
| 8.4 Inventory Item Data | 31 |
| 8.5 Inventory Menu Item | 32 |
| 8.6 Inventory Size      | 34 |
| 8.7 Inventory Widget    | 35 |

| 9. Trackable Data          | 38  |
|----------------------------|-----|
| 9.1 Overview               | 38  |
| 9.2 Data                   | 39  |
| 9.3 Component              | 40  |
| 10. Audio                  | 42  |
| 10.1 Audio Overview        | 42  |
| 10.2 Audio Utils           | 43  |
| 10.3 Music Player          | 45  |
| 11. 3D Platformer          | 47  |
| 11.1 Overview              | 47  |
| 11.2 Character             | 48  |
| 11.3 Animation Instance    | 51  |
| 11.4 Shadow Decal          | 52  |
| 12. Items                  | 53  |
| 12.1 Allowed Collector     | 53  |
| 12.2 Collectable Item      | 54  |
| 13. UI & Widgets           | 56  |
| 13.1 Collectable Item Icon | 56  |
| 13.2 Credits               | 58  |
| 13.3 FPS Counter           | 61  |
| 13.4 Input Indicator       | 63  |
| 13.5 Input Indicator Icon  | 65  |
| 13.6 Menu                  | 67  |
| 13.7 Menu Item             | 70  |
| 14. Settings               | 81  |
| 14.1 Data                  | 81  |
| 14.2 Config                | 85  |
| 14.3 Items                 | 99  |
| 14.4 Utils                 | 102 |
| 15. Utils                  | 105 |
| 15.1 Config Utils          | 105 |
| 15.2 Platform              | 107 |
| 15.3 Project Utils         | 113 |
|                            |     |

## 1. Getting Started

#### 1.1 Requirements

The Ultimate Starter Kit plugin is only available for Unreal Engine 4.27 and newer. The plugin also depends on the following plugins:

- 1. Niagara
- 2. Enchanced Input

#### 1.2 Installation

- 1. Download the latest release from GitHub
- $2. \ Navigate \ \texttt{to} \ \texttt{C:\Program Files\Epic Games\UE_{VERSION}\Engine\Plugins}$
- 3. Create a Marketplace folder if needed
- 4. Extract the release and copy to the Marketplace folder
- 5. Open Unreal Engine
- 6. Click on Edit > Plugins
- 7. Enable the plugin under the Built-in > Other category
- 8. Restart Unreal Engine

#### 1.3 Plugin Content

The Ultimate Starter Kit plugin includes content that can be used in your Blueprints. You might need to enable this first:

- 1. Open the Content Browser
- 2. Click on the settings button
- $3. \ Enable \ the \ {\tt Show Plugin Content} \ setting$

## 2. Support the Project

I created this plugin because I love making games and I want to share my passion and knowledge with other game developers. I want to make Unreal Engine more accessible and powerful for everyone who wants to create amazing games.

But creating and maintaining this plugin is not easy. It requires a lot of work, resources, and expertise. That's why I need your support to keep this project alive and growing. By donating to this project, you can:

- Help me cover the costs of development, testing, documentation, and other expenses
- Encourage me to continue working on the project and adding new features
- Enable me to spend more time on the project and less on other jobs
- Join a community of like-minded game developers who care about the same plugin

Donating to this project is not only beneficial for me, but also for you as a user. By donating to this project, you can:

- · Improve the plugin you rely on daily
- Learn new skills or improve on existing ones by studying the code or contributing yourself
- Gain a deeper knowledge about the plugin you're using
- Build your reputation and career by showing your involvement and expertise
- Have fun and satisfaction by being part of something bigger than yourself

So if you like this plugin and use it regularly, consider donating to it. Even a small amount can make a big difference. Donating to this project is a way of saying "thank you" to me and helping me create more amazing games and project for everyone.

You can donate through GitHub Sponsors here: https://github.com/sponsors/hfjooste

## 3. Special Thanks

This project uses a few assets from third parties:

- Generic Graph by jinyuliao
- Comic Helvetic Font by Alexander Pravdin
- Menu Sound Effects by Broumbroum
- Land & Jump Sound Effects by Felixyadomi
- Item Sound Effects by Scrampunk
- Music by InAudio

If you liked these assets and want to see more, please follow the links and show them some love!

## 4. Console Codenames

#### 4.1 Code names

Due to copyright issues, the plugin is not allowed to mention Xbox, Playstation or Switch anywhere in the code (including file names). To get around this issue, the consoles are referred to by the following code names:

| Console     | Code name  |
|-------------|------------|
| Xbox        | Console MX |
| Playstation | Console SP |
| Switch      | Console NS |

#### 4.2 Obfuscated code

The plugin will also use the console names to determine the platform. To avoid any copyright issues, the application will instead use an obfuscated string to determine the platform. The obfuscation and deobfuscation code can be found in <code>PlatformUtils.cpp</code>

| Console     | Obfuscated Text                  | Deobfuscated Text |
|-------------|----------------------------------|-------------------|
| Xbox        | PT1BZWk5R2U=                     | xbox              |
| Playstation | PUEzYw==<br>PT13YzBGR2RwOW1i     | ps<br>station     |
| Switch      | PTRXYXVSWFp1UjJi<br>emRYYTBOR2E= | nintendoswitch    |

## 5. Core Functionality

## 5.1 Input Devices

#### 5.1.1 Introduction

Supported input devices. This is used to update the input indicators when using different input devices

#### 5.1.2 Values

| Value             | Description  |
|-------------------|--|
| KeyboardMouse     | Using a keyboard and mouse                                     |
| GenericController | Using a controller on a desktop build                          |
| MxController      | Using an Console MX controller                                 |
| SpController      | Using a Console SP controller                                  |
| NsController      | Using a Console NS controller                                  |
| Unknown           | Unknown device (used before initializing the input indicators) |

#### 5.2 Game Instance

#### 5.2.1 Introduction

A base game instance with support for saving and loading game data using multiple save slots

#### 5.2.2 Dependencies

The USKGameInstance relies on other components of this plugin to work:

• Logger: Used to log useful information to help you debug any issues you might experience

#### 5.2.3 Using the Game Instance

You need to create a blueprint using the <code>USKGameInstance\_Implementation</code> as a parent before using the game instance. The input indicators feature is already configured if you use this base class. If you prefer to set this up manually, you can use <code>USKGameInstance</code> instead. After creating your own game instance blueprint, set this as the default game instance:

- 1. Open the Project Settings
- 2. Go to Project > Maps & Modes
- 3. Change the Game Instance Class value to your own blueprint

#### 5.2.4 Save Data

You need to create a USK Save Game object before you can save/load data. This object contains all the data that you want to save. Just add the data you want to save as variables to the blueprint. The Game Instance will handle the rest. You also need to set the following properties before you can save/load data:

• Save Game Class: A reference to the USK Save Game class that contains the data you want to save

NB: You are required to set the save slot before you can save/load data. If not, you will get a nullptr and might cause your game to crash

#### 5.2.5 Input Indicators

The Game Instance will automatically detect input events and update the current input device if needed. If the input device is changed, other classes will be notified through the <code>OnInputDeviceUpdated</code> event

#### 5.2.6 API Reference

#### Properties

| Property                       | Description  | Туре                                      | Default Value |
|--------------------------------|--|---|---------------|
| SaveGameClass                  | The class that holds the data that should be saved/loaded                          | TSubclassOf <uusksavegame></uusksavegame> |               |
| SettingsConfig                 | The configuration for the settings   | USettingsConfig*                          | nullptr       |
| IsInputIndicatorsEnabled       | Is the input indicators feature enabled?   | bool                                      | true          |
| InputMappingContext            | The input mapping context used to extract the keys based on specific input actions | UInputMappingContext*                     | nullptr       |
| KeyboardMouseInputMappings     | A map of all keyboard/mouse keys and the texture displayed in the indicator        | TMap <fkey, utexture2d*=""></fkey,>       |               |
| GenericControllerInputMappings | A map of all generic controller keys and the texture displayed in the indicator    | TMap <fkey, utexture2d*=""></fkey,>       |               |
| MxControllerInputMappings      | A map of all Console MX controller keys and the texture displayed in the indicator | TMap <fkey, utexture2d*=""></fkey,>       |               |
| SpControllerInputMappings      | A map of all Console SP controller keys and the texture displayed in the indicator | TMap <fkey, utexture2d*=""></fkey,>       |               |
| NsControllerInputMappings      | A map of all Console NS controller keys and the texture displayed in the indicator | TMap <fkey, utexture2d*=""></fkey,>       |               |

#### **Events**

| Name                 | Description   | Params |
|----------------------|---|--------|
| OnDataLoadedEvent    | Event used to notify other classes when the save data is loaded             |        |
| OnInputDeviceUpdated | Event used to notify other classes when the current input device is updated |        |
| OnGamePaused         | Event used to notify other classes when the game is paused                  |        |
| OnGameUnpaused       | Event used to notify other classes when the game is unpaused                |        |

#### **Functions**

| Name                        | Description  | Params   | Return  |
|-----------------------------|--|--|---|
| GetSaveData                 | Get the save data that is currently loaded                   |  | UUSKSaveGame* A reference to the current save data  |
| SaveData                    | Save the modified data currently in memory                   |  |   |
| SetCurrentSaveSlot          | Set the current save slot                                    | Index (int) The index of the save slot   |   |
| IsSaveSlotUsed              | Check if a save slot is used                                 | Index (int)  The index of the save slot to check                                       | bool  A boolean value indicating if the save slot is used                                     |
| EnableInputIndicators       | Enable the input indicators feature                          |  |   |
| DisableInputIndicators      | Disable the input indicators feature                         |  |   |
| GetInputIndicatorIcon       | Get the input indicator icon for a specific action           | InputAction (UInputAction*) The input action  Amount (int)                             | TArray <utexture2d*> An array of input indicator icons for the specified action</utexture2d*> |
|                             |  | The amount of icons to retrieve  |   |
| GetInputIndicatorIconForKey | Get the input indicator icon for a specific key              | Key (FKey)  The key used to retrieve the input indicator icon                          | UTexture2D*  The input indicator icon for the specified key                                   |
|                             |  | InputDevice (EInputDevice)  The input device used to retrieve the input indicator icon |   |
| GetKeyForInputAction        | Get the key used by a specific input action                  | Context (UInputMappingContext*) The input mapping context                              | FKey  The key used by the specified input   |
|                             |  | InputAction (UInputAction*) The input action   | action  |
|                             |  | MappableName (FName)  The player mappable name for the action                          |   |
| UpdateKeyBindings           | Update the key bindings<br>that was changed by the<br>player |  |   |
| PauseGame                   | Pause the game   |  |   |
| UnpauseGame                 | Unpause the game   |  |   |

#### 5.2.7 Blueprint Usage

You can use the USKGameInstance using Blueprints by adding one of the following nodes:

- Ultimate Starter Kit > Save Data > Get Save Data
- Ultimate Starter Kit > Save Data > Save Data
- Ultimate Starter Kit > Save Data > Set Current Save Slot
- Ultimate Starter Kit > Save Data > Is Save Slot Used
- Ultimate Starter Kit > Input > Enable Input Indicators
- Ultimate Starter Kit > Input > Disable Input Indicators
- Ultimate Starter Kit > Input > Get Input Indicator Icon
- Ultimate Starter Kit > Input > Get Input Indicator Icon For Key
- Ultimate Starter Kit > Input > Get Key For Input Action
- Ultimate Starter Kit > Input > Update Key Bindings
- Ultimate Starter Kit > Pause > Pause Game
- Ultimate Starter Kit > Pause > Unpause Game

#### 5.2.8 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your Build.cs file:

```
PublicDependencyModuleNames.Add("USK");
```

The USKGameInstance can now be used in any of your C++ files:

```
#include "USK/Core/USKGameInstance.h"

void ATestActor::Test()
{
    // USKGameInstance is a pointer to the UUSKGameInstance
    UUSKSaveGame* SaveData = USKGameInstance->GetSaveData();
    USKGameInstance->SaveData();
    USKGameInstance->SetCurrentSaveSlot(Index);
    bool IsSaveSlotUsedValue = USKGameInstance->IsSaveSlotUsed(Index);
    USKGameInstance->EnableInputIndicators();
    USKGameInstance->DisableInputIndicators();
    USKGameInstance->DisableInputIndicators();
    USKGameInstance->DisableInputIndicatorIcon = USKGameInstance->GetInputIndicatorIcon(InputAction, Amount);
    UTexture2D* InputIndicatorIconForKey = USKGameInstance->GetInputIndicatorIconForKey(Key, InputDevice);
    FKey KeyForInputAction = USKGameInstance->GetKeyForInputAction(Context, InputAction, MappableName);
    USKGameInstance->DupdateKeyBindings();
    USKGameInstance->PauseGame();
    USKGameInstance->PauseGame();
}
```

## 6. Logger

#### 6.1 Introduction

A system used to easily log info to file and via on-screen messages

#### 6.2 Log Levels

This plugin supports the following log types:

- 1. **Trace:** Logs that contain the most detailed messages. These messages may contain sensitive application data. These messages are disabled by default and should never be enabled in a production environment
- 2. **Debug:** Logs that are used for interactive investigation during development. These logs should primarily contain information useful for debugging and have no long-term value
- 3. Information: Logs that track the general flow of the application. These logs should have long-term value
- 4. Warning: Logs that highlight an abnormal or unexpected event in the application flow, but do not otherwise cause the application execution to stop
- 5. Error: Logs that highlight when the current flow of execution is stopped due to a failure. These should indicate a failure in the current activity, not an application-wide failure

The log levels corresponds to the following verbosity level in Unreal Engine:

| Log Level   | Log Verbosity |
|-------------|---------------|
| Trace       | VeryVerbose   |
| Debug       | Verbose       |
| Information | Display       |
| Warning     | Warning       |
| Error       | Error         |

The plugin will automatically ignore certain log levels based on the type of build:

| Log Level   | Development | Shipping |
|-------------|-------------|----------|
| Trace       | Enabled     | Disabled |
| Debug       | Enabled     | Disabled |
| Information | Enabled     | Enabled  |
| Warning     | Enabled     | Enabled  |
| Error       | Enabled     | Enabled  |

#### 6.3 Logging Methods

There are 2 different logging methods. Both of these are used each time you log something:

- On-screen messages: These messages will appear on-screen for 5 seconds (only used when running the game through the editor)
- Log File: Everything you log is also written to a file using the Unreal Engine logging feature

## 6.4 API Reference

#### 6.4.1 Macros

| Name            | Description  | Params   | Return |
|-----------------|--|--|--------|
| USK_LOG_TRACE   | Log trace information using the current function name as the tag | Text (FString)  The text that should be logged out |        |
| USK_LOG_DEBUG   | Log debug information using the current function name as the tag | Text (FString)  The text that should be logged out |        |
| USK_LOG_INFO    | Log information using the current function name as the tag       | Text (FString)  The text that should be logged out |        |
| USK_LOG_WARNING | Log a warning using the current function name as the tag         | Text (FString)  The text that should be logged out |        |
| USK_LOG_ERROR   | Log an error using the current function name as the tag          | Text (FString)  The text that should be logged out |        |

#### 6.4.2 Functions

| Name    | Description              | Params   | Return |
|---------|--------------------------|--|--------|
| Trace   | Log trace information    | Tag (FString)  The category of the log entry. This is usually the function or class name. It allows you to find out exactly where this is being logged  Text (FString)  The text that should be logged out |        |
| Debug   | Log debug<br>information | Tag (FString)  The category of the log entry. This is usually the function or class name. It allows you to find out exactly where this is being logged  Text (FString)  The text that should be logged out |        |
| Info    | Log information          | Tag (FString)  The category of the log entry. This is usually the function or class name. It allows you to find out exactly where this is being logged  Text (FString)  The text that should be logged out |        |
| Warning | Log a warning            | Tag (FString) The category of the log entry. This is usually the function or class name. It allows you to find out exactly where this is being logged  Text (FString) The text that should be logged out   |        |
| Error   | Log an error             | Tag (FString) The category of the log entry. This is usually the function or class name. It allows you to find out exactly where this is being logged  Text (FString) The text that should be logged out   |        |

### 6.5 Blueprint Usage

You can easily log info using Blueprints by adding one of the following nodes:

- Ultimate Starter Kit > Logger > Log Trace
- Ultimate Starter Kit > Logger > Log Debug
- $\bullet$  Ultimate Starter Kit > Logger > Log Info
- Ultimate Starter Kit > Logger > Log Warning
- $\bullet$  Ultimate Starter Kit > Logger > Log Error

### 6.6 C++ Usage

The logging is handled through a static class/functions. You first need to enable the plugin in your  ${\tt Build.cs}$  file:

PublicDependencyModuleNames.Add("USK");

#### The logger can now be used in any of your C++ files:

```
#include "USK/Logger/Log.h"

void ATestActor::Test()
{
    USK_LOG_TRACE("Testing trace logging");
    USK_LOG_DEBUG("Testing debug logging");
    USK_LOG_INFO("Testing info logging");
    USK_LOG_INFO("Testing warning logging");
    USK_LOG_ERROR("Testing warning logging");
    USK_LOG_ERROR("Testing error logging");
    ULog::Trace("Custom Tag", "Testing trace logging");
    ULog::Debug("Custom Tag", "Testing debug logging");
    ULog::Info("Custom Tag", "Testing info logging");
    ULog::Warning("Custom Tag", "Testing warning logging");
    ULog::Error("Custom Tag", "Testing error logging");
}
```

## 7. Dialogue System

### 7.1 Dialogue System

#### 7.1.1 Introduction

The Ultimate Starter Kit plugin contains a full dialogue system with support for different participants, choices and brances

#### 7.1.2 Creating a new dialogue

You can create a new dialogue by following these steps: 1. Right click in the Content Browser 2. Go to the Ultimate Starter Kit section 3. Click on Dialogue

This will open the newly created dialogue in the dialogue editor

#### 7.1.3 Using the editor

The dialogue editor works similar to a Behaviour Tree. You start by creating a single root node. You can then drag connections to a new dialogue entry. The game will start off with the root and follow the path automatically until it reaches the end or a choice. If a choice is encountered, it will present the options to the player and follow the correct branch after a choice is selected

## 7.2 Dialogue

#### 7.2.1 Introduction

An array of all the root entries contained by this dialogue

#### 7.2.2 API Reference

#### Properties

| Property    | Description   | Туре                                       | Default Value |
|-------------|---|--|---------------|
| RootEntries | An array of all the root entries contained by this dialogue | TArray <udialogueentry*></udialogueentry*> |               |
| AllEntries  | An array of all the entries contained by this dialogue      | TArray <udialogueentry*></udialogueentry*> |               |
| EditorGraph | A reference to the editor graph used by this dialogue       | UEdGraph*                                  | nullptr       |

## 7.3 Participant

#### 7.3.1 Introduction

A participant in the dialogue

#### 7.3.2 API Reference

#### Properties

| Property | Description  | Туре         | Default Value       |
|----------|--|--------------|---------------------|
| Name     | The name of the dialogue participant                 | FText        |                     |
| Color    | The color used to represent the dialogue participant | FLinearColor | FLinearColor::Black |

## 7.4 Entry

#### 7.4.1 Introduction

A single entry in a dialogue

#### 7.4.2 API Reference

#### **Properties**

| Property      | Description  | Туре   | Default Value |
|---------------|--|--|---------------|
| Owner         | The owner participant of the dialogue entry                | UDialogueParticipant*  | nullptr       |
| Transition    | The type of transition for this dialogue entry             | EDialogueTransitionType  |               |
| Id            | The ID of the dialogue entry                               | FName  | FNam          |
| Text          | The text to display  | FText  |               |
| Speed         | The speed of the dialogue                                  | float  | 12.5f         |
| Audio         | The audio to play with this dialogue entry                 | USoundBase*  | nullptr       |
| Dialogue      | A reference to the dialogue containing this entry          | UDialogue*   | nullptr       |
| ParentNodes   | An array of all the parent entries for this dialogue entry | TArray <udialogueentry*></udialogueentry*>                         |               |
| ChildrenNodes | An array of all the child entries for this dialogue entry  | TArray <udialogueentry*></udialogueentry*>                         |               |
| Edges         | A map of all the possible edges for this dialogue entry    | TMap <udialogueentry*, udialoguetransition*=""></udialogueentry*,> |               |

#### Functions

| Name       | Description                                     | Params | Return  |
|------------|---|--------|---|
| IsLeafNode | Check if this entry is a leaf node              |        | <b>bool</b> A boolean value indicating if this entry is a leaf node |
| GetTitle   | Get the title displayed for this dialogue entry |        | FText The title displayed for this dialogue entry                   |
| GetText    | Get the text displayed for this dialogue entry  |        | FText The text displayed for this dialogue entry                    |

#### 7.4.3 Blueprint Usage

You can use the DialogueEntry using Blueprints by adding one of the following nodes:

- Ultimate Starter Kit > Dialogue > Entry > Get Title

#### 7.4.4 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your  ${\tt Build.cs}$  file:

```
PublicDependencyModuleNames.Add("USK");
```

The  ${\tt DialogueEntry}$  can now be used in any of your C++ files:

```
#include "USK/Dialogue/DialogueEntry.h"

void ATestActor::Test()
{
    // DialogueEntry is a pointer to the UDialogueEntry
    bool IsLeafNodeValue = DialogueEntry->IsLeafNode();
    FText Title = DialogueEntry->GetTitle();
    FText Text = DialogueEntry->GetText();
}
```

## 7.5 Transition

### 7.5.1 Transition Type

#### Introduction

The type of transition used by the dialogue entry

#### Values

| Value  | Description   |
|--------|---|
| Auto   | Automatically advance to the next dialogue entry                      |
| Choice | Give the player a few choices used to create branches in the dialogue |

#### 7.5.2 Transition Data

#### Introduction

A transition from one dialogue entry to the next

#### **API Reference**

#### PROPERTIES

| Property   | Description                                     | Туре            | Default Value |
|------------|---|-----------------|---------------|
| Text       | The text displayed for this transition (choice) | FText           |               |
| StartEntry | The dialogue entry where the transition starts  | UDialogueEntry* | nullptr       |
| EndEntry   | The dialogue entry where the transition ends    | UDialogueEntry* | nullptr       |

#### EVENTS

| Name                | Description   | Params |
|---------------------|---|--------|
| OnMarkedForDeletion | Event used to notify other classes that the transition is marked for deletion |        |

## 7.6 Manager

#### 7.6.1 Introduction

The pawn responsible for managing the dialogue

#### 7.6.2 Dependencies

The DialogueManager relies on other components of this plugin to work:

- Logger: Used to log useful information to help you debug any issues you might experience
- Audio: Used to play sound effects either 2D or at a specified location

#### 7.6.3 Components

The DialogueManager uses the following components:

| Name           | Description   | Туре             |
|----------------|---|------------------|
| AudioComponent | The audio component responsible for playing the audio files of the dialogue entries | UAudioComponent* |

#### 7.6.4 API Reference

#### **Properties**

| Property            | Description  | Туре  | Default Value |
|---------------------|--|---|---------------|
| Dialogue            | The dialogue that should be played by the dialogue manager                                     | UDialogue*                                      | nullptr       |
| DialogueWidgetClass | The class of the widget used to display the dialogue   | TSubclassOf <udialoguewidget></udialoguewidget> |               |
| PlayOnStart         | A boolean value indicating if the dialogue should automatically play when the level is started | bool  | true          |
| SkipSFX             | The sound effect to play when an entry is skipped  | USoundBase*                                     | nullptr       |
| AdvanceSFX          | The sound effect to play when advancing to the next entry                                      | USoundBase*                                     | nullptr       |
| InputMappingContext | The input mapping context used to interact with the dialogue                                   | UInputMappingContext*                           | nullptr       |
| SkipAction          | The input action used to skip the current dialogue entry                                       | UInputAction*                                   | nullptr       |

#### **Events**

| Name                   | Description  | Params   |
|------------------------|--|--|
| OnDialogueEnded        | Event used to notify other classes when the dialogue has ended       | LastEntryId (FName) The ID of the last entry in the dialogue |
| OnDialogueEntryStarted | Event used to notify other classes when a dialogue entry has started | LastEntryId (FName) The ID of the dialogue entry             |
| OnDialogueEntryEnded   | Event used to notify other classes when a dialogue entry has ended   | LastEntryId (FName) The ID of the dialogue entry             |

#### **Functions**

| Name         | Description                            | Params | Return |
|--------------|--|--------|--------|
| PlayDialogue | Play the dialogue                      |        |        |
| SkipEntry    | Skip the current entry in the dialogue |        |        |

#### 7.6.5 Blueprint Usage

You can use the DialogueManager using Blueprints by adding one of the following nodes:

- Ultimate Starter Kit > Dialogue > Play Dialogue
- Ultimate Starter Kit > Dialogue > Skip Entry

#### 7.6.6 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your Build.cs file:

```
PublicDependencyModuleNames.Add("USK");
```

The DialogueManager can now be used in any of your C++ files:

```
#include "USK/Dialogue/DialogueManager.h"

void ATestActor::Test()
{
    // DialogueManager is a pointer to the ADialogueManager
    DialogueManager->PlayDialogue();
    DialogueManager->SkipEntry();
}
```

## 7.7 Widget

#### 7.7.1 Introduction

Widget used to display a dialogue

#### 7.7.2 Dependencies

The  $\mbox{DialogueTransitionType}$  relies on other components of this plugin to work:

• Logger: Used to log useful information to help you debug any issues you might experience

#### 7.7.3 Required Widgets

You need to add the following before you can compile the  ${\tt DialogueTransitionType}$  widget:

| Name          | Description                                       | Туре        |
|---------------|---|-------------|
| DialogueTitle | The text block used to display the dialogue title | UTextBlock* |
| DialogueText  | The text block used to display the dialogue text  | UTextBlock* |
| ChoiceMenu    | The menu used to display the dialogue choices     | UMenu*      |

#### 7.7.4 Optional Widgets

You can add the following widgets to enable extra functionality:

| Name           | Description  | Туре    |
|----------------|--|---------|
| SkipEntryImage | The image displayed when the dialogue entry is completed | UImage* |

#### 7.7.5 API Reference

#### **Properties**

| Property            | Description                         | Туре                                | Default Value |
|---------------------|-------------------------------------|-------------------------------------|---------------|
| ChoiceMenuItemClass | The class for all choice menu items | TSubclassOf <umenuitem></umenuitem> |               |

#### **Events**

| Name             | Description  | Params   |
|------------------|--|--|
| OnChoiceSelected | Event used to notify other classes when a choice is selected | Index (int)  The index of the choice that was selected |

## 8. Inventory

## 8.1 Inventory Component

#### 8.1.1 Introduction

Actor component responsible for tracking data in an inventory

#### 8.1.2 Dependencies

The  ${\tt InventoryComponent}$  relies on other components of this plugin to work:

- Logger: Used to log useful information to help you debug any issues you might experience
- Game Instance: Used to monitor for input device changes and handle saving/loading game data

#### 8.1.3 API Reference

#### **Properties**

| Property         | Description  | Туре  | Default Value |
|------------------|--|-------|---------------|
| InventoryId      | The ID of the inventory used when saving/loading the data      | FName |               |
| AutoSave         | Should the data in the inventory automatically be saved/loaded | bool  | true          |
| EnforceMaxAmount | Should a maximum amount be enforced for each item?             | bool  |               |
| MaxAmount        | The maximum amount of each item                                | int   | 99            |

#### **Events**

| Name                   | Description  | Params   |
|------------------------|--|--|
| OnInventoryItemUpdated | Event used to notify other classes every time an item in the inventory was updated | Id (FName) The ID of the item that was updated |
|                        |  | Amount (FName) The new amount of the item      |

#### **Functions**

| Name          | Description                                 | Params   | Return  |
|---------------|---|--|---|
| GetItems      | Get all the item currently in the inventory |  | TArray <finventoryitem> An array of all the items in the inventory</finventoryitem> |
| AddItem       | Add an item to the inventory                | Id (FName) The ID of the item to add  Amount (int) The amount to add       |   |
| RemoveItem    | Remove an item from the inventory           | Id (FName) The ID of the item to remove  Amount (int) The amount to remove |   |
| RemoveAll     | Remove all the items with the specified ID  | Id (FName) The ID of the item to remove                                    |   |
| Clear         | Remove all items from the inventory         |  |   |
| LoadInventory | Load the inventory data                     |  |   |
| SaveInventory | Save the inventory data                     |  |   |

#### 8.1.4 Blueprint Usage

You can use the InventoryComponent using Blueprints by adding one of the following nodes:

- $\bullet \ Ultimate \ Starter \ Kit > Inventory > Get \ Items$
- $\bullet \ Ultimate \ Starter \ Kit > Inventory > Add \ Item$
- $\bullet \ Ultimate \ Starter \ Kit > Inventory > Remove \ Item$
- Ultimate Starter Kit > Inventory > Remove All
- Ultimate Starter Kit > Inventory > Clear
- Ultimate Starter Kit > Inventory > Load Inventory
- Ultimate Starter Kit > Inventory > Save Inventory

#### 8.1.5 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your  ${\tt Build.cs}$  file:

```
PublicDependencyModuleNames.Add("USK");
```

The InventoryComponent can now be used in any of your C++ files:

```
#include "USK/Inventory/InventoryComponent.h"

void ATestActor::Test()
{
    // InventoryComponent is a pointer to the UInventoryComponent
    TArray<FinventoryItem> Items = InventoryComponent->GetItems();
    InventoryComponent->AddItem(Id, Amount);
    InventoryComponent->RemoveItem(Id, Amount);
    InventoryComponent->Celar();
    InventoryComponent->Celar();
    InventoryComponent->SaveInventory();
    InventoryComponent->SaveInventory();
}
```

## 8.2 Inventory Data

#### 8.2.1 Introduction

The inventory data for a single inventory

### 8.2.2 Properties

| Property | Description                         | Туре                                     | Default Value |
|----------|-------------------------------------|--|---------------|
| Items    | The array of items in the inventory | TArray <finventoryitem></finventoryitem> |               |

## 8.3 Inventory Item

#### 8.3.1 Introduction

The information about a specific inventory item

### 8.3.2 Properties

| Property | Description                      | Туре  | Default Value |
|----------|----------------------------------|-------|---------------|
| Id       | The ID of the inventory item     | FName |               |
| Amount   | The amount of the inventory item | int   |               |

## 8.4 Inventory Item Data

#### 8.4.1 Introduction

The data used to describe an inventory item

#### 8.4.2 Properties

| Property       | Description  | Туре        | Default Value |
|----------------|--|-------------|---------------|
| Name           | The name of the inventory item                           | FText       |               |
| Description    | The description of the inventory item                    | FText       |               |
| InventoryImage | The image displayed in the inventory                     | UTexture2D* | nullptr       |
| PreviewImage   | The preview image displayed when the item is highlighted | UTexture2D* | nullptr       |

## 8.5 Inventory Menu Item

#### 8.5.1 Introduction

The menu item used to display an inventory item

#### 8.5.2 Dependencies

The InventoryMenuItem relies on other components of this plugin to work:

• Logger: Used to log useful information to help you debug any issues you might experience

#### 8.5.3 Optional Widgets

You can add the following widgets to enable extra functionality:

| Name           | Description                     | Туре    |
|----------------|---------------------------------|---------|
| InventoryImage | The image of the inventory item | UImage* |

#### 8.5.4 API Reference

#### **Properties**

#### **Functions**

| Name                         | Description   | Params  | Return   |
|------------------------------|---|---|--|
| InitializeEmptyInventoryItem | Initialize an empty inventory item                  | Widget (UInventoryWidget*)  The widget that owns this menu item   |  |
| InitializeInventoryItem      | Initialize a non-empty inventory item               | Widget (UInventoryWidget*) The widget that owns this menu item  Item (FInventoryItem) The item tracked by this menu item  Data (FInventoryItemData) The data for this menu item |  |
| UpdateInventoryGridPosition  | Update the grid position of the inventory menu item | CurrentColumn (int) The current column of the inventory menu item  CurrentRow (int) The current row of the inventory menu item  |  |
| GetInventoryItem             | Get the inventory item tracked by this menu item    |   | FInventoryItem  The inventory item tracked by this menu item |
| UpdateAmount                 | Update the amount of the inventory item             | Amount (int)  The new amount of the inventory item  |  |

#### 8.5.5 Blueprint Usage

You can use the InventoryMenuItem using Blueprints by adding one of the following nodes:

- Ultimate Starter Kit > Inventory > Initialize Empty Inventory Item
- Ultimate Starter Kit > Inventory > Initialize Inventory Item
- Ultimate Starter Kit > Inventory > Update Inventory Grid Position
- Ultimate Starter Kit > Inventory > Get Inventory Item
- Ultimate Starter Kit > Inventory > Update Amount

#### 8.5.6 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your Build.cs file:

```
PublicDependencyModuleNames.Add("USK");
```

The  ${\tt InventoryMenuItem}$  can now be used in any of your C++ files:

```
#include "USK/Inventory/InventoryMenuItem.h"

void ATestActor::Test()
{
    // InventoryMenuItem is a pointer to the UInventoryMenuItem
    InventoryMenuItem->InitializeEmptyInventoryItem(Widget);
    InventoryMenuItem->InitializeEmptyInventoryItem(Widget, Item, Data);
    InventoryMenuItem->UpdateInventoryGridPosition(CurrentColumn, CurrentRow);
    FInventoryItem InventoryItem = InventoryMenuItem->GetInventoryItem();
    InventoryMenuItem->UpdateAmount(Amount);
}
```

## 8.6 Inventory Size

#### 8.6.1 Introduction

The size restrictions of the inventory

#### 8.6.2 Values

| Value        | Description  |  |
|--------------|--|--|
| FixedSize    | Limit both the width and height of the inventory                       |  |
| FixedRows    | Limit only the rows of the inventory and allow the columns to increase |  |
| FixedColumns | Limit only the columns of the inventory and allow the rows to increase |  |

## 8.7 Inventory Widget

#### 8.7.1 Introduction

The widget responsible for displaying the inventory

#### 8.7.2 Dependencies

The InventoryWidget relies on other components of this plugin to work:

• Logger: Used to log useful information to help you debug any issues you might experience

#### 8.7.3 Required Widgets

You need to add the following before you can compile the  ${\tt InventoryWidget}$  widget:

| Name          | Description   | Туре   |
|---------------|---|--------|
| InventoryMenu | The menu responsible for controlling all the menu items | UMenu* |

#### 8.7.4 Optional Widgets

You can add the following widgets to enable extra functionality:

| Name            | Name         Description           NameText         The widget responsible for displaying the highlighted item's name           DescriptionText         The widget responsible for displaying the highlighted item's description           PreviewImage         The widget responsible for displaying the highlighted item's image |             |
|-----------------|--|-------------|
| NameText        |  |             |
| DescriptionText |  |             |
| PreviewImage    |  |             |
| AmountText      | The widget responsible for displaying the highlighted item's amount  | UTextBlock* |

#### 8.7.5 API Reference

#### Properties

| Property      | Description   | Туре  | Default Value |
|---------------|---|---|---------------|
| MenuItemClass | The inventory menu item class used to display the inventory items       | TSubclassOf <uinventorymenuitem></uinventorymenuitem> |               |
| ItemData      | The data table containing all the information about the inventory items | UDataTable*   | nullptr       |
| InventorySize | The size restrictions of the inventory                                  | EInventorySize  |               |
| Rows          | The amount of rows in the inventory                                     | int   |               |
| Columns       | The amount of columns in the inventory                                  | int   |               |

#### **Events**

| Name                    | Description   | Params   |
|-------------------------|---|--|
| OnInventoryItemSelected | Event used to notify other classes every time an inventory item is selected | Name (FName) The ID of the selected inventory item |

#### **Functions**

| Name                   | Description                              | Params   | Return  |
|------------------------|--|--|---|
| LoadInventory          | Load a specific inventory                | InventoryComponent (UInventoryComponent*) The inventory to load  |   |
| UpdatePreview          | Update the preview of the inventory      | Item (FInventoryItem) The item to preview  |   |
| UpdateHighlightedIndex | Update the highlighted index             | Column (int) The column index of the item that is highlighted  Row (int) The row index of the item that is highlighted |   |
| SelectItem             | Select an inventory item                 | Id (FName) The ID of the item to select  |   |
| GetInventory           | Get the inventory managed by the widget  |  | UInventoryComponent*  The inventory managed by the widget |
| RefreshItem            | Refresh a specific item in the inventory | Id (FName) The ID of the item to refresh  Amount (int) The amount of the item  |   |
| RefreshInventory       | Refresh the entire inventory             |  |   |

#### 8.7.6 Blueprint Usage

You can use the InventoryWidget using Blueprints by adding one of the following nodes:

- Ultimate Starter Kit > Inventory > Load Inventory
- $\bullet \ Ultimate \ Starter \ Kit > Inventory > Update \ Preview$
- Ultimate Starter Kit > Inventory > Update Highlighted Index
- $\bullet \ Ultimate \ Starter \ Kit > Inventory > Select \ Item$
- Ultimate Starter Kit > Inventory > Get Inventory
- $\bullet \ Ultimate \ Starter \ Kit \! > \! Inventory \! > \! Refresh \ Item$
- $\bullet \ Ultimate \ Starter \ Kit > Inventory > Refresh \ Inventory \\$

#### 8.7.7 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your  ${\tt Build.cs}$  file:

```
PublicDependencyModuleNames.Add("USK");
```

The InventoryWidget can now be used in any of your C++ files:

```
#include "USK/Inventory/InventoryWidget.h"

void ATestActor::Test()
{
    // InventoryWidget is a pointer to the UInventoryWidget
    InventoryWidget->LoadInventory(InventoryComponent);
    InventoryWidget->UpdatePreview(Item);
    InventoryWidget->UpdateHighlightedIndex(Column, Row);
```

```
InventoryWidget->SelectItem(Id);
UInventoryComponent* Inventory = InventoryWidget->GetInventory();
InventoryWidget->RefreshItem(Id, Amount);
InventoryWidget->RefreshInventory();
}
```

# 9. Trackable Data

# 9.1 Overview

## 9.1.1 Introduction

A system that is used to easily manage different types of actor data

# 9.1.2 Trackable Data Component

Before you can manage the data, you need to create a Trackable Data Component and add it to the actor/character containing the data

# 9.1.3 Built-in data

The following data can automatically be managed without creating custom components:

- 1. Currency (using the Currency Component )
- 2. Stats (using the Stats Component)

# 9.2 Data

# 9.2.1 Introduction

All trackable data use the FTrackableData struct to specify the default values and behaviours

# 9.2.2 Properties

| Property        | Description  | Туре  | Default Value |
|-----------------|--|-------|---------------|
| InitialValue    | The initial value of the data  | float |               |
| EnforceMaxValue | Should we enforce a maximum value?                                       | bool  |               |
| MaxValue        | The maximum value of the data  | float | 100.0f        |
| AutoSave        | Should all value updates automatically be saved using the game instance? | bool  |               |
| AutoGenerate    | Should we automatically generate value every second?                     | bool  |               |
| GenerateAmount  | The amount of value to generate every second                             | float |               |
| GenerateDelay   | The delay before the value starts generating after losing value          | float |               |

# 9.3 Component

#### 9.3.1 Introduction

A component that is used to easily manage/track different types of actor data

## 9.3.2 Dependencies

The TrackableDataComponent relies on other components of this plugin to work:

- Logger: Used to log useful information to help you debug any issues you might experience
- Game Instance: Used to monitor for input device changes and handle saving/loading game data

#### 9.3.3 Data

The data to track is configured by adding items to the Data map. The component should be added to the actor/character containing the data

#### 9.3.4 API Reference

#### **Properties**

| Property | Description              | Туре                                     | Default Value |
|----------|--------------------------|--|---------------|
| Data     | The map of data to track | TMap <fname, ftrackabledata=""></fname,> |               |

#### **Events**

| Name           | Description   | Params  |
|----------------|---|---|
| OnValueZero    | Event used to notify other classes every time the data value reaches 0  | Name (FName) The name of the data item  |
| OnValueUpdated | Event used to notify other classes every time the data value is updated | Name (FName) The name of the data item  Value (FName) The current value of the data item                |
|                |   | ValuePercentage (FName)  The percentage of the current value compared to the max value of the data item |

#### **Functions**

| Name               | Description   | Params  | Return   |
|--------------------|---|---|--|
| GetValue           | Get the amount of the data                                    | Name (FName) The name of the data item                                      | float  The current amount of the data item                       |
| GetValuePercentage | Get the value of the data as a percentage of to the max value | Name (FName) The name of the data item                                      | float  The value of the data as a percentage of to the max value |
| Add                | Add an amount to the data                                     | Name (FName) The name of the data item  Amount (float) The amount to add    | float  The new amount of the data item                           |
| Remove             | Remove an amount from the data                                | Name (FName) The name of the data item  Amount (float) The amount to remove | float The new amount of the data item                            |

## 9.3.5 Blueprint Usage

 $You\ can\ use\ the\ {\tt TrackableDataComponent}\ using\ Blueprints\ by\ adding\ one\ of\ the\ following\ nodes:$ 

- Ultimate Starter Kit > Trackable Data > Get Value
- Ultimate Starter Kit > Trackable Data > Get Value Percentage
- Ultimate Starter Kit > Trackable Data > Add
- Ultimate Starter Kit > Trackable Data > Remove

## 9.3.6 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your  ${\tt Build.cs}\>$  file:

```
PublicDependencyModuleNames.Add("USK");
```

The  ${\tt TrackableDataComponent}$  can now be used in any of your C++ files:

```
#include "USK/Data/TrackableDataComponent.h"

void ATestActor::Test()
{
    // TrackableDataComponent is a pointer to the UTrackableDataComponent
    float Value = TrackableDataComponent->GetValue(Name);
    float ValuePercentage = TrackableDataComponent->GetValuePercentage(Name);
    float AddValue = TrackableDataComponent->Add(Name, Amount);
    float RemoveValue = TrackableDataComponent->Remove(Name, Amount);
}
```

# 10. Audio

# 10.1 Audio Overview

## 10.1.1 Introduction

A system used to manage the basic properties of audio files. It includes different sound classes, a sound mix and sound attenuation settings

# 10.1.2 Sound Classes

The audio system includes a few basic preconfigured sound classes:

| Class name            | Group   | Volume |
|-----------------------|---------|--------|
| USK_EffectsSoundClass | Effects | 1.0    |
| USK_MusicSoundClass   | Music   | 0.5    |
| USK_UISoundClass      | UI      | 1.0    |
| USK_VoiceSoundClass   | Voice   | 3.0    |

# 10.2 Audio Utils

#### 10.2.1 Introduction

The audio utils class is used to easily play sound effects

## 10.2.2 Dependencies

The AudioUtils relies on other components of this plugin to work:

• Logger: Used to log useful information to help you debug any issues you might experience

#### 10.2.3 API Reference

#### **Functions**

| Name              | Description   | Params   | Return |
|-------------------|---|--|--------|
| PlaySound2D       | Play a 2D sound                                       | WorldContext (UObject*) The top level object representing a map          |        |
|                   |   | SoundFX (USoundBase*) The USoundBase to play                             |        |
| PlayRandomSound2D | Play a random 2D sound                                | WorldContext (UObject*) The top level object representing a map          |        |
|                   |   | SoundFX (TArray) The array of USoundBase to select the random sound from |        |
| PlaySound         | Play a sound at the specified actor's location        | Actor (AActor*)  The actor where the sound will be played                |        |
|                   |   | SoundFX (USoundBase*) The USoundBase to play                             |        |
| PlayRandomSound   | Play a random sound at the specified actor's location | Actor (AActor*)  The actor where the sound will be played                |        |
|                   |   | SoundFX (TArray) The array of USoundBase to select the random sound from |        |

# 10.2.4 Blueprint Usage

You can use the  ${\tt AudioUtils}$  using Blueprints by adding one of the following nodes:

- Ultimate Starter Kit > Audio > Play Sound2D
- Ultimate Starter Kit > Audio > Play Random Sound2D
- Ultimate Starter Kit > Audio > Play Sound
- Ultimate Starter Kit > Audio > Play Random Sound

# 10.2.5 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your  ${\tt Build.cs}$  file:

```
PublicDependencyModuleNames.Add("USK");
```

The  ${\tt AudioUtils}$  can now be used in any of your C++ files:

```
#include "USK/Audio/AudioUtils.h"

void ATestActor::Test()
{
    UAudioUtils::PlaySound2D(WorldContext, SoundFX);
    UAudioUtils::PlayRandomSound2D(WorldContext, SoundFX);
    UAudioUtils::PlayRandomSound(Actor, SoundFX);
    UAudioUtils::PlayRandomSound(Actor, SoundFX);
}
```

# 10.3 Music Player

#### 10.3.1 Introduction

Actor responsible for playing, pausing and stopping music. It also allows you to adjust music volume

## 10.3.2 Dependencies

The inal relies on other components of this plugin to work:

• Logger: Used to log useful information to help you debug any issues you might experience

#### 10.3.3 Components

The inal uses the following components:

| Name        | Description  | Туре             |
|-------------|--|------------------|
| AudioPlayer | Actor responsible for playing, pausing and stopping music. It also allows you to adjust music volume | UAudioComponent* |

## 10.3.4 API Reference

#### **Properties**

| Property    | Description  | Туре | Default Value |
|-------------|--|------|---------------|
| PlayOnStart | Should the music automatically play when the actor is spawned? | bool | true          |

#### **Functions**

| Name      | Description                             | Params                                      | Return |
|-----------|---|---|--------|
| SetVolume | Adjust the playback volume of the music | Volume (float)  The new volume of the music |        |
| Play      | Play the music                          |   |        |
| Pause     | Pause the music                         |   |        |
| Stop      | Stop the music                          |   |        |

## 10.3.5 Blueprint Usage

You can use the inal using Blueprints by adding one of the following nodes:

- Ultimate Starter Kit > Audio > Set Volume
- Ultimate Starter Kit > Audio > Play
- Ultimate Starter Kit > Audio > Pause
- Ultimate Starter Kit > Audio > Stop

## 10.3.6 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your Build.cs file:

PublicDependencyModuleNames.Add("USK");

## The $\mbox{inal}$ can now be used in any of your C++ files:

```
#include "USK/Audio/MusicPlayer.h"

void ATestActor::Test()
{
    // inal is a pointer to the final
    inal->SetVolume(Volume);
    inal->Play();
    inal->Pause();
    inal->Stop();
}
```

# 11. 3D Platformer

# 11.1 Overview

# 11.1.1 Introduction

The plugin includes a basic 3D platformer character and animation template. This can easily be extended to add unique functionality

#### 11.2 Character

#### 11.2.1 Introduction

Base character that can be used for 3D platformer games

#### 11.2.2 Dependencies

The PlatformerCharacter relies on other components of this plugin to work:

- Logger: Used to log useful information to help you debug any issues you might experience
- Audio: Used to play sound effects either 2D or at a specified location

#### 11.2.3 Features

The following features are included in the 3D platformer character class:

- 1. **Double Jumping**: Additional jump with a different jump animation
- 2. Variable Jump Height: Adjust jump height based on how long the jump button is pressed
- 3. Coyote Time: Allow the character to jump for a short time after falling off the platform
- 4. Shadow Decal: A decal used as a shadow to indicate where the character will land
- 5. Adjustable Camera Distance: The camera automatically zooms in on the character while idle and zooms out as soon as the character starts moving
- 6. Jump & Land effects: Sound effects and particles when jumping and landing

All these features can be configured to meet your needs and can also be disabled

# 11.2.4 Components

The PlatformerCharacter uses the following components:

| Name               | Description   | Туре                 |
|--------------------|---|----------------------|
| SpringArmComponent | Base character that can be used for 3D platformer games | USpringArmComponent* |
| CameraComponent    | The camera used by the character                        | UCameraComponent*    |

# 11.2.5 API Reference

# Properties

| Property                      | Description  | Туре                                      | Default Value |
|-------------------------------|--|---|---------------|
| InputMappingContext           | The input mapping context used by the player                                       | UInputMappingContext*                     | nullptr       |
| MoveAction                    | The move input action  | UInputAction*                             | nullptr       |
| LookAroundAction              | The camera rotation input action   | UInputAction*                             | nullptr       |
| JumpAction                    | The jump input action  | UInputAction*                             | nullptr       |
| ShadowDecalClass              | The shadow decal class used to draw a shadow below the character while in the air  | TSubclassOf <ashadowdecal></ashadowdecal> |               |
| JumpSoundEffects              | An array of sound effects played when jumping                                      | TArray <usoundbase*></usoundbase*>        |               |
| JumpParticleFx                | The particle effects spawned when jumping  | UNiagaraSystem*                           | nullptr       |
| JumpParticleFxSpawnOffset     | The offset applied to the location of the jump particles when spawning             | FVector                                   |               |
| LandedSoundEffects            | An array of sound effects played when landing                                      | TArray <usoundbase*></usoundbase*>        |               |
| LandParticleFx                | The particle effects spawned when landing  | UNiagaraSystem*                           | nullptr       |
| LandParticleFxSpawnOffset     | The offset applied to the location of the land particles when spawning             | FVector                                   |               |
| VariableJumpHeight            | Does the character support variable jump height?                                   | bool                                      | true          |
| VariableJumpHeightMaxHoldTime | The amount of time to hold the jump button to reach the max height                 | float                                     | 0.3f          |
| JumpVelocity                  | The velocity applied to the character when jumping                                 | float                                     | 500.0f        |
| AirControl                    | The amount of lateral movement control available to the character while in the air | float                                     | 1000.0f       |
| FallingFriction               | The amount of friction to apply to lateral air movement when falling               | float                                     | 3.5f          |
| Gravity                       | The amount of gravity applied to the character                                     | float                                     | 2.0f          |
| CanDoubleJump                 | Can the character perform a double jump?   | bool                                      | true          |
| CanCoyoteJump                 | Does the character support coyote time when trying to jump?                        | bool                                      | true          |
| CoyoteJumpTime                | The amount of coyote time for the character  | float                                     | 0.375f        |
| CoyoteJumpVelocity            | The velocity applied to the character when performing a coyote jump                | float                                     | 700.0f        |
| BrakingFriction               | Friction coefficient applied when braking  | float                                     | 10.0f         |
| MaxAcceleration               | The rate of change of velocity   | float                                     | 2500.0f       |
| TargetArmLength               | Length of the spring arm component   | float                                     | 350.0f        |
| ArmLengthMultiplier           | The multiplier applied to the spring arm component when the character is moving    | float                                     | 0.4f          |
| CameraAdjustmentSpeed         | The speed used when adjusting the camera distance                                  | float                                     | 3.0f          |

# 11.2.6 Blueprint Usage

There is no additional functions exposed to Blueprints. Just create the character and add it to your level

# 11.3 Animation Instance

#### 11.3.1 Introduction

Base animation instance for a 3D platformer character

## 11.3.2 Dependencies

 $The \ {\tt PlatformerAnimationInstance} \ \ relies \ on \ other \ components \ of \ this \ plug in \ to \ work:$ 

• Logger: Used to log useful information to help you debug any issues you might experience

#### 11.3.3 API Reference

#### **Properties**

| Property            | Description  | Туре           | Default Value |
|---------------------|--|----------------|---------------|
| IdleAnimation       | The animation used when the character is in the idle state | UAnimSequence* | nullptr       |
| WalkAnimation       | The animation used when the character is walking           | UAnimSequence* | nullptr       |
| RunAnimation        | The animation used when the character is running           | UAnimSequence* | nullptr       |
| JumpAnimation       | The animation used when the character is jumping           | UAnimSequence* | nullptr       |
| DoubleJumpAnimation | The animation used when the character is double jumping    | UAnimSequence* | nullptr       |
| FallAnimation       | The animation used when the character is falling           | UAnimSequence* | nullptr       |
| LandAnimation       | The animation used when the character is landing           | UAnimSequence* | nullptr       |
| MovementSpeed       | The movement speed fo the character                        | float          |               |
| IsInAir             | Is the character currently in the air?                     | bool           |               |
| IsDoubleJumping     | Is the character double jumping?                           | bool           |               |

# 11.3.4 Blueprint Usage

You can use this template by creating your own animation blueprint and selecting <code>UPlatformerAnimationInstance</code> as the parent class. Set your animations and use this for your 3D platformer character

# 11.4 Shadow Decal

#### 11.4.1 Introduction

Decal used to draw a shadow beneath a character when the character is in the air

#### 11.4.2 Dependencies

The ShadowDecal relies on other components of this plugin to work:

• Logger: Used to log useful information to help you debug any issues you might experience

#### 11.4.3 API Reference

#### **Functions**

| Name       | Description                 | Params  | Return |
|------------|-----------------------------|---|--------|
| Initialize | Initialize the shadow decal | OwnerCharacter (ACharacter*) The character owning this shadow decal |        |

## 11.4.4 Blueprint Usage

You can use the ShadowDecal using Blueprints by adding one of the following nodes:

• Ultimate Starter Kit > Shadow Decal > Initialize

## 11.4.5 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your Build.cs file:

```
PublicDependencyModuleNames.Add("USK");
```

The  ${\tt ShadowDecal}$  can now be used in any of your C++ files:

```
#include "USK/Character/ShadowDecal.h"

void ATestActor::Test()
{
    // ShadowDecal is a pointer to the AShadowDecal
    ShadowDecal->Initialize(OwnerCharacter);
}
```

# 12. Items

# 12.1 Allowed Collector

# 12.1.1 Introduction

The types of actor(s) that can collect an item

# 12.1.2 Values

| Value                  | Description  |
|------------------------|--|
| AnyActor               | Any actor can collect the item                     |
| AnyPawn                | Any pawn can collect the item                      |
| AnyCharacter           | Any character can collect the item                 |
| AnyPlatformerCharacter | Any platformer character can collect the item      |
| PossessedPawn          | Only the possessed pawn can collect the item       |
| Custom                 | A custom array of actor types can collect the item |

# 12.2 Collectable Item

#### 12.2.1 Introduction

An item that can be collected by an actor

## 12.2.2 Dependencies

The  ${\tt CollectableItem}$  relies on other components of this plugin to work:

- Logger: Used to log useful information to help you debug any issues you might experience
- Audio: Used to play sound effects either 2D or at a specified location

#### 12.2.3 Collision

The item requires an actor to overlap with the item before it can be collected. Make sure you have some collider on the actor and that the intended collector can overlap with the item/collider

#### 12.2.4 API Reference

#### **Properties**

| Property                       | Description   | Туре   | Default Value                    |
|--------------------------------|---|--|----------------------------------|
| DestroyOnCollected             | Should the item be destroyed after it has been collected                    | bool   | true                             |
| AllowedCollector               | The type of actor that can collect the item                                 | EAllowedCollector                                    | EAllowedCollector::PossessedPawn |
| AllowedCollectorTypes          | The array of actor types that can collect the item                          | TArray <tsubclassof<aactor>&gt;</tsubclassof<aactor> |                                  |
| CollectedSoundEffects          | An array of sound effects played when collecting the item                   | TArray <usoundbase*></usoundbase*>                   |                                  |
| CollectedParticleFx            | The particle effects spawned when collecting the item                       | UNiagaraSystem*                                      | nullptr                          |
| CollectedParticleFxSpawnOffset | The offset applied to the location of the collected particles when spawning | FVector  |                                  |

#### **Functions**

| Name            | Description                        | Params  | Return |
|-----------------|------------------------------------|---|--------|
| CollectItem     | Collect the item                   | Collector (AActor*) A pointer to the actor that collected the item  |        |
| OnItemCollected | Called after the item is collected | Collector (AActor*)  A pointer to the actor that collected the item |        |

## 12.2.5 Blueprint Usage

You can use the  ${\tt CollectableItem}$  using Blueprints by adding one of the following nodes:

- Ultimate Starter Kit > Item > Collect Item
- Ultimate Starter Kit > Item > On Item Collected

## 12.2.6 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your  ${\tt Build.cs}$  file:

```
PublicDependencyModuleNames.Add("USK");
```

The CollectableItem can now be used in any of your C++ files:

```
#include "USK/Items/CollectableItem.h"

void ATestActor::Test()
{
    // CollectableItem is a pointer to the ACollectableItem
    CollectableItem=>CollectItem(Collector);
    CollectableItem=>OnItemCollected(Collector);
}
```

# 13. UI & Widgets

## 13.1 Collectable Item Icon

#### 13.1.1 Introduction

A widget used to display the collection state of an item by showing/hiding an image

#### 13.1.2 Dependencies

The  ${\tt CollectableItemIcon}$  relies on other components of this plugin to work:

• Logger: Used to log useful information to help you debug any issues you might experience

#### 13.1.3 Required Widgets

You need to add the following before you can compile the  ${\tt CollectableItemIcon}$  widget:

| Name | Description                                 | Туре    |  |
|------|---|---------|--|
| Icon | The Icon displayed if the item is collected | UImage* |  |

#### 13.1.4 API Reference

#### **Properties**

| Property      | Description  | Туре  | Default Value |
|---------------|--|-------|---------------|
| RequiredValue | The required value before the item is considered collected | float |               |

## **Functions**

| Name                  | Description   | Params  | Return |
|-----------------------|---|---|--------|
| UpdateState           | Update the collected state (and visibility) of the icon                                       | IsCollected (bool) Is the item collected?   |        |
| UpdateValue           | Update the value of the item and adjust the collected state if necessary                      | Value (float) The current value of the item   |        |
| MonitorTrackableValue | Monitor the trackable data and automatically update the icon state whenever the value changes | TrackableDataComponent (UTrackableDataComponent*) A reference to the TrackableDataComponent  DataName (FName) |        |
|                       |   | The name of the data item to monitor  |        |

# 13.1.5 Blueprint Usage

You can use the CollectableItemIcon using Blueprints by adding one of the following nodes:

- $\bullet$  Ultimate Starter Kit > UI > Update State
- Ultimate Starter Kit > UI > Update Value
- Ultimate Starter Kit > UI > Monitor Trackable Value

# 13.1.6 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your  ${\tt Build.cs}$  file:

```
PublicDependencyModuleNames.Add("USK");
```

The <code>CollectableItemIcon</code> can now be used in any of your  $C+\!\!\!+\!\!\!$  files:

```
#include "USK/Widgets/CollectableItemIcon.h"

void ATestActor::Test()
{
    // CollectableItemIcon is a pointer to the UCollectableItemIcon
    CollectableItemIcon->UpdateState(IsCollected);
    CollectableItemIcon->UpdateValue(Value);
    CollectableItemIcon->MonitorTrackableValue(TrackableDataComponent, DataName);
}
```

# 13.2 Credits

# 13.2.1 Credits Entry

## Introduction

An single credits entry displayed by the credits widget

## **Properties**

| Property            | Description   | Туре  | Default Value |
|---------------------|---|---|---------------|
| Title               | The title for the credits entry   | FText   |               |
| Text                | The text for the credits entry  | FText   |               |
| Duration            | The duration of the credits entry   | float   | 5.0f          |
| HorizontalAlignment | The horizontal alignment applied to the credits widget when displaying this entry | TEnumAsByte <ehorizontalalignment></ehorizontalalignment> | HAlign_Center |
| VerticalAlignment   | The vertical alignment applied to the credits widget when displaying this entry   | TEnumAsByte <everticalalignment></everticalalignment>     | VAlign_Center |

# 13.2.2 Credits Widget

#### Introduction

Widget used to display multiple animated credits entries using different alignment options and durations

#### **Dependencies**

The CreditsWidget relies on other components of this plugin to work:

• Logger: Used to log useful information to help you debug any issues you might experience

## **Required Widgets**

You need to add the following before you can compile the  ${\tt CreditsWidget}$  widget:

| Name      | Description  | Туре          |
|-----------|--|---------------|
| Root      | The root container of the widget                             | UPanelWidget* |
| Container | The container used to display the credits entries            | UPanelWidget* |
| Text      | The text block used to display the text of the credits entry | UTextBlock*   |

## **Optional Widgets**

You can add the following widgets to enable extra functionality:

| Name  | Description   | Туре        |
|-------|---|-------------|
| Title | The text block used to display the title of the credits entry | UTextBlock* |

### **Optional Animations**

You can add the following widgets to enable extra functionality:

| Name          | Description   |
|---------------|---|
| ShowAnimation | The animation played each time a new entry is shown |
| HideAnimation | The animation played at the end of each entry       |

#### **API Reference**

#### **PROPERTIES**

| Property            | Description   | Туре                                   | Default Value |
|---------------------|---|--|---------------|
| ShowAnimation       | The animation played each time a new entry is shown   | UWidgetAnimation*                      | nullptr       |
| HideAnimation       | The animation played at the end of each entry   | UWidgetAnimation*                      | nullptr       |
| AutoStart           | Should the credits automatically be started when the widget is constructed?                 | bool                                   | true          |
| RemoveOnCompletion  | Should the widget automatically be removed from the viewport when the credits are finished? | bool                                   | true          |
| StartDelay          | The delay in seconds before the first credits entry is shown after starting                 | float                                  | 1.0f          |
| DelayBetweenEntries | The delay in seconds between the previous hide animation and the next show animation        | float                                  | 3.0f          |
| Credits             | The array of credits entries to be displayed  | TArray <fcreditsentry></fcreditsentry> |               |

#### **EVENTS**

| Name                      | Description   | Params  |
|---------------------------|---|---|
| OnCreditsFinished         | Event used to notify other classes when the credits are finished      |   |
| OnCreditsNextEntryStarted | Event used to notify other classes every time a next entry is started | Name (int)  The index of the entry that was started |

#### **FUNCTIONS**

| Name  | Description               | Params | Return |
|-------|---------------------------|--------|--------|
| Start | Start showing the credits |        |        |

## **Blueprint Usage**

You can use the  ${\tt CreditsWidget}$  using Blueprints by adding one of the following nodes:

 $\bullet \ Ultimate \ Starter \ Kit > UI > Start$ 

# C++ Usage

Before you can use the plugin, you first need to enable the plugin in your Build.cs file:

```
PublicDependencyModuleNames.Add("USK");
```

The  ${\tt CreditsWidget}$  can now be used in any of your C++ files:

```
#include "USK/Widgets/CreditsWidget.h"

void ATestActor::Test()
{
    // CreditsWidget is a pointer to the UCreditsWidget
    CreditsWidget->Start();
}
```

## 13.3 FPS Counter

#### 13.3.1 Introduction

A widget used to display the current framerate

#### 13.3.2 Dependencies

The FpsCounter relies on other components of this plugin to work:

- Logger: Used to log useful information to help you debug any issues you might experience
- Game Instance: Used to monitor for input device changes and handle saving/loading game data

#### 13.3.3 Required Widgets

There is already a FpsCounter\_Implementation that you can use in your projects. But if you create your own instance of this widget, you need to add the following before you can compile:

| Name          | Description                                  | Туре        |
|---------------|--|-------------|
| FramerateText | The text block used to display the framerate | UTextBlock* |

#### 13.3.4 API Reference

#### **Properties**

| Property        | Description   | Туре         | Default Value        |
|-----------------|---|--------------|----------------------|
| UpdateDelay     | The delay in seconds between each update                            | float        | 0.125f               |
| HighFramerate   | A framerate that is considered high and will use the high color     | int          | 60                   |
| MediumFramerate | A framerate that is considered medium and will use the medium color | int          | 30                   |
| HighColor       | The color used to display high framerates                           | FLinearColor | FLinearColor::Green  |
| MediumColor     | The color used to display medium framerates                         | FLinearColor | FLinearColor::Yellow |
| LowColor        | The color used to display low framerates                            | FLinearColor | FLinearColor::Red    |

#### Functions

| Name             | Description                         | Params                                  | Return |
|------------------|-------------------------------------|---|--------|
| UpdateVisibility | Update the visibility of the widget | IsVisible (bool) Is the widget visible? |        |

## 13.3.5 Blueprint Usage

You can use the FpsCounter using Blueprints by adding one of the following nodes:

• Ultimate Starter Kit > UI > Update Visibility

# 13.3.6 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your Build.cs file:

PublicDependencyModuleNames.Add("USK");

## The FpsCounter can now be used in any of your C++ files:

```
#include "USK/Widgets/FpsCounter.h"

void ATestActor::Test()
{
    // FpsCounter is a pointer to the UFpsCounter
    FpsCounter->UpdateVisibility(IsVisible);
}
```

# 13.4 Input Indicator

#### 13.4.1 Introduction

A widget used to display input indicators based on the current input device and input action

#### 13.4.2 Dependencies

The  ${\tt InputIndicator}$  relies on other components of this plugin to work:

- Logger: Used to log useful information to help you debug any issues you might experience
- Game Instance: Used to monitor for input device changes and handle saving/loading game data

#### 13.4.3 Required Widgets

There is already a InputIndicator\_Implementation that you can use in your projects. But if you create your own instance of this widget, you need to add the following before you can compile:

| Name      | Description                                   | Туре            |
|-----------|---|-----------------|
| Container | The container used to display multiple images | UHorizontalBox* |

#### 13.4.4 API Reference

#### **Properties**

| Property                | Description  | Туре  | Default Value |
|-------------------------|--|---|---------------|
| InputIndicatorIconClass | The input indicator icon class                       | TSubclassOf <uinputindicatoricon></uinputindicatoricon> |               |
| Action                  | The input action displayed by widget                 | UInputAction*   | nullptr       |
| Size                    | The size of the image                                | float   | 50.0f         |
| Amount                  | The amount of images to display for the input action | int   | 1             |

#### **Functions**

| Name         | Description                                     | Params  | Return |
|--------------|---|---|--------|
| UpdateAction | Update the input action displayed by the widget | NewAction (UInputAction*) The new action            |        |
|              |   | NewAmount (int) The new amount of images to display |        |

### 13.4.5 Blueprint Usage

You can use the InputIndicator using Blueprints by adding one of the following nodes:

• Ultimate Starter Kit > UI > Update Action

#### 13.4.6 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your  ${\tt Build.cs}\,$  file:

PublicDependencyModuleNames.Add("USK");

## The InputIndicator can now be used in any of your C++ files:

```
#include "USK/Widgets/InputIndicator.h"

void ATestActor::Test()
{
    // InputIndicator is a pointer to the UInputIndicator
    InputIndicator->UpdateAction(NewAction, NewAmount);
}
```

# 13.5 Input Indicator Icon

#### 13.5.1 Introduction

A widget used to display a single input indicator image

#### 13.5.2 Dependencies

The  ${\tt InputIndicatorIcon}$  relies on other components of this plugin to work:

• Logger: Used to log useful information to help you debug any issues you might experience

#### 13.5.3 Required Widgets

There is already a InputIndicatorIcon\_Implementation that you can use in your projects. But if you create your own instance of this widget, you need to add the following before you can compile:

| Name      | Description                                     | Туре      |
|-----------|---|-----------|
| Container | The size box container used to resize the image | USizeBox* |
| Image     | The image used to display the input indicator   | UImage*   |

#### 13.5.4 API Reference

#### **Properties**

#### **Functions**

| Name       | Description     | Params                                    | Return |
|------------|-----------------|---|--------|
| UpdateIcon | Update the icon | <b>Size (float)</b> The size of the image |        |
|            |                 | Icon (UTexture2D*) The new icon           |        |

## 13.5.5 Blueprint Usage

You can use the  ${\tt InputIndicatorIcon}$  using Blueprints by adding one of the following nodes:

• Ultimate Starter Kit > UI > Update Icon

#### 13.5.6 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your  ${\tt Build.cs}$  file:

PublicDependencyModuleNames.Add("USK");

The InputIndicatorIcon can now be used in any of your C++ files:

```
#include "USK/Widgets/InputIndicatorIcon.h"

void ATestActor::Test()
{
    // InputIndicatorIcon is a pointer to the UInputIndicatorIcon
```

InputIndicatorIcon->UpdateIcon(Size, Icon);
}

# 13.6 Menu

#### 13.6.1 Introduction

A widget used to display menu items and handle navigation between the items

## 13.6.2 Dependencies

The Menu relies on other components of this plugin to work:

- Logger: Used to log useful information to help you debug any issues you might experience
- Game Instance: Used to monitor for input device changes and handle saving/loading game data
- Audio: Used to play sound effects either 2D or at a specified location

# 13.6.3 Optional Widgets

You can add the following widgets to enable extra functionality:

| Name            | Description   | Туре          |
|-----------------|---|---------------|
| ScrollContainer | Scroll container used for large menus with many items | UScrollBox*   |
| Container       | The container used to display the menu items          | UPanelWidget* |

#### 13.6.4 API Reference

#### **Properties**

| Property              | Description   | Туре                  | Default Value |
|-----------------------|---|-----------------------|---------------|
| AddInputBindingOnLoad | Should the input binding automatically be added as soon as the widget is loaded?                              | bool                  |               |
| PauseGameWhileVisible | Should the game automatically be paused/resumed based on the visibility of the menu?                          | bool                  |               |
| DisableWhilePaused    | Should the menu be disabled while the game is paused?   | bool                  |               |
| SelectedSFX           | The sound effect played when a menu item is selected  | USoundBase*           | nullptr       |
| BackSFX               | The sound effect played when trying to go back to a previous menu or closing the menu through the back button | USoundBase*           | nullptr       |
| InputMappingContext   | The input mapping context used to navigate the menu   | UInputMappingContext* | nullptr       |
| MenuUpInputAction     | The input action used to navigate up  | UInputAction*         | nullptr       |
| MenuDownInputAction   | The input action used to navigate down  | UInputAction*         | nullptr       |
| MenuLeftInputAction   | The input action used to navigate left  | UInputAction*         | nullptr       |
| MenuRightInputAction  | The input action used to navigate right   | UInputAction*         | nullptr       |
| MenuSelectInputAction | The input action used to select a menu item   | UInputAction*         | nullptr       |
| MenuBackInputAction   | The input action used to go back to a previous menu or close the menu   | UInputAction*         | nullptr       |

#### **Events**

| Name        | Description  | Params |
|-------------|--|--------|
| OnBackEvent | Event used to handle the back/close action of the menu |        |

#### **Functions**

| Name             | Description   | Params  | Return |
|------------------|---|---|--------|
| OnMenuUp         | Navigate up or increase the value                                 |   |        |
| OnMenuUpHold     | Increase the value while holding the menu up key                  |   |        |
| OnMenuDown       | Navigate down or decrease the value                               |   |        |
| OnMenuDownHold   | Decrease the value while holding the menu down key                |   |        |
| OnMenuLeft       | Navigate left or decrease the value                               |   |        |
| OnMenuLeftHold   | Decrease the value while holding the menu left key                |   |        |
| OnMenuRight      | Navigate right or increase the value                              |   |        |
| OnMenuRightHold  | Increase the value while holding the menu right key               |   |        |
| OnMenuSelected   | Select the current menu item                                      |   |        |
| OnMenuBack       | Go back to a previous menu or close the menu                      |   |        |
| RequestHighlight | Request to highlight a specific menu item                         | MenuItem (UMenuItem*) The menu item to highlight                          |        |
| RemoveHighlight  | Request to remove the highlighted state from a specific menu item | MenuItem (UMenuItem*)  The menu item to remove the highlighted state from |        |
| AddMenuItem      | Add a menu item to the container                                  | MenuItem (UMenuItem*) The menu item to add                                |        |

## 13.6.5 Blueprint Usage

You can use the Menu using Blueprints by adding one of the following nodes:

- Ultimate Starter Kit > UI > On Menu Up Hold
- Ultimate Starter Kit > UI > On Menu Down
- Ultimate Starter Kit > UI > On Menu Down Hold
- ullet Ultimate Starter Kit > UI > On Menu Left
- Ultimate Starter Kit > UI > On Menu Left Hold
- $\bullet$  Ultimate Starter Kit > UI > On Menu Right
- Ultimate Starter Kit > UI > On Menu Right Hold
- Ultimate Starter Kit > UI > On Menu Selected
- Ultimate Starter Kit > UI > On Menu Back
- Ultimate Starter Kit > UI > Request Highlight
- Ultimate Starter Kit > UI > Remove Highlight
- Ultimate Starter Kit > UI > Add Menu Item

# 13.6.6 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your  ${\tt Build.cs}$  file:

```
PublicDependencyModuleNames.Add("USK");
```

The Menu can now be used in any of your C++ files:

```
#include "USK/Widgets/Menu.h"

void ATestActor::Test()
{
    // Menu is a pointer to the UMenu
    Menu->OnMenuUp();
    Menu->OnMenuUpHold();
    Menu->OnMenuDown();
    Menu->OnMenuDown();
    Menu->OnMenuDownHold();
    Menu->OnMenuEeft();
    Menu->OnMenuEeft();
    Menu->OnMenuEeftlold();
    Menu->OnMenuRight();
    Menu->OnMenuRight();
    Menu->OnMenuSelected();
    Menu->OnMenuSelected();
    Menu->OnMenuSelected();
    Menu->RemoveHighlight (MenuItem);
    Menu->RemoveHighlight (MenuItem);
    Menu->RemoveHighlight (MenuItem);
}
```

# 13.7 Menu Item

# 13.7.1 Navigation

## Introduction

All the supported menu navigation types

## Values

| Value                 | Description                     |
|-----------------------|---------------------------------|
| Disabled              | No navigation allowed           |
| HighlightItem         | Highlight a different menu item |
| IncreaseDecreaseValue | Increase or decrease the value  |

# 13.7.2 Value Update Method

## Introduction

The method used to update the value of a menu item

## Values

| Value       | Description  |
|-------------|--|
| SinglePress | The value is only updated when the button is pressed |
| Hold        | The value is updated while the button is held down   |

# 13.7.3 Menu Item Widget

#### Introduction

A widget used to display a title, text and value in the form of a menu item

#### **Dependencies**

The MenuItem relies on other components of this plugin to work:

- Logger: Used to log useful information to help you debug any issues you might experience
- Game Instance: Used to monitor for input device changes and handle saving/loading game data
- Audio: Used to play sound effects either 2D or at a specified location

#### **Optional Widgets**

You can add the following widgets to enable extra functionality:

| Name                 | Description  | Туре        |
|----------------------|--|-------------|
| Title                | The TextBlock used to display the title of the menu item                           | UTextBlock* |
| NormalText           | The TextBlock used to display the text of the menu item while not highlighted      | UTextBlock* |
| HighlightedText      | The TextBlock used to display the text of the menu item while highlighted          | UTextBlock* |
| ValueText            | The TextBlock used to display the current value of the menu item                   | UTextBlock* |
| HighlightedValueText | The TextBlock used to display the current value of the menu item while highlighted | UTextBlock* |
| SelectButton         | The button used to select the menu item  | UButton*    |
| ValueSlider          | The slider used to display and update the current value of the menu item           | USlider*    |
| IncreaseValueButton  | The button used to increase the value of the menu item                             | UButton*    |
| DecreaseValueButton  | The button used to decrease the value of the menu item                             | UButton*    |
| BorderLeft           | The border displayed on the left of the menu item                                  | UImage*     |
| BorderRight          | The border displayed on the right of the menu item                                 | UImage*     |
| BorderBackground     | The background border display in the menu item                                     | UImage*     |
| ButtonLeft           | The button displayed on the left of the menu item                                  | UImage*     |
| ButtonRight          | The button displayed on the right of the menu item                                 | UImage*     |
| ButtonBackground     | The background button display in the menu item                                     | UImage*     |
| InputIndicator       | The background button display in the menu item                                     | UImage*     |

## **Optional Animations**

You can add the following widgets to enable extra functionality:

| Name                 | Description  |
|----------------------|--|
| HighlightedAnimation | The animation played when the menu item is highlighted |

## API Reference

PROPERTIES

| Property                   | Description   | Туре              | Default Value |
|----------------------------|---|-------------------|---------------|
| HighlightedAnimation       | The animation played when the menu item is highlighted                | UWidgetAnimation* | nullptr       |
| FocusByDefault             | Should the<br>menu item be<br>focused by<br>default?                  | bool              |               |
| HideOnConsoles             | Should the menu item be hidden on consoles?                           | bool              |               |
| TitleText                  | The title text<br>displayed in the<br>menu item                       | FText             |               |
| MenuItemText               | The text<br>displayed in the<br>menu item                             | FText             |               |
| HighlightedSFX             | The sound<br>effect played<br>when the menu<br>item is<br>highlighted | USoundBase*       | nullptr       |
| BorderNormalColor          | The color of<br>the border<br>when not<br>highlighted                 | FLinearColor      |               |
| BorderHighlightedColor     | The color of<br>the border<br>when<br>highlighted                     | FLinearColor      |               |
| BorderNormalImage          | The image of<br>the border<br>when not<br>highlighted                 | UTexture2D*       | nullptr       |
| BorderHighlightedImage     | The image of<br>the border<br>when<br>highlighted                     | UTexture2D*       | nullptr       |
| BorderLeftNormalImage      | The image of<br>the left border<br>when not<br>highlighted            | UTexture2D*       | nullptr       |
| BorderLeftHighlightedImage | The image of<br>the left border<br>when<br>highlighted                | UTexture2D*       | nullptr       |
| BorderRightNormalImage     | The image of the right border   | UTexture2D*       | nullptr       |

|                                 | when not<br>highlighted  |                            |   |
|---------------------------------|--|----------------------------|---|
| BorderRightHighlightedImage     | The image of<br>the right border<br>when<br>highlighted            | UTexture2D*                | nullptr                                 |
| BackgroundNormalColor           | The color of<br>the button<br>when not<br>highlighted              | FLinearColor               |   |
| BackgroundHighlightedColor      | The color of<br>the button<br>when<br>highlighted                  | FLinearColor               |   |
| BackgroundNormalImage           | The image of<br>the button<br>when not<br>highlighted              | UTexture2D*                | nullptr                                 |
| BackgroundHighlightedImage      | The image of<br>the button<br>when<br>highlighted                  | UTexture2D*                | nullptr                                 |
| BackgroundLeftNormalImage       | The image of<br>the left button<br>when not<br>highlighted         | UTexture2D*                | nullptr                                 |
| BackgroundLeftHighlightedImage  | The image of<br>the left button<br>when<br>highlighted             | UTexture2D*                | nullptr                                 |
| BackgroundRightNormalImage      | The image of<br>the right button<br>when not<br>highlighted        | UTexture2D*                | nullptr                                 |
| BackgroundRightHighlightedImage | The image of<br>the right button<br>when<br>highlighted            | UTexture2D*                | nullptr                                 |
| ValueUpdateMethod               | The method used to update the value of the menu item               | EMenuItemValueUpdateMethod | EMenuItemValueUpdateMethod::SinglePress |
| IncrementSinglePress            | The increment used when updating the value when the key is pressed | float                      | 1.0f                                    |
| IncrementHold                   | The increment used when updating the value when the                | float                      | 0.15f                                   |

|                                    | key is held<br>down   |                       |                         |
|------------------------------------|---|-----------------------|-------------------------|
| SettingsItemType                   | The type of setting item managed by this menu item (changing this will overwrite other settings)          | ESettingsItemType     | ESettingsItemType::None |
| AutoSaveSettingsOnValueChanged     | Should the settings managed by this menu item automatically be saved when the value is changed?           | bool                  | true                    |
| AutoSaveSettingsOnHighlightRemoved | Should the settings managed by this menu item automatically be saved when the highlight state is removed? | bool                  | true                    |
| AutoSaveSettingsOnSelected         | Should the settings managed by this menu item automatically be saved when the menu item is selected?      | bool                  | true                    |
| InputDevice                        | The input device associated with the action to rebind   | EInputDevice          | EInputDevice::Unknown   |
| InputMappingContext                | The input mapping context containing the action to rebind   | UInputMappingContext* | nullptr                 |
| InputAction                        | The input action to rebind  | UInputAction*         | nullptr                 |
| MappableName                       | The player<br>mappable name<br>for the action to<br>rebind  | FName                 |                         |
| ShowValueSlider                    | Should the value slider be  | bool                  | false                   |

|                      | shown for this menu item?  |                             |                                |
|----------------------|--|-----------------------------|--------------------------------|
| ShowValueButtons     | Should the increase/ decrease value buttons be shown for this menu item?         | bool                        | false                          |
| ValueMapping         | A mapping of possible values to text   | TMap <int, ftext=""></int,> |                                |
| DefaultValue         | The default value of the menu item   | int                         | 100                            |
| MinValue             | The minimum value of the menu item   | int                         | 0                              |
| MaxValue             | The maximum value of the menu item   | int                         | 100                            |
| AllowSelection       | Can the menu item be selected?   | bool                        | true                           |
| VerticalNavigation   | The type of navigation used by the menu item when pressing the up or down key    | EMenuNavigation             | EMenuNavigation::HighlightItem |
| MenuItemUp           | The menu item highlighted when the up key is pressed                             | UMenuItem*                  | nullptr                        |
| MenuItemDown         | The menu item<br>highlighted<br>when the down<br>key is pressed                  | UMenuItem*                  | nullptr                        |
| HorizontalNavigation | The type of navigation used by the menu item when pressing the left or right key | EMenuNavigation             | EMenuNavigation::HighlightItem |
| MenuItemLeft         | The menu item<br>highlighted<br>when the left<br>key is pressed                  | UMenuItem*                  | nullptr                        |
| MenuItemRight        | The menu item<br>highlighted<br>when the right<br>key is pressed                 | UMenultem*                  | nullptr                        |

| Menu | A reference to              | UMenu* | nullptr |
|------|-----------------------------|--------|---------|
|      | the menu that contains this |        |         |
|      | menu item                   |        |         |

#### EVENTS

| Name                  | Description  | Params  |
|-----------------------|--|---|
| OnSelected            | Event used to notify other classes that the menu item was selected                         |   |
| OnSelectedInContainer | Event used to notify other classes that a specific menu item in the container was selected | Index (int)  The index of the menu item that was selected |
| OnHighlighted         | Event used to notify other classes that the menu item was highlighted                      |   |
| OnHighlightRemoved    | Event used to notify other classes that the menu item's highlighted state was removed      |   |
| OnValueChanged        | Event used to notify other classes that the menu item's value was updated                  | Value (int) The new value of the menu item                |

#### **FUNCTIONS**

| Name                 | Description   | Params  | Return   |
|----------------------|---|---|--|
| SetText              | Set the text displayed in the menu item                                   | Text (FText&)  The new text displayed in the menu item  |  |
| SetTitle             | Set the title displayed in the menu item                                  | Text (FText&)  The new title displayed in the menu item   |  |
| SetHighlightedState  | Set the highlighted state of the menu item                                | IsHighlighted (bool) Is the menu item highlighted?  PlayHighlightedAnimation (bool) Should the highlighted animation be played?  PlayHighlightedSound (bool) Should the highlighted sound effect be played? |  |
| IsHighlighted        | Check if the menu item is highlighted                                     |   | bool  A boolean value indicating if the menu item is highlighted             |
| GetValue             | Get the current value of the menu item                                    |   | int The current value of the menu item                                       |
| UpdateValue          | Update the value of the menu item   | Increment (float)  The amount added to the current value of the menu item   |  |
| SelectItem           | Select the menu item  |   |  |
| SaveSettings         | Save the settings managed by this menu item                               |   |  |
| ApplySettings        | Apply the settings managed by this menu item                              |   |  |
| GetInputActionKey    | Get the key used by the specified input action                            |   | <b>FKey</b> The key used by the specified input action                       |
| OnMenuBack           | Called when trying to go back in the menu                                 |   | bool  A boolean value indicating if the back event was handled               |
| AnyKeyPressed        | Called after any key is pressed by<br>the player (used to remap controls) | Key (FKey) The key pressed by the player  |  |
| ApplyKeyBinding      | Apply the key binding for the input action                                |   |  |
| IsWaitingForKeyPress | Is the menu item waiting for a key press?                                 |   | bool  A boolean value indicating if the menu item is waiting for a key press |

#### **Blueprint Usage**

You can use the  ${\tt MenuItem}$  using Blueprints by adding one of the following nodes:

- Ultimate Starter Kit > UI > Set Text
- Ultimate Starter Kit > UI > Set Title
- Ultimate Starter Kit > UI > Set Highlighted State
- Ultimate Starter Kit > UI > Is Highlighted
- Ultimate Starter Kit > UI > Get Value
- Ultimate Starter Kit > UI > Update Value
- Ultimate Starter Kit > UI > Select Item
- Ultimate Starter Kit > UI > Save Settings
- Ultimate Starter Kit > UI > Apply Settings
- Ultimate Starter Kit > UI > Get Input Action Key
- Ultimate Starter Kit > UI > On Menu Back
- Ultimate Starter Kit > UI > Any Key Pressed
- Ultimate Starter Kit > UI > Apply Key Binding
- Ultimate Starter Kit > UI > Is Waiting For Key Press

#### C++ Usage

Before you can use the plugin, you first need to enable the plugin in your Build.cs file:

```
PublicDependencyModuleNames.Add("USK");
```

The  ${\tt MenuItem}$  can now be used in any of your C++ files:

```
#include "USK/Widgets/MenuItem.h"

void ATestActor::Test()
{
    // MenuItem is a pointer to the UMenuItem
    MenuItem->SetText(Text);
    MenuItem->SetTatle(Text);
    MenuItem->SetTitle(Text);
    MenuItem->SetTitle(Text);
    MenuItem->SetTitle(Text);
    MenuItem->SetTitle(Text);
    MenuItem->SetTitle(Text);
    MenuItem->SetTitle(Text);
    MenuItem->IsHighlightedAlue = MenuItem->IsHighlightedAnimation, PlayHighlightedSound);
    bool IsHighlightedValue = MenuItem->IsHighlighted();
    int Value = MenuItem->GetValue();
    MenuItem->SaveSettings();
    MenuItem->SaveSettings();
    MenuItem->ApplySettings();
    MenuItem->ApplySettings();
    bool OnMenuBackValue = MenuItem->GetInputActionKey();
    bool OnMenuBackValue = MenuItem->OnMenuBack();
    MenuItem->ApplyKeyPressValue = MenuItem->IsWaitingForKeyPress();
}
```

# 14. Settings

## 14.1 Data

## 14.1.1 Introduction

The settings data that is saved/loaded

## 14.1.2 API Reference

## Properties

| Property                            | Description  | Туре  | Default Value |
|-------------------------------------|--|-------|---------------|
| AudioMasterModified                 | Was the master audio volume modified?              | bool  |               |
| AudioMaster                         | The master audio volume                            | float |               |
| AudioMusicModified                  | Was the music volume modified?                     | bool  |               |
| AudioMusic                          | The music volume                                   | float |               |
| AudioEffectsModified                | Was the effects volume modified?                   | bool  |               |
| AudioEffects                        | The effects volume                                 | float |               |
| AudioUiModified                     | Was the UI volume modified?                        | bool  |               |
| AudioUi                             | The UI volume                                      | float |               |
| AudioVoiceModified                  | Was the voice volume modified?                     | bool  |               |
| AudioVoice                          | The voice volume                                   | float |               |
| GraphicsResolutionX                 | The X value of the saved resolution                | int   |               |
| GraphicsResolutionY                 | The Y value of the saved resolution                | int   |               |
| GraphicsFullscreenModified          | Was the graphics fullscreen setting modified?      | bool  |               |
| GraphicsFullscreen                  | The graphics fullscreen value                      | bool  |               |
| GraphicsViewDistanceModified        | Was the graphics view distance setting modified?   | bool  |               |
| GraphicsViewDistance                | The graphics view distance value                   | int   |               |
| GraphicsAntiAliasingModified        | Was the graphics anti-aliasing setting modified?   | bool  |               |
| GraphicsAntiAliasing                | The graphics anti-aliasing value                   | int   |               |
| GraphicsPostProcessingModified      | Was the graphics post processing setting modified? | bool  |               |
| GraphicsPostProcessing              | The graphics post processing value                 | int   |               |
| GraphicsShadowQualityModified       | Was the graphics shadow quality setting modified?  | bool  |               |
| GraphicsShadowQuality               | The graphics shadow quality value                  | int   |               |
| GraphicsTextureQualityModified      | Was the graphics texture quality setting modified? | bool  |               |
| GraphicsTextureQuality              | The graphics texture quality value                 | int   |               |
| GraphicsVisualEffectsModified       | Was the graphics visual effects setting modified?  | bool  |               |
| GraphicsVisualEffects               | The graphics visual effects value                  | int   |               |
| GraphicsShadingQualityModified      | Was the graphics shading quality setting modified? | bool  |               |
| GraphicsShadingQuality              | The graphics shading quality value                 | int   |               |
| GraphicsVsyncModified               | Was the graphics vsync setting modified?           | bool  |               |
| GraphicsVsync                       | The graphics vsync value                           | bool  |               |
| GraphicsFpsIndicatorModified        | Was the graphics FPS indicator setting modified?   | bool  |               |
| GraphicsFpsIndicator                | The graphics FPS indicator value                   | bool  |               |
| AccessibilityColorBlindMode         | The color blind mode                               | int   |               |
| AccessibilityColorBlindModeSeverity | The severity of the color blind mode               | float | 100.0f        |

| KeyBindings A map of all key bindings changed by the player TMap <fname, fkey=""></fname,> | ayer TMap <fname, fkey=""></fname,> | A map of all key bindings changed by the player | KeyBindings |
|--|-------------------------------------|---|-------------|
|--|-------------------------------------|---|-------------|

# 14.2 Config

## 14.2.1 Introduction

The configuration used for managing settings

## 14.2.2 API Reference

## Properties

| Property                  | Description  | Туре  | Default Value                        |
|---------------------------|--|---|--------------------------------------|
| AudioMasterImplementation | The implementation for the audio master settings item            | TSubclassOf <usettingsitem></usettingsitem> | USettingsItemAudioMaster::StaticClas |
| AudioMasterSoundMix       | The sound mix<br>used to manage<br>all sound<br>classes          | USoundMix*                                  | nullptr                              |
| AudioMasterText           | The text<br>displayed in<br>the master<br>audio settings<br>item | FText                                       |                                      |
| udioMasterMin             | The minimum value for the master audio settings item             | float                                       | 0.0f                                 |
| AudioMasterMax            | The maximum value for the master audio settings item             | float                                       | 100.0f                               |
| AudioMasterDefault        | The default value for the master audio settings item             | float                                       | 100.0f                               |
| AudioMusicImplementation  | The implementation for the audio music settings item             | TSubclassOf <usettingsitem></usettingsitem> | USettingsItemAudioMusic::StaticClas  |
| AudioMusicSoundClass      | The sound class used by all music                                | USoundClass*                                | nullptr                              |
| AudioMusicText            | The text<br>displayed in<br>the music<br>audio settings<br>item  | FText                                       |                                      |
| AudioMusicMin             | The minimum value for the music audio settings item              | float                                       | 0.0f                                 |
| AudioMusicMax             | The maximum value for the music audio settings item              | float                                       | 100.0f                               |
| AudioMusicDefault         | The default value for the  | float                                       | 100.0f                               |

|                            | music audio<br>settings item                                      |   |                                       |
|----------------------------|---|---|---------------------------------------|
| AudioEffectsImplementation | The implementation for the audio effects settings item            | TSubclassOf <usettingsitem></usettingsitem> | USettingsItemAudioEffects::StaticClas |
| AudioEffectsSoundClass     | The sound class used by all effects                               | USoundClass*                                | nullptr                               |
| AudioEffectsText           | The text<br>displayed in<br>the effects<br>audio settings<br>item | FText                                       |                                       |
| AudioEffectsMin            | The minimum value for the effects audio settings item             | float                                       | 0.0f                                  |
| AudioEffectsMax            | The maximum value for the effects audio settings item             | float                                       | 100.0f                                |
| AudioEffectsDefault        | The default<br>value for the<br>effects audio<br>settings item    | float                                       | 100.0f                                |
| AudioUiImplementation      | The implementation for the audio UI settings item                 | TSubclassOf <usettingsitem></usettingsitem> | USettingsItemAudioUi::StaticClas      |
| AudioUiSoundClass          | The sound class used by all UI                                    | USoundClass*                                | nullptr                               |
| AudioUiText                | The text<br>displayed in<br>the UI audio<br>settings item         | FText                                       |                                       |
| AudioUiMin                 | The minimum value for the UI audio settings item                  | float                                       | 0.0f                                  |
| AudioUiMax                 | The maximum value for the UI audio settings item                  | float                                       | 100.0f                                |
| AudioUiDefault             | The default<br>value for the<br>UI audio<br>settings item         | float                                       | 100.0f                                |

| The properties of the ranks   The second class settings from the properties of the ranks   The second class settings from the properties of the second part of the properties of the propertie   |                                  |   |   |   |
|--|----------------------------------|---|---|---|
| all voice  The text displayed in the core audio settings from  Audio Voice Pext  Audio Voice Max  The minimum value for the voice audio settings from  Audio Voice Max  The minimum value for the voice audio settings from  Audio Voice Max  The maximum value for the voice audio settings from  Audio Voice Default  The default voice audio settings from  Audio Voice Default  The default voice audio settings from  The propriet of the voice audio settings from  The implementation for the graphics resolution settings from  Graphics Resolution Implementation  The text displayed in the graphics resolution settings from  Graphics Full Surveen Implementation  The implementation for the graphics resolution settings from  Graphics Full Surveen Implementation  The implementation for the graphics resolution settings from  Graphics Full Surveen Implementation  The implementation for the graphics from  Graphics Full Surveen Implementation  The implementation for the graphics from  Graphics Full Surveen Implementation  The implementation for the graphics from  Graphics Full Surveen Implementation  The institute Implementation  Full Surveen Implementation  Graphics Full Surveen Implementation  Graphics Full Surveen Implementation  Graphics Full Surveen Implementation  The institute Implementation  The institute Implementation  The institute Implementation  The institute Implementation  The institut | AudioVoiceImplementation         | implementation<br>for the audio<br>voice settings | TSubclassOf <usettingsitem></usettingsitem> | USettingsItemAudioVoice::StaticClas         |
| displayed in the vote addio sertings item  Audio VoiceMin  The minimum value for the vote audio settings item  Audio VoiceMax  The maximum value for the vote audio settings item  Audio VoiceDefault  The default value for the voice audio settings item  Audio VoiceDefault  The default value for the voice audio settings item  GraphicsResolutionImplementation  The default value for the voice audio settings item  GraphicsResolutionImplementation  The implementation for the graphics resolution  GraphicsResolutionText  The text displayed in the graphics resolution  GraphicsPulsereentinplementation  The implementation  GraphicsPulsereentinplementation  The implementation  GraphicsPulsereentinplementation  The text displayed in the graphics fullereen settings item  The text displayed in the graphics fullereen settings item  GraphicsPulsereentinplementation  The text displayed in the graphics fullereen settings item  The text displayed in the graphics fullereen settings item  Firext  GraphicsPulsereentinabledText  The text displayed when fullereen settings item  Firext  Firext  Firext  | AudioVoiceSoundClass             | class used by                                     | USoundClass*                                | nullptr                                     |
| Value for the voice audio settings item  | AudioVoiceText                   | displayed in the voice audio                      | FText                                       |   |
| value for the voice audio settings item  AudioVoiceDefault  The default value for the voice audio settings item  GraphicsResolutionImplementation  The implementation for the graphics resolution settings item  GraphicsResolutionText  The text displayed in the graphics resolution settings item  GraphicsFullscreenImplementation  The implementation  Treating item  TsubclassOf-UsettingsItem>  UsettingsItemGraphicsResolution::StaticClas  The text displayed in the graphics resolution settings item  TsubclassOf-UsettingsItem>  UsettingsItemStatiscreen::StaticClas  TreatingsItemStatiscreen::StaticClas  TreatingsItemStatiscreen::StaticClas  The text displayed in the graphics fullscreen settings item  GraphicsFullscreenText  The text displayed in the graphics fullscreen settings item  GraphicsFullscreenEnabledText  The text displayed when fullscreen is cambled  The text figsplayed when fullscreen is cambled  The text Frext  | AudioVoiceMin                    | value for the voice audio                         | float                                       | 0.0f  |
| value for the voice audio settings item  GraphicsResolutionImplementation  The implementation for the graphics resolution settings item  GraphicsResolutionText  The text displayed in the graphics resolution settings item  GraphicsFullscreenImplementation  GraphicsFullscreenText  The text displayed in the graphics resolution settings item  The implementation for the graphics fullscreen settings item  GraphicsFullscreenText  The text displayed in the graphics fullscreen settings item  GraphicsFullscreenText  The text displayed in the graphics fullscreen settings item  GraphicsFullscreenEnabledText  The text displayed when fullscreen settings item  GraphicsFullscreenEnabledText  The text displayed when fullscreen is enabled  GraphicsFullscreenDisabledText  The text fisplayed when fullscreen is enabled  | AudioVoiceMax                    | value for the voice audio                         | float                                       | 100.0f                                      |
| implementation for the graphics resolution  GraphicsResolutionText  The text displayed in the graphics resolution settings item  GraphicsFullscreenImplementation  GraphicsFullscreenText  The text displayed in the graphics fullscreen settings item  TSubclassOf <usettingsitem>  USettingsItemGraphicsFullscreen::StaticClas  TSubclassOf<usettingsitem>  Frext  TSubclassOf<usettingsitem>  Frext  Frext  GraphicsFullscreenText  The text displayed in the graphics fullscreen settings item  GraphicsFullscreenEnabledText  The text displayed when fullscreen is enabled  GraphicsFullscreenDisabledText  The text Frext</usettingsitem></usettingsitem></usettingsitem>   | AudioVoiceDefault                | value for the voice audio                         | float                                       | 100.0f                                      |
| displayed in the graphics resolution settings item  GraphicsFullscreenImplementation  GraphicsFullscreenText  GraphicsFullscreenText  The text displayed in the graphics fullscreen settings item  GraphicsFullscreenEnabledText  The text displayed in the graphics fullscreen settings item  GraphicsFullscreenEnabledText  The text displayed when fullscreen is enabled  GraphicsFullscreenDisabledText  The text FText  | GraphicsResolutionImplementation | implementation<br>for the graphics<br>resolution  | TSubclassOf <usettingsitem></usettingsitem> | USettingsItemGraphicsResolution::StaticClas |
| implementation for the graphics fullscreen settings item  GraphicsFullscreenText  The text displayed in the graphics fullscreen settings item  GraphicsFullscreenEnabledText  The text displayed when fullscreen is enabled  GraphicsFullscreenDisabledText  The text   | GraphicsResolutionText           | displayed in<br>the graphics<br>resolution        | FText                                       |   |
| displayed in the graphics fullscreen settings item  GraphicsFullscreenEnabledText  The text displayed when fullscreen is enabled  GraphicsFullscreenDisabledText  The text FText   | GraphicsFullscreenImplementation | implementation<br>for the graphics<br>fullscreen  | TSubclassOf <usettingsitem></usettingsitem> | USettingsItemGraphicsFullscreen::StaticClas |
| displayed when fullscreen is enabled  GraphicsFullscreenDisabledText  The text  FText  | GraphicsFullscreenText           | displayed in<br>the graphics<br>fullscreen        | FText                                       |   |
|  | GraphicsFullscreenEnabledText    | displayed when fullscreen is                      | FText                                       |   |
|  | GraphicsFullscreenDisabledText   |   | FText                                       |   |

|  | fullscreen is disabled  |   |   |
|--|---|---|---|
| GraphicsFullscreenDefault              | The default<br>value of the<br>fullscreen<br>setting  | bool  | true  |
| GraphicsViewDistanceImplementation     | The implementation for the graphics view distance settings item                             | TSubclassOf <usettingsitem></usettingsitem> | USettingsItemGraphicsViewDistance::StaticClas |
| GraphicsViewDistanceText               | The text<br>displayed in<br>the graphics<br>view distance<br>settings item                  | FText                                       |   |
| GraphicsViewDistanceNearValueText      | The text<br>displayed when<br>the near value<br>is used for the<br>view distance<br>setting | FText                                       |   |
| GraphicsViewDistanceMediumValueText    | The text displayed when the medium value is used for the view distance setting              | FText                                       |   |
| GraphicsViewDistanceFarValueText       | The text<br>displayed when<br>the far value is<br>used for the<br>view distance<br>setting  | FText                                       |   |
| GraphicsViewDistanceEpicValueText      | The text<br>displayed when<br>the epic value<br>is used for the<br>view distance<br>setting | FText                                       |   |
| GraphicsViewDistanceCinematicValueText | The text displayed when the cinematic value is used for the view distance setting           | FText                                       |   |
| GraphicsViewDistanceDefault            | The default<br>value of the<br>view distance<br>setting                                     | int   | 2   |
| GraphicsAntiAliasingImplementation     | The implementation for the graphics   | TSubclassOf <usettingsitem></usettingsitem> | USettingsItemGraphicsAntiAliasing::StaticClas |

|  | anti-aliasing settings item   |   |   |
|--|---|---|---|
| GraphicsAntiAliasingText               | The text<br>displayed in<br>the graphics<br>anti-aliasing<br>settings item                  | FText                                       |   |
| GraphicsAntiAliasingLowValueText       | The text<br>displayed when<br>the low value<br>is used for the<br>anti-aliasing<br>setting  | FText                                       |   |
| GraphicsAntiAliasingMediumValueText    | The text displayed when the medium value is used for the anti- aliasing setting             | FText                                       |   |
| GraphicsAntiAliasingHighValueText      | The text<br>displayed when<br>the high value<br>is used for the<br>anti-aliasing<br>setting | FText                                       |   |
| GraphicsAntiAliasingEpicValueText      | The text<br>displayed when<br>the epic value<br>is used for the<br>anti-aliasing<br>setting | FText                                       |   |
| GraphicsAntiAliasingCinematicValueText | The text displayed when the cinematic value is used for the anti- aliasing setting          | FText                                       |   |
| GraphicsAntiAliasingDefault            | The default<br>value of the<br>anti-aliasing<br>setting                                     | int   | 2   |
| GraphicsPostProcessingImplementation   | The implementation for the graphics post processing settings item                           | TSubclassOf <usettingsitem></usettingsitem> | USettingsItemGraphicsPostProcessing::StaticClas |
| GraphicsPostProcessingText             | The text<br>displayed in<br>the graphics<br>post processing<br>settings item                | FText                                       |   |
| GraphicsPostProcessingLowValueText     | The text displayed when   | FText                                       |   |

|  | the low value<br>is used for the<br>post processing<br>setting                                |   |  |
|--|---|---|--|
| GraphicsPostProcessingMediumValueText    | The text displayed when the medium value is used for the post processing setting              | FText                                       |  |
| GraphicsPostProcessingHighValueText      | The text<br>displayed when<br>the high value<br>is used for the<br>post processing<br>setting | FText                                       |  |
| GraphicsPostProcessingEpicValueText      | The text<br>displayed when<br>the epic value<br>is used for the<br>post processing<br>setting | FText                                       |  |
| GraphicsPostProcessingCinematicValueText | The text displayed when the cinematic value is used for the post processing setting           | FText                                       |  |
| GraphicsPostProcessingDefault            | The default<br>value of the<br>post processing<br>setting                                     | int   | 2  |
| GraphicsShadowQualityImplementation      | The implementation for the graphics shadow quality settings item                              | TSubclassOf <usettingsitem></usettingsitem> | USettingsItemGraphicsShadowQuality::StaticClas |
| GraphicsShadowQualityText                | The text displayed in the graphics shadow quality settings item                               | FText                                       |  |
| GraphicsShadowQualityLowValueText        | The text<br>displayed when<br>the low value<br>is used for the<br>shadow quality<br>setting   | FText                                       |  |
| GraphicsShadowQualityMediumValueText     | The text<br>displayed when<br>the medium  | FText                                       |  |

|   | value is used<br>for the shadow<br>quality setting  |   |  |
|---|---|---|--|
| GraphicsShadowQualityHighValueText      | The text<br>displayed when<br>the high value<br>is used for the<br>shadow quality<br>setting      | FText                                       |  |
| GraphicsShadowQualityEpicValueText      | The text<br>displayed when<br>the epic value<br>is used for the<br>shadow quality<br>setting      | FText                                       |  |
| GraphicsShadowQualityCinematicValueText | The text<br>displayed when<br>the cinematic<br>value is used<br>for the shadow<br>quality setting | FText                                       |  |
| GraphicsShadowQualityDefault            | The default<br>value of the<br>shadow quality<br>setting  | int   | 2  |
| GraphicsTextureQualityImplementation    | The implementation for the graphics texture quality settings item                                 | TSubclassOf <usettingsitem></usettingsitem> | US ettings Item Graphics Texture Quality:: Static Classes and the state of the st |
| GraphicsTextureQualityText              | The text<br>displayed in<br>the graphics<br>texture quality<br>settings item                      | FText                                       |  |
| GraphicsTextureQualityLowValueText      | The text<br>displayed when<br>the low value<br>is used for the<br>texture quality<br>setting      | FText                                       |  |
| GraphicsTextureQualityMediumValueText   | The text displayed when the medium value is used for the texture quality setting                  | FText                                       |  |
| GraphicsTextureQualityHighValueText     | The text<br>displayed when<br>the high value<br>is used for the<br>texture quality<br>setting     | FText                                       |  |

| GraphicsTextureQualityEpicValueText      | The text<br>displayed when<br>the epic value<br>is used for the<br>texture quality<br>setting      | FText                                       |  |
|--|--|---|--|
| GraphicsTextureQualityCinematicValueText | The text<br>displayed when<br>the cinematic<br>value is used<br>for the texture<br>quality setting | FText                                       |  |
| GraphicsTextureQualityDefault            | The default value of the texture quality setting   | int   | 2  |
| GraphicsVisualEffectsImplementation      | The implementation for the graphics visual effects settings item                                   | TSubclassOf <usettingsitem></usettingsitem> | USettingsItemGraphicsVisualEffects::StaticClas |
| GraphicsVisualEffectsText                | The text<br>displayed in<br>the graphics<br>visual effects<br>settings item                        | FText                                       |  |
| GraphicsVisualEffectsLowValueText        | The text<br>displayed when<br>the low value<br>is used for the<br>visual effects<br>setting        | FText                                       |  |
| GraphicsVisualEffectsMediumValueText     | The text displayed when the medium value is used for the visual effects setting                    | FText                                       |  |
| GraphicsVisualEffectsHighValueText       | The text<br>displayed when<br>the high value<br>is used for the<br>visual effects<br>setting       | FText                                       |  |
| GraphicsVisualEffectsEpicValueText       | The text displayed when the epic value is used for the visual effects setting                      | FText                                       |  |
| GraphicsVisualEffectsCinematicValueText  | The text<br>displayed when<br>the cinematic  | FText                                       |  |

|  | value is used<br>for the visual<br>effects setting   |   |  |
|--|--|---|--|
| GraphicsVisualEffectsDefault             | The default<br>value of the<br>visual effects<br>setting   | int   | 2  |
| GraphicsShadingQualityImplementation     | The implementation for the graphics shading quality settings item                                  | TSubclassOf <usettingsitem></usettingsitem> | US ettings I tem Graphics Shading Quality :: Static Classical Shading Shadin |
| GraphicsShadingQualityText               | The text<br>displayed in<br>the graphics<br>shading quality<br>settings item                       | FText                                       |  |
| GraphicsShadingQualityLowValueText       | The text<br>displayed when<br>the low value<br>is used for the<br>shading quality<br>setting       | FText                                       |  |
| GraphicsShadingQualityMediumValueText    | The text displayed when the medium value is used for the shading quality setting                   | FText                                       |  |
| GraphicsShadingQualityHighValueText      | The text<br>displayed when<br>the high value<br>is used for the<br>shading quality<br>setting      | FText                                       |  |
| GraphicsShadingQualityEpicValueText      | The text<br>displayed when<br>the epic value<br>is used for the<br>shading quality<br>setting      | FText                                       |  |
| GraphicsShadingQualityCinematicValueText | The text<br>displayed when<br>the cinematic<br>value is used<br>for the shading<br>quality setting | FText                                       |  |
| GraphicsShadingQualityDefault            | The default<br>value of the<br>shading quality<br>setting  | int   | 2  |
| GraphicsVsyncImplementation              | The implementation   | TSubclassOf <usettingsitem></usettingsitem> | USettingsItemGraphicsVsync::StaticClas   |

|   | for the graphics<br>vsync settings<br>item                      |   |  |
|---|---|---|--|
| GraphicsVsyncText                         | The text displayed in the graphics vsync settings item          | FText                                       |  |
| GraphicsVsyncEnabledText                  | The text displayed when the vsync setting is enabled            | FText                                       |  |
| GraphicsVsyncDisabledText                 | The text displayed when the vsync setting is disabled           | FText                                       |  |
| GraphicsVsyncDefault                      | The default value of the vsync setting                          | bool  |  |
| GraphicsFpsIndicatorImplementation        | The implementation for the graphics FPS indicator settings item | TSubclassOf <usettingsitem></usettingsitem> | USettingsItemGraphicsFpsIndicator::StaticClas    |
| GraphicsFpsIndicatorText                  | The text displayed in the graphics FPS indicator settings item  | FText                                       |  |
| GraphicsFpsIndicatorEnabledText           | The text displayed when the FPS indicator setting is enabled    | FText                                       |  |
| GraphicsFpsIndicatorDisabledText          | The text displayed when the FPS indicator setting is disabled   | FText                                       |  |
| GraphicsFpsIndicatorDefault               | The default<br>value of the<br>FPS indicator<br>setting         | bool  |  |
| AccessibilityColorBlindModeImplementation | The implementation for the accessibility                        | TSubclassOf <usettingsitem></usettingsitem> | USettingsItemAccessibilityColorBlindMode::Static |

|  | mode settings  |       |  |
|--|--|-------|--|
| AccessibilityColorBlindModeText              | The text displayed in the accessibility color blind mode settings item                                 | FText |  |
| AccessibilityColorBlindModeNormalVisionText  | The text displayed when the normal vision value is used for the accessibility color blind mode setting | FText |  |
| AccessibilityColorBlindModeDeuteranopiaText  | The text displayed when the deuteranopia value is used for the accessibility color blind mode setting  | FText |  |
| AccessibilityColorBlindModeDeuteranomalyText | The text displayed when the deuteranomaly value is used for the accessibility color blind mode setting | FText |  |
| AccessibilityColorBlindModeProtanopiaText    | The text displayed when the protanopia value is used for the accessibility color blind mode setting    | FText |  |
| AccessibilityColorBlindModeProtanomalyText   | The text displayed when the protanomaly value is used for the accessibility color blind mode setting   | FText |  |
| AccessibilityColorBlindModeTritanopiaText    | The text<br>displayed when<br>the tritanopia   | FText |  |

|   | value is used<br>for the<br>accessibility<br>color blind<br>mode setting                             |   |  |
|---|--|---|--|
| AccessibilityColorBlindModeTritanomalyText        | The text displayed when the tritanomaly value is used for the accessibility color blind mode setting | FText                                       |  |
| AccessibilityColorBlindModeSeverityImplementation | The implementation for the accessibility color blind mode severity settings item                     | TSubclassOf <usettingsitem></usettingsitem> | USettingsItemAccessibilityColorBlindModeSeverity |
| AccessibilityColorBlindModeSeverityText           | The text displayed in the accessibility color blind mode severity settings item                      | FText                                       |  |
| ControlsRemapImplementation                       | The implementation for the controls remap settings item  | TSubclassOf <usettingsitem></usettingsitem> | USettingsItemControlsRemap::StaticClas           |
| ControlsWaitingForKeyPressText                    | The text displayed in the menu item while waiting for the user to press a new key                    | FText                                       |  |

## 14.3 Items

## 14.3.1 Types

### Introduction

An enum of all supported settings items

### Values

| Value                               | Description   |
|-------------------------------------|---|
| None                                | A setting not managed by the game instance          |
| AudioMaster                         | The master audio volume setting                     |
| AudioMusic                          | The music audio volume setting                      |
| AudioEffects                        | The effects audio volume setting                    |
| AudioUi                             | The UI audio volume setting                         |
| AudioVoice                          | The voice audio volume setting                      |
| GraphicsResolution                  | The graphics resolution setting                     |
| GraphicsFullscreen                  | The graphics fullscreen setting                     |
| GraphicsViewDistance                | The graphics view distance setting                  |
| GraphicsAntiAliasing                | The graphics anti-aliasing setting                  |
| GraphicsPostProcessing              | The graphics post processing setting                |
| GraphicsShadowQuality               | The graphics shadow quality setting                 |
| GraphicsTextureQuality              | The graphics texture quality setting                |
| GraphicsVisualEffects               | The graphics visual effects setting                 |
| GraphicsShadingQuality              | The graphics shading quality setting                |
| GraphicsVSync                       | The graphics vsync setting                          |
| GraphicsFpsIndicator                | The graphics FPS indicator setting                  |
| AccessibilityColorBlindMode         | The accessibility color blind mode setting          |
| AccessibilityColorBlindModeSeverity | The accessibility color blind mode severity setting |
| ControlsRemap                       | Remap the controls                                  |

## 14.3.2 Logic

#### Introduction

An implementation for a settings item controlling how the setting is configured, saved and applied

#### Dependencies

The  ${\tt SettingsItem}$  relies on other components of this plugin to work:

• Game Instance: Used to monitor for input device changes and handle saving/loading game data

### Implementations

There is already implementations for all settings items. But you can expand this if needed

| Category      | Name  | Description   |
|---------------|---|---|
| Audio         | SettingsItemAudioMaster                               | An implementation for the audio master settings item                            |
| Audio         | SettingsItemAudioMusic                                | An implementation for the audio music settings item                             |
| Audio         | SettingsItemAudioEffects                              | An implementation for the audio effects settings item                           |
| Audio         | SettingsItemAudioUi                                   | An implementation for the audio UI settings item                                |
| Audio         | SettingsItemAudioVoice                                | An implementation for the audio voice settings item                             |
| Graphics      | SettingsItemGraphicsResolution                        | An implementation for the graphics resolution settings item                     |
| Graphics      | SettingsItemGraphicsFullscreen                        | An implementation for the graphics fullscreen settings item                     |
| Graphics      | SettingsItemGraphicsViewDistance                      | An implementation for the graphics view distance settings item                  |
| Graphics      | SettingsItemGraphicsAntiAliasing                      | An implementation for the graphics anti-aliasing settings item                  |
| Graphics      | SettingsItemGraphicsPostProcessing                    | An implementation for the graphics post processing settings item                |
| Graphics      | SettingsItemGraphicsShadowQuality                     | An implementation for the graphics shadow quality settings item                 |
| Graphics      | SettingsItemGraphicsTextureQuality                    | An implementation for the graphics texture quality settings item                |
| Graphics      | SettingsItemGraphicsVisualEffects                     | An implementation for the graphics visual effects settings item                 |
| Graphics      | SettingsItemGraphicsShadingQuality                    | An implementation for the graphics shading quality settings item                |
| Graphics      | SettingsItemGraphicsVsync                             | An implementation for the graphics vsync settings item                          |
| Graphics      | SettingsItemGraphicsFpsIndicator                      | An implementation for the graphics FPS indicator settings item                  |
| Accessibility | Settings Item Accessibility Color Blind Mode          | An implementation for the accessibility color blind mode settings item          |
| Accessibility | Settings Item Accessibility Color Blind Mode Severity | An implementation for the accessibility color blind mode severity settings item |
| Controls      | SettingsItemControlsRemap                             | An implementation for the controls settings item                                |

#### **API Reference**

#### **FUNCTIONS**

| Name              | Description                              | Params  | Return                                   |
|-------------------|--|---|--|
| ConfigureMenuItem | Configure the menu item                  | Config (void)  The settings config specified in the game instance             |  |
|                   |  | Settings (USettingsData*) The current settings data                           |  |
|                   |  | MenuItem (UMenuItem*) The menu item to configure                              |  |
| SaveSettings      | Save the settings managed by a menu item | Settings (USettingsData*) The current settings data                           | USettingsData* The updated settings data |
|                   |  | MenuItem (UMenuItem*)  The menu item containing the updated settings          |  |
| ApplySettings     | Apply the settings                       | World (UObject*) The world context  |  |
|                   |  | Config (USettingsConfig*)  The settings config specified in the game instance |  |
|                   |  | Settings (USettingsData*) The current settings data                           |  |

#### **Blueprint Usage**

You can use the  ${\tt SettingsItem}$  using Blueprints by adding one of the following nodes:

- Ultimate Starter Kit > Settings > Configure Menu Item
- $\bullet \ Ultimate \ Starter \ Kit > Settings > Save \ Settings \\$
- Ultimate Starter Kit > Settings > Apply Settings

## C++ Usage

Before you can use the plugin, you first need to enable the plugin in your  ${\tt Build.cs}\,$  file:

```
PublicDependencyModuleNames.Add("USK");
```

The  ${\tt SettingsItem}$  can now be used in any of your C++ files:

```
#include "USK/Settings/SettingsItem.h"

void ATestActor::Test()
{
    // SettingsItem is a pointer to the USettingsItem
    SettingsItem->ConfigureMenuItem(Config, Settings, MenuItem);
    USettingsData* SaveSettingsValue = SettingsItem->SaveSettings(Settings, MenuItem);
    SettingsItem->ApplySettings(World, Config, Settings);
}
```

## 14.4 Utils

#### 14.4.1 Introduction

A Blueprint Function Library class used to load, save and apply all settings

#### 14.4.2 Dependencies

The SettingsUtils relies on other components of this plugin to work:

- Logger: Used to log useful information to help you debug any issues you might experience
- Game Instance: Used to monitor for input device changes and handle saving/loading game data

#### 14.4.3 Requirements

It's important that you configure the settings in the Game Instance before you can use the settings feature

### 14.4.4 Controls Settings

Before you can use the plugin to automatically handle the controls settings, you need to configure your Input Mapping Context. You are required to specify the Name for each key that can be changed through the plugin. This Name should match the value you specify in your Menu Item

NB: This feature is only available on Unreal Engine 5 and newer

## 14.4.5 API Reference

## **Functions**

| Name                       | Description   | Params  | Return                                  |
|----------------------------|---|---|---|
| Initialize                 | Initialize the settings                                       | GameInstance (UUSKGameInstance*) A reference to the game instance               |   |
| LoadSettings               | Load the settings   |   | USettingsData* The loaded settings data |
| SaveSettings               | Save the settings   | Settings (USettingsData*) The updated settings data                             |   |
| ApplySettingsInWorld       | Apply the settings  | World (UObject*) The world context  |   |
|                            |   | Settings (USettingsData*) The settings data to apply                            |   |
| ApplySettings              | Apply the settings  | GameInstance (UUSKGameInstance*) A reference to the game instance               |   |
|                            |   | Settings (USettingsData*) The settings data to apply                            |   |
| ConfigureMenuItem          | Configure the menu item to manage the specified settings item | MenuItem (UMenuItem*) The menu item to configure                                |   |
| SaveMenuItemSettings       | Save the settings managed by the menu item                    | MenuItem (UMenuItem*) The menu item containing the updated settings             |   |
|                            |   | ApplySettings (bool) Should the settings also be applied?                       |   |
| ApplyMenuItemSettings      | Apply the settings managed by the menu item                   | MenuItem (UMenuItem*)  The menu item containing the updated settings            |   |
| GetSettingsItemForMenuItem | Get the settings item for the specified menu item             | MenuItem (UMenuItem*)  The menu item to get the settings item for               | USettingsItem* The settings item        |
|                            |   | Config (USettingsConfig*)  The settings config specified in the game instance   |   |
| GetSettingsItem            | Get the settings item for the specified settings item type    | SettingsItemType (ESettingsItemType) The menu item to get the settings item for | USettingsItem* The settings item        |
|                            |   | Config (USettingsConfig*)  The settings config specified in the game instance   |   |

#### 14.4.6 Blueprint Usage

You can use the SettingsUtils using Blueprints by adding one of the following nodes:

- Ultimate Starter Kit > Settings > Initialize
- Ultimate Starter Kit > Settings > Load Settings
- Ultimate Starter Kit > Settings > Save Settings
- Ultimate Starter Kit > Settings > Apply Settings In World
- Ultimate Starter Kit > Settings > Apply Settings
- Ultimate Starter Kit > Settings > Configure Menu Item
- Ultimate Starter Kit > Settings > Save Menu Item Settings
- Ultimate Starter Kit > Settings > Apply Menu Item Settings
- Ultimate Starter Kit > Settings > Get Settings Item For Menu Item
- Ultimate Starter Kit > Settings > Get Settings Item

#### 14.4.7 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your Build.cs file:

```
PublicDependencyModuleNames.Add("USK");
```

The SettingsUtils can now be used in any of your C++ files:

```
#include "USK/Settings/SettingsUtils.h"

void ATestActor::Test()
{
    USettingsUtils::Initialize(GameInstance);
    USettingsData* LoadSettingsValue = USettingsUtils::LoadSettings();
    USettingsDtils::SaveSettings(Settings);
    USettingsUtils::ApplySettingsInWorld(World, Settings);
    USettingsUtils::ApplySettings(GameInstance, Settings);
    USettingsUtils::ConfigureMenuItem(MenuItem);
    USettingsUtils::SaveMenuItemSettings(MenuItem, ApplySettings);
    USettingsUtils::ApplyMenuItemSettings(MenuItem);
    USettingsUtils::ApplyMenuItemSettings(MenuItem);
    USettingsUtils::SettingsItem* SettingsItemForMenuItem = USettingsUtils::GetSettingsItemForMenuItem(MenuItem, Config);
    USettingsItem* SettingsItem = USettingsUtils::GetSettingsItemType, Config);
}
```

## 15. Utils

## 15.1 Config Utils

### 15.1.1 Introduction

A Blueprint Function Library class used to extract config values

### 15.1.2 Dependencies

The  ${\tt ConfigUtils}$  relies on other components of this plugin to work:

• Logger: Used to log useful information to help you debug any issues you might experience

#### 15.1.3 API Reference

#### **Functions**

| Name               | Description                             | Params                                    | Return                                   |
|--------------------|---|---|--|
| GetConfigValue     | Extract a config value from a given     | Filename (FString)                        | FString                                  |
|                    | config file                             | The name of the config file               | The value extracted from the config file |
|                    |   | Section (FString)                         |  |
|                    |   | The section in the config file            |  |
|                    |   | Key (FString)                             |  |
|                    |   | The key in the config file                |  |
|                    |   | DefaultValue (FString)                    |  |
|                    |   | The default value to return if the config |  |
|                    |   | file can't be read                        |  |
| GetGameConfigValue | Extract a config value from the default | Section (FString)                         | FString                                  |
|                    | game config file                        | The section in the config file            | The value extracted from the config file |
|                    |   | Key (FString)                             |  |
|                    |   | The key in the config file                |  |
|                    |   | DefaultValue (FString)                    |  |
|                    |   | The default value to return if the config |  |
|                    |   | file can't be read                        |  |

### 15.1.4 Blueprint Usage

You can use the  ${\tt ConfigUtils}$  using Blueprints by adding one of the following nodes:

- $\bullet \ Ultimate \ Starter \ Kit > Utils > Config > Get \ Config \ Value \\$
- Ultimate Starter Kit > Utils > Config > Get Game Config Value

### 15.1.5 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your  ${\tt Build.cs}\,$  file:

PublicDependencyModuleNames.Add("USK");

### The ${\tt ConfigUtils}$ can now be used in any of your C++ files:

```
#include "USK/Utils/ConfigUtils.h"

void ATestActor::Test()
{
    FString ConfigValue = UConfigUtils::GetConfigValue(Filename, Section, Key, DefaultValue);
    FString GameConfigValue = UConfigUtils::GetGameConfigValue(Section, Key, DefaultValue);
}
```

## 15.2 Platform

## 15.2.1 Platform Type

### Introduction

The types of supported platform types

## Values

| Value     | Description                        |
|-----------|------------------------------------|
| Unknown   | An unknown or unsupported platform |
| Windows   | Windows (any architecture)         |
| MacOS     | MacOS (any architecture)           |
| Linux     | Linux (any architecture)           |
| ConsoleMx | Console MX                         |
| ConsoleSp | Console SP                         |
| ConsoleNs | Console NS                         |
| Android   | Android (any architecture)         |
| IOS       | iOS                                |

## 15.2.2 Platform Utils

### Introduction

A Blueprint Function Library class used for platform detection

## API Reference

FUNCTIONS

| Name         | Description                                 | Params | Return   |
|--------------|---|--------|--|
| GetPlatform  | Get the current platform                    |        | EPlatform The current platform   |
| IsInEditor   | Is the build running inside the editor?     |        | <b>bool</b> A boolean value indicating if the build is running inside the editor     |
| IsDesktop    | Is the build running on a desktop platform? |        | <b>bool</b> A boolean value indicating if the build is running on a desktop platform |
| IsWindows    | Is the build running on Windows?            |        | <b>bool</b> A boolean value indicating if the build is running on Windows            |
| IsMacOS      | Is the build running on MacOS?              |        | <b>bool</b> A boolean value indicating if the build is running on MacOS              |
| IsMacOSx86   | Is the build running on MacOS (x86)?        |        | <b>bool</b> A boolean value indicating if the build is running on MacOS (x86)        |
| IsMacOSArm   | Is the build running on MacOS (ARM)?        |        | bool A boolean value indicating if the build is running on MacOS (ARM)               |
| IsLinux      | Is the build running on Linux?              |        | <b>bool</b> A boolean value indicating if the build is running on Linux              |
| IsConsole    | Is the build running on a console platform? |        | <b>bool</b> A boolean value indicating if the build is running on a console platform |
| IsConsoleMx  | Is the build running on Console MX?         |        | <b>bool</b> A boolean value indicating if the build is running on Console MX         |
| IsConsoleSp  | Is the build running on Console SP?         |        | <b>bool</b> A boolean value indicating if the build is running on Console SP         |
| IsConsoleNs  | Is the build running on Console NS?         |        | bool  A boolean value indicating if the build is running on Console NS               |
| IsMobile     | Is the build running on a mobile platform?  |        | bool  A boolean value indicating if the build is running on a mobile platform        |
| IsAndroid    | Is the build running on Android?            |        | bool  A boolean value indicating if the build is running on Android                  |
| IsAndroidx86 | Is the build running on Android (x86)?      |        | <b>bool</b> A boolean value indicating if the build is running on Android (x86)      |
| IsAndroidx64 | Is the build running on Android (x64)?      |        | <b>bool</b> A boolean value indicating if the build is running on Android (x64)      |

| IsAndroidArm   | Is the build running on Android (ARM)?   | bool  A boolean value indicating if the build is running on Android (ARM)         |
|----------------|--|---|
| IsAndroidArm64 | Is the build running on Android (ARM64)? | <b>bool</b> A boolean value indicating if the build is running on Android (ARM64) |
| IsIOS          | Is the build running on iOS?             | <b>bool</b> A boolean value indicating if the build is running on iOS             |

#### **Blueprint Usage**

You can use the PlatformUtils using Blueprints by adding one of the following nodes:

- Ultimate Starter Kit > Utils > Platform > Get Platform
- Ultimate Starter Kit > Utils > Platform > Is In Editor
- Ultimate Starter Kit > Utils > Platform > Is Desktop
- Ultimate Starter Kit > Utils > Platform > Is Windows
- Ultimate Starter Kit > Utils > Platform > Is MacOS
- Ultimate Starter Kit > Utils > Platform > Is MacOS (x86)
- Ultimate Starter Kit > Utils > Platform > Is MacOS (ARM)
- Ultimate Starter Kit > Utils > Platform > Is Linux
- Ultimate Starter Kit > Utils > Platform > Is Console
- Ultimate Starter Kit > Utils > Platform > Is Console MX
- Ultimate Starter Kit > Utils > Platform > Is Console SP
- Ultimate Starter Kit > Utils > Platform > Is Mobile
- Ultimate Starter Kit > Utils > Platform > Is Android
- Ultimate Starter Kit > Utils > Platform > Is Android (x86)
- Ultimate Starter Kit > Utils > Platform > Is Android (x64)
- Ultimate Starter Kit > Utils > Platform > Is Android (ARM)
- Ultimate Starter Kit > Utils > Platform > Is Android (ARM64)
- Ultimate Starter Kit > Utils > Platform > Is iOS

#### C++ Usage

Before you can use the plugin, you first need to enable the plugin in your Build.cs file:

```
PublicDependencyModuleNames.Add("USK");
```

The  ${\tt PlatformUtils}$  can now be used in any of your C++ files:

```
#include "USK/Utils/PlatformUtils.h"

void ATestActor::Test()
{
    EPlatform Platform = UPlatformUtils::GetPlatform();
    bool IsInEditorValue = UPlatformUtils::IsInEditor();
    bool IsDesktopValue = UPlatformUtils::IsDesktop();
    bool IsWindowsValue = UPlatformUtils::IsWindows();
    bool IsWacoSValue = UPlatformUtils::IsMacoS();
    bool IsMacoSXafue = UPlatformUtils::IsMacoS();
    bool IsMacoSXafue = UPlatformUtils::IsMacoSXaf();
    bool IsMacoSXarValue = UPlatformUtils::IsMacoSXaf();
    bool IsLinuxValue = UPlatformUtils::IsLinux();
    bool IsConsoleValue = UPlatformUtils::IsConsole();
    bool IsConsoleValue = UPlatformUtils::IsConsoleSp();
    bool IsConsoleNxValue = UPlatformUtils::IsConsolePx();
    bool IsConsoleNxValue = UPlatformUtils::IsConsolePx();
    bool IsConsoleNxValue = UPlatformUtils::IsConsolePx();
```

```
bool IsMobileValue = UPlatformUtils::IsMobile();
bool IsAndroidValue = UPlatformUtils::IsAndroid();
bool IsAndroidx86Value = UPlatformUtils::IsAndroidx86();
bool IsAndroidx64Value = UPlatformUtils::IsAndroidx64();
bool IsAndroidArmValue = UPlatformUtils::IsAndroidArm();
bool IsAndroidArm64Value = UPlatformUtils::IsAndroidArm64();
bool IsIOSValue = UPlatformUtils::IsIOS();
}
```

## 15.3 Project Utils

#### 15.3.1 Introduction

A Blueprint Function Library class used to extract project values

#### 15.3.2 API Reference

#### **Functions**

| Name                      | Description  | Params | Return                                     |
|---------------------------|--|--------|--|
| GetProjectId              | Get the project ID from the game config file               |        | FString The project ID                     |
| GetProjectName            | Get the project name from the game config file             |        | FString The project name                   |
| GetProjectDescription     | Get the project description from the game config file      |        | <b>FString</b> The project description     |
| GetProjectVersion         | Get the project version from the game config file          |        | <b>FString</b> The project version         |
| GetProjectCompanyName     | Get the project company name from the game config file     |        | FString The project company name           |
| GetProjectCopyrightNotice | Get the project copyright notice from the game config file |        | FString The project copyright notice       |
| GetProjectLicensingTerms  | Get the project licensing terms from the game config file  |        | <b>FString</b> The project licensing terms |
| GetProjectHomepage        | Get the project homepage from the game config file         |        | FString The project homepage               |

### 15.3.3 Blueprint Usage

You can use the ProjectUtils using Blueprints by adding one of the following nodes:

- Ultimate Starter Kit > Utils > Project > Get Project Id
- $\bullet \ Ultimate \ Starter \ Kit > Utils > Project > Get \ Project \ Name$
- Ultimate Starter Kit > Utils > Project > Get Project Description
- Ultimate Starter Kit > Utils > Project > Get Project Version
- Ultimate Starter Kit > Utils > Project > Get Project Company Name
- Ultimate Starter Kit > Utils > Project > Get Project Copyright Notice
- Ultimate Starter Kit > Utils > Project > Get Project Licensing Terms
- Ultimate Starter Kit > Utils > Project > Get Project Homepage

### 15.3.4 C++ Usage

Before you can use the plugin, you first need to enable the plugin in your Build.cs file:

PublicDependencyModuleNames.Add("USK");

#### The ${\tt ProjectUtils}$ can now be used in any of your C++ files:

```
#include "USK/Utils/ProjectUtils.h"

void ATestActor::Test()
{
    FString ProjectId = UProjectUtils::GetProjectId();
    FString ProjectName = UProjectUtils::GetProjectName();
    FString ProjectDescription = UProjectUtils::GetProjectDescription();
    FString ProjectVersion = UProjectUtils::GetProjectVersion();
    FString ProjectCompanyName = UProjectUtils::GetProjectCompanyName();
    FString ProjectCopyrightNotice = UProjectUtils::GetProjectCopyrightNotice();
    FString ProjectLicensingTerms = UProjectUtils::GetProjectLicensingTerms();
    FString ProjectHomepage = UProjectUtils::GetProjectHomepage();
}
```