- Textbook: An Engineering Approach to Computer Networking: ATM Networks, the Internet, and the Telephone Network, by S. Keshav, 1997, Addison-Wesley.
 - Useful chapters: Ch 5 layering, Ch6 System Design, Ch 9 Scheduling, Ch 11 Routing, Ch 13
 Flow control, Ch 14 Traffic management [One-to-one mapping with Lecture slides].

Routing

Packet size

- min: to detect a collision (i.e. duration of transmission from two extreme stations at max length of cable extent, must overlap by enough bits to detect collision and therefore trigger CD part of CSMA/CD)
- max: to prevent capture and to make sure delay before eventual access is not too high.

Inter-domain

BGP (Border Gateway Protocol)

Intra-domain

Fibbing paper

Multi-protocol label switching

Segment

Multicast

- hard in BGP
- · multicast in mobile routing

Mobile and telephone

Mobile

Telephone circuits: dynamic alternative routing

Flow / congestion control

open-loop vs closed-loop control

window-based vs rate-based

TCP, packet loss (congestion vs mobile host moving)

- ECN
- AIMD

- RTO (Retransmission TimeOut), congestion window
- Go-Back-N
- buffering, fast retransmit, fast recovery; wireless

Scheduling

The scheduler allocates the delay, bandwidth and loss rate to the packets in the output queues.

work-conserving: whenever there is a packet to send, the scheduler will send it.

• the sum of mean queuing delay q [seconds] to clear all the packets weighted by link load utilization ρ is *independent* of the scheduling algorithm,

$$\sum_{i=1}^n
ho_i q_i = C,$$

- where mean link utilization $\rho_i=rac{\lambda_i}{p_i}$, i.e. the ratio between the mean arrival pkt rate λ_i and the mean pkt service rate p_i [packets/s].
- ullet Alternatively, $\mu_i=rac{1}{p_i}$ is the mean per-packet service time [s/packet].

non-work-conserving: the scheduler may idle even if there are packets to send.

- allows smoothing of packet flows, or less jitter; downstream traffic more predictable since the output flow is controlled, i.e. less bursty traffic; less buffer space required.
- the sum > C, causing higher end-to-end delay; complex time synchronization required.

Fairness

max-min fairness is important for elastic traffic (best-effort service) since there's no economic incentive for routers to exceed the minimum bandwidth required. Whereas for inelastic traffic, which pays the network operator for a guaranteed bandwidth, fairness is not a concern.

Each flow is assigned m_i resource, which neither exceeds its demand x_i , nor exceeds an equal share of the remaining capacity (for unsatisfied flows), in the order of increasing flow demand,

$$m_0 = 0, m_i = \min(x_i, rac{C - \sum_{j=0}^{i-1} m_j}{n - (i-1)}).$$

The max-min fair share allocates the small demanding flows what they want, and then evenly distributes the remaining capacity among the larger demanding flows. The process is repeated until all flows are satisfied.

Protection

misbehavior by one connection should not affect the performance received by other connections (or flows), where misbehavior includes sending packets at a rate faster than its fair share.

relationship: fair \rightarrow protection, i.e., a fair scheduler automatically provides protection. However, the converse need not be true.

• because the fairness limits a misbehaving connection to its fair share. On the other hand, if connections are policed at the entrance to the network (conforming to a predeclared traffic pattern) they are protected from each other, but their resource shares may not be fair.

Scheduling algorithms

- FIFO O(1)
 - only per packet, not per flow (src/dst IP/port, protocol).
 - ⋄ ✗ no fairness and protection.
 - ✓ easy to implement, and no extra state stored in RAM.
- Priority queueing
 - ✓ guaranteed-service.
 - X starve low-priority flows, unless proper admission control and policing are used.
- Generalized Processor Sharing (GPS)
 - \circ "bitwise round-robin" benchmark (Flow A: g(A) = 1 bit \to Flow B: 1 bit \to ... \to Flow A: 1 bit \to ...).
 - \circ For N connections with positive real weights ϕ_i , and
 - $\circ S(i,t_1,t_2)$ is the amount of service received by connection i in the interval $[t_1,t_2]$,
 - \circ for any connection i with data in queue, for any connection j,

$$rac{S(i,t_1,t_2)}{S(j,t_1,t_2)} \geq rac{\phi_i}{\phi_i}.$$

- ✓ fair as each flow shares the remaining bandwidth in proportion to its weight.
- x not implementable since packets are not infinitesimal small, but is used as a reference.
 - \blacksquare Relative Fairness Bound: $RFB=|\frac{S(i,t_1,t_2)}{g(i)}-\frac{S(j,t_1,t_2)}{g(j)}|$; Absolute Fairness Bound: $AFB=|\frac{S(i,t_1,t_2)}{g(i)}-\frac{GPS(i,t_1,t_2)}{g(i)}|$,
 - ullet where $g(i)=\min_k g(i,k)$ and the service rate in switch k is r(k),

$$g(i,k) = rac{\omega(i,k)}{\sum_k \omega(j,k)} r(k).$$

- ullet Weighted Round Robin (WRR) O(1)
 - use case: high-speed ATM networks, with fixed-size packets and short round times.
 - \circ normalized weight $\hat{\omega}=rac{\omega}{u}$, where μ is the mean packet size of the flow.
 - * must know mean packet size in advance.
 - X huge state stored in RAM; new/short-lived flows need default average.
 - □ fair only over time scales longer than a round time.
 - At a shorter time scale, some connections may get more service than others (100%, ..., 0%, 0%).
 - If a connection has a small weight, or the number of connections is large, this may lead to long periods of unfairness.
- ullet Deficit Round Robin (DRR) O(1)

- o associate each flow with a deficit counter (dc), initialized to 0.
- o for non-empty queue, packet at the head is
 - served and dc = dc + quantum pkt_size, if pkt_size ≤ dc + quantum;
 - kept in the queue and serve one quantum dc += quantum, otherwise. [build up credit]
 - quantum choice: at least the largest packet size of the flow (work-conserving).
- reset dc to 0 when the queue is empty.
- ✓ no need to know the mean packet size in advance, hence no problem for new/short-lived flows.
- x huge state stored in RAM for dc for each flow.
- □ fair only over time scales longer than a frame time.
- o use case: fair longer, given small packet size and small number of flows.
- Weighted Fair Queuing (WFQ) $O(\log n)$
 - \circ smallest finish-number F(i,k,t) from GPS across queues served first,
 - \circ where flow i with weight ω_i , packet k at time t with size P(i,k,t),
 - the length of a round, that is, the time taken to serve one bit from each active connection, is proportional to the number of active connections.
 - \circ define the round number R(t) to be the number of rounds that service GPS has completed.
 - increases at a rate inversely proportional to the number of active connections.

$$egin{aligned} F(i,k,t) &= egin{cases} R(t) + rac{P(i,k,t)}{\omega_i}, & ext{if connection i is inactive} \ F(i,k-1,f) + rac{P(i,k,t)}{\omega_i}, & ext{if connection i is active} \ &= \max\{F(i,k-1,f),R(t)\} + rac{P(i,k,t)}{\omega_i}. \end{aligned}$$

- ✓ no need to know the mean packet size in advance.
- \circ **x** storage for finish numbers F(i,k,t) for each flow
- X processing time to find the smallest finish number.

algo.	work-conserving?	max-min fair?	protection?	w/o mean pkg size?
FIFO/FCFS	✓	×	×	✓
Priority	✓	×	x starve	✓
GPS	✓	✓	✓	✓
WRR	✓	long time scale 🗸	long time scale ✓	×
Deficit RR	✓	medium and	long time scales ✓	✓
WFQ	✓	✓	✓	✓

Queue management

drop from T/H, smart/random drop, flush, Active Queue Management (e.g. Random Early Detection), ECN.

Data centers

QJump, a switch priority queueing, combined with end systems traffic regulation, by exploiting its regular topology & traffic matrix (src-dst) & source behaviour.

Data center, QJump paper.

Optimization

Optimization paper.

Traffic management

QoS + Connectivity.

Elastic vs inelastic

Traffic classes and synchrony (see Flow control section)

- Guaranteed-service, or inelastic (delay sensitive and unusable for low bandwidth, i.e. utility is 0)
 - Synchronous, or real-time, e.g. gaming, video conferencing.
 - open-loop flow control with admission control (RTP over UDP).
- Best-effort, or elastic (benefit from throughput, but not delay-sensitive)
 - Asynchronous, or non-real-time, e.g. file transfer, email, web browsing.
 - closed-loop flow control with congestion control (TCP), with rate adaptive to network conditions.

Utility function, Traffic model (measure or math), time scale, renegotiation, admission control, capacity planning and macroscopic QoS.

Peak load pricing

Signalling

Related: multicast (RSVP: Resource reSerVation Protocol)

IntServ vs. DiffServ

System design

layering, randomness and hysteresis

Seven Layering