
Tema: Konfigurimi i nje Topologjie Rrjeti duke perdorur Distance Vector Routing protocol (IPv4, Ipv6)



Skenari – Ekzekutimi i RIPv1 me Subnet-e dhe midis Classfull Networks

Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	Fa0/0	172.30.1.1	255.255.255.0	N/A
	S0/0/0	172.30.2.1	255.255.255.0	N/A
R2	Fa0/0	172.30.3.1	255.255.255.0	N/A
	S0/0/0	172.30.2.2	255.255.255.0	N/A
	S0/0/1	192.168.4.9	255.255.255.252	N/A
R3	Fa0/0	192.168.5.1	255.255.255.0	N/A
	S0/0/1	192.168.4.10	255.255.255.252	N/A
PC1	NIC	172.30.1.10	255.255.255.0	172.30.1.1
PC2	NIC	172.30.3.10	255.255.255.0	172.30.3.1
PC3	NIC	192.168.5.10	255.255.255.0	192.168.5.1

Task 1: Make Changes between Scenario A and Scenario B

Step 1: Change the IP addressing on the interfaces as shown in the Topology Diagram and the Addressing Table.

Sometimes when changing the IP address on a serial interface, you may need to reset that interface by using the

shutdown command, waiting for the LINK-5-CHANGED message, and then using the **no shutdown** command.

This process will force the IOS to starting using the new IP address.

```
R1(config) #int s0/0/0
R1(config-if) #ip add 172.30.2.1 255.255.25.0
R1(config-if) #shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to administratively down
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to down
R1(config-if) #no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up
R1(config-if) #
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to up
```

Step 2: Verify that routers are active.

After reconfiguring all the interfaces on all three routers, verify that all necessary interfaces are active with the **show ip interface brief** command.

Step 3: Remove the RIP configurations from each router.

Although you can remove the old **network** commands with the **no** version of the command, it is more efficient to simply remove RIP and start over. Remove the RIP configurations from each router with the **no router rip** global configuration command. This will remove all the RIP configuration commands including the **network** commands.

```
R1(config) #no router rip
R2(config) #no router rip
R3(config) #no router rip
```

Task 2: Configure RIP

Step 1: Configure RIP routing on R1 as shown below.

R1(config)#router rip

R1(config-router)#network 172.30.0.0

Notice that only a single network statement is needed for R1. This statement includes both interfaces on different subnets of the 172.30.0.0 major network.

Step 2: Configure R1 to stop sending updates out the FastEthernet0/0 interface.

Sending updates out this interface wastes the bandwidth and processing resources of all devices on the LAN. In addition, advertising updates on a broadcast network is a security risk. RIP updates can be intercepted with packet sniffing software. Routing updates can be modified and sent back to the router, corrupting the router table with false metrics that misdirects traffic.

The **passive-interface fastethernet 0/0** command is used to disable sending RIPv1 updates out that interface. When you are finished with the RIP configuration, return to privileged EXEC mode and save the current configuration to NVRAM.

```
R1(config-router) #passive-interface fastethernet 0/0 R1(config-router) #end %SYS-5-CONFIG_I: Configured from console by console R1#copy run start
```

Step 3: Configure RIP routing on R2 as shown below.

```
R2(config) #router rip
R2(config-router) #network 172.30.0.0
R2(config-router) #network 192.168.4.0
R2(config-router) #passive-interface fastethernet 0/0
R2(config-router) #end
%SYS-5-CONFIG_I: Configured from console by console
R2#copy run start
```

Again notice that only a single network statement is needed for the two subnets of 172.30.0.0. This statement includes both interfaces, on different subnets, of the 172.30.0.0 major network. The network for the WAN link between R2 and R3 is also configured.

When you are finished with the RIP configuration, return to privileged EXEC mode and save the current configuration to NVRAM.

Step 4: Configure RIP routing on R3 as shown below.

```
R3(config) #router rip
R3(config-router) #network 192.168.4.0
R3(config-router) #network 192.168.5.0
R3(config-router) #passive-interface fastethernet 0/0
R3(config-router) #end
%SYS-5-CONFIG_I: Configured from console by console
R3#copy run start
```

When you are finished with the RIP configuration, return to privileged EXEC mode and save the current configuration to NVRAM.

Task 3: Verify RIP Routing

Step 1: Use the show ip route command to verify that each router has all of the networks in the topology in the routing table.

Rl#show ip route <Output omitted> 172.30.0.0/24 is subnetted, 3 subnets C 172.30.1.0 is directly connected, FastEthernet0/0 C 172.30.2.0 is directly connected, Serial0/0/0 R 172.30.3.0 [120/1] via 172.30.2.2, 00:00:22, Serial0/0/0 R 192.168.4.0/24 [120/1] via 172.30.2.2, 00:00:22, Serial0/0/0

Note: RIPv1 is a classful routing protocol. Classful routing protocols do not send the subnet mask with network in routing updates. For example, 172.30.1.0 is sent by R2 to R1 without any subnet mask information.

192.168.5.0/24 [120/2] via 172.30.2.2, 00:00:22, Serial0/0/0

```
R2#show ip route
<Output omitted>
     172.30.0.0/24 is subnetted, 3 subnets
        172.30.1.0 [120/1] via 172.30.2.1, 00:00:04, Serial0/0/0
        172.30.2.0 is directly connected, Serial0/0/0
       172.30.3.0 is directly connected, FastEthernet0/0
     192.168.4.0/30 is subnetted, 1 subnets
C
        192.168.4.8 is directly connected, Serial0/0/1
     192.168.5.0/24 [120/1] via 192.168.4.10, 00:00:19, Serial0/0/1
R
R2#
R3#show ip route
<Output omitted>
     172.30.0.0/16 [120/1] via 192.168.4.9, 00:00:22, Serial0/0/1
     192.168.4.0/30 is subnetted, 1 subnets
C
        192.168.4.8 is directly connected, Serial0/0/1
     192.168.5.0/24 is directly connected, FastEthernet0/0
C
```

Step 2: Verify that all necessary interfaces are active.

If one or more routing tables does not have a converged routing table, first make sure that all necessary interfaces are active with **show ip interface brief**.

Then use **show ip protocols** to verify the RIP configuration. Notice in the output from this command that the FastEthernet0/0 interface is no longer listed under **Interface** but is now listed under a new section of the output:

Passive Interface(s).

R1#

```
R1#show ip protocols
Routing Protocol is "rip"
  Sending updates every 30 seconds, next due in 20 seconds
  Invalid after 180 seconds, hold down 180, flushed after 240
  Outgoing update filter list for all interfaces is not set
  Incoming update filter list for all interfaces is not set
 Redistributing: rip
  Default version control: send version 2, receive version 2
   Interface Send Recv Triggered RIP Key-chain Serial0/1/0 2 2
 Automatic network summarization is in effect
 Maximum path: 4
 Routing for Networks:
   172.30.0.0
   209.165.200.0
Passive Interface(s):
 FastEthernet0/0
 Routing Information Sources:
   Gateway Distance Last Update 209.165.200.229 120 00:00:15
  Distance: (default is 120)
```

Step 3: View the RIP messages being sent and received.

To view the RIP messages being sent and received use the **debug ip rip** command. Notice that RIP updates are not sent out of the fa0/0 interface because of the **passive-interface fastethernet 0/0** command.

```
Rl#RIP: sending v1 update to 255.255.255.255 via Serial0/0/0 (172.30.2.1)
RIP: build update entries
    network 172.30.1.0 metric 1
RIP: received v1 update from 172.30.2.2 on Serial0/0/0
    172.30.3.0 in 1 hops
```


Step 4: Discontinue the debug output with the undebug all command.

```
R1#undebug all
All possible debugging has been turned off
```

Task 1: Make Changes between Scenario A and Scenario B

Step 1,2:

Konfigurojme sipas kërkesës gjithë IP dhe paraqesim skemën ne fund.



Step 3:

Heqim rip configuration.

```
R1(config) #no router rip
R1(config) #
R2(config) #no router rip
R2(config) #
R3(config) #no router rip
R3(config) #
```

Task 2: Configure RIP

Step 1,2:

```
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config) #hostname R1
R1(config) #
R1(config) #
R1(config) #router rip
R1(config-router) #network 172.30.0.0
R1(config-router) #passive-interface fastethernet 0/0
R1(config-router) #end
R1#
%SYS-5-CONFIG_I: Configured from console by console
R1#copy run start
Destination filename [startup-config]?
Building configuration...
[OK]
```

Step 3:

```
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config) #hostname R2
R2(config) #no router rip
R2(config) #router rip
R2(config-router) #network 172.30.0.0
R2(config-router) #network 192.168.4.0
R2(config-router) #passive-interface fastethernet 0/0
R2 (config-router) #end
R2#
%SYS-5-CONFIG I: Configured from console by console
R2#copy run start
Destination filename [startup-config]?
Building configuration...
[OK]
R2#
Step 4:
R3(config) #no router rip
R3(config) #router rip
R3(config-router) #network 192.168.4.0
R3(config-router) #network 192.168.5.0
R3(config-router) #passive-interface fastethernet 0/0
R3(config-router)#end
%SYS-5-CONFIG I: Configured from console by console
R3#copy run start
Destination filename [startup-config]?
Building configuration...
[OK]
R3#
```

Task 3: Verify RIP Routing

Step 1:

```
R1#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
      E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
     172.30.0.0/24 is subnetted, 3 subnets
        172.30.1.0 is directly connected, FastEthernet0/0
\mathbf{C}
        172.30.2.0 is directly connected, Serial0/0/0
        172.30.3.0 [120/1] via 172.30.2.2, 00:00:24, Serial0/0/0
     192.168.4.0/24 [120/1] via 172.30.2.2, 00:00:24, Serial0/0/0
R
     192.168.5.0/24 [120/2] via 172.30.2.2, 00:00:24, Serial0/0/0
```

```
R2#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
     172.30.0.0/24 is subnetted, 3 subnets
R
        172.30.1.0 [120/1] via 172.30.2.1, 00:00:22, Serial0/0/0
C
        172.30.2.0 is directly connected, Serial0/0/0
C
        172.30.3.0 is directly connected, FastEthernet0/0
     192.168.4.0/30 is subnetted, 1 subnets
\mathbf{C}
        192.168.4.8 is directly connected, Serial0/0/1
     192.168.5.0/24 [120/1] via 192.168.4.10, 00:00:03, Serial0/0/1
R
R2#
R3#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
     172.30.0.0/16 [120/1] via 192.168.4.9, 00:00:23, Serial0/0/1
     192.168.4.0/30 is subnetted, 1 subnets
        192.168.4.8 is directly connected, Serial0/0/1
     192.168.5.0/24 is directly connected, FastEthernet0/0
R3#
```

Step 2:

Router#show ip interface brief						
Interface	IP-Address	OK? Method Status Protocol				
FastEthernet0/0	192.168.5.1	YES manual up up				
FastEthernet0/1	unassigned	YES unset administratively down down				
Serial0/0/0	unassigned	YES unset administratively down down				
Serial0/0/1	192.168.4.10	YES manual up up				
Vlan1	unassigned	YES unset administratively down down				
Router#						
Router#show ip interface brief						
Interface	IP-Address	OK? Method Status Protocol				
FastEthernet0/0	172.30.1.1	YES manual up up				
FastEthernet0/1	unassigned	YES unset administratively down down				
Serial0/0/0	172.30.2.1	YES manual up up				
Serial0/0/1	unassigned	YES unset administratively down down				
Vlan1	unassigned	YES unset administratively down down				
Router#	_					
Router#show ip interface brief						
Interface	IP-Address	OK? Method Status Protocol				
FastEthernet0/0	172.30.3.1	YES manual up up				
FastEthernet0/1	unassigned	YES unset administratively down down				
Serial0/0/0	172.30.2.2	YES manual up up				
Serial0/0/1	192.168.4.9	YES manual up up				
Vlan1	unassigned	YES unset administratively down down				

Step 3,4:

```
R1#show ip protocols
Routing Protocol is "rip"
Sending updates every 30 seconds, next due in 21 seconds
Invalid after 180 seconds, hold down 180, flushed after 240
Outgoing update filter list for all interfaces is not set
Incoming update filter list for all interfaces is not set
Redistributing: rip
Default version control: send version 1, receive any version
                        Send Recv Triggered RIP Key-chain
  Interface
 Serial0/0/0
                        12 1
Automatic network summarization is in effect
Maximum path: 4
Routing for Networks:
       172.30.0.0
Passive Interface(s):
       FastEthernet0/0
Routing Information Sources:
       Gateway
                                    Last Update
                      Distance
       172.30.2.2
                                      00:00:24
Distance: (default is 120)
R1#debug ip rip
RIP protocol debugging is on
R1#RIP: received v1 update from 172.30.2.2 on Serial0/0/0
     172.30.3.0 in 1 hops
     192.168.4.0 in 1 hops
     192.168.5.0 in 2 hops
R1#unRIP: sending v1 update to 255.255.255 via Serial0/0/0 (172.30.2.1)
RIP: build update entries
     network 172.30.1.0 metric 1
RIP: received v1 update from 172.30.2.2 on Serial0/0/0
     172.30.3.0 in 1 hops
     192.168.4.0 in 1 hops
     192.168.5.0 in 2 hops
% Incomplete command.
R1#undebug all
All possible debugging has been turned off
R1#
```