


# CCNA 200-301 Day 13

#### Subnetting (Part 1)





# Things we'll cover

- CIDR (Classless Inter-Domain Routing)
- The process of subnetting



Class	First octet (binary)	First octet range (decimal)	
А	0xxxxxxx	0 - 127	0.0.0.0 ~ 127.255.255.255
В	10xxxxxx	128 - 191	128.0.0.0 ~ 191.255.255.255
С	110xxxxx	192 - 223	192.0.0.0 ~ 223.255.255.255
D	1110xxxx	224 - 239	224.0.0.0 ~ 239.255.255.255
E	1111xxxx	240 - 255	240.0.0.0 ~ 255.255.255.255



Class	First octet	First octet numeric range	Prefix Length
A	0xxxxxxx	0-127	/8
В	10xxxxxx	128-191	/16
С	110xxxxx	192-223	/24


Class	Leading bits	Size of <i>network number</i> bit field	Size of rest bit field	Number of networks	Addresses per network
Class A	0	8	24	128 (2 <sup>7</sup> )	16,777,216 (2 <sup>24</sup> )
Class B	10	16	16	16,384 (2 <sup>14</sup> )	65,536 (2 <sup>16</sup> )
Class C	110	24	8	2,097,152 (2 <sup>21</sup> )	256 (2 <sup>8</sup> )





- The IANA (Internet Assigned Numbers Authority) assigns IPv4 addresses/networks to companies based on their size.
- For example, a very large company might receive a class A
   or class B network, while a small company might receive a
   class C network.
- · However, this led to many wasted IP addresses.










New York



203.0.113.0/24

256 addresses

- -1 network address (203.0.113.0)
- -1 broadcast address (203.0.113.255)
- -1 R1's address (203.0.113.1)
- -1 R2's address (203.0.113.2)

=252 addresses

WASTED



- · Company X needs IP addressing for 5000 end hosts.
- A class C network does not provide enough addresses, so a class B network must be assigned.
- · This will result in about 60000 addresses being wasted.



#### CIDR (Classless Inter-Domain Routing)

- When the Internet was first created, the creators did not predict that the Internet would become as large as it is today.
- This resulted in wasted address space like the examples I showed you (there are many more examples).
- The IETF (Internet Engineering Task Force) introduced CIDR in 1993 to replace the 'classful' addressing system.




#### CIDR (Classless Inter-Domain Routing)

- With CIDR, the requirements of...
- Class A = /8
- Class B = /16
- Class C = /24
- ...were removed.
- This allowed larger networks to be split into smaller networks, allowing greater efficiency.
- These smaller networks are called 'subnetworks' or 'subnets'.



#### CIDR



number of host bits



#### CIDR Practice!

How many usable addresses are there in each network?


- 203.0.113.0/25
- 203.0.113.0/26
- 203.0.113.0/27
- 203.0.113.0/28
- 203.0.113.0/29
- 203.0.113.0/30
- 203.0.113.0/31
- 203.0.113.0/32

 $2^{n} - 2 = usable addresses$ 

n = number of host bits




### CIDR (/25)



 $2^{7} - 2 = 126$  usable addresses.




### CIDR (/26)



 $2^6 - 2 = 62$  usable addresses.




# CIDR (/27)



 $2^5 - 2 = 30$  usable addresses.




### CIDR (/28)



- - $2^4 2 = 14$  usable addresses.




# CIDR (/29)



 $2^3 - 2 = 6$  usable addresses.




# CIDR (/30)



 $2^2 - 2 = 2$  usable addresses.



### CIDR (/30)




203.0.113.0/30

= 203.0.113.0 - 203.0.113.3

The remaining addresses in the 203.0.113.0/24 address block (203.0.113.4 - 203.0.113.255) are now available to be used in other subnets!




# CIDR (/31)



 $2^{1} - 2 = 0$  usable addresses.



#### CIDR (/31)



203.0.113.0/31


= 203.0.113.0 - 203.0.113.1

Router(config-if)#ip address 203.0.113.0 255.255.255.254
% Warning: use /31 mask on non point-to-point interface cautiously
Router(config-if)#

The remaining addresses in the 203.0.113.0/24 address block (203.0.113.2 - 203.0.113.255) are now available to be used in other networks!



# CIDR (/32)



- 203 . 0 . 113 . 0
- - 255 · 255 · 255 · 255
    - $2^{\circ} 2 = -1$  usable addresses?




#### CIDR Notation

Dotted Decimal	CIDR Notation		
255.255.255.128	/25		
255.255.255.192	/26		
255.255.255.224	/27		
255.255.255.240	/28		
255.255.255.248	/29		
255.255.252	/30		
255.255.254	/31		
255.255.255	/32		




# Subnetting





### Subnetting



192.168.1.0/24

Divide the 192.168.1.0/24 network into four subnets that can accommodate the number of hosts required.



$$2^2 - 2 = 2$$
 usable addresses

$$2 * 2 = 4$$



$$2^3 - 2 = 6$$
 usable addresses



$$2^4 - 2 = 14$$
 usable addresses



$$2^5 - 2 = 30$$
 usable addresses




$$2^6 - 2 = 62$$
 usable addresses



#### QUIZ

The first subnet (Subnet 1) is 192.168.1.0/26. What are the remaining subnets?

HINT: Find the broadcast address of Subnet 1. The next address is the network address of Subnet 2. Repeat the process for Subnets 3 and 4.



192.168.1.0/24



# Things we covered

- CIDR (Classless Inter-Domain Routing)
- The process of subnetting (basics!)