

File-System Implementation

- File Allocation Methods
- Free-Space Management
- Efficiency and Performance
- Recovery

File-System Implementation

- ❖ File Control Block contains many details about the file
 - ❖ inode number, permissions, size, dates

file permissions

file dates (create, access, write)

file owner, group, ACL

file size

file data blocks or pointers to file data blocks


Contiguous Allocation

- An allocation method refers to how disk blocks are allocated for files:
- Contiguous allocation each file occupies set of contiguous blocks
 - Best performance in most cases
 - Simple only starting location (block #) and length (number of blocks) are required
 - Problems include finding space for file, knowing file size, external fragmentation, need for compaction off-line (downtime) or on-line

Contiguous Allocation

2

- Mapping from logical to physical
 - Block to be accessed = starting address
 - Displacement into block = length




Extent-Based Systems


- Many newer file systems (i.e., Veritas File System) use a modified contiguous allocation scheme
- Extent-based file systems allocate disk blocks in extents
- An extent is a contiguous block of disks
 - Extents are allocated for file allocation
 - ❖ A file consists of one or more extents

Linked Allocation

- Linked allocation each file a linked list of blocks
 - File ends at nil pointer
 - ❖ No external fragmentation
 - Each block contains pointer to next block
 - ❖ No compaction, external fragmentation
 - Free space management system called when new block needed
 - Improve efficiency by clustering blocks into groups but increases internal fragmentation
 - Reliability can be a problem
 - Locating a block can take many I/Os and disk seeks


Linked Allocation






Indexed Allocation

- Indexed allocation
 - Each file has its own index block(s) of pointers to its data blocks
- Logical view






Indexed Allocation


- Need index table
- Random access
- Dynamic access without external fragmentation, but have overhead of index block
- Single Level and Multilevel Index for small and large files

Indexed Allocation



UNIX UFS

4K bytes per block, 32-bit addresses




More index blocks than can be addressed with 32-bit file pointer

Performance

- Best method depends on file access type
 - Contiguous great for sequential and random
- Linked good for sequential, not random
- ❖ Declare access type at creation → select either contiguous or linked
- ❖ Indexed more complex multiple index block reads.

Free-Space Management

- File system maintains free-space list to track available blocks
- ❖ Bit vector or bit map (n blocks)



$$bit[i] = \begin{cases} 1 \Rightarrow block[i] \text{ free} \\ 0 \Rightarrow block[i] \text{ occupied} \end{cases}$$

Free-Space Management

- Bit map requires extra space
 - ❖ Example:

```
block size = 4KB = 2^{12} bytes
```

disk size = 2^{40} bytes (1 terabyte)


$$n = 2^{40}/2^{12} = 2^{28}$$
 bits (or 32MB)

Easy to get contiguous files

Linked Free Space List on Disk

Linked list (free list)

- Cannot get contiguous space easily
- No waste of space
- No need to traverse the entire list (if # free blocks recorded)



Free-Space Management

Grouping

❖ Modify linked list to store address of next n-1 free blocks in first free block, plus a pointer to next block that contains free-block-pointers (like this one)

Counting

- Because space is frequently contiguously used and freed, with contiguous-allocation allocation, extents, or clustering
 - Keep address of first free block and count of following free blocks
 - Free space list then has entries containing addresses and counts

Free-Space Management

Space Maps

- ❖ Divides device space into metaslab units and manages metaslabs
 - Given volume can contain hundreds of metaslabs
- Each metaslab has associated space map -uses counting algorithm

Efficiency and Performance


- Efficiency dependents on:
 - Disk allocation and directory algorithms
 - Types of data kept in file's directory entry
 - Pre-allocation or as-needed allocation of metadata structures
 - Fixed-size or varying-size data structures

Efficiency and Performance

- Performance
 - Keeping data and metadata close together
 - Buffer cache separate section of main memory for frequently used blocks
 - Synchronous writes sometimes requested by apps or needed by OS
 - ❖No buffering / caching writes done on disk directly
 - Asynchronous writes more common, buffered, faster


Page Cache and Buffer Cache

- A page cache caches pages rather than disk blocks using virtual memory techniques and addresses
- Memory-mapped I/O uses a page cache
- Routine I/O through the file system uses the buffer (disk) cache



Unified Buffer Cache

A unified buffer cache uses the same page cache to cache both memory-mapped pages and ordinary file system I/O to avoid double caching



Recovery

- Consistency checking compares data in directory structure with data blocks on disk, and tries to fix inconsistencies
 - Can be slow and sometimes fails
- Use system programs to back up data from disk to another storage device (magnetic tape, other magnetic disk, optical)
- Recover lost file or disk by restoring data from backup

Log Structured File Systems

- Log structured (or journaling) file systems record each metadata update to the file system as a transaction
- All transactions are written to a log
 - ❖ A transaction is considered committed once it is written to the log
 - The transactions in the log are asynchronously written to the file system structures
- If the file system crashes, all remaining transactions in the log must still be performed
- ❖ Faster recovery from crash, removes chance of inconsistency of metadata



Thank You