



Overview of Memory Management

- Demand Paging
- Copy-on-Write
- Page Replacement
- Allocation of Frames
- Thrashing


Steps in Handling a Page Fault



Page Replacement



Free Frames Allocation



Before allocation

After allocation

Allocation of Frames

- Frame-allocation algorithm determines
 - How many frames to give each process?
 - Which frames to replace?
- Two major allocation schemes
 - fixed allocation
 - priority allocation

Fixed Allocation

- Equal allocation For example, if there are 100 frames (after allocating frames for the OS) and 5 processes, give each process 20 frames
 - Keep some as free frame buffer pool

Proportional Allocation

Proportional allocation – Allocate according to the size of process

$$s_i = \text{size of process } p_i$$

$$S = \sum S_i$$

m = total number of frames

$$a_i$$
 = allocation for $p_i = \frac{S_i}{S} \times m$

$$m = 64$$

$$s_1 = 10$$

$$s_2 = 127$$

$$a_1 = \frac{10}{137} \times 64 \approx 4$$

$$a_2 = \frac{127}{137} \times 64 \approx 57$$

Priority Allocation

- Use a proportional allocation scheme using priorities rather than size
- \Leftrightarrow If process P_i generates a page fault,
 - select for replacement one of its frames
 - select for replacement a frame from a process with lower priority number

Global vs. Local Allocation


- Global replacement process selects a replacement frame from the set of all frames; one process can take a frame from another
 - But then process execution time can vary greatly
 - But greater throughput so more common

- Local replacement each process selects from only its own set of allocated frames
 - More consistent per-process performance
 - But possibly underutilized memory

Thrashing

- If a process does not have enough pages, the page-fault rate is high
 - Page fault to get page
 - Replace existing frame
 - But quickly need replaced frame back
 - This leads to:
 - Low CPU utilization
 - Operating system thinking that it needs to increase the degree of multiprogramming
 - Another process added to the system
 - ❖ Thrashing = a process is busy swapping pages in and out

Thrashing




Demand Paging and Thrashing

- Why does demand paging work? Locality model
 - Process migrates from one locality to another
 - Localities may overlap

- Why does thrashing occur?
 - ∑ size of locality > total memory size
 - Limit effects by using local or priority page replacement

Working-Set Model

- Δ = working-set window = a fixed number of page references Example: 10,000 instructions
- WS_i (working set of Process P_i) = Pages referenced in the most recent Δ
 - \diamond if Δ too small will not encompass entire locality
 - ❖ if △ too large will encompass several localities
 - if $\Delta = \infty \Rightarrow$ will encompass entire program



- $D = \sum WS_i \equiv \text{total demand frames (Approximation of locality)}$
- if $D > m \Rightarrow$ Thrashing; if D > m, then suspend/swap out processes

How to compute Working-Set?


- ❖ Approximate with interval timer + a reference bit
- **Example:** $\Delta = 10,000$: Timer interrupts after every 5000 time units
 - 2 history bits for each page is kept in memory
 - Whenever a timer interrupts, copy the reference bit to history bit.
 - Sets the values of all reference bits to 0
 - During page fault, if one of the history bits = $1 \Rightarrow$ page in working set

How to compute Working-Set?

- Why counter, history and reference bits approach not completely accurate?
- Improvement = 10 bits and interrupt every 1000 time units


Page-Fault Frequency

- More direct approach than WSS
- Establish acceptable page-fault frequency (PFF) rate and use local replacement policy
 - If actual rate too low, process loses frame
 - If actual rate too high, process gains frame



Working Sets and Page Fault Rates

- Direct relationship between working set of a process and its page-fault rate
- Working set changes over time
- Peaks and valleys over time




Buddy System

- Allocates memory from fixed-size segment consisting of physicallycontiguous pages
- Memory allocated using power-of-2 allocator
 - Satisfies requests in units sized as power of 2
 - Request rounded up to next highest power of 2
 - When smaller allocation needed than is available, current chunk split into two buddies of next-lower power of 2
 - Continue until appropriate sized chunk available
- Advantage quickly coalesce unused chunks into larger chunk
- Disadvantage fragmentation

Buddy System Allocator

- ❖ Assume 256KB chunk available
- ❖ Kernel requests 21KB
 - ❖ Split into A_{L and} A_R of 128KB each
 - ❖ One further divided into B_L and B_R of 64KB
 - ❖ One further into C_L and C_R of 32KB each
 - One used to satisfy request



Prepaging

- Reduce the large number of page faults that occurs at process startup
- Prepage all or some of the pages a process will need, before they are referenced
- But if prepaged pages are unused, I/O and memory was wasted
- \diamondsuit Assume s pages are prepaged and α of the pages is used
- Cost of s * α saved pages faults vs cost of prepaging s * (1-α) unnecessary pages
- $\Leftrightarrow \alpha$ near zero \Rightarrow prepaging loses

Page Size

- Sometimes OS designers have a choice on custom-built CPU
- Page size selection criteria:
 - Fragmentation and Resolution
 - Page table size
 - ❖ I/O overhead
 - Number of page faults
 - Locality
 - TLB size and effectiveness
- ❖ Always power of 2, usually in the range 2¹² to 2²²

TLB Reach

- TLB Reach The amount of memory accessible from the TLB
- ❖ TLB Reach = (TLB Size) X (Page Size)
- Ideally, the working set of each process is stored in the TLB
 - Otherwise there is more time spend in resolving memory references in page table (delay).
- Increase the Page Size
 - This may lead to an increase in fragmentation as not all applications require a large page size
- Provide Multiple Page Sizes
 - This allows applications that require larger page sizes the opportunity to use them without an increase in fragmentation

Program Structure

- ❖ int[128,128] data; Each row is stored in one page
- ❖ A page can store 128 words

```
Program 1 [128 x 128 = 16,384 page faults]
```

```
for (j = 0; j <128; j++)

for (i = 0; i < 128; i++)

data[i,j] = 0;
```

Program 2 [128 page faults]


```
for (i = 0; i < 128; i++)

for (j = 0; j < 128; j++)

data[i,j] = 0;
```

I/O interlock

- I/O Interlock Pages must sometimes be locked into memory
- Consider I/O Pages that are used for copying a file from a device must be locked from being selected for eviction by a page replacement algorithm
- When I/O is complete pages are unlocked





Thank You