FS(5)

FreeBSD File Formats Manual

FS

NAME

```
fs, inode -- format of file system volume
```

SYNOPSIS

```
#include <sys/param.h>
#include <ufs/ffs/fs.h>

#include <sys/types.h>
#include <sys/lock.h>
#include <sys/extattr.h>
#include <sys/acl.h>
#include <ufs/ufs/quota.h>
#include <ufs/ufs/dinode.h>
#include <ufs/ufs/extattr.h>
```

DESCRIPTION

The files <fs.h> and <inode.h> declare several structures, defined var ables and macros which are used to create and manage the underlying fo mat of file system objects on random access devices (disks).

The block size and number of blocks which comprise a file system are parameters of the file system. Sectors beginning at BBLOCK and contining for BBSIZE are used for a disklabel and for some hardware primary secondary bootstrapping programs.

The actual file system begins at sector SBLOCK with the super-block th is of size SBLOCKSIZE. The following structure describes the super-bl and is from the file < ufs/ffs/fs.h>:

```
/*
* Super block for an FFS filesystem.
*/
struct fs {
       int32 t fs firstfield;
                                   /* historic filesystem linked list,
       int32 t fs unused 1;
                                         used for incore super blocks
                                  /* offset of super-block in filesys
       int32 t fs sblkno;
       int32 t fs cblkno;
                                  /* offset of cyl-block in filesys *
                                  /* offset of inode-blocks in filesy
       int32_t fs_iblkno;
                                  /* offset of first data after cg */
       int32_t fs_dblkno;
        int32 t fs old cgoffset;
                                  /* cylinder group offset in cylinde
                                  /* used to calc mod fs ntrak */
        int32_t fs_old_cgmask;
        int32_t fs_old_time;
                                  /* last time written */
```

```
/* number of blocks in fs */
        int32 t fs old size;
                                  /* number of data blocks in fs */
        int32 t fs old dsize;
        int32_t fs_ncg;
                                  /* number of cylinder groups */
                                  /* size of basic blocks in fs */
        int32 t fs bsize;
        int32_t fs_fsize;
                                  /* size of frag blocks in fs */
        int32 t fs frag;
                                  /* number of frags in a block in fs
/* these are configuration parameters */
        int32 t fs minfree;
                                  /* minimum percentage of free block
        int32 t fs old rotdelay; /* num of ms for optimal next block
        int32 t fs old rps;
                                  /* disk revolutions per second */
/* these fields can be computed from the others */
                                  /* ``blkoff'' calc of blk offsets *
        int32 t fs bmask;
                                  /* ``fragoff'' calc of frag offsets
       int32 t fs fmask;
                                  /* ``lblkno'' calc of logical blkno
        int32 t fs bshift;
        int32 t fs fshift;
                                  /* ``numfrags'' calc number of frag
/* these are configuration parameters */
        int32 t fs maxcontig;
                                  /* max number of contiguous blks */
                                  /* max number of blks per cyl group
        int32 t fs maxbpg;
/* these fields can be computed from the others */
        int32 t fs fragshift;
                                  /* block to frag shift */
                                  /* fsbtodb and dbtofsb shift consta
        int32_t fs_fsbtodb;
                                  /* actual size of super block */
        int32 t fs sbsize;
                                  /* old fs csmask */
        int32 t fs spare1[2];
                                  /* old fs csshift */
                                  /* value of NINDIR */
        int32 t fs nindir;
        int32 t fs inopb;
                                  /* value of INOPB */
                                  /* value of NSPF */
        int32 t fs old nspf;
/* yet another configuration parameter */
        int32 t fs optim;
                                  /* optimization preference, see bel
                                  /* # sectors/track including spares
        int32_t fs_old_npsect;
        int32 t fs old interleave; /* hardware sector interleave */
        int32 t fs old trackskew; /* sector 0 skew, per track */
                                  /* unique filesystem id */
        int32 t fs id[2];
/* sizes determined by number of cylinder groups and their sizes */
        int32 t fs old csaddr;
                                  /* blk addr of cyl grp summary area
                                  /* size of cyl grp summary area */
        int32 t fs cssize;
                                  /* cylinder group size */
        int32 t fs cgsize;
        int32 t fs spare2;
                                  /* old fs ntrak */
                                  /* sectors per track */
        int32 t fs old nsect;
                                  /* sectors per cylinder */
       int32_t fs_old_spc;
       int32_t fs_old_ncyl;
                                  /* cylinders in filesystem */
                                  /* cylinders per group */
        int32_t fs_old_cpg;
                                  /* inodes per group */
        int32_t fs_ipg;
        int32 t fs fpg;
                                  /* blocks per group * fs frag */
/* this data must be re-computed after crashes */
               csum fs old cstotal; /* cylinder summary information *
/* these fields are cleared at mount time */
        int8 t
                fs fmod;
                                  /* super block modified flag */
```

```
fs clean;
                                  /* filesystem is clean flag */
        int8 t
                                  /* mounted read-only flag */
        int8 t fs ronly;
                                  /* old FS flags */
        int8_t fs_old_flags;
       u_char fs_fsmnt[MAXMNTLEN]; /* name mounted on */
                fs_volname[MAXVOLLEN]; /* volume name */
       u char
       uint64 t fs swuid;
                                  /* system-wide uid */
                                  /* due to alignment of fs swuid */
        int32 t fs pad;
/* these fields retain the current block allocation info */
                                  /* last cg searched */
        int32 t fs cgrotor;
               *fs ocsp[NOCSPTRS]; /* padding; was list of fs cs buff
       void
                                  /* # of contiquously allocated dirs
       uint8 t *fs contigdirs;
       struct csum *fs csp;
                                  /* cg summary info buffer for fs cs
                                  /* max cluster in each cyl group */
       int32 t *fs maxcluster;
                                  /* used by snapshots to track fs */
       u int
              *fs active;
        int32 t fs old cpc;
                                  /* cyl per cycle in postbl */
                                  /* maximum blocking factor permitte
        int32 t fs maxbsize;
        int64 t fs unrefs;
                                  /* number of unreferenced inodes */
        int64 t fs sparecon64[16]; /* old rotation block list head */
        int64 t fs sblockloc;
                                  /* byte offset of standard superblo
       struct csum total fs cstotal; /* cylinder summary informatio
                                  /* last time written */
       ufs time t fs time;
                                  /* number of blocks in fs */
       int64 t fs size;
                                  /* number of data blocks in fs */
       int64 t fs dsize;
       ufs2 daddr t fs csaddr;
                                  /* blk addr of cyl grp summary area
        int64_t fs_pendingblocks; /* blocks in process of being freed
        int32 t fs pendinginodes; /* inodes in process of being freed
        int32 t fs snapinum[FSMAXSNAP]; /* list of snapshot inode num
        int32 t fs avgfilesize;
                                  /* expected average file size */
                                  /* expected # of files per director
        int32 t fs avgfpdir;
                                  /* save real cg size to use fs_bsiz
        int32 t fs save cqsize;
        int32 t fs sparecon32[26]; /* reserved for future constants *
                                  /* see FS flags below */
        int32 t fs flags;
        int32 t fs contigsumsize; /* size of cluster summary array */
        int32 t fs maxsymlinklen; /* max length of an internal symlin
        int32 t fs old inodefmt;
                                  /* format of on-disk inodes */
                                  /* maximum representable file size
       uint64 t fs maxfilesize;
                                  /* ~fs bmask for use with 64-bit si
        int64 t fs qbmask;
                                  /* ~fs fmask for use with 64-bit si
        int64 t fs qfmask;
                                  /* validate fs clean field */
        int32 t fs state;
        int32 t fs old postblformat; /* format of positional layout t
                                  /* number of rotational positions *
       int32 t fs old nrpos;
                                  /* old fs postbloff */
        int32_t fs_spare5[2];
                                  /* old fs rotbloff */
        int32 t fs magic;
                                  /* magic number */
};
/*
```

* Filesystem identification

```
*/
#define FS UFS1 MAGIC
                       0x011954 /* UFS1 fast filesystem magic numb
                       0x19540119 /* UFS2 fast filesystem magic numb
#define FS UFS2 MAGIC
                       0x7c269d38 /* superblock checksum */
#define FS OKAY
#define FS_42INODEFMT
                       -1
                              /* 4.2BSD inode format */
                       2 /* 4.4BSD inode format */
#define FS 44INODEFMT
/*
 * Preference for optimization.
 */
#define FS OPTTIME
                       0
                              /* minimize allocation time */
                              /* minimize disk fragmentation */
#define FS OPTSPACE
                       1
```

Each disk drive contains some number of file systems. A file system c sists of a number of cylinder groups. Each cylinder group has inodes data.

A file system is described by its super-block, which in turn describes the cylinder groups. The super-block is critical data and is replicat in each cylinder group to protect against catastrophic loss. This is done at file system creation time and the critical super-block data do not change, so the copies need not be referenced further unless disast strikes.

Addresses stored in inodes are capable of addressing fragments of `blocks'. File system blocks of at most size MAXBSIZE can be optional broken into 2, 4, or 8 pieces, each of which is addressable; these pie may be DEV_BSIZE, or some multiple of a DEV_BSIZE unit.

Large files consist of exclusively large data blocks. To avoid undue wasted disk space, the last data block of a small file is allocated as only as many fragments of a large block as are necessary. The file sy tem format retains only a single pointer to such a fragment, which is piece of a single large block that has been divided. The size of such fragment is determinable from information in the inode, using the **blksize**(fs, ip, lbn) macro.

The file system records space availability at the fragment level; to determine block availability, aligned fragments are examined.

The root inode is the root of the file system. Inode 0 cannot be used for normal purposes and historically bad blocks were linked to inode 1 thus the root inode is 2 (inode 1 is no longer used for this purpose, however numerous dump tapes make this assumption, so we are stuck with it).

The fs_minfree element gives the minimum acceptable percentage of file system blocks that may be free. If the freelist drops below this leve

only the super-user may continue to allocate blocks. The fs_minfree e ment may be set to 0 if no reserve of free blocks is deemed necessary, however severe performance degradations will be observed if the file s tem is run at greater than 90% full; thus the default value of fs_minf is 8%.

Empirically the best trade-off between block fragmentation and overall disk utilization at a loading of 90% comes with a fragmentation of 8, thus the default fragment size is an eighth of the block size.

The element fs_optim specifies whether the file system should try to m imize the time spent allocating blocks, or if it should attempt to min mize the space fragmentation on the disk. If the value of fs_minfree (see above) is less than 8%, then the file system defaults to optimizi for space to avoid running out of full sized blocks. If the value of minfree is greater than or equal to 8%, fragmentation is unlikely to b problematical, and the file system defaults to optimizing for time.

Cylinder group related limits: Each cylinder keeps track of the availability of blocks at different rotational positions, so that sequentia blocks can be laid out with minimum rotational latency. With the defa of 8 distinguished rotational positions, the resolution of the summary information is 2ms for a typical 3600 rpm drive.

The element $fs_old_rotdelay$ gives the minimum number of milliseconds t initiate another disk transfer on the same cylinder. It is used in determining the rotationally optimal layout for disk blocks within a file; the default value for fs old rotdelay is 2ms.

Each file system has a statically allocated number of inodes. An inodis allocated for each NBPI bytes of disk space. The inode allocation strategy is extremely conservative.

MINBSIZE is the smallest allowable block size. With a MINBSIZE of 409 it is possible to create files of size 2^32 with only two levels of in rection. MINBSIZE must be big enough to hold a cylinder group block, thus changes to (struct cg) must keep its size within MINBSIZE. Note that super-blocks are never more than size SBLOCKSIZE.

The path name on which the file system is mounted is maintained in fs_fsmnt. MAXMNTLEN defines the amount of space allocated in the supe block for this name. The limit on the amount of summary information p file system is defined by MAXCSBUFS. For a 4096 byte block size, it i currently parameterized for a maximum of two million cylinders.

Per cylinder group information is summarized in blocks allocated from first cylinder group's data blocks. These blocks are read in from fs_csaddr (size fs_cssize) in addition to the super-block.

N.B.: sizeof(struct csum) must be a power of two in order for the fs_c macro to work.

The Super-block for a file system: The size of the rotational layout tables is limited by the fact that the super-block is of size SBLOCKSI The size of these tables is inversely proportional to the block size of the file system. The size of the tables is increased when sector size are not powers of two, as this increases the number of cylinders inclu before the rotational pattern repeats (fs_cpc). The size of the rotational layout tables is derived from the number of bytes remaining in (struct fs).

The number of blocks of data per cylinder group is limited because cyl der groups are at most one block. The inode and free block tables mus fit into a single block after deducting space for the cylinder group structure (struct cq).

The *Inode*: The inode is the focus of all file activity in the UNIX fil system. There is a unique inode allocated for each active file, each current directory, each mounted-on file, text file, and the root. An inode is `named' by its device/i-number pair. For further information see the include file <ufs/ufs/inode.h>.

The format of an external attribute is defined by the extattr structur

Several macros are defined to manipulate these structures. Each macro takes a pointer to an extattr structure.

```
EXTATTR_NEXT(eap)

Returns a pointer to the next extended attribute following eap.

EXTATTR_CONTENT(eap)

Returns a pointer to the extended attribute content referenced by eap.
```

EXTATTR_CONTENT_SIZE(eap) Returns the size of the extended attribute content referenced by eap.

EXTATTR_SET_LENGTHS(eap, size) Called with the size of the attribute

content after initializing the attribu name to calculate and set the ea_lengt ea_namelength, and ea_contentpadlen fields of the extended attribute structure.

The following code identifies an ACL:

```
if (eap->ea_namespace == EXTATTR_NAMESPACE_SYSTEM &&
  !strcmp(eap->ea_name, POSIX1E_ACL_ACCESS_EXTATTR_NAME) {
    aclp = EXTATTR_CONTENT(eap);
    acllen = EXTATTR_CONTENT_SIZE(eap);
    ...
}
```

The following code creates an extended attribute containing a copy of structure mygif:

```
eap->ea_namespace = EXTATTR_NAMESPACE_USER;
strcpy(eap->ea_name, "filepic.gif");
EXTATTR_SET_LENGTHS(eap, sizeof(struct mygif));
memcpy(EXTATTR_CONTENT(eap), &mygif, sizeof(struct mygif));
```

HISTORY

A super-block structure named filsys appeared in Version 6 AT&T UNIX. The file system described in this manual appeared in 4.2BSD.

FreeBSD 11.2

April 23, 2016

FreeBSD 1