# 西南林业大学 本科毕业(设计)论文

(二〇一八届)

题	目:_	RongOS — 简单操作系统的实现
分院系	<b>系部</b> :	大数据与智能工程学院
专	业:	计算机科学与技术专业
姓	· 名:	蒲启元
导师姓	- 性名:	王晓林
- 导师职称:		讲师

### RongOS — 简单操作系统的实现

### 蒲启元

(西南林业大学 大数据与智能工程学院, 云南昆明 650224)

摘 要:操作系统管理着计算机的硬件和软件资源,它是向上层应用软件提供服务 (接口)的核心系统软件,这些服务包括进程管理,内存管理,文件系统,网络通信,安全机制等。操作系统的设计与实现则是软件工业的基础。为此,在国务院提出的《中国制造 2025》中专门强调了操作系统的开发<sup>[1]</sup>。但长期以来,操作系统核心开发技术都掌握在外国人手中,技术受制,对于我们的软件工业来说很不利。本项目从零开始设计开发个简单的操作系统,包括 boot loader,中断,内存管理,图形接口,多任务,以及在这个系统上的几个小应用等。尽管这个系统很简单,但它为自主开发操作系统做了尝试。

关键词: 操作系统, 进程, 内存, 中断, boot loader

### **RongOS** — A simple OS implementation

Qiyuan Pu

School of Big Data and Intelligence Engineering Southwest Forestry University Kunming 650224, Yunnan, China

**Abstract:** Operating system manages the resources of hardware and software, it lies in the core of the system software and provides services(interfaces) to upper applications. These services include process management, memory management, file system, network communication, security mechanism and more. Operating system development is the foundation and core of software industry. Therefore, *Made in China 2025* emphasizes the development of operating system that put forward by The State Council of China. For a long time, however, the OS kernel development technology is mastered by foreigner, due to technical limitations it is detrimental to our software industry. So this project will design and develop a simple operating system, including boot loader, interrupt, memory management, graphic interface, multitasking, and some little applications based on this system. In spite of the simplicity of this system, it's a small trying for autonomous development operating system.

**Key words:** operating system, boot loader, process, interrupt, memory management

# 目 录

1	Intr	oduction	1	
	1.1	Background	1	
	1.2	Preliminary Works	1	
		1.2.1 Development Environment	1	
		1.2.2 Tools	2	
		1.2.3 Platform Setup	2	
2	ding Knowledge	3		
	2.1	Instruction Set	3	
	2.2	x86 Registers	4	
	2.3	Interrupt Call	5	
	2.4	Memory Map	5	
	2.5	Floppy Disk	6	
3	Desi	gn	8	
	3.1	Top Level Design	8	
		3.1.1 32-bit Mode and Import C Codes	8	
4	Imp	plementation		
	4.1	Boot Loader	9	
		4.1.1 Flowchart of Boot Loader	9	
		4.1.2 Running Result	10	
	4.2	32-bit Mode and Import C Codes	12	
	4.3	Screen Display and Text	12	
	4.4	Control Mouse	12	
	4.5	Memory Management	12	
	4.6	Making Window	12	

### 目 录

	4.7	Timer		. 12
	4.8	Multita	asking	. 12
	4.9	Comm	nand Line Window	. 12
	4.10	API .		. 12
	4.11	OS Pro	otection	. 12
	4.12	Graphi	ics Processing	. 12
	4.13	Windo	ow Operation	. 12
	4.14	Applic	cation Protection	. 12
	4.15	File O <sub>I</sub>	peration	. 12
	4.16	Some A	Applications	. 12
5	Pros	pects A	And Shortages	13
参	考文酶	犬		14
指	导教师	币简介		14
致	谢			16
A	Mair	ı Progr	ram Code	17
	A.1	Boot lo	oader	. 17
		A.1.1	Display boot information	. 17
		A.1.2	Read the second sector	. 17
		A.1.3	Read two sides of a track	. 18
		A.1.4	The next cylinder	. 19

# 插图目录

2-1	Floppy Disk Structure	6
4-1	Flowchart of Boot Loader	9
4-2	Running Result of Boot Loader	10

# 表格目录

# **Todo list**

compiler?	2
debugger?	2
need more words	2
What's Qemu?	2
What's Wine?	2
need rephrase	2
Figure: System overview diagram	8
need a better chart	Ö
need a better pic.	10

Introduction 1

**Background** 1.1

Contemporary software systems are beset by problems that create challenges and op-

portunities for broad new OS research. There are five areas could improve user experience

including dependability, security, system configuration, system extension, and multiproces-

sor programming.

The products of forty years of OS research are sitting in everyone's desktop computer,

cell phone, car, etc., and it is not a pretty picture. Modern software systems are broadly speak-

ing complex, insecure, unpredictable, prone to failure, hard to use, and difficult to maintain.

Part of the difficult is that good software is hard to write, but in the past decade, this prob-

lem and more specific shortcomings in systems have been greatly exacerbated by increased

networking and embedded systems, which placed new demands that existing architectures

struggled to meet. These problems will not have simple solutions, but the changes must be

pervasive, starting at the bottom of the software stack, in the operating system.

The world needs broad operating system research. Dependability, security, system con-

figuration, system extension, and multi-processor programming illustrate areas were contem-

porary operating systems have failed to meet the software challenges of the modern comput-

ing environment.

1.2 **Preliminary Works** 

1.2.1 **Development Environment** 

OS platform: Debian 9, Linux kernel 4.12.0-1-amd64

Editor: GNU Emacs 25.2.2

**Run time VM:** QEMU emulator 2.8.1

-1-

**Assembler:** Nask.

Compiler: \_\_\_\_\_\_compiler?

Debugger: \_\_\_\_\_\_ debugger?

#### **1.2.2** Tools

Some tools used to develop RongOS, see tools.<sup>1</sup>.

need more words.

### 1.2.3 Platform Setup

Debian System: there is a small tutorial.<sup>2</sup>

#### Qemu

### What's Qemu?

QEMU, for my x86\_64 architecture:

\$ sudo apt-get install qemu-system-x86\_64

#### Wine

#### What's Wine?

Note that the tools is exe formate, so on Debian system, you need to install wine:

\$ sudo apt-get update

\$ sudo apt-get update

\$ sudo apt-get install wine

#### Debian i386 support

Maybe you also need to add i386 architecture cause of AMD64 on your machine to use

these tools:\_\_\_\_\_\_need sudo dpkg --add-architecture i386

\_\_\_\_\_\_

https://github.com/Puqiyuan/RongOS/tree/master/Tools
http://cs2.swfc.edu.cn/~wx672/lecture\_notes/linux/install.html

### 2 Leading Knowledge

### 2.1 Instruction Set

An instruction set architecture (ISA) is an abstract model of a computer. It is also referred to as architecture or computer architecture. An ISA defines everything a machine language programmer needs to know in order to program a computer.

An ISA may be classified in a number of different ways. A common classification is by architectural complexity. A complex instruction set computer (CISC) has many specialized instructions, some of which may only be rarely used in practical programs. A reduced instruction set computer (RISC) simplifies the processor by efficiently implementing only the instructions that are frequently used in programs, while the less common operations are implemented as subroutines, having their resulting additional processor execution time offset by infrequent use.

On traditional architectures, an instruction includes an opcode that specifies the operation to perform, such as add contents of memory to register—and zero or more operand specifiers, which may specify registers, memory locations, or literal data. The simple OS is based on x86 architecture, the following instructions are common for RongOS:

**db:** the abbreviation of define byte, write a byte, also 8 bits to file.

**resb:** the abbreviation of reserve byte, reserved bytes and filling 0x00 in these reserved space.

**dw:** the abbreviation of define word, write two bytes, also 16 bits to file.

**dd:** the abbreviation of define double-word, write four bytes, also 32 bits to file.

**org:** load the program to specified address.

**jmp:** jump to another instruction.

**mov:** assign the right value to left variable.

**jc:** the abbreviation of jump if carry, it means if carry flag is 1, jump.

### 2.2 x86 Registers

In computer architecture, a processor register is a quickly accessible location available to a computer's central processing unit (CPU). Registers usually consist of a small amount of fast storage, although some registers have specific hardware functions, and may be read-only or write-only. Almost all computers, whether load/store architecture or not, load data from a larger memory into registers where it is used for arithmetic operations and is manipulated or tested by machine instructions. Manipulated data is then often stored back to main memory, either by the same instruction or by a subsequent one. Modern processors use either static or dynamic RAM as main memory, with the latter usually accessed via one or more cache levels.

Processor registers are normally at the top of the memory hierarchy, and provide the fastest way to access data. The term normally refers only to the group of registers that are directly encoded as part of an instruction, as defined by the instruction set. Registers are normally measured by the number of bits they can hold, for example, an "8-bit register" or a "32-bit register". For x86 architecture, these registers existing:

**ax:** accumulator **dl:** data low **si:** source index

**bx:** base **bh:** base high **di:** destination index

cx: counter ah: accumulator high es: extra segment

**dx:** data **ch:** counter high **cs:** code segment

**bl:** base low **dh:** data high **ss:** stack segment

**al:** accumulator low **sp:** stack pointer **ds:** data segment

**cl:** counter low **bp:** base pointer **fs:** no name

In these registers, bx, bp, si and di can be used to specify the address of memory. But ax, cx, dx and sp can not. When mov instruction using, the number of bit of operation number should be same. 16 bits registers: ax, cx, dx, bx, sp, bp, si, di, es, cs, ss, ds and fs. 8 bits registers: al, cl, dl, bl, ah, ch, dh and bh. Actually, all these 8 bits registers are part of corresponding 16 bits registers, low 8 bits or high 8 bits.

### 2.3 Interrupt Call

BIOS interrupt calls perform hardware control or I/O functions requested by a program, return system information to the program, or do both. A key element of the purpose of BIOS calls is abstraction-the BIOS calls perform generally defined functions, and the specific details of how those functions are executed on the particular hardware of the system are encapsulated in the BIOS and hidden from the program. The following interrupt calls are common for RongOS:

Interrupt Number Register Parameter R		Return Value	Function
	ah=0x0e(write character in tty mode)		
0x10	al=character code	null	video services
	bh=0, bl=colorcolor		
	ah=0x02(read sectors)		
	ah=0x03(write sectors)		
	ah=0x04(verify sectors)	FLACS.CF=0	
0x13	ah=0x0c(seek to specified track)	no error, ah = 0	disk services
OAIS	al=number of sectors processing	FLAGS.CF=1	disk services
	ch=cylinder & 0xff cl=sector number	error, ah=error number	
	dh=header number dl=driver number		
	es:bx=buffer address		

### 2.4 Memory Map

In the boot process, a memory map is passed on from the firmware in order to instruct an operating system kernel about memory layout. It contains the information regarding the size of total memory, any reserved regions and may also provide other details specific to the architecture. For load RongOS to memory, the memory lay out should be clarify:

Range(in hexadecimal)	Range(in decimal)	Size(in bytes)	Usage
0000 — 03ff	0000 — 1023	1024	interrupt vector table
0400 — 04ff	1024 — 1279	256	BIOS data area
0500 — 051f	1280 — 1311	32	Reserved
0520 — 7bff	1312 — 31743	30432	conventional memory
7c00 — 7dff	31744 — 32255	512	master boot record
7e00 — 9ffff	32256 — 655359	623104	conventional memory
a0000 — affff	655360 — 720895	64K	VGA graphics RAM
b0000 — b7fff	720896 — 753663	32K	monochrome text mode
b8000 — bffff	753664 — 786431	32K	color text mode
c0000 — c7fff	786432 — 819199	32K	VGA video ROM
c8000 — cbfff	819200 — 835583	16K	IDE hard drive
cc000 — cffff	835584 — 851967	16K	optional adaper

### 2.5 Floppy Disk

There are many ways to boot an operating system, from hard disk, USB, floppy disk,etc.

The structure of floppy disk is simple and for this simple operating system, it's enough.

Fig. 2-1 shows the inside of a floppy disk:




图 2-1 Floppy Disk Structure

A floppy disk, also called a floppy, diskette, or just disk, is a type of disk storage composed of a disk of thin and flexible magnetic storage medium, sealed in a rectangular plastic enclosure lined with fabric that removes dust particles. Floppy disks are read and written by a floppy disk drive (FDD).

For 3.5 inch HD floppy, There are 80 cylinders from the outermost to the core on each


### 2 Leading Knowledge

side, numbering 0, 1, ..., 79. The head can assign be 0 or 1, representing two sides of floppy. When specify head number and cylinder number, forming a ring, named track in jargon. The track is large so we divide it to 18 small parts, named sector. A sector can store 512 byte. So the capacity of a floppy is:

$$18 \times 80 \times 2 \times 512 = 1474560 Byte = 1440 KB$$

# 3 Design

## 3.1 Top Level Design



### 3.1.1 32-bit Mode and Import C Codes

### 4 Implementation

### 4.1 Boot Loader

### 4.1.1 Flowchart of Boot Loader

Fig. 4-1 shows how the boot loader works.

#### need a better chart

#### 图 4-1 Flowchart of Boot Loader

The boot loader is implemented in Intel assembly. It works as following:

- 1. **Display boot information:** Firstly, the boot sector display some boot information, when al=0, the null character of boot information hit. Interrupt 0x10 is used for show a character. Appendix A.1.1 is the code to perform this function.
- 2. **Read the second sector:** Then jump to load C0-H0-S2, ax register saved the address where beginning puts the sectors from floppy. And preparing parameters for interrupt 0x13 in registers. The 0x13 interrupt used for read sector from floppy to memory. Appendix A.1.2 is the code to perform this function.
- 3. **Read two sides of a track:** If there is a carry, representing some thing wrong when read floppy, so reset the registers and try again read floppy, until five times trying. Register si is a counter. If no carry, jump to next segmentation, as one sector read to memory already, the address space should increase 512 byte. Then sector number(cl register) added 1 and compare it to 18, if it's smaller than 18, jump to readloop, read the next sector. If the value of cl register bigger or equal to than 18, meaning that one track 18 sector in this side of floppy read already, then reversed the head, add 1 to dh register. If the value of dh register after adding larger than or equal to 2, it's saying the original head is 1, one track of two sides read already. Otherwise the value of dh register smaller than 2, read this side indicating by dh register, jump to readloop segmentation. Appendix A.1.3 is the code to perform this function.

4. **The next cylinder:** So the next step is moving a cylinder, add 1 to register *ch*. Otherwise the value of *dh* register smaller than 2, read this side indicating by *dh* register, jump to *readloop* segmentation. After *ch* register add 1, if it's smaller than 10, jump to *readloop*, otherwise end loading floppy to memory process, for we only load ten cylinders of floppy. Appendix A.1.4 is the code to perform this function.

### 4.1.2 Running Result

Fig. 4-2 shows the running results of boot loader. From this picture we see that the boot loader loaded 10 cylinders from floppy successfully.

need a better pic.

图 4-2 Running Result of Boot Loader

4.2	32-bit Mode and Import C Codes
4.3	Screen Display and Text
4.4	Control Mouse
4.5	Memory Management
4.6	Making Window
4.7	Timer
4.8	Multitasking
4.9	Command Line Window
4.10	API
4.11	OS Protection
4.12	<b>Graphics Processing</b>
4.13	Window Operation
4.14	Application Protection
4.15	File Operation

**4.16** Some Applications

# **5 Prospects And Shortages**

# 参考文献

[1] 国务院, 中国制造 2025, chinese, **2015-05**.

# 指导教师简介

王晓林, 男, 49岁, 硕士, 讲师, 毕业于英国格林尼治大学, 分布式系统专业, 现任西南林业大学计信学院教师, 执教 Linux、操作系统、网络技术等方面的课程, 有丰富的 Linux 教学和系统管理经验。

### 致 谢

首先我想感谢我的老师,王晓林。大学期间,他给了我很多指导,包括专业方面和上大学的意义等。很多时候,他对学生的要求看起来都是不近情理的,但正是通过这个"痛苦"的过程,我锻炼了坚强的意志,和战胜困难的信心。谢谢你,王老师。我最想感谢的是我的女友,她容忍我在完成这个设计时的很多个夜晚不陪她,给我支持,鼓励我,不抱怨。所以我愿意把这个简单操作系统命名为 RongOS,蓉便是她名字的最后一个字。谢谢你,我最亲爱的。

# 附录 A Main Program Code

### A.1 Boot loader

### A.1.1 Display boot information

```
init:

mov al, [si]
add si, 1 ; increment by 1.

cmp al, 0

je load ; if al == 0, jmp to load, the msg_init info

displayed.

the lastest character is null character, coding in 0.

mov ah, 0x0e ; write a character in TTY mode.
mov bx, 15 ; specify the color of the character.
int 0x10 ; call BIOS function, video card is number 10.
jmp init
```

#### A.1.2 Read the second sector

```
readloop:

mov si, 0 ; si register is a counter, try read a sector
; five times.

retry:

mov ah, 0x02 ; parameter 0x02 to ah, read disk.

mov al, 1 ; parameter 1 to al, read disk.

mov bx, 0

mov dl, 0x00 ; the number of driver number.

int 0x13 ; after prepared parameters, call 0x13

interrupted.
```

### A.1.3 Read two sides of a track

```
jnc next; if no carry read next sector.

add si, 1; tring again read sector, counter add 1.

cmp si, 5; until five times

jae error; if tring times large than five, failed.

; reset the status of floppy and read again.

mov ah, 0x00

mov dl, 0x00

int 0x13

jmp retry

next:

mov ax, es

; we can not directly add to es register.

add ax, 0x0020; add 0x0020 to ax
```

```
mov es, ax; the memory increase 0x0020 * 16 = 512 byte.

; size of a sector.

add cl, 1; sector number add 1.

cmp cl, 18; one track have 18 sector.

jbe readloop; jump if below or equal 18, read the next

sector.

mov cl, 1; cl number reset to 1, ready to read the other

side.

add dh, 1; the other side of floppy.

cmp dh, 2; only two sides of floppy.

jb readloop; if dh < 2, read 18 sectors of the other

sides
```

### A.1.4 The next cylinder

```
mov dh, 0 ; after finished read the other side, reset head to 0.
add ch, 1 ; two sides of a cylinder readed, add 1 to ch.
cmp ch, CYLS ; read 10 cylinders.
jb readloop
```