# 西南林业大学 本科毕业(设计)论文

(二〇一八届)

题	目:	RongOS — 一个简单操作系统的
		设计与实现
八份	不逊。	
分阮	系部:_	大数据与智能工程学院
专	₩:_	计算机科学与技术专业
姓	名:_	蒲启元
导师	姓名:_	王晓林
导师	职称:	讲师

# RongOS — 一个简单操作系统的设计与实现

## 蒲启元

(西南林业大学 大数据与智能工程学院,云南昆明 650224)

摘 要:操作系统管理着计算机的硬件和软件资源,它是向上层应用软件提供服务(接口)的核心系统软件,这些服务包括进程管理,内存管理,文件系统,网络通信,安全机制等。操作系统的设计与实现则是软件工业的基础。为此,在国务院提出的《中国制造2025》中专门强调了操作系统的开发<sup>[1]</sup>。但长期以来,操作系统核心开发技术都掌握在外国人手中,技术受制,对于我们的软件工业来说很不利。本项目从零开始设计开发一个简单的操作系统,包括 boot loader,中断,内存管理,图形接口,多任务等功能模块,以及能运行在这个系统之上的几个小应用程序。尽管这个系统很简单,但它是自主开发操作系统的一次尝试。

关键词:操作系统,进程,内存,中断,boot loader

# *RongOS* — A simple OS implementation

Qiyuan PU

School of Big Data and Intelligence Engineering Southwest Forestry University Kunming 650224, Yunnan, China

**Abstract:** Operating system manages the hardware and software resources in a running computer system. It is the core of any modern software system and provides services (interfaces) to upper layer applications. The services it provides include process management, memory management, file system, network communication, security mechanism and more. Operating system development is the foundation and core of software industry. Therefore, *Made in China 2025* emphasizes the development of operating system that put forward by The State Council of China. For long time, however, the OS kernel development technology is dominated by foreigners. This technical limitation is detrimental to the development of our software industry. In this project, we presents a simple operating system which includes a boot loader, interrupt services, memory management functions, a graphic interface, and multi-process management functions. Also, some trivial user-level applications are provided for system testing purpose. This simple toy OS is an experimental trial for developing an operating system from scratch.

**Key words:** operating system, boot loader, interrupt, process management, memory management

# **Contents**

1	Intr	oductio	n	1
	1.1	Backgı	round	1
	1.2	Prelim	inary Works	1
		1.2.1	Development Environment	1
		1.2.2	Tools	2
		1.2.3	Platform Setup	2
2	Desi	gn		4
	2.1	Top Le	evel Design	4
	2.2	Detaile	ed Design	4
		2.2.1	Boot Up	4
		2.2.2	Kernel	6
		2.2.3	API	18
		2.2.4	APPs	21
3	Imp	lementa	ntion	22
	3.1	Boot U	Jp	22
	3.2	Kernel	[	25
		3.2.1	Memory Management	25
		3.2.2	Process Management	28
		3.2.3	Graphic Management	32
		3.2.4	Driver	33
	3.3	API .		35
	3.4	APPs		35
4	Con	clusions	S	41

## **CONTENTS**

参	考文繭	伏		42
Su	pervis	sor		42
Ac	know	ledgme	nts	44
A	Mair	ı Progra	am Code	45
	A.1	Boot lo	ader	45
		A.1.1	Display boot information	45
		A.1.2	Read the second sector	45
		A.1.3	Read two sides of a track	45
		A.1.4	The next cylinder	46
	A.2	Kernel	Modules	46
		A.2.1	Memory check process	46
		A.2.2	Memory allocation process	48
		A.2.3	Memory release process	48
		A.2.4	Task allocate	50
		A.2.5	Task add	50
		A.2.6	Task scheduling	51
		A.2.7	Task running	51
		A.2.8	Task sleep	52
		A.2.9	Task remove	52
		A.2.10	Graphic height setting	53
		A.2.11	Palette setting	55
		A.2.12	PIC	56
		A.2.13	Keyboard and Mouse	56

# **List of Figures**

2-1	top-level design	-
2-2	context switch	Ć
2-3	a state of sheets	13
3-1	algorithm of read two sides of one track	23
3-2	the working flowchart of boot loader	24
3-3	insert an entry no merge	26
3-4	insert an item merged with the previous item	27
3-5	insert an item merged with the latter item	27
3-6	algorithm of release memory	36
3-7	flow chart of relase memory	37
3-8	process of task management	37
3-9	algorithm to add tasks to task pool and prepare to run	38
3-10	task scheduling	38
3-11	algorithm of sheet height setting	39
3-12	height setting one	40
3-13	height setting three	40
3-14	height setting two	40
3-15	height setting four	40
3-16	all four setting height conditions	40

# **List of Tables**

2-1	memory management table																													6
-----	-------------------------	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	--	---

# **List of Corrections**

correct picture	4
do you have VFS?	4
say some more	$\epsilon$
wikipedia	17
more about each function	18
more about each function	18
Not clear. You have to explain what is al/ah for. For example, as shown in table	
al is for, ah is for int $0x10$ is for	22

Introduction 1

This section will introduce the purpose and current status of the operating system re-

search. The setup of the development environment will also be presented here.

**Background** 1.1

Contemporary software systems are beset by problems that create challenges and op-

portunities for broad new OS research. There are five areas could improve user experience

including dependability, security, system configuration, system extension, and multiproces-

sor programming.

The products of forty years of OS research are sitting in everyone's desktop computer,

cell phone, car, etc., and it is not a pretty picture. Modern software systems are broadly speak-

ing complex, insecure, unpredictable, prone to failure, hard to use, and difficult to maintain.

Part of the difficult is that good software is hard to write, but in the past decade, this prob-

lem and more specific shortcomings in systems have been greatly exacerbated by increased

networking and embedded systems, which placed new demands that existing architectures

struggled to meet. These problems will not have simple solutions, but the changes must be

pervasive, starting at the bottom of the software stack, in the operating system.

The world needs broad operating system research. Dependability, security, system con-

figuration, system extension, and multi-processor programming illustrate areas were contem-

porary operating systems have failed to meet the software challenges of the modern comput-

ing environment<sup>[2]</sup>.

1.2 **Preliminary Works** 

1.2.1 **Development Environment** 

OS platform: Debian 9, Linux kernel 4.12.0-1-amd64

-1-

#### 1 Introduction

Editor: GNU Emacs 25.2.2

Run time VM: QEMU emulator 2.8.1

**Assembler:** Nask

**Compiler:** CC1(Based on gcc)

**Debugger:** GNU gdb 7.12

**Version Control:** git 2.15

#### **1.2.2** Tools

Some tools were used to develop *RongOS*, See *tools*<sup>1</sup>. Note that these tools are Windows executable. Please install wine if you want to run these tools on Linux. In these tools, the most important ones are:

**nask.exe:** the assembler, a modified version of NASM<sup>[3]</sup>

**cc1:** the C compiler

#### 1.2.3 Platform Setup

The development platform (mainly the Debian system) was set up by following the *Debian Installation tutorial*<sup>2</sup>. The main steps include:

- 1. Installing the base Debian system;
- 2. Installing necessary software tools, such as emacs, web browser, qemu, wine, etc.;
- 3. Cloning configuration files by following the tutorial mentioned above;
- 4. Some more fine tweaks to satisfy my personal needs.

#### Qemu

QEMU is a generic and open source machine emulator and virtualizer<sup>[4]</sup>. In this project, QEMU was used as the test bed.

Installing QEMU for my x86\_64 architecture can be easily done by executing the following command:

\$ sudo apt-get install qemu-system-x86\_64

1https://github.com/Puqiyuan/RongOS/tree/master/z\_tools

2http://cs2.swfc.edu.cn/~wx672/lecture\_notes/linux/install.html

#### Wine

Wine (originally an acronym for "Wine Is Not an Emulator") is a compatibility layer capable of running Windows applications on several POSIX-compliant operating systems, such as Linux, macOS, and BSD<sup>[5]</sup>.

Because the tools I used in this project are in Windows executable format, so on Debian system, Wine is needed to be installed:

```
$ sudo apt-get update
$ sudo apt-get install wine
```

#### Debian i386 support

On 64-bit systems you need to enable multi-arch support for running 32-bit Windows applications (many modern apps are still 32-bit, also for large parts of the Windows subsystem itself). Our development tools were 32-bit Windows applications, so we needed to have i386 support for our 64-bit Linux system.

```
$ sudo dpkg --add-architecture i386
$ sudo apt-get update
```

# 2 Design

This chapter describes the design issues in the entire software system, including system startup, the kernel, APIs, and some applications.

## 2.1 Top Level Design

As shown in Fig. 2-1 shown, **Fixme: correct picture**, all applications require services Fixme! from the operating system through a set of function calls. This set of functions provided by the OS kernel is usually called *system calls*. However, the user applications do not invoke these system calls directly. Instead, they call the API library functions. The process in which the API invokes a system call and hands over processing to the kernel is called *trapping*.

Within the kernel, there are some important software modules working to keep the system running well. The process control subsystem provides graphics processing, CPU scheduling, and memory management functions for processes. Fixme: do you have VFS? Fixme! The file subsystem provides a friendly way to the user processes for accessing disk data. For example, to launch an application program stored on the disk, the function in the file system must be invoked to find the specific application. All of these subsystems may interact with the driver or hardware control module so as to operate on the system hardwares.

# 2.2 Detailed Design

This section discusses the system design in details, including the function of each module, data structures used in boot loader, kernel, API, and APPs.

## 2.2.1 **Boot Up**

At this stage the boot loader loads the operating system kernel into memory. This is done in the following four steps:




Fig. 2-1 top-level design

- 1. Display boot information;
- 2. Read the second sector:
- 3. Read two sides of a track;
- 4. Read the next cylinder until all twenty cylinders have been read.

At this stage, it is also necessary to complete the 32-bit protection mode switch and jump to the entry point of the operating system.

#### 2.2.2 Kernel

The kernel receives the API calls from user processes, and operates the hardwares through the device drivers. Fixme: say some more.

#### **Memory Management**

Memory management refers to the technology that allocates and uses computer memory resources while the software is running. Its main purpose is how to allocate efficiently and quickly, and release for reusing memory resources when appropriate. This is critical to any advanced computer system where more than a single process might be underway at any time.

Several methods have been invented to improve the effectiveness of memory management. For modern operating systems, memory virtualization technology is used. This technique separates the memory space used by the process from the actual physical memory. Processes that are temporarily not running will be moved to secondary storage through paging or swapping. How virtual memory is designed and how it is implemented will have a wide impact on the overall system performance.

For *RongOS*, table 2-1 reflects the memory management system. An *entry* is a record

Start Address	Free Size
1	301
348	50
800	1000
3001	•••

Table 2-1 memory management table

reflects how much memory space is free from where. Actually, this table is an member *struct* 

#### FREEINFO in struct MEMMAN.

#### **Data Structures used in MM**

```
struct FREEINFO
{
   unsigned int addr; /* start address of free space */
   unsigned int size; /* size of free mem in bytes*/
};
```

• is used to record the size in bytes of free memory while the system is running.

```
struct MEMMAN
{
  int frees;  /* free memory blocks */
  int maxfrees;
  int lostsize; /* the sum of the failed memory size to freed*/
  int losts;  /* number of failures */
  struct FREEINFO free[MEMMAN_FREES]; /* free memory block info */
};
```

• is used to record the entire memory usage, such as the total remaining free memory space and *entry*.

#### **Memory Management Functions**

```
unsigned int memtest(unsigned int start, unsigned int end);
```

• Check the memory capacity and confirm that the memory is intact. *start* is the start address of the memory check and *end* is the end address of the memory check. This function returns the maximum value of available addresses. Memory is available between this value and the *start* value.

```
unsigned int memman_total(struct MEMMAN* man);
```

• Report the sum of all empty space. It will look for each *entry* in the *man* to add up the free space in it.

```
unsigned int memman_alloc(struct MEMMAN *man, unsigned int size);
```

Allocate memory to the application, where *size* is the space requested by the application. Success returns the available starting address, otherwise 0. *man* records information about all available entries in memory.

```
int memman_free(struct MEMMAN *man, unsigned int addr, unsigned int size);
```

• Releases memory, where *addr* is the starting address variable and *size* is the size of the release variable. Returns 0 if successful, otherwise -1.

```
unsigned int memman_alloc_4k(struct MEMMAN *man, unsigned int size);
```

• Basically it is similar to the *memman\_alloc* function, but memory is allocated in 4k memory units and the starting address of the allocated memory is returned if successful. *size* is the size of requested space.

• Basically it is similar to the *memman\_free*, but memory space is freed in units of 4k, *addr* is the starting point variable, and *size* is the release size.

#### **Task Management (Scheduler)**

The general operating systems need to be able to support multitasking. Simply saying that multi-tasking is running multiple programs at the same time. But this only gives the user an illusion. For a single CPU, it cannot handle multiple programs at the same time. It merely divides the CPU time into many small pieces for different programs to run. The operating system should be able to do task switching, that is to pass the CPU from one process to another. And at a later time to switch it back, as shown in Fig. 2-2.

The operating system is responsible for allocating resources to processes when managing tasks. Manage the communication between them. To meet these goals, the operating system maintains a data structure called PCB(process control block) for each task. The PCB describes the resources and the state of the task, which also allows the operating system to exert control to each task.




Fig. 2-2 context switch

#### **Data Structures For Task Management**

```
struct TASKLEVEL

int running; /* how many tasks are running */
int now; /* which task is currently running */
struct TASK* tasks[MAX_TASKS_LV]; /* all tasks in one level */
};
```

• is used to record the status of each task in a level. The definition of level, see 3.2.2.

```
struct TSS32
    int esp0, esp1, esp2; /* stack pointer register */
     int ss0, ss1, ss2;
                          /* stack segment register */
4
                /* control register */
                /* instruct pointer register */
     int eip;
    int eflags; /* registers flag */
    int eax;
                /* accumulator register */
                /* counter register */
    int ecx;
    int edx;
                /* data register */
                /* base register */
    int ebx;
               /* stack pointer register */
    int esp;
    int ebp;
                /* base pointer register*/
                /* source index register */
    int esi;
                /* destination index register */
    int edi;
                /* extra segment register */
    int es;
                /* code segment register */
    int cs;
    int ss;
                /* stack segment register */
                /* data segment register */
    int ds;
    int fs;
                /* segment part 2 */
    int gs;
                /* segment part 3 */
                /* LDT segment selector */
    int ldtr;
    int iomap;
                /* I/O map base address */
  };
```

• holds information about task status segments, which are based on CPU specifications<sup>[6]</sup>. The *eip* register records where in the memory the next instruction to be executed by the CPU is located.

• is used to control all tasks in the system. This structure uses the *now\_lv* variable to record the current running *level* in the system. See Fig. 3-8.

```
struct TASK
3
     int sel;
                          /* the number of GDT */
                         /* the state of task */
     int flags;
4
     int level;
                          /* the level of task */
                         /* the priority of task */
6
     int priority;
     struct FIF032 fifo; /* a fifo buffer */
7
     TSS32 tss;
                          /* TSS segment for a task */
8
     struct CONSOLE* cons; /* the console window address of task */
9
                          /* data segment address of APPs */
     int ds_base;
     int cons_stack;
                           /* the stack address of APPs */
     struct SEGMENT_DESCRIPTOR ldt[2]; /* tow LDT segments of task */
     struct FILEHANDLE* fhandle; /* file handles for manipulating files */
13
     int* fat; /* file allocation table */
14
     char* cmdline; /* store the command line context */
     unsigned char langmode; /* which font to use */
     unsigned char langbyte1; /* store the first byte of the full-width

→ character */

18
   };
```

• is used to manage variables for a task. Record the task's sections, permissions, stacks, etc. Actually, this is a PCB.

#### **Task Management Functions**

```
struct TASK *task_now(void);
```

Returns the address of which task level of which task is currently running.

```
struct TASK *task_init(struct MEMMAN *memman);
```

• Initialize all empty tasks. This function will register all 1000 empty tasks to the GDT table. Initialize all levels of task running variables *running* to 0. The pointer *now* of each level indicating that the task is currently running is also set to 0. In fact, this function registers all empty PCBs for future management tasks. At the same time, the task that calls this task needs tobe managed so the address of a PCB is returned. An idle task needs to be set in the last *level*. Ensure that at least one task is running in the system.

```
struct TASK *task_alloc(void);
```

Get an empty PCB from the *task pool 3.2.2*. Return its address if successful, otherwise
 0.

```
void task_run(struct TASK *task, int level, int priority);
```

• Add a task to *task pool*. The *level* and *priority* of tasks through this function can also be set. If the task is asleep, wake it up. Note that this function will not immediately cause the running of task after the execution of this function. Instead wait to be scheduled.

```
void task_switch(void);
```

• Switch to the next task. This function will select one of the highest *level* tasks to run from the *task pool*.

```
void task_sleep(struct TASK *task);
```

• Put a task into sleep. The task that is being promoted to sleep may be the currently running task in the system. If this is the case, it must also schedule the task in the entire *task pool*. Then jump to this new task and start running.

#### **Graphic Management**

The patterns on the screen belong to one *sheet*. A *sheet* is a structure that records how a certain height of a certain area of a computer screen should be displayed. Graphics management is also responsible for refreshing the computer screen when the content displayed by a *sheet* changes. Graphic management is also responsible for setting the height of the *sheet*. The *sheet* height setting is a relatively complex part of the graphics management, which will be explained in detail in the implementation section. Usually the lowest *sheet* is the computer desktop, which is the background layer. The highest *sheet* is the mouse layer. In general, for modern operating systems, graphics management is not a matter of the operating system kernel. So this part only shows in detail the more complicated part of the *sheet* height setting. Fig. 2-3 shows the possible state of some of the *sheet* on the computer screen. The figure shows three *sheet* and is labeled 0, 1, 2. Of course there may be more than three *sheet*. *Sheet* 2 is in the highest position, and *sheet* 0 is the lowest.




Fig. 2-3 a state of sheets

#### **Graphic Management Data Structures**

• is used to record layer-related information, including the layer's size and position.

• is used to manage the structure of multiple layer information, including how many layers there are in total, the size and height of each layer.

#### **Graphic Management Functions**

• Initialize a sheet control structure, *vram* is the address of video RAM. *xsize* and *ysize* is the size of sheet. Mark all sheet structures as 0 to indicate that they are not used.

```
struct SHEET *sheet_alloc(struct SHTCTL *ctl);
```

• Return a *SHEET* structure if success, otherwise 0. Find an unused *sheet* from the sheet structure control structure and making this *sheet* in using.

• Set the properties of the *buf* pf *sheet*.

```
void sheet_updown(struct SHEET *sht, int height);
```

• Set the height of layer *sht*. The height of the *sheet* is more complicated to set, which will be explained in detail in the implementation section.

```
void sheet_refresh(struct SHEET *sht, int bx0, int by0, int bx1, int by1);
```

• Refreshes the screen range specified by *bx0*, *by0*, *bx1* and *by1*. There are many *sheet* on the computer screen. Not all the ranges of all *sheet* will be refreshed when the screen is refreshed. Considering the efficiency of the refresh, this also requires a delicate design. But this is generally not something that the operating system kernel cares about, so it will be omitted.

```
void sheet_free(struct SHEET *sht);
```

• Release a *sheet*. In addition to marking the *sheet* as unused, the first thing to do is to hide the *sheet*.

Make a window in SHEET buf. A window is almost indistinguishable from a sheet.
 When we create a window, we simply write different data to the buf of the sheet to make it appear as a window.

```
void putfonts8_asc_sht(struct SHEET *sht, int x, int y, int c, int b, char

     *s, int 1);
```

• Paint the background color *b* and write the characters and finish the refreshing. *l* specifies the length of the string *s* to be written.

#### **System Calls**

The application requests the operating system kernel to provide services through system calls. These services include both hardware services such as reading disks and software services such as creating child processes and communicating between processes. But in the *RongOS* operating system, the user process is not directly facing the system call, but the API. System calls provide an essential interface between a API and the operating system kernel.

#### **System Calls Prototype**

```
void cons_putchar(struct CONSOLE *cons, int chr, char move);
```

• Put a *chr* character on *cons* console. A *console* is a command line window where users can enter commands to run. Entering a character at the command line involves moving the mouse. This is controlled by *move* variable.

```
void cons_newline(struct CONSOLE *cons);
```

• Newline in *cons* console. The command line needs to wrap when the enter key is pressed.

```
void cons_putstr0(struct CONSOLE *cons, char *s);
```

• Put string *s* in *cons* console, no length was specified. This function will call *void cons\_putchar(struct CONSOLE \*cons, int chr, char move)* to complete its service.

```
void cons_putstr1(struct CONSOLE *cons, char *s, int 1);
```

• Put string *s* in *cons*, *l* is the length of string *s*. In general, the service provided by this function is similar to that of *void cons\_putstr0(struct CONSOLE \*cons, char \*s)*. Only in this function can specify the length of the string by *l*.

```
int cmd_app(struct CONSOLE *cons, int *fat, char *cmdline);
```

• Start an application based on the input from the command line *cmdline*. emphfat is a file allocation table. In this table it records which files are stored on which blocks and how these blocks relate to each other. This function finds the application to start by searching the *fat* table and runs it.

#### **Driver**

The device drivers are used to control and manipulate the hardware. It is the dividing line between hardware and software. A driver provides a software interface to hardware devices, enabling operating systems and other computer programs to access hardware functions without needing to know precise details of the hardware being used. In this way, application programmers can develop hardware-independent programs.

When the driver is called, it sends the command to operate the hardware. Once the hardware device returns data, the driver informs the calling program to process it. The entire process is an interruption.

For *RongOS*, the main hardware devices are floppy disks, mice, keyboard, and screen. So the following driver functions are mainly used to manipulate them.

#### **Driver Functions**

```
void set_palette(int start, int end, unsigned char *rgb);
```

• Initialize the palette. It is necessary to set the color number in the palette register for setting palette mode.

```
void init_pic(void);
```

• Initialize the PIC. PIC is an abbreviation for programmable interrupt controller. PIC is used to inform the CPU if there is an interrupt.

```
void init_keyboard(struct FIF032 *fifo, int data0);
```

• Initialze the keyboard. The mouse control circuit is included in the keyboard control circuit. Therefore, if the initialization of the keyboard circuit is completed, the initialization of the mouse circuit is completed.

```
void enable_mouse(struct FIF032 *fifo, int data0, struct MOUSE_DEC *mdec);
```

• Activate mouse. Makes the mouse itself effective.

#### **FAT File System**

The file system defines how data is stored and accessed. The file system divides the entire storage space according to a certain form. This facilitates the storage of files while

increasing the utilization of storage media. The small blocks thus divided are called sectors.

The FAT records which sectors all files are stored on. Fixme: wikipedia

#### **FAT Data Structure**

```
struct FILEINFO
2
     unsigned char name[8]; /* file name */
3
     unsigned char ext[3];
                                 /* extend name of file */
4
     unsigned char type;
                                /* file attributes */
5
     char reserve[10];
                                /* reserve byte */
6
     unsigned short time;  /* the time for storing file */
unsigned short date;  /* the date for storing file */
     unsigned short clustno; /* the file from which sector on the disk is

    stored */

   };
```

• is used to record file-related information, such as file name, size, etc.

Fixme!

#### **FAT Functions** Fixme: more about each function

```
void file_readfat(int *fat, unsigned char *img);
```

read file allocation table

```
void file_loadfile(int clustno, int size, char *buf, int *fat, char *img);
```

• read file contents into memory

```
struct FILEINFO *file_search(char *name, struct FILEINFO *finfo, int max);
```

• search for files based on provided *name*.

#### 2.2.3 API

In computer programming, APIs are subroutines that are used to develop applications. Usually, it communicates all parts of the software. A good API makes application development easier. By abstracting the underlying implementation and only exposing objects or actions the developer needs, an API simplifies programming.

#### **All APIs**

Fixme: more about each function

Fixme!

```
void api_putchar(int c);
```

• output a character *c* on the console window.

```
void api_putstr0(char *s);
```

• ouput a string s on the console window.

```
void api_putstr1(char *s, int 1);
   • output a string s on console window, l is the length of this string.
void api_end(void);
   • end the application's running.
int api_openwin(char *buf, int xsiz, int ysiz, int col_inv, char *title);
   • open a window, return the hanlder of window.
void api_putstrwin(int win, int x, int y, int col, int len, char *str);
   • display string str on window.
void api_boxfilwin(int win, int x0, int y0, int x1, int y1, int col);
   • draw a box on the window
void api_initmalloc(void);
   • initialize the structure of the management memory
char *api_malloc(int size);
   • allocating memory for the application.
void api_free(char *addr, int size);
   • free up memory used by the application.
void api_point(int win, int x, int y, int col);
```

• draw a pint on win window. void api\_refreshwin(int win, int x0, int y0, int x1, int y1); • refresh the window. void api\_linewin(int win, int x0, int y0, int x1, int y1, int col); • draw a straight line. void api\_closewin(int win); · close window. int api\_getkey(int mode); • accept keyboard input. int api\_alloctimer(void); • get timer. void api\_inittimer(int timer, int data); • set the data of timer sending. void api\_settimer(int timer, int time); • set the time of timer. void api\_freetimer(int timer); • release timer.

```
void api_beep(int tone);
   · make a buzzer sound
int api_fopen(char *fname);
   • open file, return file hanlder
void api_fclose(int fhandle);
   · close file
void api_fseek(int fhandle, int offset, int mode);
   · locate a file
int api_fsize(int fhandle, int mode);
   • return the size of fhandle file.
int api_fread(char *buf, int maxsize, int fhandle);
   • read file, return read bytes.
int api_cmdline(char *buf, int maxsize);
   • return the context of command line.
int api_getlang(void);
   • return the language mode.
```

#### 2.2.4 **APPs**

Since this design is only about the operating system itself, only three representative applications are introduced. The first is the application of the display color: *color*. The second is the application for timing: *sundial*. The third application is to imitate the application of stars in the sky: *stars2*.

# 3 Implementation

## 3.1 Boot Up

The boot loader is implemented in Intel assembly. It works as follows:

- 1. **Display boot information:** Firstly, the code in boot sector (See Appendix A.1.1) outputs some boot information. When *al*=0, the null character of boot information hit. Fixme! Interrupt *0x10* is used for showing a character on the screen. Fixme: Not clear. You have to explain what is al/ah for. For example, as shown in table... al is for..., ah is for... int 0x10 is for...
- 2. **Read the second sector:** Then jump to load C0-H0-S2, *ax* register saved the address where beginning puts the sectors from floppy. And preparing parameters for interrupt *0x13* in registers. The *0x13* interrupt used for read sector from floppy to memory. (See Appendix A.1.2).

#### 3. Read two sides of a track:

If there is a carry indicating some thing went wrong while reading the floppy disk, reset the registers and try reading it again. The read process aborts after five unsuccessful read.

Register *si* is a counter. If no carry (success), jump to next segment, as one sector has been read into memory already. The address should increase 512 byte. Then sector number (*cl* register) is added by 1 and compare it to 18, if it's smaller than 18, jump to *readloop*, read the next sector.

If the value of *cl* register is bigger or equal to 18, meaning that one track 18 sector in this side of floppy read already, then reversed the head, add 1 to *dh* register.

If the value of *dh* register after adding larger than or equal to 2, it's saying the original head is 1, one track of two sides read already. Otherwise the value of *dh* register smaller than 2, read this side indicating by *dh* register, jump to *readloop* segmentation. Appendix A.1.3 is the code performing this function.

There is a pseudo code about this process:

```
Result: Read two sides of one track
 1 ENTRANCE: call readloop();
 2 Procedure readloop()
       clear the times of failed to 0, si \leftarrow 0;
       call retry();
 5 Procedure retry()
       register parameter preparing;
       read a sector;
      if no carry then
         call next();
 9
10
          add 1 to si, si \leftarrow si + 1;
11
          compare si with 5;
12
          if si >= 5 then
13
              goto error, FINISHED;
14
15
16
             reset registers and call retry() to read again;
17
          end
       \mathbf{end}
18
19 Procedure next()
20
       memory address moved back 0x200;
       add 1 to cl, preparing for reading the next sector, cl \leftarrow cl + 1;
\mathbf{21}
      if cl \ll 18 then
22
        call readloop() to read this sector;
23
24
          cl > 18, it means that one side of this track is read already;
25
26
          add 1 to dh, dh \leftarrow dh + 1, reverse the head pointer;
          if dh < 2 then
27
              it means the 1 side has not read yet, call readloop();
28
          else
29
              both sides have finished reading, FINSHED;
30
          end
31
      end
```

Fig. 3-1 algorithm of read two sides of one track

4. **The next cylinder:** So the next step is moving a cylinder, add 1 to register *ch*. Otherwise the value of *dh* register smaller than 2, read this side indicating by *dh* register, jump to *readloop* segmentation. After *ch* register add 1, if it's smaller than 10, jump to *readloop*, otherwise end loading floppy to memory process, for we only load ten cylinders of floppy. Appendix A.1.4 is the code to perform this function.

The above four steps can be intuitively reflected in the Fig. 3-2.




Fig. 3-2 the working flowchart of boot loader

## 3.2 Kernel

## 3.2.1 Memory Management

#### **Memory Check**

For memory management, memory must be checked to see how large the memory is. After i486, the CPU turned on the cache function. In order to avoid checking the cache, the CPU's cache function must be turned off. So first check the version of the CPU. Then check the memory capacity. When checking the memory capacity, first write a value to the same address and immediately read out whether the observation is equal to the previously written value. The entire inspection process can be summarized as follows.

- 1. Check the version of the CPU.
- 2. If the version of the CPU is greater than 386 then caching is disabled, otherwise nothing will be done.
- 3. Check memory
- 4. If the CPU version is greater than the 386 restore cache feature. Otherwise do nothing. Step 2 can be divided into the following steps
  - 1. Save the original value of a location in memory.
  - 2. Write a constant to the above memory address.
  - 3. Read the above memory address and invert it.
  - 4. The inverted value of the constant prepared in advance is compared with the value obtained in the third step.
  - 5. Equal to continue to check, otherwise stop.

In general, the C compiler has optimized optimization, so it seems that the above comparison is definitely equivalent. So the above check subfunction should be done in assembly language. Specific implementation, please see appendix A.2.1.

#### **Memory Allocation**

First explain some of the variables used to implement the memory allocation function. *size* refers to the space requested by the application but *SIZE* is the free space of one *entry*. *free* is the number of memory available memory.

- 1. Traversing all the free entries in memory to find an *entry* gives it more free space than the application requested. If found then 2, otherwise 6.
- 2. Add *size* to start address of *entry* found in 1. Subtract *size* from free space *SIZE* in *entry* found in 1. Jump to 3.
- 3. Determine if the remaining free space *SIZE* in the entry is 0. If so, go to 4. Otherwise 5.
- 4. Subtract the number of memory available entries *free* by 1.
- 5. Returns the starting address of available memory.
- 6. Returns 0 for memory allocation failure.

Specific implementation see code A.2.2.

#### **Memory Release**

Memory release is a more complex part of memory management. In order to keep the memory free entries in an orderly manner and merge adjacent entries, the memory release code becomes somewhat complicated. It is mainly divided into the following categories.

1. Neither merge with the previous *entry* nor with the latter *entry*. For this case, this entry needs to be inserted into the free memory entry. As the figure 3-3 shows. As shown in




Fig. 3-3 insert an entry no merge

the figure, the starting address of *new x* 803 is not adjacent to the previous termination address 669, and its termination address 960 is also not adjacent to the starting address 1000 of the next entry. The so-called neighboring means that the difference between the two addresses is 1. Same as below.

2. Can be merged with the previous entry. As the figure 3-4 shows. As shown in the




Fig. 3-4 insert an item merged with the previous item

figure, the starting address of  $new \times 670$  is adjacent to the previous termination address 669, but its termination address 960 is not adjacent to the starting address 1000 of the next entry.

3. Can be merged with the latter entry. As the figure 3-5 shows. The termination address




Fig. 3-5 insert an item merged with the latter item

999 of *new x* is adjacent to the starting address 1000 of the next entry, but its starting address of *new x* 803 is not adjacent to the previous termination address 669.

The memory release process can be described as follows.

1. Find the insertion position *i*. The so-called insertion position is an *entry* number that

- satisfies certain conditions. This condition is that the *size* of this *entry* is larger than the size requested by the application.
- 2. If i > 0, merge if the newly inserted *entry* can be merged with the previous *entry*, the same as for the latter *entry*. As long as it merges with the former, the function returns 0 and the release is successful. Otherwise jump to 3.
- 3. The program proceeds here so that the newly inserted *entry* must not be merged with the previous *entry*. Now check if the newly inserted *entry* can be merged with the latter *entries*. If so, merges it and return 0. Otherwise jump to 4.
- 4. The program proceeds here to represent that the newly inserted *entry* cannot be merged with any of the entries. Now check the number of used entries with 4090. If the former is less than the latter, move all items after the i'th item back one position to make room for new items. Then insert this new *entry*. Otherwise jmup to 5.
- 5. Failed to release, return -1.

The above release process can be explained by the algorithm 3-6. Of course, the flow chart 3-7 will be more clear. For specific code implementation, see A.2.3

## 3.2.2 Process Management

Process management is a very complex but very important part of operating system development. This part of the development has a very big impact on the performance of the entire system. For the *RongOS* operating system, all tasks are managed hierarchically. Fig. 3-8 clearly shows how all the tasks in the system are managed.

From *level 0* to *level 10*, there are a total of ten levels in the system. All these ten levels and the space they prepare for the task are called *task pool*. For each task, it also has a *priority* attribute. It actually specifies how long each process can run, also known as a *time slice*.

As Fig. 3-8 shows, each level can hold 100 tasks. The lower the level number, the higher the level's privilege. For example, x-level permissions are higher than x+1. The scheduler will select the task to run from a high-privilege level. Only lower-level tasks are scheduled when the task at the higher privilege level is completed. While tasks within the same layer are run in turn, their running time may be different, that is, the *time slice* is also called *priority*.

This can be illustrated by the peripheral loop arrows in *level 0* in Fig. 3-8. The other *levels* are also similar except that the peripheral loop arrows are ignored.

In Fig. 3-8, a task is added to its corresponding level. There are many tasks in each level waiting for scheduling or a running task. Tasks that are waiting for scheduling are represented in italics but the task being run is underlined in each level. A place after the last task waiting to be scheduled is the *insertion point* of a new task at a certain level.

The PIC chip will generate 100 clock interrupts per second. Each time a clock interrupt occurs, it is serviced by the interrupt service routine 0x20. This subroutine will call the scheduler to schedule a task to run based on the above method of selecting the task to run. When a run is completed in one round, there are three destinations for a process.

- 1. The task did not complete, but the *time slice* was used up. It will be added to the task pool again and wait for it to be selected again to begin another run.
- 2. The task completes the run and then enters the end processing subroutine.
- 3. The *time slice* of the process runs out, but it goes to *sleep*. The so-called *sleep* state means that the process is paused, waiting for something to happen and waking it up again, adding it to the *task pool* and starting a round of running. Something such as a keyboard input program waits for user input.

As shown in Fig. 3-8, it can be seen as a snapshot of all the tasks in the system. In this transient state, a task is being added to the (3 + 1 = 4) point of *x-level* of *task pool*. What is running in the system is task ④ of *level 0*.

#### Task Allocate and Add

After the new process arrives, it must apply for a task structure to record its information. This process is simpler simply by iterating through the *tasks0* structure array variable to find an unused task structure and assign it to the new task. *tasks0* is used to record information for all tasks. At the same time put the address of this structure into the *tasks* structure array. This structure *tasks* is used to record the addresses of all tasks. Note that *tasks* and *tasks0* are functionally different arrays of structures. *tasks0* records information for all 1000 tasks in the system, while *tasks* record their addresses.

The next step is to add to the *task pool* and wait to be scheduled. When adding, specify

the *level* and *priority*. The specified *level* and *priority* may not be the same as the original task, or they may be the same. Different situations need to be handled differently. This can be done by the following steps.

- If the *level* passed in is less than 0, it means that the task is added without changing the *level* of the task, and the *level* of the original task is used to cover the incoming level.
   The check here is mainly for processing when the task is awakened. When the task is awakened it should not change its *level*. Continue to step 2.
- 2. If the passed in *priority* is greater than 0, the *priority* of the original task is overwritten with the passed in priority. Continue to step 3.
- 3. If this task is waiting to be scheduled and the incoming *level* is different from its original *level*. This means that this task must be removed from the original *level*. Continue to step 4.
- 4. If the task is not in the task pool, it is added to the *task pool* according to its *level*. These steps may change the level of the task, set the level change flag *lv\_change* to 1 so that the next time the scheduler schedules the task, it must find the task in the entire *task pool* to run again.

Specific code implementation, see A.2.4 and A.2.5. Fig. 3-9 is an algorithm that adds tasks to the task pool to run.

#### **Task Scheduling and Running**

The next step is for the scheduler to start scheduling task to running. The work of the scheduler requires the support of clock interrupts. Every time a clock interrupt occurs, the scheduler is run once. The *now\_lv* variable is used to record which level is currently running. The *now* variable is a pointer to a running task of a certain level. The specific workflow of the scheduler is described in the following steps.

- 1. Find the currently running level *tl* by *now\_lv*. Move the *now* pointer of this layer by one position. Continue to step 2.
- 2. If the number of *running* tasks is equal to the *now* pointer. Move back *now* pointer to0. Continue to step 3
- 3. Check if the *lv\_change* flag is 1. If it is 1, check the entire *task pool* to find the new

*now\_lv* and set the *lv\_change* flag to 0. Continue to step 4.

4. Get the currently running task from *now\_lv* with the *now* pointer, set the time slice, and jump to the task to start running.

Specific code implementation, see A.2.6 and A.2.7. Fig. 3-10 is the algorithm of task scheduling and switching.

#### Task Sleep

The task may go to *sleep* after it finishes running. A task going to sleep is actually removing it from the *task pool*. Sleeping the task requires considering whether this task is a running task. If this is the case, after the task is removed, the task switch will be performed. Then jump to the newly switched task. These steps can be summarized as follows

- 1. Call *task\_now* to return to the currently running task. Go to the next step.
- 2. Call *task\_remove* to remove this task from *task pool*. Go to the next step.
- 3. The task that is going to sleep are compared with the tasks that is running. If they are equal, switch to the new task to start running.

Specific code implementation, see A.2.8.

#### Task\_now and Task\_remove Functions

There are also two small functions that facilitate task management and are introduced here. One is the *task\_now* function and the other is the *task\_remove* function. *task\_now*. The *task\_now* function is used to return the address of the task that is currently running on the system. This function is relatively simple. The first is to find the current running level based on the *now\_lv*, then the level of the now pointer to find the task that the layer is running, and finally returns its address.

The *task\_remove* function is somewhat complicated. It may involve moving all tasks for a layer. It may also cause various pointers to appear strange. All of these must be considered carefully, otherwise the system may experience unpredictable and strange behavior. Its running process can be summarized as follows.

- 1. First find the corresponding level of the task *tl*. Go to the next step.
- 2. Find out where this task is. Go to the next step.

- 3. Reduce the number of processes running by 1. Go to the next step.
- 4. If the position of this task is before the *now* pointer, the *now* pointer is decremented by one. Go to the next step.
- 5. If the *now* pointer is greater than the number of *running* processes, it is necessary to correct the *now* pointer to 0. Go to the next step.
- 6. Change the *flags* of the task to 1 to indicate that the task is dormant. Go to the next step.
- 7. Move the tasks between i and *running* one step forward.

Specific code implementation, see A.2.9.

## 3.2.3 Graphic Management

In modern operating systems, graphics management is often not a concern of the operating system kernel. However, as a simple multitasking 32-bit operating system with windows it is necessary to demonstrate the implementation of a graphical management subproblem. The issue that was selected for detailed discussion was the more complex *sheet* height settings in the graphics management section.

#### **Sheet Height Setting**

There are many *sheet* on the computer screen. Which *sheet* is located at which height requires careful design and detailed consideration. When the *sheet* height is set, the height of other layers must be taken into account. When the setting is complete, the relative height of other *sheet* cannot be changed. First, the algorithm for setting the height of the *sheet* is given in Fig. 3-11.

The height of passing in may not be compliant, for example, pass a negative number and so on. Therefore, it is necessary to check the height value first. If it does not meet the regulations, it needs to be corrected. *Sheet* height settings can be divided into four sections.

1. The original height of the *sheet* is higher than the newly transmitted height. The *sheet* between the newly transmitted height and the original height needs to be moved upward by a height. After the move is complete, place the original height *sheet* on the new

height. Fig. 3-12 shows this situation. The following explanations are necessary to understand this diagram. These explanations are also used for the next three cases. 1, each horizontal line represents a *sheet*, the label on the right represents the height of the layer. 2, the old and new heights are mark done the left. 3, the label next to the arrow represents the order of movement. 4, the bottom dashed line represents the hidden *sheet*, while the topmost dashed line represents the highest *sheet*.

- 2. The original height of the *sheet* is higher than the newly transmitted height. However, the height of the new pass is less than 0. This means that the *sheet* at old height needs to be hidden, the so-called hiding is to set its height to -1. *Sheet* above this height need to be moved down one height. Fig. 3-14 shows this situation.
- 3. The original height of the *sheet* is less than the newly transmitted height. The *sheet* between the newly transmitted height and the original height needs to be moved down by a height. After the move is complete, place the original height *sheet* on the new height. Fig. 3-13 shows this situation.
- 4. The original height of the *sheet* is less than the newly transmitted height. However, the height of the new pass is greater than top. This means that the *sheet* at old height needs to be displayed, the so-called displayed is to set its height larger than 0. *Sheet* above this new height need to be moved upward one height. Fig. 3-15 shows this situation.

Specific code implementation, see A.2.10.

#### 3.2.4 Driver

The following parts of the driver are implemented.

#### **Palette**

The palette setting needs to write the color number into the palette register. There are two main palette registers, one is register write 0x3c8, and the other is data port 0x3c9. The palette settings are divided into the following steps.

- 1. Masking interrupts first.
- 2. Write the number of the palette to be set to 0x3c8. Finally write 0x3c9 in order of R,

G, and B.

3. Allow interrupts.

Specific code implementation, see A.2.11.

#### **PIC**

In design, the CPU can only handle one interrupt. The PIC monitors the eight signals at the input pins. As soon as an interrupt signal comes in, the only one is turned on and notified to the CPU.

The primary PIC is directly connected to the CPU, and the slave PIC is connected to the primary PIC. The master PIC is responsible for handling the 0th to 7th interrupt signals, and the slave PIC is responsible for handling the 8th to 15th interrupt signals. So the PIC settings can be divided into the following steps.

- 1. Disable interrupts.
- 2. Setting 0 to 7 interrupts is accepted by the main PIC.
- 3. Setting 8 to 15 interrupts is accepted by the main PIC.
- 4. Resume interruption.

Specific code implementation, see A.2.12.

#### **Keyboard and Mouse**

For the mouse and keyboard to work, instructions must be sent to the appropriate circuits and devices. But the mouse circuit is included in the keyboard circuit. Therefore, only the keyboard circuit needs to be initialized for the circuit. The mouse device needs to be activated additionally. The control circuit needs to be effective first, otherwise the device sending data to the control circuit will have unpredictable consequences.

What command to send, where to send please refer to the specific code implementation A.2.13, these are specified by the hardware.

- 3.3 API
- **3.4 APPs**

```
Result: free memory
 1 ENTRANCE: call memFree(struct MEMMAN *man, unsigned int
    addr, unsigned int size);
2 Procedure memFree(struct MEMMAN *man, unsigned int addr,
    unsigned int size)
      Finding the starting address of the first entry i is greater than the
 3
        released address addr;
      if i > 0 then
 4
          if i'th entry can be merged with the previous one then
 5
              man->free[i-1].size \leftarrow man->free[i-1].size + size;
 6
              if i entry is less than the number of free entries then
 7
                  if i'th can be merged with the latter then
 8
                      man->free[i-1].size \leftarrow man->free[i-1].size +
                       man->free[i].size;
                      man->frees \leftarrow man->frees - 1;
10
                      move all free entries after i by one;
11
                  else
                      nothing to do here;
13
                  end
14
              else
15
                 nothing to do here;
16
              end
17
          else
18
              Successfully released, return 0, FINISHED;
19
          end
20
       else
21
          nothing to do here;
22
      end
23
      if i < the number of free entries then
24
          if i'th entry can be merged with the latter then
25
              man->free[i].addr \leftarrow addr;
26
              man-sfree[i].size \leftarrow man-sfree[i].size + size;
27
              Successfully released, return 0, FINISHED;
28
          else
29
              nothing to do here;
30
          end
31
      else
32
          nothing to do here;
33
      end
34
      if the number of free items used < the maximum number of free
35
        items(4090) then
          move back all free entries after i'th entry by one;
36
          man-> frees \leftarrow man->frees + 1;
37
          man \rightarrow free[i].addr \leftarrow addr;
38
          man \rightarrow free[i].size \leftarrow size;
39
          Successfully released, return 0, FINISHED;
40
      else
41
42
          nothing to do here;
43
      the number of release failures plus one;
44
      increase the size to release the failed space;
45
      Release failed, return -1, FINISHED;
46
```

Fig. 3-6 algorithm of release memory




Fig. 3-7 flow chart of relase memory




Fig. 3-8 process of task management

```
Result: schedule a task to run
 1 ENTRANCE: call taskRun(sturct TASK *task, int level, int priority);
 {\bf 2} \ {\bf Procedure} \ {\tt taskRun} ({\it struct} \ {\it TASK} \ {\it *task, int level, int priority})
        if level < 0 then
            don't change level, level \leftarrow task - > level;
        else
 5
           nothing to do here;
 6
        \dot{\mathbf{e}}\mathbf{n}\mathbf{d}
        if priority > \theta then
 8
 9
            Change the priority, task - > priority \leftarrow priority;
10
        else
11
           nothing to do here;
        end
12
        \mathbf{if}\ \mathit{the}\ \mathit{task}\ \mathit{is}\ \mathit{running}\ \mathit{and}\ \mathit{not}\ \mathit{at}\ \mathit{the}\ \mathit{level}\ \mathit{you}\ \mathit{want}\ \mathit{to}\ \mathit{set}\ \mathbf{then}
13
14
            Remove the task from the original level;
15
         nothing to do here;
16
17
        end
        if task is not running, but sleeping then
18
19
            set the new level, task - > level \leftarrow level;
            waking up from sleep, call taskAdd(task);
20
21
         nothing to do here;
22
        end
23
24
        change the lv_change flag to 1, therefore, tasks must be switched
         when the task is scheduled next time;
25 Procedure taskAdd(struct\ TASK\ *task)
        look for the corresponding level of the task;
27
        place the task in the location indicated by running;
        runinng++; Mark the task as running;
28
```

Fig. 3-9 algorithm to add tasks to task pool and prepare to run

```
Result: Schedule a task to run
 1 ENTRANCE: call taskSwitch();
 2 Procedure taskSwitch()
       find out what task is running now\_task in the current system based
        on now_lv and now;
       add the now pointer to 1 for the next task scheduling;
       if if the now pointer equals the number of running tasks then
          zero the now pointer;
       else
        nothing to do here;
 9
       end
       \mathbf{if}\ \mathit{lv\_change}\ \mathit{is}\ \mathit{not}\ \mathit{\theta}\ \mathbf{then}
10
           call taskSwitchSub();
          get the currently running layer;
12
13
       _{
m else}
         nothing to do here;
14
       end
15
       get the new\_task from the currently running level at now pointer;
16
       set the timer of the task according to the priority of the task;
18
       \mathbf{if}\ \mathit{new\_task}\ != \mathit{now\_task}\ \mathbf{then}
          jump to new_task run;
19
20
       _{
m else}
21
        nothing to do here;
       end
22
23 Procedure taskSwitchSub()
       for i \leftarrow 0 to 9 by 1 do
24
          if running task of i level > 0 then
25
26
              break;
27
           else
           nothing to do here;
29
          end
30
       modify the current running level now\_lv to i;
31
       modify the lv_change to 0, so the next time don't need to call
32
        taskSwitchSub();
```

Fig. 3-10 task scheduling

```
Result: Set the height of a sheet
 1 ENTRANCE: call sheetMove(/struct SHTCTL *ctl, struct SHEET
     *sht, int height));
 2 Procedure sheetMove(struct SHTCTL *ctl, sturct SHEET *sht, int
     height)
       old \leftarrow the original height of sht;
       if height > top sheet plus 1 then
 4
 5
          height \leftarrow top + 1;
 6
       else
        nothing to do here;
 7
       end
 8
       if height < -1 then
 9
          this means to hide sht sheet, height \leftarrow -1;
10
11
       else
          nothing to do here;
\bf 12
       \mathbf{end}
13
       if old > height then
14
           if height >= 0 then
15
              for h \leftarrow old to height by 1 do
16
                  increases the height of all sheets between height and old
17
                  modify the height of all sheets to h;
18
19
              place the sht sheet at height;
20
           else
21
              if highest sheet top > old then
22
                  for h \leftarrow old to top by 1 do
23
                      drop all sheets between old and top by one height;
24
                      modify the height of all sheets to h;
25
                  end
26
              else
27
28
               nothing to do here;
29
              end
              the displayed sheet is reduced by one, top \leftarrow top - 1;
30
           end
31
           refersh screen;
32
       else
33
           if old < height then
34
              if old >= 0 then
35
                  for h \leftarrow old to height by 1 do
36
                      drop all sheets between old and height by one height;
37
                      modify the height of all sheets to h;
38
                  end
39
                  place the sht sheet at height;
40
              else
                  for h \leftarrow top \text{ to } height \text{ by } 1 \text{ do}
42
                      increases the height of all sheets between top and
43
                       height by one;
                      modify the height of all sheets to h+1;
44
45
46
                  place the sht sheet at height;
                  the displayed sheet is increased by one, top \leftarrow top + 1;
47
48
              end
              refersh screen;
49
50
           else
              nothing to do here;
51
           end
52
       \mathbf{end}
53
```

Fig. 3-11 algorithm of sheet height setting




Fig. 3-16 all four setting height conditions

## 4 Conclusions

What goes in your "Conclusions" chapter? The purpose of this chapter is to provide a summary of the whole thesis or report. In this context, it is similar to the Abstract, except that the Abstract puts roughly equal weight on all thesis/report chapters, whereas the Conclusions chapter focuses primarily on the findings, conclusions and/or recommendations of the project.

There are a couple of rules -one rigid, one common sense, for this chapter:

- All material presented in this chapter must have appeared already in the report; no new material can be introduced in this chapter. (rigid rule of technical writing)
- Usually, you would not present any new figures or tables in this chapter.
   (rule of thumb)

Generally, for most technical reports and Masters theses, the Conclusions chapter would be 3 to 5 pages long (double spaced). It would generally be longer in a large PhD thesis. Typically you would have a paragraph or two for each chapter or major subsection. Aim to include the following (typical) content.

- 1. Re-introduce the project and the need for the work -though more briefly than in the intro:
- 2. Re-iterate the purpose and specific objectives of your project.
- 3. Re-cap the approach taken -similar to the road map in the intro; however, in this case, you are re-capping the data, methodology and results as you go.
- 4. Summarize the major findings and recommendations of your work.
- 5. Make recommendations for future research.

Ohttps://thesistips.wordpress.com/2012/03/25/how-to-write-your-introduction-abstract-and-summary/

## 参考文献

- [1] 国务院,中国制造 2025, 2015-05.
- [2] G. C. Hunt, J. R. Larus, D. Tarditi, T. Wobber in HotOS, 2005.
- [3] 川合秀实, 30 天自制操作系统, 1st ed., 人民邮电出版社, 2012-08.
- [4] W. contributors, QEMU Wikipedia, The Free Encyclopedia, [Online; accessed 12-January-2018], **2017**.
- [5] W. contributors, Wine (software) Wikipedia, The Free Encyclopedia, [Online; accessed 12-January-2018], **2017**.
- [6] Intel, Intel® 64 and IA-32 Architectures Software Developer's Manual, Volume 3A, 1st ed., **2006-10**.

# **Supervisor**

Xiaolin WANG (Mr.), 49 years old, got his MSc degree at University of Greenwich in UK. Currently he's been working as a lecturer at the School of Big Data and Intelligence Engineering, Southwest Forestry University in China, teaching Linux, Operating Systems, and Computer Networking.

## **Acknowledgments**

I would like to thank my supervisor Mr. WANG Xiaolin for his continuous support of my four years undergraduate study. I am extremly thankful to him for sharing expertise, and sincere and valuable guidance and encouragement extended to me.

What I most want to thank is my girlfriend. She tolerated me when I finished this graduation project many nights did not accompany her, gave me support, encouraged me, and did not complain. So I would like to name this simple operating system as *RongOS*. Rong is the last word of her name. Thank you, my dearest.

My special thanks to a great company - Google, I think I need to thank you in this very formal place in my graduation thesis. Every time you gave me a lot of help, the knowledge and other abilities I learned from you will have a profound impact on my future life. I am grateful for every search, because I know you will give me the results I want. Without you, this paper cannot be completed. Thank you.

## A Main Program Code

## A.1 Boot loader

## A.1.1 Display boot information

```
init:
    mov al, [si]
    add si, 1 ; increment by 1.
    cmp al, 0
    je load ; if al == 0, jmp to load, the msg_init info displayed.
    ; the lastest character is null character, coding in 0.

mov ah, 0x0e ; write a character in TTY mode.
    mov bx, 15 ; specify the color of the character.
    int 0x10 ; call BIOS function, video card is number 10.
    jmp init
```

#### A.1.2 Read the second sector

```
load:
            mov ax, 0
            mov ax, 0x0820; load CO-HO-S2 to memory begin with 0x0820.
            mov es, ax
            mov ch, 0 ; cylinder 0.
            mov dh, 0; head 0.
            mov cl, 2; sector 2.
    readloop:
            mov si, 0 ; si register is a counter, try read a sector
98
    ; five times.
    retry:
            mov ah, 0x02; parameter 0x02 to ah, read disk.
            mov al, 1; parameter 1 to al, read disk.
            mov bx, 0
            mov dl, 0x00; the number of driver number.
            int 0x13; after prepared parameters, call 0x13 interrupted.
106
```

#### A.1.3 Read two sides of a track

```
jnc next; if no carry read next sector.

add si, 1; tring again read sector, counter add 1.

cmp si, 5; until five times

jae error; if tring times large than five, failed.
```

```
; reset the status of floppy and read again.
        mov ah, 0x00
        mov dl, 0x00
        int 0x13
        jmp retry
next:
        mov ax, es
        ; we can not directly add to es register.
        add ax, 0x0020; add 0x0020 to ax
        mov es, ax; the memory increase 0x0020 * 16 = 512 byte.
        ; size of a sector.
        add cl, 1; sector number add 1.
        cmp cl, 18; one track have 18 sector.
        jbe readloop; jump if below or equal 18, read the next sector.
        mov cl, 1; cl number reset to 1, ready to read the other side.
        add dh, 1; the other side of floppy.
        cmp dh, 2; only two sides of floppy.
        jb readloop; if dh < 2, read 18 sectors of the other sides
```

## A.1.4 The next cylinder

```
mov dh, 0; after finished read the other side, reset head to 0.
add ch, 1; two sides of a cylinder readed, add 1 to ch.
cmp ch, CYLS; read 10 cylinders.
jb readloop
```

## A.2 Kernel Modules

## A.2.1 Memory check process

```
unsigned int memtest(unsigned int start, unsigned int end)

{
    char flg486 = 0;
    unsigned int eflg, cr0, i;

//check whether it is 386 or 486 or later.

eflg = io_load_eflags();
    eflg |= EFLAGS_AC_BIT;
    io_store_eflags(eflg);
    eflg = io_load_eflags();

if ((eflg & EFLAGS_AC_BIT) != 0)
    flg486 = 1;

eflg &= ~EFLAGS_AC_BIT;
    io_store_eflags(eflg);
```

```
if (flg486 != 0)
                      {
                              cr0 = load_cr0();
                              cr0 |= CRO_CACHE_DISABLE; // caching prohibited
                              store_cr0(cr0);
                      }
             i = memtest_sub(start, end);
             if (flg486 != 0)
                      {
                              cr0 = load_cr0();
                              cr0 &= ~CRO_CACHE_DISABLE; // cache permission
                              store_cr0(cr0);
                      }
             return i;
41
42
     {\tt \_memtest\_sub}\colon ; {\tt unsigned} {\tt int} {\tt memtest\_sub} {\tt (unsigned} {\tt int} {\tt start}, {\tt unsigned} {\tt int}
        end)
                      push edi
                      push esi
                      push ebx; store the value of three registers
                      mov esi, 0xaa55aa55 ; pat0 = 0xaa55aa55
                      mov edi, 0x55aa55aa; pat1 = 0x55aa55aa
                      mov eax, [esp + 12 + 4]; i = start
    mts_loop:
                      mov ebx, eax
                      add ebx, Oxffc; p = i + Oxffc
                      mov edx, [ebx]; old = *p;
                      mov [ebx], esi ; *p = pat0
                      xor dword [ebx], Oxffffffff ; *p ^= Oxffffffff
                      cmp edi, [ebx] ; if (*p != pat1) goto fin
                      jne mts_fin
                      xor dword [ebx], Oxffffffff ; *p ^= Oxffffffff
                      cmp esi, [ebx] ; if (*p != pat0) goto fin;
                      jne mts_fin
                      mov [ebx], edx; *p = old;
                      add eax, 0x1000; i += 0x1000;
241
                      cmp eax, [esp + 12 + 8]; if (i \le end) goto mts_loop;
                      jbe mts_loop
                      pop ebx
                      pop esi
                      pop edi
                      ret
```

```
249 mts_fin:
250 mov [ebx], edx; *p = old;
251 pop ebx
252 pop esi
253 pop edi
254 ret
```

## A.2.2 Memory allocation process

```
unsigned int memman_alloc(struct MEMMAN *man, unsigned int size)
64
66
     unsigned int i, a;
      for (i = 0; i < man -> frees; i++)
67
          if (man -> free[i].size >= size) // discovering an free space of
              sufficient size
              a = man -> free[i].addr;
              man -> free[i].addr += size;
              man -> free[i].size -= size;
              if (man -> free[i].size == 0)// if the free size of the i'th
                  item is zero
                {
                  man -> frees--;
                  for (; i < man -> frees; i++)
                    man -> free[i] = man -> free[i + 1]; // move
                }
              return a;
        }
     return 0;
84
   }
```

## A.2.3 Memory release process

```
int memman_free(struct MEMMAN *man, unsigned int addr, unsigned int size)
    // release

int i, j;

/*

considering easiness of summarization, it is better for free[] to be
    arranged in order of addr
    So first, decide where to put

*/

for (i = 0; i < man -> frees; i++)

{
    if (man -> free[i].addr > addr)
        break;
}
```

```
// free[i - 1].addr < addr < free[i].addr
if (i > 0) // if there is an free entry near the released entry
    if (man -> free[i - 1].addr + man -> free[i - 1].size == addr)
        man -> free[i - 1].size += size;
        if (i < man -> frees)
          {
            if (addr + size == man -> free[i].addr)
                man -> free[i - 1].size += man -> free[i].size;
                //delete man->free[i]
                man -> frees--;
                for (; i < man -> frees; i++)
                    man -> free[i] = man -> free[i + 1]; // moving all
                        after i'th item.
                  }
              }
          }
        return 0; // successful completion
 }
if (i < man -> frees)
    if (addr + size == man -> free[i].addr)
      {
        man -> free[i].addr = addr;
        man -> free[i].size += size;
        return 0; // successful completion
      }
 }
if (man -> frees < MEMMAN_FREES)</pre>
  {
    for (j = man \rightarrow frees; j > i; j--)
        man -> free[j] = man -> free[j - 1];
   man -> frees++;
    if (man -> maxfrees < man -> frees)
        man -> maxfrees = man -> frees; // update maximum value
   man -> free[i].addr = addr;
```

```
man -> free[i].size = size;
return 0; // successful completion
}

// can not move backwards.
man -> losts++;
man -> lostsize += size;

return -1; // failed end.
```

#### A.2.4 Task allocate

```
struct TASK* task_alloc(void)
116
       int i;
       struct TASK *task;
       for (i = 0; i < MAX_TASKS; i++)</pre>
            if (taskctl -> tasks0[i].flags == 0)
              {
                 task = &taskctl -> tasks0[i];
                 task -> flags = 1; // mark in use
                task -> tss.eflags = 0x00000202;
                task -> tss.eax = 0; // leave it 0 for now
                task -> tss.ecx = 0;
                task \rightarrow tss.edx = 0;
                task \rightarrow tss.ebx = 0;
                task \rightarrow tss.ebp = 0;
                task -> tss.esi = 0;
                task -> tss.edi = 0;
                task \rightarrow tss.es = 0;
                task \rightarrow tss.ds = 0;
                task -> tss.fs = 0;
                task \rightarrow tss.gs = 0;
                task \rightarrow tss.iomap = 0x40000000;
                task \rightarrow tss.ss0 = 0;
                return task;
       return 0; // all are in use
```

#### A.2.5 Task add

```
void task_add(struct TASK *task)

f 
struct TASKLEVEL *tl = &taskctl -> level[task -> level];

tl -> tasks[tl -> running] = task;

tl -> running++;
```

```
task -> flags = 2; // in running
return;
}
```

## A.2.6 Task scheduling

```
186
    void task_switch(void)
      struct TASKLEVEL *tl = &taskctl -> level[taskctl -> now_lv];
      struct TASK *new_task, *now_task = tl -> tasks[tl -> now];
      tl -> now++; // addition for the next task switch in the same level
      if (tl -> now == tl -> running)
        t1 \rightarrow now = 0;
      if (taskctl -> lv_change != 0)// need to change level
        {
          task_switchsub();// find the highest level tasks
          tl = &taskctl -> level[taskctl -> now_lv];
        }
      new_task = tl -> tasks[tl -> now];
      timer_settime(task_timer, new_task -> priority);
      if (new_task != now_task)
        farjmp(0, new_task -> sel);
      return;
    }
49
    void task_switchsub(void)
      int i;
      // find the highest level
      for (i = 0; i < MAX_TASKLEVELS; i++)</pre>
          if (taskctl -> level[i].running > 0)
             break; // found
        }
      taskctl -> now_lv = i;
      taskctl -> lv_change = 0;
      return;
    }
```

## A.2.7 Task running

```
void task_run(struct TASK *task, int level, int priority)
{

if (level < 0)
    level = task -> level; // don't change level
```

```
if (priority > 0)
    task -> priority = priority;

if (task -> flags == 2 && task -> level != level)// change in active
    level
    task_remove(task);// flag will be 1

if (task -> flags != 2) // waking up from sleep

{
    task -> level = level;
    task_add(task);
}

taskctl -> lv_change = 1; // change the lv_change, so next time must
    check level
return;
}
```

## A.2.8 Task sleep

```
void task_sleep(struct TASK *task)
      struct TASK *now_task;
      if (task -> flags == 2)
        {
           // if it is running
          now_task = task_now();
          task_remove(task); // when this function done, flags will be 1
          if (task == now task)
               // sleeping myself, task switch needing
              task_switchsub();
              now_task = task_now();
              farjmp(0, now_task -> sel);
        }
      return;
    }
184
```

#### A.2.9 Task remove

```
void task_remove(struct TASK *task)
{
  int i;
  struct TASKLEVEL *tl = &taskctl -> level[task -> level];

for (i = 0; i <tl -> running; i++)// find where the task is
  {
   if (tl -> tasks[i] == task)
      break; // here
```

```
32     }
33
34     tl -> running--;
35     if (i < tl -> now)
36         tl -> now--;
37
38     if (tl -> now >= tl -> running)
39         tl -> now = 0; // if now is a strange value, fix it
40
41     task -> flags = 1;// sleeping
42
43     for (; i < tl -> running; i++)
44         tl -> tasks[i] = tl -> tasks[i + 1];
45
46     return;
47     }
```

## A.2.10 Graphic height setting

```
void sheet_updown(struct SHEET *sht, int height)// insert the sheet at the
        location of height
      struct SHTCTL *ctl = sht -> ctl;
      int h, old = sht -> height; // remember the height before setting
      // if the height is too low or too high, fix it.
      if (height > ctl -> top + 1)
        {
          height = ctl -> top + 1;
        }
      if (height < -1)
261
          height = -1; // -1, hidden the sheet
      sht -> height = height; // set height
      //the following are mainly sort of sheets[]
      if (old > height) // it gets lower than before
267
        {
          if (height >= 0) //still showing, pull up
               for (h = old; h > height; h--)
                   ctl -> sheets[h] = ctl -> sheets[h - 1];
                   ctl -> sheets[h] -> height = h;
              ctl -> sheets[height] = sht;
               sheet_refreshmap(ctl, sht -> vx0, sht -> vy0, sht -> vx0 + sht
               \rightarrow -> bxsize, sht -> vy0 + sht -> bysize, height + 1);
```

```
sheet_refreshsub(ctl, sht -> vx0, sht -> vy0, sht -> vx0 + sht
        \rightarrow -> bxsize, sht -> vy0 + sht -> bysize, height + 1, old);
    else // hide
      {
        if (ctl -> top > old)// pull down
          {
            for (h = old; h < ctl \rightarrow top; h++)
                ctl -> sheets[h] = ctl -> sheets[h + 1];
                ctl -> sheets[h] -> height = h;
          }
        ctl -> top--; //since the number of sheets decrease by one, the
        → height at the top decreases
        sheet_refreshmap(ctl, sht->vx0, sht->vy0, sht->vx0 +

    sht->bxsize, sht->vy0 + sht->bysize, 0);
        sheet_refreshsub(ctl, sht -> vx0, sht -> vy0, sht -> vx0 + sht
        \rightarrow -> bxsize, sht -> vy0 + sht -> bysize, 0, old - 1);
      }
 }
else if (old < height) // it gets higher than before
 {
    if (old >= 0) // pull down
        for (h = old; h < height; h++)</pre>
            ctl -> sheets[h] = ctl -> sheets[h + 1];
            ctl -> sheets[h] -> height = h;
        ctl -> sheets[height] = sht;
      }
    else // from non-display state to display state
        for (h = ctl \rightarrow top; h >= height; h--)// lift up
          {
            ctl -> sheets[h + 1] = ctl -> sheets[h];
            ctl \rightarrow sheets[h + 1] \rightarrow height = h + 1;
          }
        ctl -> sheets[height] = sht;
        ctl -> top++; // since the number of being displayed increases
        → by one, the height at the top increases
      }
    sheet_refreshmap(ctl, sht->vx0, sht->vy0, sht->vx0 + sht->bxsize,
    → sht->vy0 + sht->bysize, height);
    sheet_refreshsub(ctl, sht -> vx0, sht -> vy0, sht -> vx0 + sht ->

→ bxsize, sht -> vy0 + sht -> bysize, height, height);

 }
```

```
321 return;
322 }
```

## A.2.11 Palette setting

```
void init_palette(void)
4
            static unsigned char table_rgb[16 * 3] =
5
6
                             0x00, 0x00, 0x00,
                             0xff, 0x00, 0x00,
9
                             0x00, 0xff, 0x00,
                             Oxff, Oxff, Ox00,
                             0x00, 0x00, 0xff,
                             Oxff, 0x00, 0xff,
                             0x00, 0xff, 0xff,
                             Oxff, Oxff, Oxff,
                             0xc6, 0xc6, 0xc6,
                             0x84, 0x00, 0x00,
                             0x00, 0x84, 0x00,
                             0x84, 0x84, 0x00,
                             0x00, 0x00, 0x84,
                             0x84, 0x00, 0x84,
                             0x00, 0x84, 0x84,
                             0x84, 0x84, 0x84
                    };
            unsigned char table2[216 * 3];
        int r, g, b;
        set_palette(0, 15, table_rgb);
        for (b = 0; b < 6; b++)
          {
            for (g = 0; g < 6; g++)
              {
                for (r = 0; r < 6; r++)
                    table2[(r + g * 6 + b * 36) * 3 + 0] = r * 51;
                    table2[(r + g * 6 + b * 36) * 3 + 1] = g * 51;
                    table2[(r + g * 6 + b * 36) * 3 + 2] = b * 51;
                  }
              }
          }
        set_palette(16, 231, table2);
41
            return;
   }
43
44
45
   void set_palette(int start, int end, unsigned char *rgb)
   {
47
```

```
int i, eflags;
48
            eflags = io_load_eflags();
            io_cli();
            io_out8(0x03c8, start);
            for (i = start; i <= end; i++)</pre>
                              io_out8(0x03c9, rgb[0] / 4);
                              io_out8(0x03c9, rgb[1] / 4);
                              io_out8(0x03c9, rgb[2] / 4);
                              rgb += 3;
                     }
            io_store_eflags(eflags);
            return;
63
64
    }
```

#### A.2.12 PIC

```
void init_pic(void)
7
      io_out8(PICO_IMR, Oxff); // all interrupts are forbidden
8
      io_out8(PIC1_IMR, 0xff);
9
      io_out8(PICO_ICW1, 0x11); // edge trigger mode
      io_out8(PICO_ICW2, 0x20); // IRQO - 7 received by int20 - 27
      io_out8(PICO_ICW3, 1 << 2); // connect PIC1 via IRQ2
     io_out8(PICO_ICW4, 0x01); // no buffer mode
      io_out8(PIC1_ICW1, 0x11); // edge trigger mode
      io_out8(PIC1_ICW2, 0x28); // IRQ8 - 15 received by int28 - 2f
     io_out8(PIC1_ICW3, 2); // connect PIC1 via IRQ2
     io_out8(PIC1_ICW4, 0x01); // no buffer mode
      io_out8(PICO_IMR, Oxfb); //11111011, all forbidden expect PIC1
      io_out8(PIC1_IMR, Oxff); // all interrupt forbidden
     return;
24
   }
```

## A.2.13 Keyboard and Mouse

```
void wait_KBC_sendready(void)

{
    // wait for the keyboard controller to be able to transmit data.
for (;;)

{
    if ((io_in8(PORT_KEYSTA) & KEYSTA_SEND_NOTREADY) == 0)
        break;
```

```
}
28
     return;
32
   void init_keyboard(struct FIF032 *fifo, int data0)
     // memory of FIFO buffer to be written is stored
     keyfifo = fifo;
     keydata0 = data0;
     // initialization of keyboard controller
     wait_KBC_sendready();
40
     io_out8(PORT_KEYCMD, KEYCMD_WRITE_MODE);
41
     wait_KBC_sendready();
      io_out8(PORT_KEYDAT, KBC_MODE);
43
44
     return;
   }
45
   void enable_mouse(struct FIF032 *fifo, int data0, struct MOUSE_DEC *mdec)
     // memory of FIFO buffer to be written is stored
23
     mousefifo = fifo;
     mousedata0 = data0;
     // mouse effective
     wait_KBC_sendready();
      io_out8(PORT_KEYCMD, KEYCMD_SENDTO_MOUSE);
     wait_KBC_sendready();
30
      io_out8(PORT_KEYDAT, MOUSECMD_ENABLE);
     // if it works, ACK(oxfa) will be sent.
     mdec -> phase = 0; // waiting for mouse Oxfa.
     return;
35
   }
36
```