



## User manual

### Screen Composer & SignMeeting Jooxter

2.12.11 001A



## **Legal information**

### **Screen Composer & SignMeeting Jooxter 2.12.11 (001A\_en)**

© 2021 INNES

#### **Rights and Responsibilities**

All rights reserved. No part of this manual may be reproduced in any form or by any means without written permission of the publisher. Products and services mentioned herein may be trademarks and/or registered trademarks of their respective owners. The publisher and the author make no claim to these trademarks.

While every precaution has been taken in the preparation of this document, the publisher and author assume no responsibility for errors or omissions, or for damages resulting from the use of this document, or from the use of the programs and source code that may accompany it. In no event shall the publisher and author be liable for any loss of profit or other commercial loss caused or contributed to by the use of this document.

#### **Product information**

The design and specifications of the product are subject to change at any time and INNES reserves the right to change them without notice. This includes the hardware, embedded software and this manual, which should be considered as a general guide to the product. The accessories supplied with the product may differ slightly from those described in this manual, depending on the developments of the various suppliers.

# Table of contents

## Part I : Introduction

Introduction	1.1
--------------	-----

## Part II : Screen Composer installation and settings

Installation	2.1
Qeedji System AOSP devices configuration to work with Screen Composer G4	2.1.1
Gekkota devices configuration to work with Screen Composer G4	2.1.2
Getting started	2.2
Screen Composer > About	2.2.1
Screen Composer > Preferences > Repositories	2.2.2
Screen Composer > Preferences > Network	2.2.3
Screen Composer > Preferences > Middlewares	2.2.4
Screen Composer > Preferences > Licenses and Apps	2.2.5
App installation	2.2.5.1
App license keys installation	2.2.5.2
Screen Composer > Preferences > Advanced	2.2.6
File > Project settings > Devices	2.2.7
File > Project settings > Project and App	2.2.8
File > Project settings > Publication	2.2.9
File > Project settings > Tasks	2.2.10

## Part III : Project

SignMeeting Jooxter new project	3.1
Files	3.1.1
Files > Edition and metadata	3.1.1.1
Files > Open and preview	3.1.1.2
Files > Unitary preview	3.1.1.3
Fonts	3.1.1
Variables	3.1.1
Devices	3.1.1
Data sources	3.1.1
Display profiles	3.2
SignMeeting > Display profiles > Room screen	3.2.1
SignMeeting > Display profiles > Summary screen by event	3.2.2
SignMeeting > Display profiles > Summary screen by resource	3.2.3
SignMeeting > Display profiles > Room label	3.2.4
Devices	3.3
Room resources association to a device	3.3.1
LDAP	3.4
RFID	3.5
SMTP	3.6

## Part IV : Publication

App publication	4.1
Middleware publication	4.2

## Part V : Contacts

Contacts	5.1
----------	-----

## Part VI : Appendix

Appendix: Jooxter calendar system	6.1
Appendix: Jooxter administration	6.2
Appendix: CSS mapping	6.3
Appendix: Data mapping	6.4
Appendix: Information message when using an inconsistent resource Id	6.5
Appendix: Room screen CSS	6.6
Appendix: Summarization by event CSS	6.7
Appendix: Summarization by resource CSS	6.8
Appendix: Room label CSS	6.9

Appendix: How to customize CSS	6.10
Appendix: Standby screen/backgroud image/CSS hierarchy	6.11
Appendix: Banner characteristics	6.12
Appendix: Microsoft LDAP attribute editor	6.13
Appendix: Briva LDAP attributes	6.14
Appendix: Logs INNES Screen Composer G4	6.15
Appendix: Set temporarily SignMeeting in native mode to access to the AOSP settings	6.16

# **Part I**

---

**Introduction**

## **1.1 Introduction**

This user manual explains how to configure a SignMeeting Jooxter App project with INNES Screen Composer 64 and how to use it on the devices.

### **Supported calendar system**

SignMeeting Jooxter App is dealing with the Jooxter calendar system for example with the URL <https://en.app.jooxter.com/>.

The level of Jooxter APIs supported by SignMeeting Jooxter 2.YY.ZZ (or above) is v3. For further information, contact support@innes.pro.

### **Other application**

When SignMeeting Jooxter has to run on the device, it is advised to remove all other applications which could start at the same time on the device.

## Display profiles


The SignMeeting Jooxter App allows to display the events of one or several room resources taking place along the day on a tablet or on a screen connected to a media player and manage meetings booking for several resources and for the next days.

Depending on the chosen *display profile*, the SignMeeting Jooxter App can allow to manage instant booking with dedicated interactive buttons.

In this SignMeeting Jooxter App version, these are the supported display profiles:

### Display profiles

#### Room screen



Usually designed to run on touch screen tablets, the *Room screen display profile* allows to display until two following events in two areas: the upper area for the current event and the lower area for the next event. This *display profile* supports dedicated Book now / Delete / Confirm buttons to manage instant booking for the resources associated to this device.

#### Summary screen by event



Usually designed to run on media players connected to an secondary screen (but can also run on AOSP tablets or Gekkota 4 tablets), the *Summary screen by event display profile* allows to display a list of events taking place along the day, on different pages, for several resources, with one event per raw. It can support until two directionals pictograms per room name to improve the room way finding signalization.

#### Summary screen by resource



Usually designed to run on media players connected to an secondary screen (but can also run on AOSP tablets or Gekkota 4 tablets), the *Summary screen by resource display profile* allows to display a table of events, taking place along the day, on different pages, for several resources, with one resource par raw. Several events can be displayed per raw.

#### Room label



Suitable only to run on the *SMH300 hub* communicating with *SLATE106* devices, the *Room label display profile* allows to display until two events in two areas: the upper area for the current event and the lower area for the next event.

All the display profiles'styles can be customized with a CSS theme.

## Access control

SignMeeting Jooxter supports access control:

- by single badging or
- by single badging, with badge ID and user registered in your LDAP server.

*☞ Access control requires that the device has a built-in or an external badge reader.*

*☞ INNES may be able to provide a LDAP solution called [Briva LDAP](#), gateway able to communicate with an access control system like, for example, [Uniflow](#). For further information, contact [sales@innes.pro](mailto:sales@innes.pro).*

## Screen Composer compatibilities

The configuration of SignMeeting Jooxter and its publication on device is done by using [INNES Screen Composer G4](#). For further information, refer to the chapter § [Screen Composer > Installation](#).

## **Part II**

**Screen Composer installation and  
settings**

## 2.1 Installation

INNES Screen Composer G4 Desktop is a single-user and single-computer station application. In this user manual, each INNES Screen Composer G4 project, whose extension is `.isz`, is based on a SignMeeting Jooxter App product.

Once your SignMeeting Jooxter App product is configured, INNES Screen Composer G4 allows to publish it on several devices.

**After a first installation, INNES Screen Composer G4 embeds no App product.**

Some core INNES Screen Composer G4 license keys must be installed in order to have the publishing tokens required to publish to devices.

As soon as an SignMeeting Jooxter App is published on a device, a core license key is automatically associated with that device, using its MAC id.

If you use a pack of 20 core license keys or a pack of 5 core license keys, the total number of core license keys must be greater than or equal to the number of devices registered in your Screen Composer, regardless of the number of Apps used.

The using of the SignMeeting Jooxter App requires also the installation of an SignMeeting Jooxter App license key.

### Prerequisite

INNES Screen Composer G4 must be installed on a recent computer:

- OS: MS-Windows 10,
- Processor: Core i5/i7,
- DDR: 4 GB (or more),
- HDD: 160 GB (or more).

**The firewall of this computer must allow the port 80 (http) so that INNES Screen Composer G4 can publish on the devices, available by default on the port 80.**

### Supported OS/devices

INNES Screen Composer G4 can work with :

- Qeedji System AOSP 9.10.14 (or above) for:
  - AMP300 (media player),
  - TAB10s (10" tablet),
- Gekkota OS 4.13.13 (or above) for:
  - SMT210 (10" tablet),
- Gekkota OS 4.14.14 (or above) for:
  - DMB400 (media player),
  - SMA300 (media player),
- Gekkota OS 5.11.10 (or above) for:
  - DMB300 (media player),
  - DMB400 (media player),
- Gekkota OS 4.13.14 (or above) for:
  - SMH300 (hubs),
- Gekkota RT 4.14.10 for:
  - MS-Windows computers.

**Before working with INNES Screen Composer G4, the devices must be properly configured. For further information, refer to the chapter § [Gekkota devices configuration for INNES Screen Composer G4](#) and the chapter § [Qeedji System AOSP devices configuration for INNES Screen Composer G4](#).**

### Installation

To install INNES Screen Composer G4, execute `screen-composer-nt_ia32-setup-4.<yy>.<zz>.exe`.

Select the appropriate user interface language among the suggested INNES Screen Composer G4 languages:

- English,
- French,
- German.

**160 MB disk memory are first required to be able to install INNES Screen Composer G4. Then some additional disk space will depend on the space required for your project repository.**

The default directory for the installation is:

- C:\Program Files (x86)\INNES Screen Composer G4 .

The default shortcuts located in the Windows startup menu is:

- INNES Screen Composer G4 .

### Launch

When the installation is completed, launch INNES Screen Composer G4 by using the:

- MS-Windows startup menu,
- MS-Windows cortana.



INNES Screen Composer G4

## Language

To change the language of the INNES Screen Composer G4 user interface, uninstall INNES Screen Composer G4 and install it again by choosing among the supported languages described before.

## Uninstallation

Use the Add or remove programs tool in MS-Windows System settings to remove the INNES Screen Composer G4 program from your computer.

## 2.1.1 Qeedji System AOSP devices configuration to work with Screen Composer G4

The Qeedji System AOSP devices are the devices that have a AQS operating system whose version is 9.<yy>.<zz>. To work with INNES Screen Composer G4 , ensure that your devices have a AQS 9.10.12 firmware version (or above).

In case using a AMP300 device, provide a suitable power supply to it, through the LAN/PoE RJ45 connector, the POWER IN USB-C or the USB 1 USB-C connector if your display device supports USB-C supply, then wait the LED status is blinking once every four seconds. If coming straight from factory, the device should display the test card content. In case using a TAB10s device, provide a suitable power supply to it then wait the device is displaying the content of the AQS desktop on the screen.

An Qeedji System AOSP device can be configured with its Web user interface by using this URL [http://<aqs\\_device\\_ip\\_addr>/](http://<aqs_device_ip_addr>) with a recent version of a Web browser like Google Chrome , Mozilla Firefox and Microsoft Edge (Chromium) .

- The default login credentials for the Administration User connection profile, allowing to connect to the device configuration Web user interface, are admin / admin .

Then click on the Administration button to display the device configuration Web user interface.

- After having made some parameters modification, the device must be restarted so that the modifications are fully reflected.

For further information about the connection to the device configuration Web user interface, refer to the appropriate user manual.

AQS device user manuals
<a href="#">AMP300 user manual</a>
<a href="#">TAB10s user manual</a>

### Web UI: Configuration > Administrator

The default hostname is TAB10s for TAB10s device and AMP300 for AMP300 device. It is recommended that you enter a different hostname value for each device. In case several devices are located in different buildings or geographical locations, we recommend that you enter hostname values containing information about the building and the location (e.g. Hall-RD-Paris-1).

- For security reasons, it is advised to change the login credentials of the Administration User connection profile to access to the device configuration Web user interface.
- If modified, store preciously the login credentials because they are required in INNES Screen Composer G4 to communicate with the devices.

### Web UI: Configuration > LAN1

Provide the network connectivity to the device by plugging an Ethernet cable then ensure that the device has a consistent IP address value.

- If the tablet needs to access to the LAN network, install the appropriate PoE to USB-C adapter allowing to provide IP network connectivity to the tablet then ensure that the tablet has a consistent IP address.
- Activating temporarily the Test Card App launching at start-up allows to check whether the LAN1 network interface (I/F) is ON and whether the network interface STATE is up. It is also possible to view this status in the Network panel of the Information menu.

### Web UI: Configuration > WLAN1

If the device needs to access to the WIFI network, activate and configure the WIFI on the device then ensure that the device has a consistent IP address value.

- Activating temporarily the Test Card App launching at start-up allows to check whether the WLAN1 network interface (I/F) is ON and whether the network interface STATE is up. It is also possible to view this status in the Network panel of the Information menu.

### Web UI: Configuration > Output

In case using an AMP300 device, plug a display device on it through the USB 1 USB-C connector or through the HDMI connector. Set an output resolution supported by your display device.

- The 90°, 180° and 270° rotation is supported on AMP300 devices but is not supported on the TAB10s devices.

### Web UI: Configuration > App

After having published the SignMeeting Jooxter App on the device, the device installs the SignMeeting Jooxter App then restarts automatically once. After this device restart, the couple of App name (SignMeeting Jooxter, SignMeeting Jooxter UI) must appear in the table of activable Apps.

- It is advised to deactivate all other unuseful Apps.

### Web UI: Configuration > Server

Enter the appropriate DNS server and gateway values to access to the Web contents.

The date and time is set automatically thanks to a Web NTP server .

- If ever the device could not be allowed to access to a Web NTP server , a NTP server needs to be implemented on your local network to provide the current date and time to the device.

## **Web UI: Configuration > Date & Time**

It is advised that the device is on time. The `date` and `time` is set automatically thanks to a Web NTP server . It is advised that the timezone is properly set.

## **Web UI: Maintenance > Test Card**

When the device configuration is completed, the `Test Card` App launching at start-up must be deactivated to see the SignMeeting Jooxter App running on the screen.

## **Web UI: Maintenance > Firmware**

To work with `INNES Screen Composer G4` , the firmware version of `Qeedji System AOSP` for `TAB10s` device or `AMP300` device, must be 9.10.12 (or above).

## **Kiosk mode**

When delivered straight from factory, the device is in `native` mode. The SignMeeting Jooxter App is executed automatically in `kiosk` mode, making that the `back`, `menu` and `swipe` AOSP features are inactivated and so can not be used. You can exit temporally from the `kiosk` mode by pressing on the `system button` of the AQS device.

## 2.1.2 Gekkota devices configuration to work with Screen Composer G4

### Gekkota 4 devices

The Gekkota 4 devices are the devices that have a Gekkota OS or Gekkota RT middleware whose version is 4.<yy>.<zz>. To work with INNES Screen Composer G4 , ensure that your devices have a Gekkota OS 4.13.10 firmware version (or above).

To work as devices with INNES Screen Composer G4 , ensure that your dedicated MS-Windows computers have Gekkota RT 4.13.15 version (or above) and fill the following configuration:

- OS: MS-Windows 10,
- Processor: Core i5/i7,
- DDR: 4 GB (or more),
- HDD: 160 GB (or more).

To install Gekkota RT on a dedicated MS-Windows computer, download the Gekkota RT middleware from the [Innes Web site](#), execute the `gekkota_rt-nt_ia32-setup-4.<yy>.<zz>.exe` installer on the dedicated MS-Windows computer. After the installation is completed, the Gekkota RT may start up automatically and display an information message *Information - No content*.

**» Depending on the computer, the Gekkota start-up duration may be few minutes.**

Provide a suitable power supply to the device then wait the LED status is blinking once every four seconds. If coming straight from factory, the `test card` content should be displayed on the screen.

A Gekkota G4 device can be configured with its Web user interface by using this URL `http://<gekkota_4_device_ip_addr>/` with a recent version of a Web browser like Google Chrome , Mozilla Firefox and Microsoft Edge (Chromium) .

**» The default login credentials to connect to the Web user interface are admin / admin .**

Then click on the `Administration Console` button to display the device configuration Web user interface.

**» After having made some parameters modification, the device must be restarted so that the modifications are fully reflected.**

For further information, refer to the appropriate user manual.

Gekkota OS G4 device user manuals
<a href="#">SMT210 user manual</a>
<a href="#">DMB400 user manual</a>
<a href="#">SMA300 user manual</a>
<a href="#">SMH300 user manual</a>

### Gekkota 5 devices

The Gekkota 5 devices are the devices that have a Gekkota Os middleware whose version is 5.<yy>.<zz>. To work with INNES Screen Composer G4 , ensure that your devices have a Gekkota OS 5.10.11 firmware version (or above).

A Gekkota 5 device can be configured with its web-based configuration interface using this URL `http://<gekkota_5_device_ip_addr>/` with a recent version of a web browser like Google Chrome , Mozilla Firefox and Microsoft Edge .

**» The default login credentials to connect to the device configuration Web user interface are admin / admin .**

**» After having made some parameters modification, the device must be restarted so that the modifications are fully reflected.**

### Web UI: Configuration > Administrator

It is recommended that you enter a different `Hostname` value for each device. In case several tablets are located in different buildings or geographical locations, we recommend that you enter hostname values containing information about the building and the location (e.g. Hall-RD-Paris-1).

For security reasons, it may be useful to change the `Administrator name` and `password` login credentials to access to the device's WebDAV server.

**» If modified, store previously the login credentials because they are required to register properly the devices in INNES Screen Composer G4.**

### Web UI: Configuration > WLAN

If the device supports the `WIFI` option and needs to access to the `WIFI` network, activate and configure properly the WLAN interface:

- DHCP,
- IP address,
- subnet mask,
- gateway.

**» Activating temporarily the `Test card` allows to check whether this network interface STATE is up. It is also possible to view this status in the `Network` panel of the `Information` menu.**

### Web UI: Configuration > LAN

If the device needs to access to the `LAN` network, activate and configure properly the LAN interface:

- DHCP,

- IP address,
- subnet mask,
- gateway.

☞ Activating temporarily the `Test Card` allows to check whether this network interface STATE is up. It is also possible to view this status in the `Network` panel of the `Information` menu.

## Web UI: Configuration > Output

When using a portrait `display profile`, it is required to apply a 90° (or 270°) rotation to the media player output as well.

☞ The 90°, 180° and 270° rotation is supported on media-players but is not supported on the tablets.

## Web UI: Configuration > App

Is it required that the device `App` mode is configured in `Push WebDAV`.

## Web UI: Configuration > License

The `license` key is already registered in the device when it is coming straight from factory.

☞ When using Gekkota5 middleware, the license key value specific to the Gekkota 5 middleware is not provided. For further information, contact `sales@qeeji.tech`.

☞ The device license key has been provided by email when the device has been ordered then delivered. In case the license key has been erased and lost, another device license key can be obtained by sending an email to `License@qeedji.tech` by specifying in the subject of the message the MAC address value and the serial number value of the device.

## Web UI: Configuration > Servers

It is advised that the device is on time. The `date` and `time` is set automatically thanks to a Web `NTP` server.

If ever the device could not be allowed to access to a Web `NTP` server, a `NTP` server needs to be implemented on your local network to provide the `date` and `time` to the device.

## Web UI: Configuration > Date and time

It is advised that the device is on time. Set an appropriate value for `Timezone`, `Date` and `Time`.

☞ When the `date` and `time` is modified, the device restarts automatically once so that the time modification is applied as soon as possible.

## Web UI: Maintenance > Test Card

When the device configuration is completed, the `Test Card` must be deactivated to see the SignMeeting Jooxter App running on the screen.

☞ Activating temporarily the `Test Card` allows to check whether the STATE of a network interface is up.

## 2.2 Getting started

To work with INNES Screen Composer G4 , launch INNES Screen Composer G4 then:

- [install once your INNES Screen Composer G4 core license key with the user email.](#)

To create a project in INNES Screen Composer G4 based on the SignMeeting Jooxter App, you need to:

- [create a project](#),
- [install the SignMeeting Jooxter App with its licenses keys](#),
- [define a default project repository](#) to store especially, in the Files view of your project repository:
  - CSS theme ( .css ),
  - medias (images, videos),
  - Javascript script ( .js ).

To publish your SignMeeting Jooxter App on your devices, your need to add some devices to your project, choose the Publish the App to devices button value, and click on the  button. For further information, refer to the chapter § [File > Project settings > Devices](#).

To launch INNES Screen Composer G4 , search the INNES Screen Composer G4 Desktop application and launch it.



## Welcome page


This is the welcome page when no App is installed, no Project is opened and no project repository is created.

The available buttons at this step are:

- New project (1),
- Open project (2),
- Reveal in the explorer (3) the default repository:  
C:\Users\<username>\INNES Screen Composer G4\workspace 1\ (4).

The available links at this step are:


- Install licenses and install Apps (5),
- Set up the repositories and models (6).



The last opened projects will appear in the Recent projects (12) pane.


The available items, at this step, in the File (10) menu are:

- New project (1),
- Open project (2),
- Quit (7).



The available items in the Screen Composer [\(11\)](#) menu are:

- Preferences [\(8\)](#),
- About [\(9\)](#).



## About

The [About](#) pane allows to display information about INNES Screen Composer G4 . Fur further information, refer to the chapter § [Screen Composer > About](#).

## Repositories


The default project repository for your project is:

C:\Users\<username>\INNES Screen Composer G4\workspace 1\

To create another project repository, refer to the chapter § [Repositories](#).

## Licenses and Apps

No SignMeeting Jooxter App [\(12\)](#) is installed by default in INNES Screen Composer G4 .




To install the SignMeeting Jooxter App, refer to the chapter § [SignMeeting Jooxter App installation](#).

To install your SignMeeting Jooxter App and your INNES Screen Composer G4 core license key with the user email, refer to the chapter § [Screen Composer > Preferences > Licenses and Apps](#).

## New project

To create a new INNES Screen Composer G4 project, click on the `New project` button (or `New project` item of the `File` menu).



Enter a label for your project and select the SignMeeting Jooxter App on which the project is based.

- ☞ If there is no SignMeeting Jooxter App available at this step, click on the `Edit Apps` button to install an App. For further information, refer to the chapter § [Screen Composer > Preferences > Licenses and Apps](#).
- ☞ Once the project is saved, it can be reopened with the `Open project` item of the `File` menu.


For further information, refer to the chapter § [SignMeeting JOOXTER new project](#).

## 2.2.1 Screen Composer > About

In the Screen Composer menu, click on the **About** item to see the version of INNES Screen Composer G4.

The **About** pane allows to display information about:

- INNES Screen Composer G4 version (e.g. 4.11.11),
- INNES Web site,
- Rights notice.



## 2.2.2 Screen Composer > Preferences > Repositories

A project repository must be mounted on a local directory of your MS-Windows file system allowing to store medias, content models and projects resources. It is required to define a default repository when creating your Screen Composer project.

INNES Screen Composer G4 can have different project repositories. But only one project repository is active per project at a time.

When created, a project repository contains this tree:

```
- /.db,  
- /.fonts,  
- /.medias,  
- /.models,  
- /.tmp,  
- .lock,  
- .uuids.
```

 It is recommended to use an empty directory for the repository. Indeed, in case you decide to remove this repository afterwards, the directory will be completely removed from your file system.

The /.medias directory is corresponding to  Media tab of the project repository.

The /.models directory is containing the content models and URI models.

 In this version, there is no specific view allowing to list all the content models and all the URI models.


To show the available repositories, select the Preferences item of the Screen Composer menu then select the Repositories item.

Each project repository has a label  (1) which can be then modified afterwards. The default project repository is named Repository #1.

It is possible to create HTML widget from content model. To install the content models packs in your repository, download the appropriate content model packs (*Education, General, Traffic Info France, Signage*) (.zip) on your computer from the [INNES support Web site](#). Then click on the `Install models from your computer`  (2) button.

It is possible also to create URI from URI model. To install the URI models packs in your repository, download the appropriate URI model packs (*Device peripherals, Web TV channels, TV channels France*) (.zip) on your computer from the [INNES support Web site](#). Then click on the `Install models from your computer`  (2) button.

To add a new project repository, click on the  (3) button then select an appropriate directory.



It is possible also to switch to another project repository afterwards. For further information, refer to the chapter § [File > Project settings > Project and App](#).

 The repositories references are stored in the `prefs.js` file:

`C:\Users\<username>\AppData\Roaming\INNES Screen Composer G4\prefs.js`

 To open the directory location of your project repository in the MS-Explorer, click on the `Reveal in the explorer`  (4) button.

## 2.2.3 Screen Composer > Preferences > Network

In the Preferences item of the Screen Composer menu, select the Network item.

Set the toggle button to the right (blue color) to use a proxy server.


Several configurations are then possible:

- Manual configuration (1),
- Discover (2),
- Use the operating system settings (3),
- Automatic configuration (4).

### Proxy > Manual configuration

Select the Manual configuration radio to enter the proxy configuration yourself:

- the proxy IP address and login credentials for HTTPS (5),
- the proxy IP address and login credentials for HTTP (6),
- the proxy IP address and login credentials for FTP (7),
- the domains exceptions .



### Proxy > Discover configuration


Select the Discover radio to try to detect a proxy configuration.

### Proxy > Use operating system settings

Select the Use operating system settings radio to use the MS-Windows proxy configuration.

### Proxy > Automatic configuration

Select the Automatic configuration radio to use a proxy configuration script. Enter here the URL to get the proxy configuration script.




## 2.2.4 Screen Composer > Preferences > Middlewares

In the Preferences item of the Screen Composer menu, select the Middlewares item.

Click on the  button to choose the middlewares to import in INNES Screen Composer G4 .

 The middlewares are effectively imported in INNES Screen Composer G4 when the OK button is clicked to close the pane.



## 2.2.5 Screen Composer > Preferences > Licenses and Apps

### License policy

There are two core INNES Screen Composer G4 license key delivery formats:

- a newer format based on core INNES Screen Composer G4 license keys pack:
- this can be a Screen Composer core for 20 devices core license key pack: capable of supporting up to twenty publishing tokens for publishing to devices with a single SignMeeting Jooxter App license key,
- this can be a Screen Composer core for 5 devices core license key pack: capable of supporting up to five publishing tokens for publishing to devices with a single SignMeeting Jooxter App license key,
- it can also be an additional Screen Composer core for 10 additional devices core license key pack: capable of supporting up to ten additional publishing tokens to publish to devices with still a single SignMeeting Jooxter App license key, bringing the total number of supported devices to respectively thirty (twenty + ten) or fifteen (five + ten).<sup>1</sup>
- an older format based on a single core INNES Screen Composer G4 license key:
- this Screen Composer core license key is capable of supporting older several SignMeeting Jooxter App <sup>2</sup> license keys.

<sup>1</sup> It is possible to install other Screen Composer core for 10 additional devices license keys packs to support more publishing tokens to publish on devices (e.g.: 20 + 10 + 10 + 10 + .... or 5 + 10 + 10 + 10 + ...).

<sup>2</sup> In this case, you also need as many SignMeeting Jooxter App license keys as devices registered in your INNES Screen Composer G4 projects to have the required publishing tokens.

### Installation

The INNES Screen Composer G4 core license keys have been delivered by INNES to the recipient email provided by the customer (e.g. cico@contoso.fr) with this kind of email body<sup>1</sup>:

- Screen Composer core license key format:

```
Copy the core license key line below and paste it in.  
Core license key :  
WViS1 - ffaf - wuTW - S4ab - zz/ff; PSN01200-00251 CD1; Screen Composer core
```

- Screen Composer core for 20 devices license key format:

```
Copy the core license key line below and paste it in.  
Core license key :  
ZWTxF - ff/o - w7Y1 - Gziz - ncIff ; PSN01202-00000 CD3 ; Screen Composer core for 20 devices
```

- Screen Composer core for 10 additionnal devices license key format:

```
Copy the core license key line below and paste it in.  
Core license key :  
MDHar - ffJS - QL7h - 194D - DJlff ; PSN01560-00000 CD4 ; Screen Composer core for 10 additional devices
```

The license shown above is a fake license.

Open this email, and copy the entire line with the Screen Composer core suffix included.

- Screen Composer core license key format:

```
WViS1 - ffaf - wuTW - S4ab - zz/ff; PSN01200-00251 CD1; Screen Composer core
```


- Screen Composer core for 20 devices license key format and optional Screen Composer core for 10 additionnal devices license key formats:

```
ZWTxF - ff/o - w7Y1 - Gziz - ncIff ; PSN01202-00000 CD3 ; Screen Composer core for 20 devices  
MDHar - ffJS - QL7h - 194D - DJlff ; PSN01560-00000 CD4 ; Screen Composer core for 10 additional devices
```


 In case you have other licenses keys linked to a specific SignMeeting Jooxter App product, you can copy them and paste them as well. A new SignMeeting Jooxter App part will be created in the pane and the licenses will be spread accordingly on the Screen Composer side and on the SignMeeting Jooxter App side. For further information, refer to the chapter § [App license keys installation](#).

To access to the Licenses and Apps pane, select the Preferences item of the Screen Composer menu. To work with INNES Screen Composer G4 with this computer:

- enter the License e-mail value  of the e-mail account used to get the licenses (e.g. ciso@contoso.fr),
- click on the  Add licenses keys  button to add the Screen Composer core license key.




Paste ⑯ the license coming from your e-mail body.




For example:

A green checkmark ⑯ is showing that the license key is valid.

- Screen Composer core license key format:




- Screen Composer core for 20 devices and optional Screen Composer core for 10 additional devices license key formats:



The max. number of devices (in the example: 20 + 10 devices) supported in your project appears in this column (in the example: Max 30 = Max 20 + Max 10 ).

## Demo licenses

In case demo license key, the expiration date **⑯** and the max. of supported devices appear (e.g.: *Expires on Sunday, May 1, 2022, Max 5 devices*).



## 2.2.5.1 App installation


### App download and installation

Before creating a new INNES Screen Composer G4 project, you need get the last available SignMeeting Jooxter App version available for download from the [INNES Web site](#).

The SignMeeting Jooxter App file matches this pattern: `signmeeting_jooxter-screen_composer-addin-2.<yy>.<zz>.appi`.


From the welcome screen:

- either click on the `Add licenses and install Apps` (4) blue link,
- or click on the `Preferences` (2) item of the `Screen Composer` (1) menu then select the `Licenses and Apps` (3) item.




Click on the `Install an App from your computer` (5) and select the appropriate SignMeeting Jooxter App file:

- Filename pattern: `signmeeting_jooxter-screen_composer-addin-<xx>.<yy>.<zz>.appi`.



The SignMeeting Jooxter App (6) appears in the pane.



To remove the App, select the App and click on the Remove the App button.

- ☞ It is not possible to remove an App product which is currently used by the opened project.
- ☞ Once installed, the SignMeeting Jooxter App is stored automatically in the following directory `C:\Users\<username>\AppData\Roaming\INNES Screen Composer G4\innes\appis\`.

## 2.2.5.2 App license keys installation

### License policy

Each SignMeeting Jooxter App license key is associated to :

- a user email address (e.g. *ciso@contoso.fr*),
- a SignMeeting Jooxter App product (e.g. *SignMeeting Jooxter for Screen Composer*).

**⚠** You must have as much SignMeeting Jooxter App license keys as you have devices in your project.

**⚠** A SignMeeting Jooxter App license key cannot be used twice for two different devices in two different projects.

**⚠** A SignMeeting Jooxter App license key value can be paired to only one device, which is identified by its *MAC Id*. The pairing is done at the publication.

**☞** Once the SignMeeting Jooxter App licenses keys are installed, they are kept permanently in Screen Composer, and are visible for every projects.

### Installation

The SignMeeting Jooxter App license keys have been delivered by INNES to the user email address provided by the customer (e.g. *ciso@contoso.fr*) with this kind of user email body<sup>1</sup>:

- Copy all the Apps license key lines below (at once) and paste them in.

Apps License Keys (Qty = 3) :

Enter the appropriate licenses keys for your App product

```
HhBo - om6gl - px7Jp - 8itiV - zzViw ; PSN00930-00000 CD8 ; SignMeeting Jooxter for Screen Composer
kpjle - 5tew - x7uq - ubsee - zziaa ; PSN00930-00001 CD5 ; SignMeeting Jooxter for Screen Composer
tk5cK - efdCF - lyf1 - 8os1 - zzyBw ; PSN00930-00002 CD2 ; SignMeeting Jooxter for Screen Composer
```


**☞** When importing the SignMeeting Jooxter App license keys, a suffix is showing which App product, the license keys are given for.

The license shown above are fake license.


Copy the entire line with the *SignMeeting Jooxter for Screen Composer* suffix included.

```
HhBo - om6gl - px7Jp - 8itiV - zzViw ; PSN00590-00000 CD8 ; SignMeeting Jooxter for Screen Composer
kpjle - 5tew - x7uq - ubsee - zziaa ; PSN00590-00001 CD5 ; SignMeeting Jooxter for Screen Composer
tk5cK - efdCF - lyf1 - 8os1 - zzyBw ; PSN00590-00002 CD2 ; SignMeeting Jooxter for Screen Composer
```

Click on the  Add licenses keys **①** button to add the SignMeeting Jooxter App licenses keys.




A green checkmark **②** is showing that the license keys are valid. The expiration date **③** does appear (e.g.: *Expires on Sunday, May 1, 2022*).




## Publication and App license key pairing

To publish successfully, the number of device added to your project (e.g. (1) to (5)) must be equal to (or be lower than) the number of SignMeeting Jooxter App license keys to pair (e.g. 5 SignMeeting Jooxter App licenses keys from (6) to (10)).




When the publication is completed, Screen Composer keeps the pairing status of the SignMeeting Jooxter App license keys with the project's devices MAC Id .

The SignMeeting Jooxter App license key's pairing status is identified by a padlock (13) meaning that the SignMeeting Jooxter App license key is paired with this device.




In case, the number of SignMeeting Jooxter App license keys is not sufficient, a information message is raised when the publication is launched.



To work around,

- add the appropriate number of SignMeeting Jooxter App license keys missing to your project or,
- remove the excess devices from your project.

**☞** In case, you have added an unexpected device to your project and published on it, an SignMeeting Jooxter App license key value is spent for nothing. To work around, remove this device from your project and click on the **Unlock all** **☞ 17** button to forget **18** the overall SignMeeting Jooxter App license key pairing configuration then publish again.



## 2.2.6 Screen Composer > Preferences > Advanced

In the Preferences item of the Screen Composer menu, select the Advanced item.

Set the toggle button to the right (blue color) to Open the last project as soon as a INNES Screen Composer G4 is launched.



Set the toggle button to the left (grey color) to display the welcome pane instead of to Open the last project as soon as a INNES Screen Composer G4 is launched.



## 2.2.7 File > Project settings > Devices

Before launching a devices discovery (UPnP) on your local network, check that the devices are properly configured to work with INNES Screen Composer G4 and to work with the SignMeeting Jooxter App.


For further information about Qeedji System AOSP 9 devices, refer to the chapter § [Qeedji System AOSP devices configuration for Screen Composer G4](#).

For further information about Gekkota 4 devices, refer to the chapter § [Gekkota devices configuration for INNES Screen Composer G4](#).

To add devices to your project, click on the Project settings item of the File (1) menu, then select the Devices (2) item.

Click on the Discover (3) button to discover by UPnP the devices which are alive on the local network.

INNES Screen Composer G4 can detect Gekkota 4, Gekkota 3 and Qeedji System AOSP 9 devices.




A list of the devices is detected.


Project settings > Devices > Discover				
Label	IP Address	MAC Address	Model	Middleware
DMB400-F1	192.168.1.140	00:1CE602:23D3	DMB400	Gekkota 4
DMB400	192.168.57.3	00:1CE602:35A3	DMB400	Gekkota 4
SLATE106-F2R1	192.168.1.88	00:1CE602:273F	SMH300	Gekkota 4
SMA300-F2	192.168.1.23	00:1CE602:43CF	SMA300	Gekkota 4
SMA300-H1	192.168.1.64	00:1CE602:3C11	SMA300	Gekkota 4
SMT210-F1R1	192.168.1.62	00:1CE602:00BE	SMT210	Gekkota 4
TAB10S-F1R2	192.168.1.129	00:1CE602:50C6	TAB10s	Qeedji System AOSP 9

The SignMeeting Jooxter App is not compatible with Gekkota 3 devices.

In the list of the devices detected, select the appropriate devices (1) (2) (3) (4) (5) (6) to be added to your project. Then click on the Add (7) button.



Once the devices are added to your project, select the one applicant for the publication.



When the devices are detected thanks to the UPnP discovery, the default `admin/admin` login credentials and the default `http://` scheme value may be not consistent. Double check these parameters each time you add a new device to the project.


⚠ The login credentials per each device cannot be automatically detected and are set by default to `admin / admin` when a device is added to the project. If required, modify the login credentials with consistent values.

⚠ The device only available with the `https://` scheme cannot be detected automatically.

☞ The port value to access to this the device is automatically detected.

☞ Once the devices are added to your project with their appropriate scheme and login credentials, you can export the device configuration into a `.csv` file with the `Export` (1) button. With the `Import` (2) button, it is possible afterwards to import the devices configuration.

To change the login credentials, the scheme value or the port value to access to the Web server of the device with INNES Screen Composer G4 , select the appropriate device in the list **③** an click on the **>Edit** **④** button.




For each Qeedji System AOSP and Gekkota devices, you can watch or modify:



- the device label **①** in INNES Screen Composer G4 : the default label value given here is the device's hostname value,
- the device scheme **②** on which the device is available (*http://* or *https://*),
- the device port **③**,
- the device IP address **④**,
- the Username **⑤** and password **⑥**: login credentials to access to the device WebDAV server,
- the MAC Id **⑦**: MAC identifier for the license<sup>1</sup>,
- the model and OS **⑧**.

<sup>1</sup> Using an invalid MAC Id for a device should lead to the display of a black content when SignMeeting Jooxter App is running.

<sup>2</sup> For Qeedji System AOSP devices, the MAC ID must match the MAC address value of the WLAN interface. For Gekkota 3 and Gekkota 4 devices, the MAC ID must match the MAC address value of the LAN interface.


The *https://* scheme may be not yet supported for Qeedji System AOSP devices. Check with your device provider.





For Gekkota 3 and Gekkota 4 devices, you can change the model (8) among the values here after:


- SMT210,
- DMB400,
- SMA300,
- SMH300,
- DME204,
- MS-Windows PC,
- DMB300,
- DMC200.



For SMA300, SMT210 and MS-Windows PC, after having chosen the device model, choose the device OS <sup>⑨</sup> among the suggested value:


- Gekkota 4 ,
- Gekkota 3 <sup>3</sup>.

<sup>3</sup> Some SignCom feature like the Enforce on media with pagination a page progression with a default page duration option is not working when it is running on Gekkota 3 devices.



In this user manual, the label for each device have been modified to define the location of the device in the building.

Device model	Device OS	Hostname received from devices during a discovery	Device label for display profile illustration
TAB10s	Qeedji System AOSP	TAB10S-F1R2	floor 1 > room 2 - tablet
SMT210	Gekkota 4	SMT210-F1R1	floor 1 > room 1 - tablet
DMB400	Gekkota 4	DMB400-F1	floor 1 – large screen 1
SMA300	Gekkota 4	SMA300-H1	hall – large screen
SMA300	Gekkota 4	SMA300-F2	floor 2 – vertical screen
SMH300	Gekkota 4	SLATE106-F2R1	floor 2 > room 1 - label




## 2.2.8 File > Project settings > Project and App

In the Project settings item of the File menu, select the Project and App item. The panel allow to show:

- the **(1)** label of your project,
- the **(2)** repository name used by your project,
- the **(3)** SignMeeting Jooxter App name and SignMeeting Jooxter App version.

To create a new project repository , click on the **■ Edit repositories** **(4)** button. For further information, refer to the chapter § [Screen Composer > Preferences > Repositories](#).

To change the repository for your project, click on the **▼** drop down **(5)** button.



When you have just made a `repository#` change, it is advised to check whether the used image, video or css set in the SignMeeting Jooxter form are still present in the new repository. Else the publication may not work. To work around, it is advised to close the project and open the project again. In that case, all the inconsistent file will be removed automatically from the SignMeeting Jooxter form. A red stamp will show where to set back a consistent image, video or css when required to have a successful publication.


## 2.2.9 File > Project settings > Publication

In the Project settings item of the File menu, select the Publication item. The panel allows to choose among select several publication ways:

- Publish to devices ①,
- Publish to a directory ②,
- Publish to a server ③.

### Publish the App to devices

Select the Publish to devices ① publication mode (default mode) to choose to publish the SignMeeting Jooxter App on the devices added to the project and checked as applicant for the publication.



Activating the Publish to devices ① publication mode allows also to access to three values for the blue button at the top of the interface:

- Publish the App to devices ④: when this value is selected, clicking on the button allows to publish immediately the SignMeeting Jooxter App to the devices.



- Publish a purge to devices ⑤: when this value is selected, clicking on the button allows to remove immediately the SignMeeting Jooxter App from the devices. A information message No content should be then displayed on the devices.




- Publish the middlewares to devices ⑥: when this value is selected, clicking on the button allows to send all the middlewares file to the devices so that the device middleware version can be updated.



## Publish the App to a directory

Select the `Publish to a directory` (2) publication mode to choose to publish the App on a local directory of your computer. Then select a target directory with the file picker (6) button.



It allows also to access to a specific `Publish to a directory` (7) button. when this value is selected, clicking on the  button allows to publish immediately the SignMeeting Jooxter App on this directory.



- When the `Publish the App to a directory` and `Publish the middlewares to a directory` buttons value are available, the `Publish a purge to devices` and the `Publish an App to devices` button values are not available.

Once having clicked on the `Publish the App to a directory`, the SignMeeting Jooxter App is copied on the directory with the appropriate manifests file with the pattern `manifest.<MAC>.xml`, with one manifest per device, making that the content is still suitable for the different devices.

App format example:

```
app/  
manifest.00-1c-e6-02-00-be.xml  
manifest.00-1c-e6-02-50-c6.xml
```

This App content can be for example copied entirely on a USB mass storage which can be then inserted in the USB port of the different devices. Each device will load automatically the appropriate part of the App.


- To support the USB mass storage insertion with this `manifest.<MAC>.xml` format, the Gekkota 4 devices may require to have the identification method set to `MAC`. Do the same for `manifest.<UUID>.xml` or `manifest.<Hostname>.xml`.
- An additional `manifest.xml` is generated to support Gekkota 3 devices. For these devices, when using USB storage device to upgrade their content, it is not recommended to use variable in the App.

## Publish the App to a server

Selecting the **Publish to a server** (3) publication mode allows to publish the SignMeeting Jooxter App to a remote HTTP/WebDAV server.

Fill the required parameters to connect to the HTTP/WebDAV server:

- IP address,
- port,
- directory path,
- login credentials' username,
- login credentials' password.



When the **Publish the App to a server** (8) button value is selected, clicking on the allows to immediately publish the App content on the specified WebDAV server directory.




When the **Publish the App to a server** button is available, the **Publish a purge to devices** button, the **Publish an App to devices** button and the **Publish an App to a directory** button are not available anymore.

## 2.2.10 File > Project settings > Tasks


To create a planification to restart the devices registered in your project, select the `Project settings` item of the `File` menu then select the `Tasks` item. Then click on the `Reboot Devices` tab:

- click on the `+ Add a task` button (2) to add a new planification task then,
- click on the `+ Add a recurrence` button (3) to customize the planification recurrence.



To create a planification to set the screen of the devices registered in your project in standby, click on the `Switching device to standby mode` tab (4):

- click on the `+ Add a task` button (5) to add a new planification task then,
- click on the `+ Add a recurrence` button (6) to customize the planification recurrence,
- click on the `+ Add an exception` button (7) to add some Exceptions days when the devices must not be in standby.



**Once the tasks are created or modified, the publication of the App on the devices is required so that the tasks are effective on the devices.**

# **Part III**


Project

## SignMeeting Jooxter new project

Here is the SignMeeting Jooxter App logo:



Once the SignMeeting Jooxter App (1) is installed with its licenses keys, click on the New project (2) button (or the New project item from the File menu).



Fill the free text label (3).


The default project repository is named Repository #1 (4) and is located by default in C:\Users\<username>\INNES Screen Composer G4\workspace 1\. You can decide to choose another one with the repository drop down list (5) or create another one by clicking on the Edit repositories (6) button. For further information, refer to the chapter § [Repositories](#).

If only the SignMeeting Jooxter App product is available, the SignMeeting Jooxter (7) App product is automatically selected.

If you have several App products installed, use the App product's drop down list (8) to select the SignMeeting Jooxter App product.

If it is not available, install the SignMeeting Jooxter App product with the (9) button.

The last SignMeeting Jooxter App version is available in the [INNES support Web site](#).




Click on the `Create` button.

The resources for your SignMeeting Jooxter App project are located on the left side:

- Files (1),
- Fonts (2),
- Devices (3),
- Variables (4),
- Data sources (5).

There are five main configuration tabs for your SignMeeting Jooxter project on the right side:

- Display profiles (6),
- Devices (7),
- LDAP (8),
- RFID (9),
- SMTP (10).



Once your project is created, you have to add **devices** to your project and activate some of them as applicant for the publication. For further information, refer to the chapter § [File > Project settings > Devices](#).

Then do create a **data source** allowing the SignMeeting Jooxter App to connect to the Web server hosting the **.ics** calendar file. For further information, refer to the chapter § [SignMeeting Jooxter > Datasource](#).

**Tip** Only one instance of the **Room Screen** display profile is available by default when creating a project. The **Room Screen** display profile is generally suitable for tablet devices. The instances of other display profiles like **Summary screen by event**, **Summary screen by resource** and **Room Label** must be created by the user. For further information, refer to the chapter § [SignMeeting > Display profiles](#).

You can abound your library with with folders and files:

- logo, background images in the suitable aspect ratio for your device ( **.jpg** , **.png** , **.gif** ),
- video ( **.mp4** ),
- document ( **.pdf** ), MS-PowerPoint presentation ( **.pptx** , **.ppsx** ),
- CSS themes ( **.css** ),
- Javascript script ( **.js** ),
- Fonts files.


For further information, refer to the chapter § [Files](#).

## SignMeeting Jooxter project saving

To save your project into a **.isz** file:

- click on the **Save** (10) button,
- click on the **Save** item from the **File** menu,
- or [CTRL] + [s].

**Warning** The project is not saved automatically. It is recommended to save it regularly.




## SignMeeting project closing

To close the project:

- click on the Close  button,
- or click on the Close button from the File menu.

### 3.1.1 Files


Click on the  **Files** (1) button to view the **Files** content of your project repository.




### 3.1.1.1 Files > Edition and metadata

#### Edition

Select a text file (.css, .csv, .htm, .html, .ics, .js, .json, .md, .mdp, .sdp, .srt, .tsv, .txt, .vtt, .xml) then click on the **Edit** (1) button.



Modify the content according to your needs and click on the **Save** (2) button.




Then click on the **Close** button to close the file and make appear back the SignMeeting Jooxter App configuration tabs.

## Default metadata


This panel also allows to watch its metadatas at first glance. The number of displayed metadata depends on the selected media.

The following metadata can be found:

- Thumbnail (1): media presentation thumbnail,
- Name (2): name of the file with its extension,
- Size (3): memory footprint of the media on your storage space,
- Modified (4): date of the last file modification,
- Indexed (5): indicates whether the media has been successfully indexed in the database,
- Resolution (6): width and height of the media in pixels,
- Ratio (7): the values *Landscape 16/9, Portrait 9/16, Landscape 4/3, Portrait 3/4* appear when the resolution is strictly 16/9, 9/16, 4/3 or 3/4,
- Frame rate (8): frame rate of the video in frames per second,
- Duration (9): the intrinsic duration of the media when played once fully.




The number of available metadata depends on the type of the media.



## Adding additional metadatas


When they are not already present, it is possible to add additional metadatas to your media with the Add  **(8)** button.



- New duration **(9)**: allows to add an intrinsic duration to the media,
- New title **(10)**: allows to add standardized titles , language level dependant:
  - the first level is corresponding to the international language (most often English),
  - the following ones are corresponding to the desired languages,
- New description **(11)**: allows to add standardized descriptions , language level dependant:
  - the first level is corresponding to the international language (most often English),
  - the following ones are corresponding to the desired languages,
- New keywords **(12)**: allows to associate keywords with your media. These keywords can then be used in the play rules in playfolders or playlist.
- New rating **(13)**: allows to associate a rating to your media from 1 to 5 stars. This rating can then be used in the play rules in playfolders or playlists,
- New validity periods **(14)**: allows to associate a validity period with your media that is used during the game in a time slot. Outside this validity period , this media can no longer be viewed within a time slot,
- New validity variables **(15)**: allows to associate a validity variable with your media through a variable such as Calendar , Text , Location OR File Name . It is useful for example to apply a different play rule depending on the location of a range of devices.

<sup>1</sup> Max. 260 characters per keyword. The capital letters of keywords are converted to lower case. During a CTRL+V, the keyword is automatically validated. When the ";" key is entered, the keyword is automatically validated. To set several keywords at a time for media, edit the keyword metadata and paste the keywords values separated by ; (e.g. keyword1;keyword2;keyword3;keyword4 ).

For videos with the extension .mov , .mp4 and .m4v , the button  **(16)** Choose this image as thumbnail **(16)** allows to capture an image from the video at a desired moment and add it automatically as a thumbnail to present the media **(17)**



The video thumbnail can also be modified. Click on the  Edit  button to load your own picture with the formats .png , .svg , .gif , .jpg or .jpeg .


### 3.1.1.2 Files > Open and preview

Click on the **Files**  button to open the **Files** view of the project repository.

To abound the **Files** view of your repository, select a folder then click on the three dot  button which gives access to several items:

-  Create a folder 
-  Create a text file 
  -  Create an URI (file URL, Web page),
  -  Create a playlist to play a list of medias according to some play rules,
  -  Create a playfolder to play the media inside a folder according to some play rules,
  -  Create a text file (.css, .csv, .htm, .html, .ics, .js, .json, .md, .mdp, .sdp, .srt, .tsv, .txt, .vtt, .xml),
  -  Create from a model to create a HTML widget based on a content model,
-  Import files : with the supported extensions .apng, .ASF, .avi, .css, .csv, .eof, .gif, .htm, .html, .ics, .ismc, .jpg, .jpeg, .js, .json, .m2v, .m4a, .m4v, .maf, .maff, .md, .mjgp, .mka, .mks, .mkv, .mov, .mp3, .mpd, .mpg, .mx, .odt, .odp, .oga, .ogg, .ogv, .otf, .pdf, .playfolder, .playlist, .png, .pps, .ppsx, .ppt, .pptx, .ps, .sdp, .srt, .svg, .swf, .ts, .tsv, .ttf, .txt, .uri, .vob, .vtt, .webm, .wgt, .wma, .wmv, .woff, .xls, .xlsx, .xml, .xspf,
-  Rename 
-  Delete 

 The  **Collapse all folders**  button is not supported.




Organize the **Files** view of your project repository by:


- creating folders,
- creating text files,
- importing medias or CSS themes.

The *Display by thumbnail* / *Display by tree* toggle button allows to change the way to show the files tree.

Here is a files tree example when the *Display by tree* mode is selected.




Here is an files tree example when the *Display by thumbnail* mode is selected.



To organize the files and folders in the `Files` view of your project repository, select a file (or a folder), and make a right click to access to a contextual menu having the following items:


- Open (1) allows to open the file on the right side to preview it, add metadata or edit it (for file only),
- Reveal in the explorer (2): allows to see the file (or the folder) location by opening a new MS-Windows explorer session and set the focus on the file (or the folder),
- Create a folder (3),
- Create a text file (4),
  - Create an URI (11),
  - Create a playlist (12),
  - Create a playfolder (13),
  - Create a text file (14),
  - Create from a model (15),
- Import files (5),
- Cut (6),
- Copy (7),
- Paste (8),
- Rename (9),
- Delete (10).



Select a file makes appear then fly the mouse pointer over the file with the mouse makes appear three buttons at its right, shortcut to the item of the contextual menu:

- Open (1),
- Rename (2),
- Delete (3)

When a file is already opened but not edited, clicking on the Open (1) button of another file, closes automatically the previous opened file.




### 3.1.1.3 Files > Unitary preview

All the medias types whose the extension is supported by INNES Screen Composer G4 can be previewed, including URIs, playfolders, playlists and MS-PowerPoint (.pptx, .ppsx) media.


#### Text file overview

To obtain a short overview of the content of a text file (.css, .csv, .htm, .html, .ics, .js, .json, .md, .mdp, .sdp, .srt, .tsv, .txt, .vtt, .xml), select a text file in the library, and click on the Open  (1) button.



The file and the path elements are highlighted in orange color. The text file overview appears on the right, above the SignMeeting Jooxter App configuration tab.

Click on the Close  (2) button to close the file overview and make appear back the SignMeeting Jooxter App configuration tab.




## Medias

For the medias, that can be visually rendered with an aspect ratio, a preview window is displayed when the file is opened.

 The video that are not previewable in a Web browser cannot be previewed in INNES Screen Composer G4.

Select a video ( .mp4 , .m4v , .mov ) or an image ( .png , .svg , .gif , .jpg ) in the library, and click on the open  (1) button.

The availability of some buttons of the preview window toolbar depends on the type of media to visualize.



Select a media in your library (e.g. a video):


- click on the **Restart** button  (1) to move to the beginning of the media,
- click on the **Play** button  (2) to play the media,
- click on the **Volume** button  (3) to increase or decrease the volume while the video is played,
- click on the **Choose this picture as thumbnail** button  (4) to choose the current image of the video as file's thumbnail,
- click on the **Expand** button  (5) to preview it in a full screen window,
- the bargraph allows to start the video at a particular timestamp.

When the full screen preview window is displayed, the **Minimize**  button allows to reduce the preview window size.

### 3.1.1 Fonts

On the left side, click on the **Fonts** A (1) tab.

When no font face has been imported in your project, no font face is visible in the **Fonts** (2) tab.




Click on the **Import fonts from the system** (7) button to import fonts from the MS-Windows system.

Click on the **Import fonts from a file** (8) button to import fonts from a MS-Explorer directory containing fonts files.

To be supported, fonts must be in **.otf** or **.ttf** format.

Once imported in your INNES Screen Composer G4 , the fonts names (3) are displayed with their font family (4). For each, The **Abg** text (5) is displayed as rendering example with the fonts style.



To remove several fonts at a time, select either several fonts names or several fonts families and click on the **Remove** (6) button.

The **SignMeeting** font used in the layout in runtime can only be configured with a CSS theme. The font file can be for example added in the root folder of the css file, files which must be added in the **Linked files** part of the appropriate display profile thanks to a font file dropping from the **Medias** tab. This font class must be created in the css file. For further information, refer to the chapter § [Appendix: How to customize CSS](#).

The font dropping from the **Fonts** tab to the **Linked files** part of a display profile is not supported.

### 3.1.1 Variables

The variables can be used in medias like `URIs` or `playfolders` to play, with a same Screen Composer project, a different content depending on:

- the variable values affected to the devices,
- the variable values intrinsic to the device,
- the system date of the device.


The variables ① type to use in these different cases are respectively:

- the `Custom` variables,
- the `Device information` variable,
- the `Date and time` variable.

The `Custom` variables name and the `Custom` variables values must be created then affected to the different device by the end user.

The `Device information` variable values must be created by the user in relation to the values existing in the fleet of devices.

The `Custom` variable values and the `Device information` variable values created by the user are linked to the repository in which they have been created. If a new project is created by using this same repository, these variable values previously created stay available.



In this SignMeeting version, there is no use case to use variables. Indeed:

- the drag'n drop of `URIs` or `playfolders` medias from the medias tab to the SignMeeting form inputs is not yet supported,
- the drag'n drop of variables from the `Variables` tab to the SignMeeting form input is not supported.


Consequently this chapter linked to the `Variables` \$0 ① tab is not detailed.

### 3.1.1 Devices

On the left side, click on the **Devices**  **(1)** button to open the **Devices** view of the project repository.

On the right side, click on the **Devices**  **(2)** button to open the **Devices** configuration tab of the SignMeeting Jooxter App.


When no device is added to your project, no device is visible in the **Devices**  **(3)** view of the project repository.




Click on the **Devices settings**  button, short cut to the **Devices** item of the **File** menu of the **Project settings**, to add and manage the devices of your project. For further information, refer to the chapter § [File > Project settings > Devices](#).

Once the devices are added to your project, they are visible in the  **Devices** tab of your project repository. The devices are shown in a black style **(3)** color when they are checked as applicant for publication.

When some devices are added in your project, they appear automatically in the **Devices**  **(4)** configuration tab of the SignMeeting Jooxter App.




The devices are shown in italic and grey **(5)** color style when they are not checked as applicant for publication.



### 3.1.1 Data sources

A data source must be created so that the SignMeeting Jooxter App can communicate with the room resources of your Jooxter calendar.

Click on the Data source  button to open the Data source view of your project repository, then click on the Configure a new data source  button.



### Connection tab

Select the Connection  tab (default) and fill the SignMeeting Jooxter App configuration tab by entering:


- a free text data source label 
- the URL of the Web server hosting your .ics calendar file:
  - scheme :
    - http ,
    - https .
  - domain or IP address 
  - port ,<sup>2</sup>
  - file path .

<sup>2</sup> The default port value suggested is 80 with the http scheme and 443 with the https scheme.

URL example: <https://app.jooxter.com/> (and port: 443)

When an authentication is required to access to the server, check the Authentication  option , with the default Username/Password mode then fill the login credentials:

- Username 
- Password 



Adjust the *Data source synchronization* configuration with your needs. By default, SignMeeting Jooxter App is connecting to the Web server hosting the `.ics` calendar file every 10 minutes:

- Refresh every **⑩**: 10 minutes.

SignMeeting Jooxter has a function to Keep the calendar event data in cache **⑪** for 2 days by default to keep displayed the meetings in case the device is losing network connection for a while.

**☞ When using the Room Label display profile until 10 SLATE106 devices, setting the data source synchronization below 5 minutes could prevent SLATE106 devices to be updated properly.**

Click on the `Save` button to save the modifications.

## Other settings tab


The Other settings **⑫** allows to set the *time span of a day*:

- Start time **⑬**: if a meeting starts before this `Start time`, the meeting is shown on the screen with this `Start time`.
- End time **⑭**: if a meeting ends after this `End time`, the meeting is shown on the screen with this `End time`.

**☞ Usually the start time and the End time are corresponding to your office hours.**


**☞ If the meeting is completely outside this `start time / end time`, it cannot be displayed at all on the screen.**

The *Booking wording* field set allows to define the automatical naming pattern for the event title when a event is programmed with a device by using the `Book now` button or using the `reservation and consultation page` access button of the main page. The *Booking wording* input **⑮** supports free text and variables. To add a variable, click on the `$()` **⑯** button.



These are the different variable values **⑯** that can be printed in the meeting title.

Type	Name	Value displayed in the title
LDAP	<b>⑰</b> <code>ldap:rfid-tag:attribute1</code> <b>⑱</b> <code>ldap:rfid-tag:attribute2</code>	additional attributes value linked to <code>rfid-tag</code> to fetch in the LDAP server. Ex (LDAP): in case Attribute 1 = <code>Displayname</code> , the name and firstname of the badge owner.
User	<b>⑲</b> <code>ldap:user:attribute1</code> <b>⑳</b> <code>ldap:user:attribute2</code>	additional attributes value linked to <code>user</code> to fetch in the LDAP server.
Meeting start/end	<b>㉑</b> <code>calendar-event:time:start</code> <b>㉒</b> <code>calendar-event:time:end</code> <b>㉓</b> <code>calendar-event:time:interval</code>	Meeting start time, Meeting end time, Meeting start-end time.
Meeting location	<b>㉔</b> <code>calendar-event:location</code>	Room name.
Random number	<b>㉕</b> <code>math:random:2digit-number</code>	Random number from 1 to 99.



**☞** The variable are used only at the event creation. In case the event is modified afterwards, the SignMeeting Jooxter App can not upgrade the meeting title generated automatically. This remark is relevant especially when using the `calendar-event` time values.

**☞** `rfid-tag` attributes and the `User` attributes to fetch are configured in the LDAP configuration tab.


The Hide the meeting content for privacy levels ⑦ option allows to apply a special treatment for private ⑧ events:

- hide the meeting content for the selected privacy levels,
- if the Substitution message ⑨ is checked and the label input filled, hide the meeting content for the selected privacy levels and display for each a substitution title.


## Link room resources

Once the `data source` is configured to connect to `Jooxter` calendar, you have to add room resources `Id` to this data source, that need be handled by then by your devices.

Select the data source ① just created (e.g. **SignMeeting**) then on the right, click on the Add a resource ② button.



**⚠** Enter for each resource, the exact resource `Id` ③. To retrieve all your resource `Id`, refer to the chapter § [Appendix: retrieve the Jooxter resource Id](#).



In the example below, the resource Id are:


- *room1@demo.contoso.com*,
- *room2@demo.contoso.com*,
- *room3@demo.contoso.com*.

When the room resource `Id` is entered, it is possible to enter the label. Entering a `Label` (4) for a room resource allows to display this `Label` on the screen instead of the room resource `Id`, value which is often a number internal to Joxster.


In the user manual, the room resources id will be named like that:

**Room resource Id**

```
room1@demo.contoso.com
room2@demo.contoso.com
room3@demo.contoso.com
```



At this step, the wished room resources are properly attached to the datasource.



The data source configuration is completed.

## Multiple data sources

If required, the App can support several data sources. In this case, do the same operation, by adding another data source with:

- another Joomster account,
- others room resource ids.

*A same room resource id can be affected to only one data source.*


## 3.2 Display profiles

By default only one instance of the `Room screen` *display profile* is available when a new SignMeeting Jooxter App project is created.

If this only `Room screen` *display profile* is suitable for your SignMeeting Jooxter App project configuration, refer to the chapter § [SignMeeting > Display profiles > Room screen](#).


A recap of the display profiles features differentiation is shown in the chapter § [Introduction](#).

If you need to create another *display profile* instance, select the **Display profiles** (1) configuration tab of your SignMeeting Jooxter App project, then click on the **Display profile manager** button (2).




The default `Room screen` (3) *display profile* appears in the table listing all the available *display profiles* created. Click on the **Add** (4) button to add a *display profile* among:

- Summary screen by event (orientation: `Landscape` OR `Portrait` ),
- Summary screen by resource (orientation: `Landscape` OR `Portrait` ),
- Room label ,
- Room screen .




Click on the **Type** drop down list **⑤**.



Choose among these *display profiles* values:

- Room screen **⑥**,
- Room label **⑦**,
- Summary screen by event **⑧**,
- Summary screen by resource **⑨**.

For example, select in the list, the **Summary screen by event** **⑧** *display profile*.




Once the *display profile* is chosen, click on the refresh **⑩** button to generate automatically a consistent label for your *display profile*.


You can rename the *display profile* like you want.

When available for the *display profile* selected, select the appropriate *Orientation* value for your *display profile*:

- Landscape **⑪**,
- Portrait **⑫**.




Click on the **Save** **⑬** button.



The new *Summary screen by event* **⑭** *display profile* instance is created and appears in the list:

- to modify the label of a *display profile* instance, select it and click on the **Edit** **⑯** button,
- to delete a *display profile* instance, use the **Delete** **⑰** button,
- to add another *display profile* instance, click on the **Add** **⑮** button and restart the operation.


Once all the required *display profiles* are created for your project, you can use the **↑** up (18) button and the **↓** down (19) button to change the order of the display profile tab.



Then the *display profiles* configuration tabs are displayed in the wished order, for example:

1. Room screen (1)
2. Summary screen by event - Landscape (2)
3. Summary screen by resource - Portrait (3)
4. Room label (4)

To configure a *display profile* instance, click on the appropriate *display profile* instance configuration tab (1, 2, 3, 4, ...)



If your devices need to support authentication by RFID, refer to the chapter § [RFID](#).

If your devices need to support user authentication by LDAP, refer to the chapter § [LDAP](#).

If your devices need to support the notification page which needs the SMTP, refer to the chapter § [SMTP](#).

### 3.2.1 SignMeeting > Display profiles > Room screen

The Room screen *display profile* allows to display on the screen until two following events in two areas:

- the upper area for the event in progress,
- the lower area for the next event.

The Room screen *display profile* is usually suitable for interactive tablets installed near a meeting room.

This Room screen *display profile* supports dedicated button:

- the Book now button allows to book an instant event for
  - 30 minute,
  - 1 hour,
  - 2 hours,
- the Delete button allows to delete or shorten the event in progress to free up the resource,
- the Confirm button, supported on Room Screen *display profile* only, allows to confirm the booking of the event in progress,
- the Notification button allows to access to a specific notification page supporting several customizable buttons to notify by email address of specialised departments when some trouble is faced when using the resource's equipment,
- the reservation and consultation page access button allows to access to a reservation page to book/modify/remove events for the next days and for several different room resources.

 The using of the buttons requires to have a device with an interactive screen.

To configure a Room screen *display profile*, select the  **Display profiles** **①** configuration tab of your SignMeeting Jooxter App project, then select a  Room screen *display profile* instance **②**.

 The lenght of the configuration form is more than one page. Use the scroll bar to go to the end of the form.

## Banner


The Banner (3) pane allows to display or not a banner with at the top (4) or at the bottom (5) of the main page.

The Banner can contain:

- the current Time (6) with different formats:
  - HH:MM (12) (e.g. 7.00),
  - HH:MM (24) (e.g. 19:00),
- the current Date (7) with different format<sup>1</sup>

Label	EN (default)	FR	DE
one-or-two-digit day, one-or-two-digit month, two-digit year (e.g. 12/1/22)	12/01/22	01/12/22	01.12.22
one-or-two-digit day, one-or-two-digit month, four-digit year (e.g. 12/1/2022)	12/01/2022	01/12/2022	01.12.2022
one-or-two-digit day, three-letter abbreviation month, four-digit year (e.g. 1-Dec-2022)	01-Dec-2022	01 Dec 2022	01. Dec. 2022
two-digit day, literal month, four-digit year (e.g. Dec, 01 2022)	December, 01 2022	01 décembre 2022	01. Dezember 2022
two-digit day, literal month, two-digit year (e.g. Dev 01, 22)	December 01, 22	01 décembre 22	01. Dezember 22
three-letter-abbreviation day, two-digit day, two-digit month, four-digit year (e.g. Thu 01 12 2022)	Thu 01 12 2022	jeu 01 12 2022	Don 01 12 2022
literal day, two-digit day, literal month, four-digit year (e.g. Thursday, December 01, 2022)	Thursday, December 01, 2022	jeudi 01 décembre 2022	Donnerstag, 01.Dezember 2022

- the organisation Logo<sup>2</sup> (8) ( .jpg , .gif , .png<sup>3</sup>),
- the Room (9) name from the displayed event: it displays only the room name of the current page of events,
- Free/busy indicator : allows to display reservation status:
  - green: no event in progress,
  - orange: event started but presence confirmation required,
  - red: event started and presence confirmed.



<sup>1</sup> The date translation (day and month reversed) and the date format (dot or slash character), depending on the language, are made directly on the device by respecting the regionality language of the device.

<sup>2</sup> It is recommended to use a image whose height in pixel is the banner height in pixel of the target screen resolution. Then adjust the height of the organisation logo inside this image to control its size. For further information about the banner height, refer the chapter § Appendix: Banner characteristics.

<sup>3</sup> Do better use .png logo if possible, format which is supporting the transparency capability.

The busy colors are the same for the indicator on the screen and for the LED of the tablet.

## Main page

Scroll ③ to see the Main page ④ pane's part.

The Main page pane allows to select the event part to display:

- **Display information for the current meeting:**


- Label for the header ⑤: allows to display a free text to show the current meeting area (*Current meeting* is the default value),
- Label when there is no current meeting ⑥: allows to display a free text when there is no event in progress for the current room page,
- Display title ⑦: allows to display the event summary,
- Display location ⑧: allows to display the data source room label in which the event takes place,
- Display time range ⑨: allows to display the event start time and the event end time (e.g.: 8.00 to 10.00),
- Display description ⑩: allows to display the event detailed description (if required, a prefix, empty by default, can be displayed before the description values),
- Display organizer ⑪: allows to display the event organizer (e.g.: the *delegate account* or the user which is currently authenticated) (if required, a prefix, empty by default, can be displayed before the organizer values),
- Display attendees ⑫: allows to display the attendees (if required, a prefix, empty by default, can be displayed before the attendees values). The attendees name are displayed on a same line. In case overlap, a scrolling effect allows to watch all the attendees names.
- Display the attached image ⑬: allows to display the first picture attached to a event.

☞ The attendees values are scrolled automatically.

☞ SignMeeting Jooxter supports the attachments display for the current meeting only. In case several pictures are attached to the meeting, only the first one is displayed. The supported picture formats are .gif, .png & jpg.


- Display information for the next meeting ⑭: allows to display information for the next meeting

- Label for the header ⑮: allows to display a free text to show the current meeting area (*Current meeting* is the default value),
- Label when there is no next meeting ⑯: allows to display a free text when there is no event in progress for the current room page,
- Display title ⑰: allows to display the event summary,
- Display location ⑱: allows to display the data source room label in which the event takes place,
- Display description ⑲: allows to display the event detailed description (if required, a prefix, empty by default, can be displayed before the description value),
- Display organizer ⑳: allows to display the event organizer (e.g.: the *delegate account* or the user which is currently authenticated) (if required, a prefix, empty by default, can be displayed before the organizer value),
- Display attendees ㉑: allows to display the attendees (if required, a prefix, empty by default, can be displayed before the attendees values),
- Display time range ㉒: allows to display the event start time and the event end time (e.g.: 8.00 to 10.00),
- **Display countdown (RFU).**



Scroll ③ to the bottom to see the Reservation process action ④ pane's part.

- **Reservation process action:** allows to activate the buttons for interactivity:
  - Button book now ②4,
  - Button confirm my presence ②5 (also called check-in)
    - Show this action <n> minutes before the start of the meeting ②6: allows to show the confirm my presence before the meeting has started (15 minutes by default),
    - Shorten the meeting if no confirmation after <n> minutes ②7: allows to shorten the meeting to free up the room when the meeting reservation has not been confirmed,
  - Button report as empty (shorten the meeting) ②8 (also called check out in some company):
    - Show this action <n> minutes before the end of the meeting (15 minutes by default).
  - Custom script ②9: allows to load a custom script to customize the SignMeeting behaviour, e.g. to control external peripherals embedded in electric doors, to start to play webcam camera, or to handle a presence sensor, to control Distech Controls devices,
    - Allow custom script to display extra buttons if required : allow to customize the main page by adding some custom button like Open the door, Maintain, Resume.
- Background image ②0: allows to put an image, dragged from the Files view of the project repository, as background of the main page.



The variable ③ in the Background image ②0 input can be used only to replace **filename** value:


- drop the root folder of the image to display,
- click on the active \$0 variable button and select the wished variable name,
- select then the appropriate extension of the image to display.

**! The Background image ②0 input is not editable. Use the Sweep button to erase the input content.**


<sup>3</sup>Ensure that your device has the appropriate variable value.

Variable name	Variable format when set in the input
deviceInfo:hostname	\${deviceInfo:hostname}
deviceInfo:mac	\${deviceInfo:mac}
deviceInfo:uuid	\${deviceInfo:uuid}
deviceInfo:field1	\${deviceInfo:field1}
deviceInfo:field2	\${deviceInfo:field2}
deviceInfo:field3	\${deviceInfo:field3}
deviceInfo:field4	\${deviceInfo:field4}
deviceInfo:field5	\${deviceInfo:field5}


**! When using variables, the target files must be added manually in the Linked files part of the form.**



Main page rendering example with Book Now button:



Main page rendering example with Confirm my presence and Report as empty button::



## Complementary pages

Scroll ③ to the bottom to see the `Complementary pages` ④ pane's part.


The `Reservation and consultation page` ③ allows to support, in the main page, an access button with an optional label ② giving access to a `Reservation and consultation page`. This page allows to consult a grid of rooms reservation for all the room resources made visible for this page, with one page per day.

**Note:** The devices resources need to be configured according to. For further information, refer to the chapter § [Room resources association to a device](#).


In this `Reservation and consultation page` page, the support for these buttons can be inactivated:

- `Add button` ④,
- `Edit button` ⑤,
- `Delete button` ⑥.

Reservation and consultation page page rendering example:




Clicking on the `Room` label in this screen allows to display some intrinsic attribute linked to this room like its `capacity`.



The option `Return to the main page after being idle for <n> seconds` ⑦ allows to set the duration, before displaying back the `main page`, after being stayed for a couple of time (by default, 60 seconds) without user activity on:


- the `reservation and consultation page`,
- the `notification page`.



The Notification page **38** allows to support, in the main page, an access button with an optional label **39** giving access to custom notification buttons . It can support for several buttons, for example, to:


- raise some trouble faced when using the room equipment (cooling, heating, wifi), to specific department,
- call a room services (drinkings, lunch trays, sandwiches, coffees), ...

Notification page page rendering example:




**☞** More than 60 pictograms are available in the pictogram library.

A new item needs to be configured for each new notification button. Click on the Add **40** button.




Then fill for this notification button:

- a label **41** (e.g. *Lunch*, *Drinkings*, *Cooling issue*, *WIFI issue*,...),
- a email address **42**,
- a pictogram, which is displayed upon the button **43**,
- a email subject **44** (e.g. *Lunch service*, *cooling trouble*, ...).




Restart the operation for each notification button. They should appear, for example, like explained below.



Use the **+ Add** ④7/**Edit** ④8/**Delete** ④9 buttons to handle your custom notification buttons.

☞ The notification buttons appears in the main page when at least one button has been created.

☞ The support for the notification page requires that the SMTP tab is properly configured.



## General settings

Scroll ③ to the bottom to see the General settings ④ pane's part.

The Display all alternatively with an interval of <n> seconds ⑤ option allows to define the page duration when the events for several room need to be displayed on the main page.


☞ If more than one room resource is displayed on the main page, SignMeeting Jooxter displays alternatively, the current event and the next event on the same page, with one room per page, and one page every 10 seconds (duration by default). In this case, the access to the buttons is still supported for each page.

The Background content when there is no current nor future meeting field set allow to configure a screen saver when there is no current or next meeting:

- Show the screen saver after <n> minutes ⑥: allows to display the screen saver <n> minutes after the current meeting has ended,
- Leave <m> minutes before the start of the next meeting ⑦: allows to quit the screen saver minutes before the next meeting starts (instead of exactly when the meeting starts).

When the screen saver is activated,

- Select the Media to display ⑧ when the screen saver is running, then drop an image ( .jpg , .gif , .png ) ⑨, a document ( .pdf ), a MS-PowerPoint presentation ( .pptx ) or a video ( .mp4 ) ⑩ from the Files view of the project repository to the Media to display input ⑪.
- Use an interactive marker ⑫ with a label to display ⑬ allows to display a marker on the screen when the screen saver is running, inviting the user to touch the screen to quit the screen saver.



The Media to display ⑧ input is not editable. The variable <sup>3</sup> in the Media to display ⑧ input can be used only to replace filename value:

- drop the root folder containing the media,
- click on the active \$0 variable button and choose the wished variable name,
- select then the appropriate image or video extension.


☞ Check the image and video capabilities of your device before choosing your media.

☞ Use the 🗑 Sweep button to erase the input content.


<sup>3</sup>Ensure that your device has the appropriate variable value.

Variable name	Variable format when set in the input
deviceInfo:hostname	\${deviceInfo:hostname}
deviceInfo:mac	\${deviceInfo:mac}
deviceInfo:uuid	\${deviceInfo:uuid}
deviceInfo:field1	\${deviceInfo:field1}
deviceInfo:field2	\${deviceInfo:field2}
deviceInfo:field3	\${deviceInfo:field3}
deviceInfo:field4	\${deviceInfo:field4}
deviceInfo:field5	\${deviceInfo:field5}

☞ When using variables, the file target by the variable must be dropped manually in the Linked files part of the form.




Screen saver rendering example:




To load a Personalized theme (.css) (60), download one of the suitable CSS for Room screen display profile (dark theme or light theme), import it in the Files view of your project repository of your repository (61) then drop it in the Personalized theme (62) input.

The CSS API is compliant with Mozilla & W3C <https://developer.mozilla.org/en-US/docs/Web/CSS/background>. To customize the Room Screen CSS, refer to the chapter § Appendix: Room screen CSS.



## Linked files

The private images and the font files called in your .css CSS theme and the images or the video files whose name is conditioned by variable need to be added manually by a single drop from the Medias tab (63) to the Linked files input (64).



**SignMeeting Jooxter will support in Q4/2022 some personalisation script allowing to support additional buttons for specific needs. For further information, contact [sales@innes.pro](mailto:sales@innes.pro).**

### 3.2.2 SignMeeting > Display profiles > Summary screen by event

The Summary screen by event *display profile* allows to display a summary of events taking place in several room resources along the day, with one event per row, and one event attribute per column.

This *display profile* is usually suitable for devices, connected to screen much larger than 10" installed in halls: corridors halls, floors halls...

The number of rows per page and the number of column per page can be customized.

To configure a Summary screen by event *display profile*, select the **Display profiles** **①** tab, then select a **Summary screen by event** *display profile* instance **②**.

The length of the configuration form is more than one page. Use the scroll bar to go to the end of the form.

#### Banner

The **Banner** tab allows to display or not a banner with at the **top** **④** or at the **bottom** **⑤** of the main page.

The **Banner** **③** can contain:

- the current **Time** **⑥** with different formats:
  - HH:MM (12) (e.g. 7.00),
  - HH:MM (24) (e.g. 19:00).
- the current **Date**<sup>1</sup> **⑦** with different formats:


Label	EN (default)	FR	DE
one-or-two-digit day, one-or-two-digit month, two-digit year (e.g. 12/1/22)	12/01/22	01/12/22	01.12.22
one-or-two-digit day, one-or-two-digit month, four-digit year (e.g. 12/1/2022)	12/01/2022	01/12/2022	01.12.2022
one-or-two-digit day, three-letter abbreviation month, four-digit year (e.g. 1-Dec-2022)	01-Dec-2022	01 Dec 2022	01. Dec. 2022
two-digit day, literal month, four-digit year (e.g. Dec, 01 2022)	December, 01 2022	01 décembre 2022	01. Dezember 2022
two-digit day, literal month, two-digit year (e.g. Dev 01, 22)	December 01, 22	01 décembre 22	01. Dezember 22
three-letter-abbreviation day, two-digit day, two-digit month, four-digit year (e.g. Thu 01 12 2022)	Thu 01 12 2022	jeu 01 12 2022	Don 01 12 2022
literal day, two-digit day, literal month, four-digit year (e.g. Thursday, December 01, 2022)	Thursday, December 01, 2022	jeudi 01 décembre 2022	Donnerstag, 01.Dezember 2022

- the organisation **Logo**<sup>2</sup> **⑧** ( .jpg , .gif , .png <sup>3</sup>),
- the **page title** **⑨** located in the banner.

<sup>1</sup> The date translation (day and month reversed) and the date format (dot or slash character), depending on the language, are made directly on the device by respecting the regional language of the device.

<sup>2</sup> It is recommended to use a image whose height in pixel is the banner height in pixel of the target screen resolution. Then adjust the height of the organisation logo inside this image to control its size. For further information about the banner height, refer the chapter § [Appendix: Banner characteristics](#).

<sup>3</sup> Do better use .png logo if possible, format which is supporting the transparency capability.



## Main page


Scroll ③ to see the Main page ④ pane's part.

- Display <n> section(s) per page ⑩ (by default, 11): allows to set the number max. of event to display per page,
- Time per page ⑪: allows to set the duration par page when several page of events are displayed,
- Shift the start event display ⑫:
  - <n> minutes before the start of the event ⑬: allows to start to display the events only <n> minutes before they start,
  - To the start of day ⑭: allows to start to display the next events taking place today from midnight,
- Extend the event display ⑮:
  - <n> minutes after the end of the event ⑯: allows to keep displayed events having took place today until <n> minutes after they have ended,
  - To the end of day ⑰: allows to keep displayed events having took place today until the end of the day,

It is possible to choose a Title font size ⑱ (for the column header titles) and the Font size for events ⑲ (for the events) among the value:

- Small,
- Medium,
- Large.

To define an image as background, select ⑳ an image ( .png , .jpg , .gif ) in the Files view of your project repository ㉑ and drop it in the background image input ㉒.



The variable <sup>3</sup> in the Background image ㉒ input can be used only to replace filename value:


- drop the root folder of the image to display,
- click on the active \$0 variable button and select the wished variable name,
- select then the appropriate extension of the image to display.

*☞ The Background image ㉒ input is not editable. Use the Sweep button to erase the input content.*

<sup>3</sup>Ensure that your device has the appropriate variable value.

Variable name	Variable format when set in the input
deviceInfo:hostname	\${deviceInfo:hostname}
deviceInfo:mac	\${deviceInfo:mac}
deviceInfo:uuid	\${deviceInfo:uuid}
deviceInfo:field1	\${deviceInfo:field1}
deviceInfo:field2	\${deviceInfo:field2}
deviceInfo:field3	\${deviceInfo:field3}
deviceInfo:field4	\${deviceInfo:field4}
deviceInfo:field5	\${deviceInfo:field5}

*☞ When using variables, the target files must be added manually in the Linked files part of the form.*



Scroll ③ to see the columns layout ④ of the Main page part of the *display profile configuration tab*, at the *Display a header with column labels* ② level.

This part of the SignMeeting Jooxter App configuration tab allows to customize the number of columns per pages, with one event attribute per column.

Check the option *Display a header with column labels* ② to display an additional raw allowing to display the column header labels.

By default only 3 columns are displayed:

- location ,
- summary ,
- time\_range .


On each event raw, it is possible to display these event attributes:

- location ②4: event location, with the default column header label ③3 *Location*,
- summary ②5: event summary with the default column header label ③4 *Event*,
- description ②6: event description with the default column header label ③5 *Description*,
- time\_range ②7: event start time and event end time with the default column header label ③6 *Hours*,
- organizer ②8: event organizer with the default column header label ③7 *Organizer*,
- attendees ②9: event attendees with the default column header label ③8 *Attendees*,
- sign1 ②0: first directional pictogram allowing to help to find the meeting room,
- sign2 ②1: second directional pictogram allowing to help to find the meeting room,
- attachment ②2: allows to display the first image ( .png , .jpg , .gif ) attached to the meeting.

☞ When much columns are displayed, it should be required to adjust the event style font size.

☞ There is no default column header label for sign1 ③9, sign2 ③0 and attachment ③1. If these columns are displayed, it is advised to enter a header label for each column.


☞ Each event attribute value can be aligned ⑤ horizontally independently: to the left , to the right , to the middle .



To adjust the column widths, drag to the left or to the right the movable column splitters **④** with your mouse according to your needs.

The events can be displayed by respecting a sorting policy based on some event attribute value and a sorting order **⑤** criteria :

- by the **Dates** **⑥** event value with the order:
  - Start time in ascending order **⑦**,
  - Start time in descending order **⑧**,
  - End time in ascending order **⑨**,
  - End time in descending order **⑩**,
- by the **Summary** **⑪** event value with the order:
  - Sort alphabetic in ascending order **⑫**,
  - Sort alphabetic in descending order **⑬**,
- by the **Description** **⑭** event value with the order:
  - Sort alphabetic in ascending order **⑮**,
  - Sort alphabetic in descending order **⑯**,
- by the **Location** **⑰** event value with the order:
  - Sort alphabetic in ascending order **⑱**,
  - Sort alphabetic in descending order **⑲**,
  - Sort numeric in ascending order **⑳**,
  - Sort numeric in descending order **㉑**,
  - Sort by index in descending order **㉒**,
  - Sort by index in descending order **㉓**.




## Complementary pages

Scroll ③ to the bottom to see the Complementary pages ④ pane's part.

The Reservation and consultation page ③ allows to support, on the main page, an access button giving access to a Reservation and consultation page . This page allows to consult a grid of rooms reservation for all the room resources made visible for this page, with one page per day.

- This feature requires to have a screen supporting user interactivity like touch screen devices, or tablets. When using a media player connected to a touch screen device, check also that user interactivity is properly activated.
- The devices resources need to be configured in SignMeeting Jooxter according to. For further information, refer to the chapter § [Room resources association to a device](#).



In this Reservation and consultation page page, the support for these buttons can be inactivated:

- Add button ④,
- Edit button ⑤,
- Delete button ⑥.

The option Return to the main page after being idle for <n> seconds ⑦ allows to set the duration, before displaying back the main page, after being stayed for a couple of time (by default, 60 seconds) without user activity on the reservation and consultation page .

## General settings

Scroll ③ to the bottom to see the General settings ④ pane's part.


The *Background content when there is no current nor future meeting* field set allows to define a label to display when no screen saver ⑤ is running and when there is neither current meeting nor future meeting.

The *Background content when there is no current nor future meeting* allows also to configure a screen saver when there is neither current meeting, nor next meeting:

- Show the screen saver after <n> minutes ⑥ allows to display the screen saver <n> minutes after the current meeting has ended.

When the screen saver feature is activated,

- Select the Media to display ⑦ when the screen saver is running, then drop an image ( .jpg , .gif , .png ) ⑧ , a document ( .pdf ) , a MS-PowerPoint presentation ( .pptx ) or a video ( .mp4 ) ⑨ from the Files view of the project repository to the Media to display input ⑩ .
- Use an interactive marker ⑪ with a label to display ⑫ allows to display a marker on the screen when the screen saver is running, inviting the user to touch the screen to quit the screen saver.



The Media to display ⑦ input is not editable. The variable <sup>3</sup> in the Media to display ⑦ input can be used only to replace filename value:

- drop the root folder containing the media,
- click on the active \$0 variable button and choose the wished variable name,
- select then the appropriate image or video extension.


**Check the image and video capabilities of your device before choosing your media.**

**Use the Sweep button to erase the input content.**


<sup>3</sup>Ensure that your device has the appropriate variable value.

Variable name	Variable format when set in the input
deviceInfo:hostname	\${deviceInfo:hostname}
deviceInfo:mac	\${deviceInfo:mac}
deviceInfo:uuid	\${deviceInfo:uuid}
deviceInfo:field1	\${deviceInfo:field1}
deviceInfo:field2	\${deviceInfo:field2}
deviceInfo:field3	\${deviceInfo:field3}
deviceInfo:field4	\${deviceInfo:field4}
deviceInfo:field5	\${deviceInfo:field5}

**When using variables, the file target by the variable must be dropped manually in the Linked files part of the form.**



Screen saver rendering example:




To load a Personalized theme ( .css ), download one of the suitable [CSS for Summary screen by event display profile](#), import it in the Files view of your project repository [④⁸](#) then drop it in the Personalized theme [④⁹](#) input.

The CSS API is compliant with Mozilla & W3C: <https://developer.mozilla.org/en-US/docs/Web/CSS/background>. To customize the Summary screen by event CSS, refer to the chapter § [Appendix: Summarization by event CSS](#).

## Linked files

The private images and the font files called in your `.css` CSS theme and the images or the video files whose name is conditioned by variable need to be added *manually* by a single drop from the `Medias` tab **(50)** to the `Linked files` input **(51)**.



### 3.2.3 SignMeeting > Display profiles > Summary screen by resource

The Summary screen by resource *display profile* allows to display a summary of events taking place in several room resources along the day, with:

- several events of one resource per raw,
- the events of only a part of the day are displayed per page:
  - e.g.:
    - 1st page: 8.00 - 12.00,
    - 2nd page: 12.00 - 16.00,
    - 3rd page: 16.00 - 20.00, ...

This *display profile* is usually suitable for devices, connected to screen much larger than 10", installed in halls: corridors halls, floors halls...

To define the start time for the first page, refer to the chapter [SignMeeting Jooxter data sources > Other settings](#) tab.

☞ The number of rows per page and the time range per page can be customized.

To configure a Summary screen by resource *display profile*, select the **Display profiles** **①** tab, then select a **Summary screen by resource display profile** instance **②**.

☞ The length of the configuration form is more than one page. Use the scroll bar to go to the end of the form.

#### Banner

The **Banner** tab allows to display or not a banner at the top **④** or at the bottom **⑤** of the main page.

The **Banner** **③** can contain:

- the current Time **⑥** with different formats:
  - HH:MM (12) (e.g. 7.00),
  - HH:MM (24) (e.g. 19:00).
- the current Date <sup>1</sup> **⑦** with different formats:


Label	EN (default)	FR	DE
one-or-two-digit day, one-or-two-digit month, two-digit year (e.g. 12/1/22)	12/01/22	01/12/22	01.12.22
one-or-two-digit day, one-or-two-digit month, four-digit year (e.g. 12/1/2022)	12/01/2022	01/12/2022	01.12.2022
one-or-two-digit day, three-letter abbreviation month, four-digit year (e.g. 1-Dec-2022)	01-Dec-2022	01 Dec 2022	01. Dec. 2022
two-digit day, literal month, four-digit year (e.g. Dec, 01 2022)	December, 01 2022	01 décembre 2022	01. Dezember 2022
two-digit day, literal month, two-digit year (e.g. Dev 01, 22)	December 01, 22	01 décembre 22	01. Dezember 22
three-letter-abbreviation day, two-digit day, two-digit month, four-digit year (e.g. Thu 01 12 2022)	Thu 01 12 2022	jeu 01 12 2022	Don 01 12 2022
literal day, two-digit day, literal month, four-digit year (e.g. Thursday, December 01, 2022)	Thursday, December 01, 2022	jeudi 01 décembre 2022	Donnerstag, 01.Dezember 2022

- the organisation Logo <sup>2</sup> **⑧** ( .jpg , .gif , .png <sup>3</sup> ),
- the page title **⑨** located in the banner.

<sup>1</sup> The date translation (day and month reversed) and the date format (dot or slash character), depending on the language, are made directly on the device by respecting the regional language of the device.

<sup>2</sup> It is recommended to use a image whose height in pixel is the banner height in pixel of the target screen resolution. Then adjust the height of the organisation logo inside this image to control its size. For further information about the banner height, refer the chapter § [Appendix: Banner characteristics](#).

<sup>3</sup> Do better use .png logo if possible, format which is supporting the transparency capability.



If not all the meetings can be display on a page, `SignMeeting` displays automatically the other pages in alternance.


## Main page

Scroll ③ to see the Main page ④ pane's part.

- Time per page ⑩ (default value: 10): allows to set the duration in second per page when several page of events are displayed,
- Time per page without event ⑪ allows to shorten the page duration in second for pages displaying no event at all,
- Maximum number of rooms per pages ⑫ (default value: 10): allows to define the number of raws par page, with a room per raw,
- Number of hours per page ⑬ (from 4 to 20, default value: 10): allows to define the time range per page
  - For example, enter the value 3 if the time range per page must be:
    - page #1: from 8.00 to 11.00,
    - page #2: from 11.00 to 14.00,
    - page #3: from 14.00 to 17.00, ...
- Room name column title ⑭: allows to set a room name column header label (empty by default).
- Font size for column headers ⑮ for the title of the page and Font size for events ⑯ among the value:
  - Small,
  - Medium,
  - Large.
- Display the meetings for the whole day (including meeting that have ended) ⑰: if unchecked, allows to display only the events in progress. If checked, allows to display the events in progress, the coming events and the over events.
- Do not display pages whose rooms have no meeting at any time on the current day ⑱: do not spend time to display empty page.
- Always stay on the page of the current slot ⑲: allow to display the pages whose the current time is included between the page time start time and the page end time:
  - For example, it is 10.00. There are some meetings booked every hours from 8.00 to 16.00, spread on 2 pages (from 8.00 to 12.00 and 12.00 to 16.00), only the first page is displayed because 10.00 included between 8.00 and 12.00, time range of the first page.

**⚠ It is not recommended to use at the same time both the option *Display the meetings for the whole day* and *Always stay on the page of the current slot* at the same time.**

To define an image as background, select ㉑ an image ( .png , .jpg , .gif ) in the Files ㉒ view of your project repository and drop it in the background image input ㉓.



The variable ³ in the Background image ㉓ input can be used only to replace **filename** value:


- drop the root folder of the image to display,
- click on the active \$0 variable button and select the wished variable name,
- select then the appropriate extension of the image to display.

<sup>3</sup>Ensure that your device has the appropriate variable value.

**⚠ The Background image ㉓ input is not editable. Use the Sweep button to erase the input content.**

Variable name	Variable format when set in the input
deviceInfo:hostname	`\${deviceInfo:hostname}`
deviceInfo:mac	`\${deviceInfo:mac}`
deviceInfo:uuid	`\${deviceInfo:uuid}`
deviceInfo:field1	`\${deviceInfo:field1}`
deviceInfo:field2	`\${deviceInfo:field2}`
deviceInfo:field3	`\${deviceInfo:field3}`
deviceInfo:field4	`\${deviceInfo:field4}`
deviceInfo:field5	`\${deviceInfo:field5}`

When using variables, the target files must be added manually in the `Linked files` part of the form.




## Complementary pages

Scroll ③ to the bottom to see the Complementary pages ④ pane's part.

The Reservation and consultation page ② allows to support, in the main page, an access button giving access to a Reservation and consultation page . This page allows to consult a grid of rooms reservation for all the room resources made visible for this page, with one page per day.

▪ This feature requires to have a screen supporting user interactivity like touch screen devices, or tablets. When using a media player connected to a touch screen device, check also that user interactivity is properly activated.

▪ The devices resources need to be configured in SignMeeting Jooxter according to. For further information, refer to the chapter § Room resources association to a device.



In this Reservation and consultation page page, the support for these buttons can be inactivated:

- Add button ②,
- Edit button ③,
- Delete button ④.

The option Return to the main page after being idle for <n> seconds ⑤ allows to set the duration, before displaying back the main page, after being stayed for a couple of time (by default, 60 seconds) without user activity on the reservation and consultation page .

## General settings

Scroll ③ to the bottom to see the General settings ④ pane's part.


The *Background content when there is no current nor future meeting* allow to define a label to display when no screen saver ② is running and when there is not current meeting or future meeting.

The *Background content when there is no current nor future meeting* allows to configure a screen saver when there is no current or next meeting:

- Show the screen saver after <n> minutes ②: allows to display the screen saver <n> minutes after the current meeting has ended.

When the screen saver feature is activated,

- Select the Media to display ③ when the screen saver is running, then drop an image (.jpg, .gif, .png) ④, a document (.pdf), a MS-PowerPoint presentation (.pptx) or a video (.mp4) ⑤ from the Files view of the project repository to the Media to display input ⑥.
- Use an interactive marker ⑦ with a label to display ⑧ allows to display a marker on the screen when the screen saver is running, inviting the user to touch the screen to quit the screen saver.




The Media to display ③ input is not editable. It is possible to add only a filename as variable<sup>3</sup> in the Media to display ④ input:

- drop the root folder containing the media,
  - click on the active \$0 variable button and choose the wished variable name,
  - select then the appropriate image or video extension.
- Note:**
- Check the image and video capabilities of your device before choosing your media.
  - Use the Sweep button to erase the input content.


<sup>3</sup>Ensure that your device has the appropriate variable value.

Variable name	Variable format when set in the input
deviceInfo:hostname	`\${deviceInfo:hostname}`
deviceInfo:mac	`\${deviceInfo:mac}`
deviceInfo:uuid	`\${deviceInfo:uuid}`
deviceInfo:field1	`\${deviceInfo:field1}`
deviceInfo:field2	`\${deviceInfo:field2}`
deviceInfo:field3	`\${deviceInfo:field3}`
deviceInfo:field4	`\${deviceInfo:field4}`
deviceInfo:field5	`\${deviceInfo:field5}`

**Note:** When using variables, the file target by the variable must be dropped manually in the Linked files part of the form.



Screen saver rendering example:




To load a Personalized theme ( .css ), download one of the suitable CSS for Summary screen by resource display profile, import it in the Files view of your project repository [36](#) then drop it in the Personalized theme [37](#) input.

The CSS API is compliant with Mozilla & W3C <https://developer.mozilla.org/en-US/docs/Web/CSS/background>. To customize the Summary screen by resource CSS, refer to the chapter § [Appendix: Summarization by resource CSS](#).

## Linked files

The private images and the font files called in your `.css` CSS theme and the images or the video files whose name is conditioned by variable need to be added *manually* by a single drop from the `Medias` tab **(38)** to the `Linked files` input **(39)**.



### 3.2.4 SignMeeting > Display profiles > Room label

The Room label display profile allows to display on the screen until two following events in two areas:

- the upper area for the event in progress,
- the lower area for the next event.

The Room label display profile is only suitable for SMH300 devices, which can communicate with one or several SLATE106 devices installed near a meeting room door.

**Note:** The pairing operation between the SMH300 hub and your SLATE106 devices must be finalized before configuring then publishing the SignMeeting Jooxter App.

To configure a Room screen display profile, select the **Display profiles** tab (1), then select a Room screen display profile instance (2).

**Note:** The lenght of the SignMeeting Jooxter App configuration tab is more than one page. Use the scroll bar to go to the end of the SignMeeting Jooxter App configuration pane.

#### Banner

The Banner tab (3) allows to display or not a banner at the top (4) of the main page.


The Banner can contain:

- The current Date (5) with different format<sup>1</sup>:

Label	EN (default)	FR	DE
one-or-two-digit day, one-or-two-digit month, two-digit year (e.g. 12/1/22)	12/01/22	01/12/22	01.12.22
one-or-two-digit day, one-or-two-digit month, four-digit year (e.g. 12/1/2022)	12/01/2022	01/12/2022	01.12.2022
one-or-two-digit day, three-letter abbreviation month, four-digit year (e.g. 1-Dec-2022)	01-Dec-2022	01 Dec 2022	01. Dec. 2022
two-digit day, literal month, four-digit year (e.g. Dec, 01 2022)	December, 01 2022	01 décembre 2022	01. Dezember 2022
two-digit day, literal month, two-digit year (e.g. Dev 01, 22)	December 01, 22	01 décembre 22	01. Dezember 22
three-letter-abbreviation day, two-digit day, two-digit month, four-digit year (e.g. Thu 01 12 2022)	Thu 01 12 2022	jeu 01 12 2022	Don 01 12 2022
literal day, two-digit day, literal month, four-digit year (e.g. Thursday, December 01, 2022)	Thursday, December 01, 2022	jeudi 01 décembre 2022	Donnerstag, 01.Dezember 2022

- The organisation Logo (6) (.jpg, .gif, .png),
- The Room name (7) where the meeting takes place.

<sup>1</sup> The date translation (day and month reversed) and the date format (dot or slash character), depending on the language, are made directly on the device by respecting the regional language of the device.



## Main page


Scroll to see the Main page **(3)** pane's part.

The *Display information for the current meeting* field set support these parameters:

- Label when there is no current meeting **(8)**: allows to display or not a text when there is no current meeting. By default: *No current meeting*,
- Display title **(9)**: allows to display or not the meeting title,
- Display time range **(10)**: allows to display or not the meeting *start time* and *end time*, e.g.: *10:30 – 12:30*.
- Shift the start event display \* **(11)**: allow to anticipate the meeting display taking account of the content update delay for the SLATE106 (max. 15 minutes):
  - <n> minutes before the start of the event:
    - 15 minutes before the start of the event **(12)**: the meeting is displayed 15 minutes (default value) before it starts,
    - 30 minutes before the start of the event **(12)**: the meeting is displayed 30 minutes before it starts,
  - As soon as possible **(13)**: the meeting is displayed in the current meeting area part as soon as possible.
- Display description **(14)**: allows to display or not the meeting description (if required, a prefix, empty by default, can be displayed before the description value),
- Display organizer **(15)**: allows to display or not the meeting organizer (if required, a prefix, empty by default, can be displayed before the organizer value).

The *Display information for the next meeting* **(16)** field set allows to activate an area for the next meeting which is supporting these parameters:

- Label for the header **(17)**: label showing the location of the next meeting bottom half area,
- Label when there is no next meeting **(18)**: allows to display or not a message when there is no meeting. By default: *no other meeting*,
- Display title **(19)**: allows to display or not the meeting title,
- Display time range **(20)**: allows to display or not the meeting *start time* and *end time* (e.g.: *10:30 – 12:30*).



The Reservation process actions part supports :


- Shorten the meeting if no Check In after <n> minutes : allows to activate or not the automatic meeting shortening when the meeting has not been checked-in within the interval, this in order to free up the room resource,
- Custom script (25) allow to load a custom script to customize the SignMeeting Joxter behaviour. For more information, contact sales@innes.pro.

With the Room Label display profile, Check in button and Check out buttons are deprecated for any new SMH300/SLATE106 installation. In return, to support Check in and Check Out feature, do use an EnOcean motion sensor device and use a meetingControlEnOceanMotionSensor\_001A.js personalisation script suitable for Room Label display profile only (SMH300). When the meeting confirmation is supported by your calendar system, it allows to Check in automatically a meeting when people are detected in the room. The Check in by script can work only when the meeting is really pending, meaning that it doesn't work inside the anticipated display period.

In the default configuration of the meetingControlEnOceanMotionSensor\_001A.js personalisation script:

- when the sensor is detecting a presence, the meeting room booking is confirmed immediately,
- when the sensor is detecting no presence for more than 15 minutes, value defined by the pendingFreeDelay variable at the beginning of the script, the meeting is shortened and the room is made free.


Download the suitable [meetingControlEnOceanMotionSensor.js](#), import it in the Files (26) view of your project repository then drop it in the Custom script (27) input.



## General settings

To load a Personalized theme ( .css ), download the suitable CSS for Room label display profile example), import it in the Files (29) view of your project repository then drop it in the Personalized theme (30) input.

The CSS API is compliant with Mozilla & W3C <https://developer.mozilla.org/en-US/docs/Web/CSS/background>. To customize the Room Label CSS, refer to the chapter § Appendix: Room label CSS.



### 3.3 Devices


- Before associating the display profiles to your devices, ensure that all your display profiles instances have been created.
- Before activating the access control for a device, ensure that the NFC/RFID detection has been activated in the RFID tab.
- Before activating the access control for a device, with authentication by user and RFID tag registered in LDAP, ensure that the LDAP has been properly activated and configured in the LDAP tab.

On the left side, click on the **Devices**  **(1)** button to open the **Devices** view of the project repository.

On the right side, click on the **Devices**  **(2)** button to open the **Devices** configuration tab of the SignMeeting Jooxter App.

The devices, added to in your project and appearing on the left, appear automatically on the right as well.

In the example, six devices **(3)** **(4)** **(5)** **(6)** **(7)** **(8)** are added in the SignMeeting Jooxter App project. If this pane is empty, refer to the chapter § [File > Project settings > Devices](#) to add some devices to your project.




The  pictogram with a red stamp is showing that no `display profile` instance is associated to this device.

- No display profile instance is associated by default to the device when a new project is created.


To edit a device configuration, fly the mouse pointer over a device name with your mouse, to make appear the  **Edit** button **(9)**, and click on it.

- You can also double click on a device name to edit it.



Device model types	Output rotation	Suitable display profiles
TAB10s SMT210	NA	Room screen (most of time) Summary screen by event - Landscape Summary screen by resource - Landscape
DMB400 SMA300	0° (or 180°)	Summary screen by event - Landscape Summary screen by resource - Landscape Room screen (rare)
DMB400 SMA300	90° (or 270°)	Summary screen by event - Portrait Summary screen by resource - Portrait
SMH300	NA	Room label

A message is shown when there is no suitable display profile instance for a device type. To work around, create an appropriate display profiles instance.



## Display profile association to device


Before associating some room resources to your devices, make a plan of the device names to room resources association.

Device label	Device type	Device rotation <sup>1</sup>	Display profile instance name
floor 1 > room 2 - tablet	tablet	NA <sup>2</sup>	Room screen
floor 1 > room 1 - tablet	tablet	NA <sup>2</sup>	Room screen
hall - large screen	media player	0°	Summarization by event - Landscape
floor 1 – large screen 1	media player	0°	Summarization by event - Landscape
floor 2 – vertical screen	media player	90°	Summarization by resource - Portrait
floor 2 > room 1 - label	SMH300	0°	Room label

<sup>1</sup> The device rotation means that the device output must be configured with a 90° or 270° rotation.


<sup>2</sup> NA for Not applicable. In this case, the tablet device do not support the 90°/180°/270° rotation.

To associate a *display profile* to a device, edit it, and click on the *display profile* drop down list 




Then select one of the available *display profiles* instances created.

The Room screen , Summary screen by event  and Summary screen by resource  display profiles are compatible with all the device models  except the SMH300 device model.



The Room label **(15)** display profile is compatible only with the SMH300/SLATE106 solution **(16)**.




Click on the **OK** button to validate the *display profile* instance association.

**Do the same operation for all the devices of your project.**

**⚠** The overall publication cannot work if one of the device has not a associated *display profile* instance.

When all the devices have a *display profile* associated, there should not be red stamp anymore. The red stamp are now orange which is showing that some device have no room resource associated.



You can notice that there is one specific pictogram per *display profile* type:

<b>Display profile type</b>	<b>Display profile pictogram</b>
Room screen	
Summarization by event	
Summarization by resource	
Room label	

## Activation of the main page's buttons on user/badge authentication



By default, no authentication (authentication `Anonymous`) is required to use the main page's buttons, for example to use:

- the `Book now` button,
- the `Delete` button,
- the `Confirm` button,
- the `Notification` page button.

Authentication is never required to access to the reservation and consultation page.

If required you can activate the access control for some of the devices. For that, edit a device, and select the required authentication method:

- `Anonymous` (default): no authentication,
- `Anonymous` using a `RFID badge`: the access control is done by an only badging, with a NFC/RFID protocol supported by the device
- `Anonymous` using a badge `RFID` validated via `LDAP`: the access control is done by badging, with a NFC/RFID protocol supported by the device, and with the badge ID and the user owner properly registered in the LDAP server



The `Disconnection after <n> seconds` (30 seconds by default) field allows to configure the timeout, after which the authenticated user is automatically disconnected. In this case, a new badging is required to authenticate again.

- In case using an anonymous authentication, meaning empty dn and empty password, the option `connection as anonymous allowed` needs to be activated inside the LDAP server as well.
- Presenting a badge a first time allows to authenticate and use the main page. Presenting a badge afterwards, before the automatical disconnection, allows to disconnect from SignMeeting Jooxter.
- If required, do the same operation for all the devices of your project.

## CSS class

The CSS class allow to apply a custom class, additional class implemented in the CSS.

*That can be for example a specific background image.*

For example, if the CSS file contains a custom CSS class which is named `.cssBackgroundImage`, enter the `cssBackgroundImage` key word in the CSS class input of the SignMeeting Jooxter App configuration pane.

For further information about how to use, refer to the appropriate CSS appendix.

*If required, do the same operation for all the devices of your project.*

## Enable console mode

The `Enable console` mode allows to run SignMeeting Jooxter App in diagnostic mode, allowing to print some status information on the SignMeeting Jooxter inter-connections with:

- the calendar system,
- the LDAP server,
- the badge detection.

*If required, do the same operation for all the devices of your project.*

## Room resources association to a device

To associate room resources to your devices, refer to the chapter § [Room resources association to a device](#).

### 3.3.1 Room resources association to a device

*It is considered at this step that a consistent display profile instance has been associated to each of the devices of your project.*

Now, you have to associate at least one room resource per device.

*It is possible to associate a same room resource Id to several devices.*

*Before associating some room resources to your devices, make a association map between the device name and the room resources.*

Device label	Device type	Device rotation	Display profile instance name	Room event visible on the main page	Room events visible only on the reservation page
floor 1 > room 2 - tablet	tablet	0°	Room screen	room1@demo.contoso.com	room1@demo.contoso.com room2@demo.contoso.com room3@demo.contoso.com
floor 1 > room 1 - tablet	tablet	0°	Room screen	room2@demo.contoso.com	room1@demo.contoso.com room2@demo.contoso.com room3@demo.contoso.com
hall – large screen	media player	0°	Summarization by event - Landscape	room1@demo.contoso.com room2@demo.contoso.com room3@demo.contoso.com	
floor 1 – large screen 1	media player	0°	Summarization by event - Landscape	room1@demo.contoso.com room2@demo.contoso.com room3@demo.contoso.com	
floor 2 – vertical screen	media player	90°	Summarization by resource - Portrait	room1@demo.contoso.com room2@demo.contoso.com room3@demo.contoso.com	
floor 2 > room 1 - label	hub for SLATEs	0°	Room label	index1: room1@demo.contoso.com index2: index3: index4: index5: index6: index7: index8: index9: index10:	


Click on the Data source  (1) button to open the Data source view of your project repository.

Click on the Devices configuration tab (2) of your SignMeeting Jooxter App.

Expand the data source (3) to see all its resources.


Select the required room resources for the first device (4). And drop them to the required device (5). A dotted line appears when the resource are dropped at the right place towards a device.

 [SHIFT]+[up]/[SHIFT]+[down] key combination are supported for the multiple selection, and key combination with [CTRL]+[up]/[CTRL]+[down] as well.




When at least one resource is associated to a device, the orange stamp disappears for this device. Do the same for each device by selecting the required resources (6).

 It is possible to publish the SignMeeting Jooxter App without any resource associated but that has not a functional sense.




Do the same for all data sources by following the map above.

 It is not possible to associate, to a same device, some resources coming from different data sources.




☞ You can minimize or expand the room resources for a device with the bottom/right triangle (7)/(8) button.



☞ Don't associate, to a same device, some resources coming from different datasources else SignMeeting cannot work properly and a information message is raised: "An error occurred in the application, No datasource is linked to this device (code -3)."'

To remove one room resource associated to a device, fly the mouse pointer over one room resource, and click on the **delete** (9) button.




When several room resources are selected, the unitary **edit** and **delete** (10) button per resource is not available anymore.

To remove more than one resource at a time, select several room resources, and click on the overall **delete** (11) button.

To edit the configuration of several resource at a time, select several room resources, and click on the overall **edit** (12) button.

**Info:** The overall edition does not work for the directional pictograms.




## Setup resource visibility

For all the resources, you can setup their visibility:

- on the main page,
- on the reservation and consultation page.


By default the events booking capability and the events display are supported on the main page and on the reservation and consultation page for all the resources.

To change the visibility for a resource, fly the mouse pointer over a resource with your mouse and click on the Edit **(11)** button.



To remove the events booking/display for a specific resource on the main page, uncheck Show events for this room on the main page **(12)**.


To remove the events booking/display for a specific resource on the reservation and consultation page, uncheck Show this room in the reservation and consultation page **(13)**.



A different pictogram is associated to the four combination of these two values.

Resource pictogram	Values combination
📅 ⑯	Show events for this room on the main page and Show this room in the reservation and consultation page are checked
📅 ⑰	only Show events for this room on the main page is checked
🚩	only Show this room in the reservation and consultation page is checked
NONE	none of them <sup>1</sup>

<sup>1</sup> This case is for very rare case when the room is temporary not visible at all in the interface.




## Directional pictograms

The resource associated to the **Summarization by event display profile** have the capability to be displayed with until two directional pictograms per resource name.

Click on the **Devices** configuration tab (1).


Expand with the bottom/right triangle (2) the room resources for a device having a **Summarization by event** (3) display profile.

fly the mouse pointer over a resource with your mouse and click on the **Edit** (4) button.



To associate a first directional pictogram, check the **Associate direction pictogram n°1 to this resource** (5) option. Use the left arrow (6) and right arrow (7) to choose one of the embedded pictograms on the theme of building signage (arrows, stairs, lifts, ...).


**Note:** The pictograms have a font format. So they are adopting the CSS style color of the event values.




If the pictograms library is not suitable for your project, you can choose to enter the path to a private directional pictograms (8) located in the **Files** view of your project repository. In this case, enter in the input, the appropriate relative path filename. e.g.: **[Medias]/Images/orientation/arrowLeft.png** (9).

**Note:** Remember you have to use private directional pictograms in the appropriate color according to your organisation theme policy.


**Note:** It is recommended to load **.png** image with transparency.



A red stamp is showing that the images path filename is not correct.



To associate a second directional pictogram, check the **Associate direction pictogram n°2 to this resource**  option and do the same as explained above for **Associate direction pictogram n°1 to this resource**.



### 3.4 LDAP

The **LDAP** tab allows to activate and configure the LDAP user and/or badge searching criteria when access control with authentication by RFID/LDAP is activated.

Click on the **LDAP** **(1)** configuration tab of your SignMeeting Jooxter App project to access to the **LDAP** pane.

Turn on the button to **ON** **(2)** to activate the connection to the LDAP server.


Enter your LDAP serveur **URL** **(3)**. If login credentials are required, activate the **Authentication** **(4)** checkbox and fill its login credentials:

- **Login** **(5)**,
- **Password** **(6)**.

For example:

- URL : `ldap://192.168.100.244,`
- Login : `cn=Administrator,cn=Users,dc=exchange2013,dc=contoso,dc=fr,`
- Password : `pwd1.`


If no login credentials are required, the authentication is **anonymous**.



Once the configuration is done, the default filtering attributes are dynamically updated in the **Attribute(s)** column.

#### Authentication by badge ID in LDAP

To configure the authentication by badge, activate the **RFID tag** raw **(7)** and click on the **Edit** **(8)** button.




The Root **⑨** input allows to define the `dn` of the directory (or parent directory) from where the badge need to be researched, and so win time by searching at the right directory location. e.g.: `cn=Functions,dc=exchange2013,dc=contoso,dc=fr`.

The Filter **⑩** input allows to target a subset of LDAP users & resources thanks to an additional filtering configuration to find out the badge ID with the best efficiency. The supported filters are:

- by Entity type:
  - e.g.: `(objectClass=user)` (default),
- by group membership:
  - e.g.: `(memberOf=CN=DoorAdmins,cn=Users,dc=exchange2013,dc=contoso,dc=fr)`,
- by attributes & optional validity conditions, with binary operator: AND (&), OR (|)
  - e.g.: `(&(badgeID=*)(|(ou=directory1)(ou=SecondFuncs)))`
    - with `ou` = organisation unit

⚠ Active Directory does not support extensible matching filtering, e.g.: `(DN = *irectory *)`; Consequently, the filter like finding out a DN whose name is containing a specific string is not working. For further information on the case: <https://msdn.microsoft.com/en-us/library/cc223241.aspx>.

⚠ Whenever the users are spread into different directories of the LDAP, it is advised to implement groups and use `memberOf` filters.



The Cross reference attribute **⑪** allows to define the attribute name in which your badge ID value are located. e.g. If your badge ID is stored in the `badgeID` attribute name of the LDAP server, replace the `crossReference` attribute name by the `badgeID` attribute name.

☞ The research is considered successful as soon as a first resource containing this badge id is found.


☞ Attributes: The default attribute name for the RFID badge is Badge ID. If the Badge ID does not exist in your LDAP, you can change it here according to your LDAP configuration.

It is possible to configure SignMeeting Jooxter to retrieve some `Extra attribute(s)` values when realizing the LDAP request for authentication. These attribute can be then used in SignMeeting Jooxter to generate automatical event title label. By default, there is no `Extra attribute(s)` defined. To add until two `Extra attribute(s)`:

- check the `Attribute1` (12) and fill the input with a LDAP attribute name,
- check the `Attribute2` (13) and fill the input with another LDAP attribute name.

For example:

- `Attribute 1 : cn`,
- `Attribute 2 : codePage`.



For further information about the available LDAP attributes, refer to the chapter § [Appendix: LDAP attribute Editor](#).

**Tip** Do prefer use string type or integer type attributes for `Extra attribute(s)`. Indeed, the other types may not be displayed properly (hexadecimal, date, UID).

When using Briva LDAP (3.10.21 or above), the `Attribute 1 (or 2)` name must worth one of the `dstName` or `dstAttribute` value of the config.js Briva configuration script.

For example:

- `Attribute 1 : registration`,
- `Attribute 2 : DisplayName`.


For further information about the available LDAP attributes, refer to the chapter § [Appendix: Briva LDAP attribute](#).

Some `Validity attributes` (14) can be tested in addition to the RFID badge & user availability. To activate some badge validity test, activate the wished validity criteria:

- by `Validity attributes`,
- by `Validity start date attribute`,
- by `Validity end date attribute`.

Then associate for each of them a LDAP attribute and a validity data format. For example:

Validity criteria	associated LDAP attribute	Data format <sup>1 2</sup>
<code>Validity end date attribute</code>	<code>expirationTime</code>	Active directory generalized time



That requires that the associated `expirationTime` LDAP attribute has a value containing a validity date in the appropriate format.

<sup>1</sup> The supported `Validity attributes` formats are: yes/no, 1/0, true/false, On/off.


<sup>2</sup> The supported `Validity start date attribute` and `Validity end date attribute` supported formats are:

- d/m/yy (e.g.: 2/12/21),
- d/m/yyyy (e.g.: 2/12/2021),
- account expires timestamp (e.g.: number of nanoseconds since 1st Jan 1601),
- Active directory generalized time (e.g.: 20151009225600.0Z).

Once the RFID badge is found in the LDAP and the validity condition are filled, the authentication by badge is considered as successful. So the connection to SignMeeting Jooxter App is established and the user can access to the buttons of the main page.


In case the validity attribute is not found in LDAP (e.g. in case typo error inserted in validity attribute), the condition is considered as fully filled meaning that the RFID badge account validity attribute is successful.

Configuration example:



## Authentication by badge ID and user registered in LDAP

To configure the authentication by user in LDAP, activate also the `User` raw <sup>9</sup> and click on the `Edit` <sup>10</sup> button.




**Users:** allows to indicate from which DN base the user associated to this RFID badge can be found out.

- Root : type DN base (or DN parent base) from where the user can be found out (e.g. `cn=Users,dc=exchange2013,dc=contoso,dc=fr`)

For **Filter** input, refer to the chapter [Authentication by badge ID and user in LDAP](#).

**Tip:** If any a user is not associated to the RFID badge, the authentication will succeed as soon as the badge ID is found, even if it is associated to no people.

Configuration example:



For **Extra attribute(s) to retrieve**, refer to the chapter [Authentication by badge ID and user in LDAP](#).

**⚠** Do not use the LDAP attributes already used by SignMeeting Jooxter:

- CN<sup>1</sup>,
- Mail,
- sAMAccountName,
- uid,
- badgeID,
- valid.

<sup>1</sup>When the user is authenticated, the user's email (CN) becomes the organizer of all the meetings done with SignMeeting Jooxter.


### 3.5 RFID

The **RFID** tab allows to activate the NFC/RFID badge detection.

When the NFC/RFID badge detection is activated, the access control can be then activated for some or your device.

Click on the  **RFID** **(1)** configuration tab of your SignMeeting Jooxter App project to access to the **RFID** pane.

Turn the button to **ON** **(2)** to activate the NFC/RFID detection.



The **apply a filter to RFID detection** option allows to only detect some NFC badges with a specific baud rate or a specific modulation.

The available modulations filters are:

- ISO 14443 Type A,
- ISO 14443 Type B,
- JEWEL,
- ISO 14443 BI,
- ISO 14443 B2SR,
- ISO 14443 B2CT,
- FeliCa,
- DEP.

The available baud rates filters are:

- 106,
- 212,
- 424,
- 847.

 *Do not activate the NFC modulation filtering before having made some successful badging tests before.*


### 3.6 SMTP

The `SMTP` tab allows to activate the `SMTP` and configure the `SMTP` email account with its login credentials. The `SMTP` account is used to send notification email.

Click on the  `SMTP` **(1)** configuration tab of your SignMeeting Jooxter App project to access to the `SMTP` pane.

Turn the button to `ON` **(2)** to activate the `SMTP` and fill the `SMTP` account:

- URL **(3)**,
- Login **(4)**,
- Password **(5)**.



☞ To know the authentication list supported by Gekkota , please refer to [Gekkota Email and supported authentication](#) application note.

☞ About Gmail account, `PLAIN` and `LOGIN` authentications are not activated by default. To activate them, go in Gmail account and activate the option: `Allowing Less secure apps to access your account` .

# **Part IV**


**Publication**

## 4.1 App publication

The `Publish to devices` button allow to publish the SignMeeting Jooxter App on the devices, applicant for the publication.

There are different ways to publish the App. For further information, refer to the chapter § [File > Project settings > Publication](#).


When the publication is successful for all the devices, applicant for publication, the `The operation was successfully completed` message appears.



## App publication failure report

When the publication was not successful for at least one device, a `publication report` popup appears after a while and gives information on the publication status.

Publication report status	Information
✓	The SignMeeting Jooxter App has been published on the devices.
✗	Screen composer has detected an error in your project. Consequently, the SignMeeting Jooxter App cannot be published on some devices.




To get more information on the error in your project, fly the mouse pointer over the **✗** red cross to get more information about the publication report status for a device.

The error tooltip is usually very helpful. This table gives more information about how to fix the issue.

Publication report status error tooltip	Information
The middleware of the device is not compatible with this App	Check the compatibility of your SignMeeting Jooxter App. Remove from devices applicant for the publication all the one that are not compatible with this SignMeeting Jooxter App (for example, Gekkota 3 devices).
No profile defined.	No <i>display profile</i> has been associated to your device. Go in the <i>Devices</i> tab and associate a <i>display profile</i> instance to the device having a red stamp.
The operation has failed because the devices is not accessible	The device is no more available on the network (it is not supplied, the network cable is removed, the IP address or the port has changed). Check that the device is working properly and retry a device discovery .
The operation was not completed correctly because the login, password or port for one of the devices are not valid	The device has been added to your project with a wrong login credentials or wrong port to access the device WebDAV server
An internal error has occurred. Please try the operation later	One of the reasons could be this one: you are using a <i>https://</i> scheme which is not yet supported in INNES Screen Composer G4 .
An error has occurred during the publication, please check your form	You have checked an option in the SignMeeting Jooxter App configuration tab without filling the associated input (e.g.: Logo option is checked but the associated path filename is empty).
No file found at this location ./medias/[...]	Upgrade your Screen Composer version. Upgrade your SignMeeting Jooxter App version.

## Publication error because insufficient App license keys

If you have not enough SignMeeting Jooxter license keys installed of a total of *core* key license for insufficient device, this error is raised at the publication. To work around, remove some devices from your project or install more SignMeeting Jooxter App licenses keys. For further information, refer to the chapter § [Screen Composer > Preferences > Licenses and Apps](#)




## 4.2 Middleware publication

When the `Publish middlewares to devices` button value is selected, clicking on the  button allows to publish all the selected middlewares available in the `Screen Composer > Preferences > Middlewares` pane on the devices applicant for the publication.

If the button is not available, refer to the chapter § [File > Project settings > Publication](#) and the chapter § [Screen Composer > Preferences > Middlewares](#).


When the publication is successful for all the devices applicant for publication, the information message `The operation was successfully completed` appears.



## Middleware publication failure report

When one of the selected devices cannot be updated because there is no suitable middleware for it or the device is not available, a `publication report` popup appears after a while and gives information on the publication status.

Publication report status	Information
	No corresponding middleware.
	The middleware update has failed.



To get more information on the error in your project, fly the mouse pointer over the  red cross to get more information about the publication report status for a device.

The error tooltip is usually very helpful. This table gives more information about how to fix the issue.

Publication report status error tooltip	Information
No corresponding middleware	This device has been selected as applicant for the middlewares publication but there is no appropriate middleware available in the Screen Composer > Preferences > Middlewares pane.
The middleware update has failed	This device is probably not available on the network anymore. So check whether the device is working properly by checking its LED status behaviour. Check the network connectivity between your computer and the device. Check again whether the device is registered in INNES Screen Composer G4 with the appropriate port and IP address value.

# **Part V**

---

**Contacts**

## 5.1 Contacts

For further information, please contact us:

- **Technical support:** [support@innes.en](mailto:support@innes.en),
- **Sales department:** [sales@innes.en](mailto:sales@innes.en).

Refer to the INNES Web site for FAQ, application notes, and software downloads: <http://www.innes.pro/en/>.

INNES SA  
5A rue Pierre Joseph Colin  
35700 RENNES

Tel: +33 (0)2 23 20 01 62  
Fax: +33 (0)2 23 20 22 59

# **Part VI**

---

**Appendix**

## 6.1 Appendix: Jooxter calendar system


Connect to the Jooxter calendar Web interface (e.g. <https://en.app.jooxter.com/>) with your login credentials.

These several views are available:

- **① Spaces**,
- **② Scheduler**,
- **③ My bookings**,
- **④ Colleagues**.


### Spaces tab

From the default **Spaces** **①** tab, it is possible to visualize the resource location. To create a new event, click on the **Book** **⑤** button.



### Scheduler tab

To add a meeting in the **Scheduler** **②** tab, click on a calendar timeslot of the appropriate resource.



Then fill the event attributes:

- title **⑥**,
- start date **⑦**,
- start time **⑧** and end time **⑨**.

Check on of the button to apply a preprogrammed timeslot for your event:

- Book all day **⑩** option in case your event must fill all the day with preprogrammed time range (e.g. 8:30 AM - 6h30 PM),
- Morning **⑪** option in case your event must fill all the day (8:30 - 1:00 PM),
- Afternoon **⑫** option in case your event must fill all the day (8:30 - 1:00 PM)

**☞** The **Book all day** option is available only when there is no event at all already programmed in the day.

To define the event recurrence, click on the **One time** button.

Select the resource name's calendar **(14)** in which the event must be created.

The screenshot shows the Jooxter Scheduler interface. On the left, a list of rooms (Room 10 to Room 16) is shown with their capacities. A booking for 'Labs Innes' from 10:15 AM to 12:00 PM on April 29, 2022, is highlighted. The 'One time' button is selected. The location dropdown shows 'Room 11'. Other booking options like 'All Day', 'Morning', and 'Afternoon' are also visible.

Scroll to the bottom to click on the **More options** button to fill additional event attributes:

- organizer **(13)**,
- public/private **(14)**,
- description **(15)**,
- local attendees **(16)**.

**☞** Enter the three first characters of an attendee name of your organization to display the available attendees name having this characters subset.

Click on the **Or add an external attendee** **(17)** button to add to your event some external attendees which are not part of your organization.

The screenshot shows the Jooxter Scheduler interface with the 'More options' section expanded. It includes fields for organizer (13), public/private status (14), description (15), and a search bar for external attendees (16). The 'Or add an external attendee' button (17) is visible at the bottom.

**☞** In Jooxter, it is not possible to create a meeting having a start date in the past.

**☞** In Jooxter, it is not possible to change a fix duration event into an all day long event. To work around, delete your event to empty the resource calendar for this day and create your all day long event.

## Delete a meeting

To delete a event, click on the event **(18)** in the resource calendar, then press on the **Delete** **(19)** button.

The screenshot shows the Jooxter Scheduler interface. On the left, a grid displays available rooms ('Ressource 1' and 'Ressource 2') and their capacities ('5' and '6') across time slots from 6:00 AM to 2:00 PM. A specific slot from 8:00 AM to 9:00 AM is highlighted with a red circle containing the number '18'. On the right, a detailed view of the selected meeting for 'Ressource 1' is shown. The meeting is titled 'Meeting' and is scheduled for 'Thursday, 28 Apr 2022' from 08:00 to 09:00. It is located at 'Labs Innes'. There are two buttons at the bottom: a red 'Delete' button with a circled '19' and a blue 'Modify' button.

**☞** In Jooxter, it is not possible to modify or remove an event taking place in the past.


## Checkin/checkout a meeting

The checkin **(20)** button allow to validate that some attendees are really attending the meeting. While the meeting is not checked in, the meeting can be deleted **(21)**.

The screenshot shows the Jooxter Scheduler interface. A meeting is listed for 'Ressource 2' at 'Innes' from 9:19 AM to 10:19 AM on April 27th, 2022. The event details are shown in a modal on the right. The meeting is titled 'test in the past' and is scheduled for 'Wednesday, 27 Apr 2022' from 16:10 to 18:15. It is located at 'Labs Innes'. The 'Checkin' button is highlighted with a green background and a circled '20'. There are two buttons at the bottom: a red 'Delete' button with a circled '21' and a blue 'Modify' button.

Once the checkin **(20)** is done, the meeting can not be deleted because the Delete **(21)** button is not available. In this case, only the event modification, by clicking on the Modify **(22)** button, is supported.

The **checkout** (23) button allows to terminate the event by shortening it when the meeting is over. That allows to free up the resource.



The screenshot shows the Jooxter Scheduler interface. On the left, there's a calendar view for Wednesday, April 27th, 2022. A booking for "Ressource 2" is visible from 9:19 AM to 10:19 AM. On the right, a detailed view of this booking is shown. It includes the resource name "Ressource 2", its location "Salle de réunion 6 Innes Floor 0", and the duration "16:10 • 18:15". Below this, there are "Checkout" and "Modify" buttons, both of which are circled in red.


A event just created, whose date is today and start time is set to a value in less than 15 minutes from now is automatically checked-in by the Jooxter calendar system.

## Predefined time ranges

The default preprogrammed time ranges are defined in your account profile:

- Morning : 8:30 AM - 1:00 PM,
- Afternoonning : 1:00 PM - 6:30 PM,
- All Day : 8:30 AM - 6:30 PM.

To modify these preprogrammed time ranges, click on the `Profile` item.



The screenshot shows the Jooxter Scheduler interface with a booking for "Room 18" and "Room 19" on Friday, May 6th, 2022. On the right side, the user profile menu is open, showing options such as "Labs INNES", "Profile", "Manage my spaces", and "Administration".

Click on the **modify** button.

The screenshot shows the Jooxter user profile modification interface. At the top right, there are buttons for 'Modify' and 'Reset password'. Below this, there are two columns of profile information:

Email	labs@innes.fr	Department
Phone number		Profile
Building	Innes	Language
Corporation	Innes	Type

Below these sections are authentication details and registration information:

Authentication method	jooxter
Registered since	2/28/17, 5:06 PM
Groups	• All

At the bottom, there is a 'Default week' section with time range profiles for each day of the week. The Monday profile is shown as:

Monday	8:30 AM	→	1:00 PM
--------	---------	---	---------

Scroll to the bottom and in the **Default week** part, change the time range profile for each day.

The screenshot shows the 'Default week' section of the profile modification page. It lists the days of the week with their respective time range profiles. The Monday profile is visible again:

Monday	12:00 AM	→	1:00 PM
	1:00 PM	→	11:45 PM

Each day has two profiles, one for the morning and one for the evening.

Scroll to the top and click on the **Update** button to finalize the operation.

**Tip:** The maximum end time in the input is 11:45 PM. To set the value 11:59 PM, click in the input, enter the 11:59 with your keyboard, then select 11:59 PM.

## 6.2 Appendix: Jooxter administration

Connect to the Jooxter administration Web interface (e.g. <https://admin.app.jooxter.com/admin>) with your user login credentials having an administrator profile.

These several items are available:

- ① Account ,
- ② Buildings ,
- ③ Floors ,
- ④ Resources ,
- ⑤ Devices ,
- ⑥ Resource types ,
- ⑦ Resource groups ,
- ⑧ Corporations ,
- ⑨ Users ,
- ⑩ Users groups ,
- ⑪ Export .

The screenshot shows the Jooxter administration interface. At the top right, there are links for "User interface", "Labs Innes", and "Log out". Below the header, there's a grid of icons with labels: Account, Corporations, Buildings, Floors, Resources, Users, Resource Types, Devices, Resource Groups, and Export. On the left, a vertical sidebar lists the same categories with their corresponding icons. The "Resources" item in the sidebar and its corresponding icon in the grid are both circled in red. The sidebar also includes "Intégrations" and "Ask for support ?". The bottom right corner of the page displays the text "2022 © Jooxter".

### New resource creation

To create a new resource, click on the Resources ④ item then scroll to the bottom.

The screenshot shows the "Resources" list page. The left sidebar has the "Resources" item circled in red. The main area features a search form with fields for Name, Resource Type, Capacity, Building, and Floor. Below the search form is a table titled "Resources list" with columns for Name, Resource Type, and Capacity. The table contains 15 entries, each representing a room or meeting room with a capacity of 10. The bottom right corner of the page displays the text "2022 © Jooxter".

Name	Resource Type	Capacity
Ressource 1	Amphitheatre meeting room	5
Ressource 2	Amphitheatre meeting room	6
Room 1	Stand-up meeting room	10
Room 10	Stand-up meeting room	10
Room 11	Stand-up meeting room	10
Room 12	Stand-up meeting room	10
Room 13	Stand-up meeting room	10
Room 2	Stand-up meeting room	10
Room 3	Stand-up meeting room	10
Room 4	Stand-up meeting room	10
Room 5	Stand-up meeting room	10

Click on the Add a new resource button.

Name	Resource Type	Capacity
Ressource 1	Amphitheatre meeting room	5
Ressource 2	Amphitheatre meeting room	6
Room 1	Stand-up meeting room	10
Room 10	Stand-up meeting room	10
Room 11	Stand-up meeting room	10
Room 12	Stand-up meeting room	10
Room 13	Stand-up meeting room	10
Room 2	Stand-up meeting room	10
Room 3	Stand-up meeting room	10
Room 4	Stand-up meeting room	10
Room 5	Stand-up meeting room	10
Room 6	Stand-up meeting room	10
Room 7	Stand-up meeting room	10
Room 8	Stand-up meeting room	10
Room 9	Stand-up meeting room	10

**Cancel** **Add a new resource**

Fill the appropriate attributes for your resource:

- `Name`,
- `Description`,
- `Is bookable`,
- `Is visible`,
- `Capacity`,
- `Building`,
- `Floor`,
- `Booking days and time range`.

If a meeting confirmation is required, scroll to the bottom.

**Resource**

**Name \***: Room 14

**Is bookable**:

**Is visible**:

**Description**: Room 14 desc

**Resource Type \***: Stand-up meeting room

**Capacity \***: 10

**Building \***: Innes

**Floor**: Floor 0 (0)

**Resource Group**: All resources

**Owner**: Labs Innes


And choose the `Check-in required` option with a value for the `delay to checkin`.

The screenshot shows the 'admin.app.jooxter.com/addresource' page. On the left sidebar, there are links for Resource Groups, Corporations, Users, User groups, Export, Intégrations, and Ask for support?. The main form area contains fields for Resource Type (Stand-up meeting room), Capacity (10), Building (Innes), Floor (Floor 0 (0)), Resource Group (All resources), Owner (Labs Innes), Labels, Open hours (From 00:00 to 23:59, Mon-Fri checked), and Details (Check-in required checked, Delay to checkin 30 minutes).

**Tip:** It is advised to have the same check-in configuration for all the resources that are used by a same SignMeeting Jooxter project.

## New resource type creation

To create a new resource type, click on the Resources type (6) item.



Click on the Add a new resource type button.

The screenshot shows the 'Resource types' list page in the Jooxter admin interface. The left sidebar contains navigation links for Home, Account, Buildings, Floors, Resources, Devices, Resource Types (which is the current page), Resource Groups, Corporations, Users, User groups, Export, Integrations, and Ask for support?. The main content area displays a table titled 'Resource types list' with columns for Name and Short name. There are three entries: 'Amphitheatre meeting room' with short name 'AMR', 'Department meeting room' with short name 'DMR', and 'Stand-up meeting room' with short name 'SUMR'. At the bottom of the table, it says 'Showing 1 to 3 of 3 entries' and has 'Previous 1 Next' buttons. Below the table are 'Cancel' and 'Add a new resource type' buttons. The footer of the page includes the text '2022 © Jooxter'.

Fill the resource type attributes:

- Resource type name ,
- Booking minimum duration ,
- Booking maximum duration ,

To allow recurring event, click on the Recurrence button.

The screenshot shows the 'Resource type info' configuration page for a new resource type. The left sidebar is identical to the previous screenshot. The main form has fields for 'Name \*' (Meeting room) and 'Short name \*' (Meeting room). It includes a dropdown for 'Metatype \*' set to 'Meeting room'. Under 'Recurrence', there is a checkbox that is unchecked. Other settings include 'Pictogram' (classic), 'Icon size on map' (Medium), and 'Display resource name on map' (checked). At the bottom are 'Cancel' and 'Validate' buttons.

## Retrieve your resource Id

Once the resource are created, to retrieve the Jooxter resource Id required to fully fill the SignMeeting datasource, click on the Resources (1) item.

Watch the URL in your Web browser. The `resource_id` is located at the end of the URL (in the example, the `resource_id` for `Room 1` is `92211`).

Restart the operation for each by clicking on the other `resource` name rows, the one after the other.

### 6.3 Appendix: CSS mapping

SignMeeting Jooxter	Calendar field	Current meeting CSS	Next meeting CSS
Title	SUMMARY	mainpage_current_summary	mainpage_next_summary
Description	DESCRIPTION	mainpage_current_description	mainpage_next_description
Label description	N/A	mainpage_current_description-label	N/A
Location	LOCATION	mainpage_current_location	N/A
Time range	DTSTART / DTEND	mainpage_current_date	mainpage_next_date
Organisator	ORGANIZER, CN	mainpage_current_organizer	mainpage_next_organizer
Organisator label	N/A	mainpage_current_organizer-label	mainpage_next_organizer-label
Event type	N/A	mainpage_current_meeting-state	mainpage_next_meeting-state
Attendees	ATTENDEE, CN	mainpage_current_attendees	mainpage_next_attendees
Attendees label	N/A	mainpage_current_attendees-label	mainpage_next_attendees-label

## 6.4 Appendix: Data mapping

<b>SignMeeting Jooxter label</b>	<b>Calendar field</b>	<b>SignMeeting Jooxter fields</b>
Id	UID	bookingId
Title	SUMMARY	title
Location (resource label)	LOCATION	resourceName
Description	DESCRIPTION	description
Resource Id	RESOURCE, Id	resourceName
Time range	DTSTART/DTEND	timestampFrom/timestampTo
Organizer	ORGANIZER, CN	ownerName
Attendees	ATTENDEE	Guests (email + Firstname + Lastname)

## 6.5 Appendix: Information message when using an inconsistent resource Id

Theis message should be displayed for a while after having tried to book a meeting in a meeting room resource having an inconsistent resource id:

A problem occured while trying to add the new meeting.  
Malformed request

To work around, remember the resource name in which booking attempt has been done and check its resource id in the SignMeeting datasource.

## 6.6 Appendix: Room screen CSS

### CSS file example

This is an example of a `signmeeting_theme_room_screen_light-00XX.css` file.

```
/**  
 * Room Screen customizable CSS applying a light theme.  
 *  
 * Feel free to edit the proposed fields based on your needs.  
 *  
 * If you want to use an external media (image, video...),  
 please ensure that it has been added in the publication (see ScreenComposer MEDIA tab).  
 * Then specify the URL relatively to this file's location.  
 *  
 * Example 1: The CSS and the media are in the same directory.  
 *      ./assets/theme_room_screen.css  
 *      ./assets/my_image.png  
 *      => The style to apply is:  
 *          background-image: url("my_image.png");  
 *      The path requires just the image's file name.  
 *  
 * Example 2: The CSS and the media are in two different directories.  
 *      ./css/theme_room_screen.css  
 *      ./images/my_image.png  
 *      => The style to apply is:  
 *          background-image: url("../images/my_image.png");  
 *      The path goes up one level (..), then follows the "images" directory  
(images/) and ends up with the image's file name (my_image.png)  
*/  
  
/* Defines the default colors and font */  
body {  
    color: #333;  
}  
  
/* Banner */  
#banner {  
    background-color: white;  
}  
  
#banner #date_and_time,  
#banner #active_directory_connection_status,  
#banner #banner_title {  
    color: #333;  
    font-size: 1em;  
}  
  
/* Main Page container element */  
.container {  
    background-image: url('data:image/png;base64,iVBORw...5CYII=');  
    /* background-image: none; */  
    background-size: 100%;  
}  
  
/*  
CSS classes matching the deviceInfo variables specific to each device are set on the container.  
It allows you to apply specific CSS rules based on the device.  
A prefix is used for CSS compatibility and to match the deviceInfo Name.  
e.g.:  
    .MAC_00-1C-E6-02-38-63 #mainpage_current_summary {  
        color: red;  
    }  
The names of the classes is the concatenation of the device specific information:  
    - MAC_<mac_address_value> with <mac_address_value> being the current MAC address of your device.  
    - UUID_<uuid_device_value> with <uuid_device_value> being the Universal Unique identifier of  
    your device.  
    - HOSTNAME_<hostname_value> with <hostname_value> being the Hostname defined on your device,  
    - FIELD<field_number>_<field_value> with <field_number> being the index of the field variable  
    (from 1 to 5) and <field_value> its value on your device.  
*/  
.MAC_00-1C-E6-02-38-63 #mainpage_current_summary {  
    color: inherit;  
}
```

```

/* Current Meeting section */
#mainpage_current_summary,
#mainpage_current_location,
#mainpage_current_organizer,
#mainpage_current_organizer-label,
#mainpage_current_attendees,
#mainpage_current_attendees-label,
#mainpage_current_description,
#mainpage_current_description-label,
#mainpage_current_date,
#mainpage_current_meeting-state {
    color: #111;
}

/* Splitter line between the current and the next meeting sections */
#divEventTwo {
    border-top: 1px solid #333;
}

/* Next Meeting section */
#mainpage_next_summary,
#mainpage_next_location,
#mainpage_next_attendees,
#mainpage_next_attendees-label,
#mainpage_next_organizer,
#mainpage_next_organizer-label,
#mainpage_next_description,
#mainpage_next_description-label,
#mainpage_next_date,
#mainpage_next_meeting-state {
    color: #333;
}

/* Buttons for the current and next meeting */
.mainpage_current_buttons,
.mainpage_next_buttons {
    background-color: #344E59 !important;
    color: white !important;
}
.mainpage_current_buttons_inactive,
.mainpage_next_buttons_inactive {
    opacity: 0.38 !important;
}

/* Buttons for the booking actions */
#booking_page_access_button {
    background-color: #344E59 !important;
    color: white !important;
}


/* Button to access the shortcut page */
#notification_page_access_button {
    background-color: #344E59 !important;
    color: white !important;
}

/* Shortcut page used for the notifications */
#shortcutPage.notification_page_background {
    background-image: url("../..../gui/css/images/tweed.png") !important;
}

```

## CSS mapping for main page suffix labels and events values

- ① #mainpage\_current\_location
- ② #mainpage\_current\_date
- ③ #mainpage\_current\_meeting-state
- ④ #mainpage\_current\_summary
- ⑤ #mainpage\_current\_organizer-label
- ⑥ #mainpage\_current\_organizer
- ⑦ #mainpage\_current\_attendees-label
- ⑧ #mainpage\_current\_attendees
- ⑨ #mainpage\_current\_description-label
- ⑩ #mainpage\_current\_description
- ⑪ #mainpage\_next\_location
- ⑫ #mainpage\_next\_date
- ⑬ #mainpage\_next\_meeting-state
- ⑭ #mainpage\_next\_summary
- ⑮ #mainpage\_next\_organizer-label
- ⑯ #mainpage\_next\_organizer
- ⑰ #mainpage\_next\_attendees-label
- ⑱ #mainpage\_next\_attendees
- ⑲ #mainpage\_next\_description-label
- ⑳ #mainpage\_next\_description
- ㉑ .container



## CSS mapping for buttons and split line

- ㉒ #booking\_page\_access\_button
- ㉓ #notification\_page\_access\_button
- ㉔ #shortcutPage.notification\_page\_background
- ㉕ #divEventTwo

Current meeting


No current meeting

<sup>22</sup>

Book now

ROOM 1  
15:15 - 16:30  
*Next meeting*Support & training session  
*Marc Dupont*<sup>25</sup>**CSS mapping for notification page**

- <sup>26</sup> #shortcutPage.notification\_page\_background



## 6.7 Appendix: Summarization by event CSS

### CSS file example

This is an example of a `signmeeting_theme_summary_screen_by_event-00XX.css` file.

```
/**  
 * Summarization by event customizable CSS  
 *  
 * Feel free to edit the proposed fields based on your needs.  
 *  
 * If you want to use an external media (image, video...),  
 please ensure that it has been added in the publication (see ScreenComposer MEDIA tab).  
 * Then specify the URL relatively to this file's location.  
 *  
 * Example 1: The CSS and the media are in the same directory.  
 *      ./assets/theme_room_summarization.css  
 *      ./assets/my_image.png  
 *      => The style to apply is:  
 *          background-image: url("my_image.png");  
 *      The path requires just the image's file name.  
 *  
 * Example 2: The CSS and the media are in two different directories.  
 *      ./css/theme_room_summarization.css  
 *      ./images/my_image.png  
 *      => The style to apply is:  
 *          background-image: url("../images/my_image.png");  
 *      The path goes up one level (..), then follows the "images" directory (images/) and ends up with  
 the image's file name (my_image.png)  
 */  
  
/* Banner */  
.summaryByEvent #banner {  
    background-color: #3366FF;  
}  
.summaryByEvent #banner #date_and_time,  
.summaryByEvent #banner #active_directory_connection_status,  
.summaryByEvent #banner #banner_title {  
    color: #fff;  
    /* font-size: 1em represents 100% */  
    font-size: 1em;  
}  
.summaryByEvent.portrait #banner #date_and_time,  
.summaryByEvent.portrait #banner #active_directory_connection_status,  
.summaryByEvent.portrait #banner #banner_title {  
    color: #fff;  
    /* font-size: 0.8em represents 80% */  
    font-size: 0.8em;  
}  
  
/* Main Page container element */  
.container {  
    background-image: inherit;  
    /* background-image: url("my_image.png"); */  
    /* background-image: none; */  
    background-color: #3366FF;  

```

```

/*
CSS classes matching the deviceInfo variables specific to each device are set on the container.
It allows you to apply specific CSS rules based on the device.
A prefix is used for CSS compatibility and to match the deviceInfo Name.
e.g.:
.MAC_00-1C-E6-02-38-63 #mainpage_current_summary {
    color: red;
}
The names of the classes is the concatenation of the device specific information:
- MAC_<mac_address_value> with <mac_address_value> being the current MAC address of your device.
- UUID_<uuid_device_value> with <uuid_device_value> being the Universal Unique identifier of your device.
- HOSTNAME_<hostname_value> with <hostname_value> being the Hostname defined on your device,
- FIELD<field_number>_<field_value> with <field_number> being the index of
the field variable (from 1 to 5) and <field_value> its value on your device.
*/
.MAC_00-1C-E6-02-38-63 .eventSection .cell {
    color: orange;
}

/* Event section */
.eventSection {
    border-color: white;
    /* R, G, B, transparency => background-color: rgba(0, 0, 0, 0.5); */
    background-color: rgba(0, 0, 0, 0.5);
}
.eventSection .cell {
    color: white;
}

/* Table Header */
.headerBar {
    border-color: black;
    /* R, G, B, transparency => background-color: rgba(0, 0, 0, 0.7); */
    background-color: rgba(0, 0, 0, 0.7);
}
.headerBar .cell {
    color: white;
}

/* Buttons for the booking actions */
#booking_page_access_button {
    background-color: #344E59 !important;
    color: white !important;
}

```

## CSS mapping for the summary screen by event - landscape display profile

- ① .summaryByEvent #banner ,
- ② .summaryByEvent #banner #date\_and\_time ,
- ③ .summaryByEvent #banner #active\_directory\_connection\_status ,
- ④ .summaryByEvent #banner #banner\_title ,
- ⑤ .container ,
- ⑥ .headerBar .cell ,
- ⑦ .headerBar ,
- ⑧ .eventSection .cell ,
- ⑨ .eventSection ,

Location	Event	7	6 Hours	
ROOM 3	Support & training session	9	09:15 - 11:15	←
ROOM 1	Cloud Application training		10:00 - 11:15	↔
ROOM 2	Cloud Application training		11:15 - 12:15	↑↓ →
ROOM 3	Support & training session		11:45 - 13:00	←

5

#### CSS mapping for the summary screen by event - portrait display profile

- ⑩ .summaryByEvent #banner ,
- ⑪ .summaryByEvent.portrait #banner #date\_and\_time ,
- ⑫ .summaryByEvent.portrait #banner #active\_directory\_connection\_status ,
- ⑬ .summaryByEvent.portrait #banner #banner\_title ,
- ⑭ .container.portrait ,
- ⑮ .headerBar .cell ,
- ⑯ .headerBar ,
- ⑰ .eventSection .cell ,
- ⑱ .eventSection ,

Location	Event	Hours
ROOM 2	Cloud Application training	15:15 - 16:45
ROOM 3	Support & training session	15:30 - 17:00
ROOM 1	Cloud Application training	15:30 - 17:00
ROOM 3	Cloud Application training	17:00 - 18:30
ROOM 2	Support & training session	17:30 - 18:30
ROOM 1	Cloud Application training	18:30 - 19:00
ROOM 2	Kick-off meeting	18:45 - 20:00
ROOM 1	Kick-off meeting	19:30 - 20:00
ROOM 3	Cloud Application training	19:45 - 20:00



## 6.8 Appendix: Summarization by resource CSS

### CSS file example

This is an example of a `signmeeting_theme_summary_screen_by_resource-00xx.css` file.

```
/**  
 * Summary screen by resource customizable CSS  
 *  
 * Feel free to edit the proposed fields based on your needs.  
 *  
 * If you want to use an external media (image, video...), please ensure that it has been added in  
 the publication (see ScreenComposer MEDIA tab).  
 * Then specify the URL relatively to this file's location.  
 *  
 * Example 1: The CSS and the media are in the same directory.  
 *      ./assets/theme_room_summarization.css  
 *      ./assets/my_image.png  
 *      => The style to apply is:  
 *          background-image: url("my_image.png");  
 *      The path requires just the image's file name.  
 *  
 * Example 2: The CSS and the media are in two different directories.  
 *      ./css/theme_room_summarization.css  
 *      ./images/my_image.png  
 *      => The style to apply is:  
 *          background-image: url("../images/my_image.png");  
 *      The path goes up one level (..), then follows the "images" directory (images/) and ends up with  
 the image's file name (my_image.png)  
 */  
  
/* Banner */  
.summaryByResource #banner {  
    background-color: #A2A2A2;  
}  
  
.summaryByResource #banner #date_and_time,  
.summaryByResource #banner #active_directory_connection_status,  
.summaryByResource #banner #banner_title {  
    color: #fff;  
    /* font-size: 1em represents 100% */  
    font-size: 1em;  
}  
  
.summaryByResource.portrait #banner #date_and_time,  
.summaryByResource.portrait #banner #active_directory_connection_status,  
.summaryByResource.portrait #banner #banner_title {  
    color: #fff;  
    /* font-size: 0.8em represents 80% */  
    font-size: 0.8em;  
}  
  
/* Main Page container element */  
.container {  
    background-image: inherit;  
    /* background-image: url('data:image/png;base64,iVBORw0KG...ORK5CYII>'); */  
    /* background-image: none; */  
    background-size: 100%;  

```

```

/*
CSS classes matching the deviceInfo variables specific to each device are set on the container.
It allows you to apply specific CSS rules based on the device.
A prefix is used for CSS compatibility and to match the deviceInfo Name.
e.g.:
.MAC_00-1C-E6-02-38-63 .room_title {
  color: red;
}
The names of the classes is the concatenation of the device specific information:
- MAC_<mac_address_value> with <mac_address_value> being the current MAC address of your device.
- UUID_<uuid_device_value> with <uuid_device_value> being the Universal Unique identifier of your device.
- HOSTNAME_<hostname_value> with <hostname_value> being the Hostname defined on your device,
- FIELD<field_number>_<field_value> with <field_number> being the index of the field variable
(from 1 to 5) and <field_value> its value on your device.
*/
.MAC_00-1C-E6-02-38-63 .room_title {
  color: inherit;
}

/* Column header label for the rooms */
.room_title {
  color: #FFFFFF;
  background-color: #393939;
  border-color: #000000;
}

/* Row header label for the rooms */
.room_name {
  color: #FFFFFF;
  background-color: #393939;
  border-color: #000000;
}

/* Column header label for the time interval */
.title_time_interval {
  color: #FFFFFF;
  background-color: #393939;
  border-color: #000000;
}

/* Row background if there is no meeting */
.calendar_event_free {
  background-color: rgb(162, 162, 162);
  border-color: #000000;
}

/* Row background if there is a meeting */
.calendar_event_busy {
  border-color: #000000;
  background-color: rgb(214, 33, 75);
}

/* Cell label for the meeting's title */
.calendar_event_title {
  color: #000000;
}


/* Cell label for the meeting's organizer */
.calendar_event_organizer {
  color: #000000;
}

/* Buttons for the booking actions */
#booking_page_access_button {
  background-color: #344E59 !important;
  color: white !important;
}

```

## CSS mapping for the summary screen by resource - landscape display profile

- ① .summaryByResource #banner
- ② .summaryByResource #banner #date\_and\_time ,
- ③ .summaryByResource #banner #active\_directory\_connection\_status ,
- ④ .summaryByResource #banner #banner\_title
- ⑤ .container
- ⑥ .room\_title
- ⑦ .title\_time\_interval
- ⑧ .room\_name
- ⑨ .calendar\_event\_free
- ⑩ .calendar\_event\_busy
- ⑪ .calendar\_event\_organizer
- ⑫ .calendar\_event\_title



## CSS mapping for the summary screen by resource - portrait display profile

- ⑯ .summaryByResource #banner
- ⑰ .summaryByResource.portrait #banner #date\_and\_time ,
- ⑱ .summaryByResource.portrait #banner #active\_directory\_connection\_status ,
- ⑲ .summaryByResource.portrait #banner #banner\_title
- ⑳ .container
- ㉑ .room\_title
- ㉒ .room\_name
- ㉓ .title\_time\_interval
- ㉔ .calendar\_event\_free
- ㉕ .calendar\_event\_busy
- ㉖ .calendar\_event\_title
- ㉗ .calendar\_event\_organizer

15:21  
6/17/21

**Meetings of the day**

Rooms	8H-9H	9H-10H
ROOM 1	(21) (22) Marc Dupon	(23) (24) Marc Dupont Kick-off meeting
ROOM 2		Marc Dupont Cloud Application training
ROOM 3		Marc Dupont Kick-off meeting

(13) (14) (15) (16) (17) (18) (19) (20) (21) (22) (23) (24)



## 6.9 Appendix: Room label CSS

### CSS file example

This is an example of a `signmeeting_theme_room_label_001B.css` file.

```
/**  
 * Room label customizable CSS  
 *  
 * Feel free to edit the proposed fields based on your needs.  
 *  
 * For the color palette, it is recommended to use:  
 *     color: #000; // black  
 *     color: #474747; // dark gray  
 *     color: #696969; // gray  
 *     color: #B3B3B3; // light gray  
 *     color: #FFF;      // white  
 *  
 * If you want to use an external media (image, video...), please ensure that it has been added in the  
 publication (see ScreenComposer MEDIA tab).  
 * Then specify the URL relatively to this file's location.  
 *  
 * Example 1: The CSS and the media are in the same directory.  
 *     ./assets/theme_room_screen.css  
 *     ./assets/my_image.png  
 *     => The style to apply is:  
 *         background-image: url("my_image.png");  
 *     The path requires just the image's file name.  
 *  
 * Example 2: The CSS and the media are in two different directories.  
 *     ./css/theme_room_screen.css  
 *     ./images/my_image.png  
 *     => The style to apply is:  
 *         background-image: url("../images/my_image.png");  
 *     The path goes up one level (..), then follows the "images" directory (images/) and ends up with the  
 image's file name (my_image.png)  
 */  
  
/* Banner */  
.roomLabel #banner {  
    background-color: #FFF;  
}  
  
.roomLabel #banner #date_and_time,  
.roomLabel #banner #active_directory_connection_status,  
.roomLabel #banner #banner_title {  
    color: #000;  
}  
  
/* Main Page container element */  
.container {  
    background-image: url('data:image/png;base64,iVBOR...RK5CYII=');  
    background-size: 100%;  
}  
  

```

```

/* Current Meeting section */
#mainpage_current_summary,
#mainpage_current_location,
#mainpage_current_attendees,
#mainpage_current_meeting-state {
    color: #000000;
}

#mainpage_current_date,
#mainpage_current_description,
#mainpage_current_organizer {
    color: #474747;
}

#mainpage_current_description-label,
#mainpage_current_organizer-label,
#mainpage_current_attendees-label {
    color: #696969;
}

/* Next Meeting section */
#mainpage_next_summary {
    color: #000000;
}

#mainpage_next_date {
    color: #474747;
}

#mainpage_next_meeting-state {
    color: #696969;
}

/* Buttons for the booking actions */
#buttonBar,
.labelButtonIcon {
    color: #474747;
}

```

#### CSS mapping for suffix labels and events values

The screenshot shows a meeting summary card with the following details:

- Date:** 11/6/2020 (14)
- Location:** Room 1 (16)
- Time:** 14:00 - 16:00 (1)
- Title:** Kick-off meeting (2)
- Organiser:** Innes Screen Manager (3)
- Description:** Samples delivery, dependencies, integration plan, mass production (5)
- Notes:** Description (6)
- Next meeting:** Project Meeting (9)
- Time:** 17:30 - 19:00 (10)
- Label:** Next meeting (11)

Red circles with numbers (1) through (16) are overlaid on the text to indicate which CSS classes correspond to which parts of the meeting summary.

- (1) `#mainpage_current_date ,`
- (2) `#mainpage_current_summary ,`
- (3) `#mainpage_current_organizer-label ,`
- (4) `#mainpage_current_organizer ,`
- (5) `#mainpage_current_description-label ,`
- (6) `#mainpage_current_description ,`
- (7) `#mainpage_current_meeting-state ("Current meeting"),`

- ⑧ #mainpage\_next\_date ,
- ⑨ #mainpage\_next\_summary ,
- ⑩ #mainpage\_next\_meeting-state ("Next meeting"),
- ⑪ .container (background),
- ⑫ .roomLabel #banner ,
- ⑬ .roomLabel #banner #date\_and\_time ,
- ⑭ .roomLabel #banner, #active\_directory\_connection\_status ,
- ⑮ .roomLabel #banner #banner\_title .

## 6.10 Appendix: How to customize CSS

To customize the CSS to set a color for a particular label,

- set the `#RRGGBB` color (from `#000000` to `FFFFFF` for each appropriate class according to your organisation theme.
- set the RGB color with integer values: `rgb(R_val, G_val, B_val)` or
- set the color with its name `white`, `black`, `red`, `green`, `pink`, `blue`, `yellow`, `brown`, ...

<b>#RRGGBB</b>	<b>Description</b>
RR	red value of the RGB color in hexadecimal (from 00 to FF)
GG	green value of the RGB color in hexadecimal (from 00 to FF)
BB	blue value of the RGB color in hexadecimal (from 00 to FF)

e.g. for the yellow color, use the `#FFFF00` color.

<b>rgb (Rval, Gval, B_val)</b>	<b>Description</b>
R_val	red value of the RGB color in decimal (from 0 to 255)
G_val	green value of the RGB color in decimal (from 0 to 255)
B_val	blue value of the RGB color in decimal (from 0 to 255)

e.g. for the yellow color, use the `rgb(255, 255, 0)` color.

For the background, you can use the `rgba(Rval, Gval, Bval0, Transp0_1)` function allowing to set a transparency value for the background color.

<b>rgba (Rval, Gval, Bval, Transp0_1)</b>	<b>Description</b>
R_val	red value of the RGB color in decimal (from 0 to 255)
G_val	green value of the RGB color in decimal (from 0 to 255)
B_val	blue value of the RGB color in decimal (from 0 to 255)
Transp01	decimal value from 0 to 1

e.g. for the yellow color with a 25% transparency, use `rgba(255, 255, 0, 0.25)`.

For the background, you can use also the `background-image: url("my_image.png");` function. In this case, you have to insert it also as linked file in the summary screen by event display profile. If the file is not located at the root of the CSS directory, fill the relative path filename `background-image: url("../images/my_image.png");`

It is possible also to create a custom class name to define the background image for a device. This custom class must be used in the SignMeeting Jooxter configuration pane.

```
.customBackgroundImage {
    background-image: url("../images/crystal_blue.jpg");
}
```

You can set a particular CSS theme configuration for a specific device by using:

- its `MAC` identification method value,
- its `UUID` identification method value,
- its `hostname` identification method value,
- one of its device information `field1` to `field5` values.

```
MAC_00-1C-E6-02-38-63 .eventSection .cell {
    color: orange;
}
.container.FIELD1_paris {
    background-image: url("images/background-qrcode.jpg");
}
```

You can increase or decrease the font size of some labels by settings a decimal value before `em;`.

```
font-size: 0.8em;
```

The value `inherit` tell that the custom CSS will benefit of the default built-in value without changing it.

For the Room screen display profile, you can change the color and the thickness (in pixel) of the event splitter.

```
#divEventTwo {
    border-top: 1px solid #333;
}
```

When the presentation is like explained below, that means that the same style is applied to different classes. e.g. for `.mainpage_current_buttons` and `.mainpage_next_buttons`

```
.mainpage_current_buttons,
.mainpage_next_buttons {
    background-color: #344E59;
    color: white;
}
```

If you want to have a different style for each classes, split it in two like explained,

```
.mainpage_current_buttons
{
    background-color: #010203;
    color: white;
}
.mainpage_next_buttons {
    background-color: #111213;
    color: black;
}
```

If the `!important;` key word is put at the end of a line, that means this code part is required to apply the style properly, so don't remove it.

```
#booking_page_access_button {
    background-color: #344E59 !important;
    color: white !important;
}
```

For the summarization by resource display profile, you can modify the outline color of the square with the attribute `border-color: #000000;`.

```
.room_name {
    color: #FFFFFF;
    background-color: #393939;
    border-color: #000000;
}
```

It is possible set a font style by declaring a `@font-face` class in the CSS file like explained below and by using it for the banner style. In the example, the `broadw.ttf` font file is available in the `Files` view fo the project repository at the root folder of the CSS file and the `broadw.ttf` font file is added in the `Linked files` part of the configuration tab of the appropriate *display profile*.

```
.summaryByEvent #banner #banner_title {
    color: rgb(220,175,117);
    /* font-size: 1em represents 100% */
    font-size: 1em;
    font-family:"Broadway";
}

@font-face {
    font-family: "Broadway";
    src: url("./broadw.ttf");
}
```

In portrait mode, the size of the button to access to the reservation and consultation page may be too large. Its is possible to reduce it by using the percentage of the font-size like explained below:

```
/* Size/color of the access button for the reservation page */
#booking_page_access_button {
    background-color: #344E59 !important;
    color: white !important;
    font-size: 0.7em;
}
```

## 6.11 Appendix: Standby screen/background image/CSS hierarchy

Room screen layer hierarchy

Layer hierarchy	Information	Level
Screen saver (optional, displayed if there is no meeting)	<ul style="list-style-type: none"> <li>- Default texture with trademark* (default)</li> <li>- Custom image</li> <li>- Custom video</li> </ul> <p>*when a custom CSS is embedded, the trademark is not displayed</p>	4 (higher)
Background image	Custom background image	3
Custom CSS using variable MAC UUID, hostname	The CSS can support some styles based on the <MAC>, the <UUID>, the <hostname> or the <deviceinfo field1..5> device values. It can customize buttons colour, background colour or image and custom class. When the variable value is matching with a device, the CSS style based on the MAC, UUID or hostname is applied to the corresponding device. In case using some custom images based on styles using MAC, UUID, hostname variable values, ensure that the image is properly added in linked files	2
Custom CSS	Buttons color customization, background color or image, custom class <i>In case using custom images, ensure that the image is well present in your library</i>	1
Default built-in CSS	default colour	0 (lower)

## Appendix: Banner characteristics


Landscape screen resolution	Components height
800x600	Banner <i>status bar</i> height: px Banner <i>logo</i> height: px
1280x800	Banner <i>status bar</i> height: 16 px Banner <i>logo</i> height: 64 px
1024x600	Banner <i>status bar</i> height: 12 px Banner <i>logo</i> height: 48 px
1920x1080	Banner <i>status bar</i> height: 22px Banner <i>logo</i> height: 86px
3840x2160	Banner <i>status bar</i> height: 43px Banner <i>logo</i> height: 173px

Portrait screen resolution	Components height
1080x1920	Banner <i>logo</i> height: 96 px

## 6.13 Appendix: Microsoft LDAP attribute editor

In the properties of the LDAP directory resource, click on the Attribute editor tab to watch the list of available attributes.



## 6.14 Appendix: Briva LDAP attributes

INNES is selling a LDAP solution called `Briva LDAP`, gateway able to communicate with your access control system through a custom connector like for example the `Uniflow` connector. The connector can be based on an Excel file or can use access control system Web services.

INNES can develop your own connector if required. For further information, contact [sales@innes.pro](mailto:sales@innes.pro). Some `Briva LDAP` connectors are already available on the INNES Web site <http://www.innes.pro/en/support/index.php?BrivaG3/Briva-Ldap/Briva-LdapServers>

Example of `config.js` server configuration script for Briva LDAP server.

The Attributes 1 or Attributes 2 inputs can worth:

- `registration`,
- `Lastname`,
- `Firstname`,
- `badgeID`,
- `cn`,
- `Displayname`.

```
{
  "sheetName" : "Personnes",

  "rowHeader" : 4,
  "rowDataStart" : 5,

  "dataMapping" :
  [
    {"srcName" : "Matricule",
     "dstName" : "registration",
     "mandatory" : true,
     "format": "string"
    },
    {"srcName" : "Nom",
     "dstName" : "Lastname",
     "mandatory" : true,
     "format": "string"
    },
    {"srcName" : "Prénom",
     "dstName" : "Firstname",
     "mandatory" : true,
     "format": "string"
    },
    {"srcName" : "Badges",
     "dstName" : "badgeID",
     "mandatory" : true,
     "format": "extractNumber"
    }
  ],
  "dataTransformation" :
  [
    {
      "srcAttributes" : ["Firstname", "Lastname"],
      "dstAttribute" : "cn",
      "separator" : " "
    },
    {
      "srcAttributes" : ["Firstname", "Lastname"],
      "dstAttribute" : "Displayname",
      "separator" : " "
    }
  ]
}
```

## 6.15 Appendix: Logs INNES Screen Composer G4

For debug purpose, some logs can be activated in the `.xml` file below:

`C:\Program Files (x86)\INNES Screen Composer G4\res\log4xpcom\log4xpcom.xml`

The INNES Screen Composer G4 log are printed in `.log` file below:

`C:\Users<user>\AppData\Roaming\Innes Screen Composer G4\innes\logs\INNES Screen Composer G4.log`

## 6.16 Appendix: Set temporarily SignMeeting in native mode to access to the AOSP settings

On the Qeedji system AOSP device, the SignMeeting Jooxter App is launched in `kiosk` mode, meaning that the `AOSP settings` menu is not available. To access to the `AOSP settings` menu, press on the `system` button for half a second. The SignMeeting Jooxter App is now executed in `native` mode.

After you have been able to access to the `AOSP settings` menu, to return back to the SignMeeting Jooxter App executed in `kiosk` mode, press again on the `system` button for half a second.

For further information about the `system` button, refer to the user manual of Qeedji system AOSP devices.