

# Cisco SRWE Summary

Get the latest version of the note [here](#)

- Cisco SRWE Summary
  - Preamble
  - Virtual local area networks
    - Introduction
      - About
      - Benefits of a vLAN
      - Types of vLANs
      - Broadcast Domains
      - Collision Domains
    - vLAN Tagging
      - 802.1Q standard
      - Access ports and Trunk ports
        - Purpose
        - Dynamic trunking protocol
      - Native vLAN
        - Same VID on the native vLAN
        - Untagged frames on the native vLAN
      - Voice vLAN
    - Inter-vLAN routing - Legacy inter-vLAN routing - Router on a stick - Layer 3 Switch SVI
    - Spanning tree protocol
      - The STP algorithm
        - About Bridge ID (BVID)
        - Bridge priority
        - System ID
        - MAC Address
      - Step 1: Elect the root bridge
      - Step 2: Elect Ports
        - Bandwidth path cost
        - Electing root port
        - Electing designated ports
        - Electing blocked ports
        - Electing blocked ports among multiple connections
      - STP timers and port states
        - Port States
        - Status activity
      - RSTP and other alternatives of STP
        - STP vs RSTP
        - Portfast and BPDU Guard
        - Alternatives to STP

- Etherchannel
  - A Port Channel
  - Caviats
  - LACP and PAgP Protocol
  - Protocol outcomes
- First Hop Redundancy Protocol //todo

## Preamble

First things first, this document was made for my own purposes, its accuracy is not guaranteed to be perfect. There may be loads of gross oversimplification. ***Please use this document at your own risk.***

Other than that, this document is well paired with the **Cisco Internetwork Operating System Command list** document as it contains all configurations.

## Virtual local area networks

### Introduction

### About

A VLAN (Virtual Local Area Network) is a logical group of devices on a network that can communicate with each other as if they were on the same physical network. VLANs are created by assigning ports on network switches to different VLANs, effectively creating multiple virtual switches within a single physical switch.

### Benefits of a vLAN

Benefit	Description
Smaller broadcast domains	A broadcast domain is the area in a network which a broadcast packet can traverse.
Better Security	Only users in the same vLAN can communicate with each other. Routers can be used to control communication between VLANs.
Improved IT efficiency	Managing networks is simpler using VLANs
Better performance	Smaller broadcast domains reduce unnecessary congestion and avoids bothering devices on the network.


### Types of vLANs

Type	Description
------	-------------

Type	Description
Default	vLAN 1 is the vLAN all switches start off with. It cannot be change or be removed. There is also nothing special about it.
Data	These custom VLANs are used to separate different types of traffic from different departments in your organization.
Native	This VLAN has a rule that all frames have a <b>VLAN ID</b> when traversing through <b>tagging</b> with the 802.1Q encapsulation standard.
Management	a VLAN reserved for management, including telnet, SSH, HTTPS,
Voice	A VLAN exclusive for Voice over IP (VoIP), it requires guaranteed bandwidth, priority over other traffic, detour around congested areas of a network and ideally a latency under 150ms

## Broadcast Domains

Broadcast domains are an area in a network where broadcast packets can traverse. Generally an unconfigured **switch** and **hub** will send broadcast everywhere. The only device that can stop broadcasts are layer 3 **routers**.




Configured switches for VLAN use however can limit the spread of broadcast to within the VLAN only. It really is as if its a different VLAN, just facilitated on the same switch.

## Collision Domains

A collision domain is an area in the network where frames being sent can possibly collide and cause errors.

**Switches** and **routers** divide up collision domains as they smartly control the flow of data. **Hubs** however do not have any sort of logic, and pass data around everywhere, it **expands** the collision domain.



## vLAN Tagging

The standard Ethernet frame header does not contain information about the VLAN to which the frame belongs.

To distinguish where a frame comes from among the VLANs, a **tag** is inserted into the frame header. This process is called tagging, it is accomplished by using the IEEE 802.1Q header standard.


Standard Ethernet					IEEE 802.1Q header					
Dst MAC	Src MAC	Type/Length	Data	FCS	Dst MAC	Src MAC	Tag	Type/Length	Data	FCS

## 802.1Q standard

The following fields are present in a tag

- **Type** - A 2-byte value called the tag protocol ID (TPID) value. For Ethernet, it is set to hexadecimal 0x8100.
- **User priority** - A 3-bit value that supports level or service implementation.

- **Canonical Format Identifier (CFI)** - A 1-bit identifier that enables Token Ring frames to be carried across Ethernet links.
- **VLAN ID (VID)** - A 12-bit VLAN identification number that supports up to 4096 VLAN IDs.




## Access ports and Trunk ports

### Purpose

Typically these tagged frames are sent over a trunk connection between switches.

**Access** ports are regular ports that switches will receive frames to forward to as usual.



**Trunk** ports are ports where traffic from different VLANs are expected to traverse.




## Dynamic trunking protocol

During configuration, you will find you can set the switch ports to not just **access** and **trunk**, but **dynamic auto** and **dynamic desirable**.

A Desirable mode switch will actively negotiate for trunk mode. The auto mode switch will go with anything its told. Trunk and access modes are static and having 2 switches with those different modes will result in a connection disruption.



\*Both switches are shy to talk, they ended up in access mode



\*The switches have a disagreement, connection is disrupted

## Native vLAN

Normally a native vLAN handles tagged frames to forward. But there are some situations that the 802.1Q protocol instructs to drop the frame.

### Same VID on the native vLAN

Generally traffic sent to the native vLAN should not be tagged. If the VID of the frame is the same as the native vLAN, the frame will be dropped.

### Untagged frames on the native vLAN

It is not unusual for the native vLAN to receive **untagged** frames.

When a trunk port receives untagged frames, it will forward it on the native vLAN. If there are no devices on the native vLAN and no other trunk ports on the vLAN, the frame is dropped.

## Voice vLAN

//todo

## Inter-vLAN routing


vLANs are used to segment switched Layer 2 networks for a variety of reasons. But Layer 2 switches can't really forward packets to different vLANs for hosts.

A Layer 3 router is needed to route to different VLANs.

3 Inter-vLAN options are:

1. **Legacy inter-vLAN routing**, its legacy so no
2. **Router-on-a-stick**, good for small to medium networks
3. **Layer 3 Switch Virtual Interface(SVI)**, good for medium to large networks


### Legacy inter-vLAN routing



In this routing method, we literally stick multiple cables from the switch to the router. Each port of the router is for one VLAN.

The problem becomes obvious when we try to scale up, at some point we will run out of ports in the routers.


### Router on a stick



The 'router-on-a-stick' inter-VLAN routing method overcomes the limitation of the legacy inter-VLAN routing method. It only requires one physical Ethernet interface to route traffic between multiple VLANs on a network.

Routers have **sub-interfaces** in one port interface, it allows you to configure multiple IP Addresses for each of the sub-interface. Effectively, serving as many default gateways in just one port.

## Layer 3 Switch SVI



The modern method of performing inter-VLAN routing is to use Layer 3 switches and switched virtual interfaces (SVI). An SVI is a virtual interface that is configured on a Layer 3 switch, as shown in the figure.

Layer 3 Switches can be thought of as both a switch and a router. It shares many commands between switches and router.

## Spanning tree protocol

The Spanning Tree Protocol (STP) is a protocol that allows for redundancy in connections while preventing loops or cycles in a layer 2 topology.

The Spanning tree is recalculated whenever a link or switch goes down, or whenever a switch is added.


Per-VLAN Spanning Tree (PVST) versions of STP support an instance of STP for every VLAN. So many switches may have the role of root bridge in different VLANs.

### The STP algorithm

#### About Bridge ID (BUID)

Fun fact, Switches used to be otherwise known as **bridges**, hence the relation.

Switches have a BUID to communicate with each other, in the STP algorithm, the BUID is a method used to elect the **root bridge**



Switches can exchange all this information through sending **Bridge Protocol Data Units (BPDUs)**.

## Bridge priority

This is the first number used to determine which switch becomes the root bridge. By default every switch starts off at **32768**. It can be changed anywhere from 0-61440 in increments of 4096 strictly.

## System ID

The extended system ID value is a decimal value added to the bridge priority value in the BID to identify the VLAN for this BPDU

## MAC Address

Eventually when the priority and system ID cant tie break the root bridge, the unique MAC address is used.

The switch having the MAC address with the lowest value, expressed in hexadecimal will win rights to become root bridge.

### Step 1: Elect the root bridge

The switches first have to decide a single switch to be the **root bridge**. It will be the reference point for path calculations when building the spanning tree.

The numbers they use to elect a root bridge follows below, from first to last resort:

1. Lowest Bridge priority + Sys ID
2. Lowest MAC Address

### Step 2: Elect Ports

Once the root bridge has been elected. SWwitches do a spanning tree calculation to find out the best path to the root bridge.

## Bandwidth path cost


Speed	STP IEEE 802.1D	RSTP IEEE 802.1w
<b>10 Gbps</b>	2	2,000
<b>1 Gbps</b>	4	20,000
100 Mbps	19	200,000
10 Mbps	100	2,000,000

Though these ports have a default cost, it could also be configured

## Electing root port

The **root port** is a port of a switch that eventually leads to the root bridge, the port chosen as a root port is usually the one with the lowest cost.

\*Assume every connection is a fast ethernet, so the cost is 19




In the diagram above, the root ports always have a path closest to the Root bridge. Paths that attempt to detour through another switch incur a high cost and thus aren't chosen and eventually blocked.

## Electing designated ports


The **root bridge** will turn all of its ports into **designated mode**.

For other non-root switches, ports not going toward the root bridge are **designated**. A pattern that tends to follow is that in a connection, if one side is **root**, it follows that the other is **designated**.




And for connections where both sides are **designated**, that means the path is redundant, eventually the switches will decide systematically one side to be **alternate** or **blocked**.

### Electing blocked ports



Choose the best path



Choose the lowest entire BID  
 $32769.1111.1111.1111 < 32769.5555.5555.5555$

When a switch has 2 paths, it will block the port with the higher path cost.

But when the costs are the same, the entire **BID** is the tie breaker instead. The switch will choose the port connecting to a switch with a lower BID as the root port, the other one gets blocked.

Note: When we say lowest BID, it is not different from comparing lowest Bridge priority and then Mac Address. The Bridge priority number is the most significant number, and so regardless of MAC, the lowest Bridge priority will always have the lowest overall BID.


## Electing blocked ports among multiple connections

So what if a switch has more than one connection.

First, block the more expensive path.

If they are equal, block the higher sender port priority.

And finally, if all that is equal, just resort to blocking the higher port ID.



## STP timers and port states

Recall that STP will recalculate the spanning tree whenever changes to the topology are made.

There are several timers in STP that determine how quickly the protocol reacts to changes in the network topology. These timers include:

1. Hello Time: The hello time is the amount of time between two BPDUs (Bridge Protocol Data Units) being sent out on a port. By default, the hello time is 2 seconds. But it can be changed from 1 to 10.
2. Forward Delay: The forward delay is the amount of time that a port stays in the listening and learning states before moving into the forwarding state. By default, the forward delay is 15 seconds. But it can be changed from 4 to 30.
3. Max Age: The max age is the amount of time that a switch will wait before changing the STP topology. By default, the max age is 20 seconds. Can be changed from 6 to 40.


That explains part of the phenomenon when you add switches in packet tracer and the connections are still down, only after a while they come back up.

Note: These default times are changed from the root bridge, which dictates the value of these timers for the STP domain.

So there's no need to configure the times for every switch.

Also, to avoid problems with STP. IEEE encourages keeping the network within 7 switches in diameter when using default timers.

## Port States



State	Description
Blocking	The port is an alternate port and does not participate in frame forwarding. A Switch port uses the Max Age timer to wait for a BPDU, if it does not receive, it will go into blocking mode
Listening	After blocking, the switch listens for BPDUs. It uses it to determine the path to the root.
Learning	After listening, the switch goes into learning mode. Here it processes the BPDUs and prepares to participate in forwarding. Here it also populates its MAC Address table.
Forwarding	The switch port is finally ready to forward frames. It operates as normal here

## Status activity


State	BPDU	MAC Table	Forward
Blocking	Receive		
Listening	Receive and send		

State	BPDU	MAC Table	Forward
Learning	Receive and send	Updating	
Fowarding	Receive and send	Updating	Yes
Administratively Down			

## RSTP and other alternatives of STP

RSTP (IEEE 802.1w) is the new protocol to supercede IEEE 802.1D STP. It is also backwards compatible.

### STP vs RSTP



## Portfast and BPDU Guard

Sometimes we have dedicated switch ports for end devices. It can be a pain to wait for the port to go online when you connect an end device.

**Portfast** removes the whole timer thingy, and the port immediately goes into fowarding mode. Not only that, it **will not send BPDUs**. So keep a port in portfast mode only if its for end devices.

BPDU Guard mode will causes the port to become in an error state when receiving any BPDUs. By shutting down the port, we prevent loops, later an admin must manually fix it.


## Alternatives to STP

//todo

## Etherchannel

## A Port Channel

EtherChannel is originally developed by Cisco as a way to group multiple redundant connections into a single **port channel**. This allows to make use of redundant connections where normally the STP would have blocked it to avoid bridge loops.



Since the port channel is treated as a regular link. When a link in the inner channel goes down, STP will not require recalculation as the other redundant links can still carry data.

## Caveats

You **cannot** mix different port types together into a port channel. A port channel cannot have both Gigabit Ethernet and Fast Ethernet. The etherchannel can group 8 identical ports together.

Like trunking, the etherchannel on the other switch must be configured the same way. Same trunk mode, vlan, duplex, speed, etc.

## LACP and PAgP Protocol

There are 2 protocols for switches to negotiate etherchannels. LACP and PAgP.

Switches using the LACP can have 3 modes:

- On:** *Dont negotiate at all and assume LACP, otherside must be strictly on to establish*
- Desirable:** *Initiates negotiation and sends LACP packets*
- Auto:** *Passively respond to LACP packets for negotiating*

Switches using the PAgP can have 3 modes:

- On:** *Dont negotiate at all and assume PAgP, otherside must be strictly on to establish*
- LACP active :** *Initiates negotiation and sends PAgP packets*
- LACP passive:** *Passively respond to PAgP packets for negotiating*

To explain in other words, the whole deal with Desirable and auto is a matter of deciding consent. They are similar to how trunking is negotiated with DTP. However oddly in here, when one switch is **on**, even if the other switch is in a passive or auto state, the channel will not be established. In DTP, one switch can be in trunking mode, and the other can be auto or desirable and trunking is established.

## Protocol outcomes

### PAgP Modes

Switch 1	Switch 2	Channel establishment
On	On	Yes

Switch 1	Switch 2	Channel establishment
On	Desirable	No
On	Auto	No
Desirable	Desirable	Yes
Desirable	Auto	Yes
Auto	Desirable	Yes
Auto	Auto	No

### LACP Modes

Switch 1	Switch 2	Channel establishment
On	On	Yes
On	Passive	No
On	Active	No
Active	Active	Yes
Active	Passive	Yes
Passive	Active	Yes
Passive	Passive	No

LACP and PAgP behave identically.

First Hop Redundancy Protocol //todo



You have reached the end