A Quick Guide for the pbdNCDF4 Package (Ver. 0.1-3)

Pragneshkumar Patel¹, George Ostrouchov^{1,2}, Wei-Chen Chen³, Drew Schmidt¹, David Pierce⁴

> ¹National Institute for Computational Sciences, University of Tennessee, Knoxville, TN, USA

> ²Computer Science and Mathematics Division, Oak Ridge National Laboratory, Oak Ridge, TN, USA

³Department of Ecology and Evolutionary Biology, University of Tennessee, Knoxville, TN, USA

> ⁴Climate Research Division, Scripps Institution of Oceanography, UC San Diego, San Diago, CA, USA

Contents

Acknowledgement		iii	
1.	Introduction	1	
	1.1. System Requirements	1	
	1.2. Installation	2	
	1.3. A Quick Example	2	
2.	Non-Standard System Installations	3	
	2.1. Special Path for NetCDF4	3	
	2.2. Parallel HDF5 and NetCDF4	4	
3.	Collective I/O of pbdNCDF4	4	
4.	Windows System	5	
	4.1. Install from Binary	6	
	4.2. Build from Source	6	
	4.3. Detail Steps	7	
D.	oforonaga	0	

 \bigodot 2012-2014 pbdR Core Team.

Permission is granted to make and distribute verbatim copies of this vignette and its source provided the copyright notice and this permission notice are preserved on all copies. This publication was typeset using LATEX.

Acknowledgement

Patel, Ostrouchov, and Schmidt were supported in part by the project "NICS Remote Data Analysis and Visualization Center" funded by the Office of Cyberinfrastructure of the U.S. National Science Foundation under Award No. ARRA-NSF-OCI-0906324 for NICS-RDAV center. Ostrouchov and Chen were supported in part by the project "Visual Data Exploration and Analysis of Ultra-large Climate Data" funded by U.S. DOE Office of Science under Contract No. DE-AC05-00OR22725.

Chen was supported in part by the Department of Ecology and Evolutionary Biology at the University of Tennessee, Knoxville, and a grant from the National Science Foundation (MCB-1120370.)

This work used resources of National Institute for Computational Sciences at the University of Tennessee, Knoxville, which is supported by the Office of Cyberinfrastructure of the U.S. National Science Foundation under Award No. ARRA-NSF-OCI-0906324 for NICS-RDAV center. This work also used resources of the Oak Ridge Leadership Computing Facility at the Oak Ridge National Laboratory, which is supported by the Office of Science of the U.S. Department of Energy under Contract No. DE-AC05-00OR22725. This work used resources of the Newton HPC Program at the University of Tennessee, Knoxville.

We also thank Brian D. Ripley, Kurt Hornik, Uwe Ligges, and Simon Urbanek from the R Core Team for discussing package release issues and helping us solve portability problems on different platforms.

Warning: The findings and conclusions in this article have not been formally disseminated by the U.S. Department of Energy and should not be construed to represent any determination or policy of University, Agency and National Laboratory.

This document is written to explain the main functions of pbdNCDF4 (Ostrouchov et al. 2012), version 0.1-3. Every effort will be made to ensure future versions are consistent with these instructions, but features in later versions may not be explained in this document.

Information about the functionality of this package, and any changes in future versions can be found on website: http://r-pbd.org/.

1. Introduction

The pbdNCDF4 package is an interface to the parallel NetCDF4 library (NetCDF Group 2008) hosted by the Unidata program at the University Corporation for Atmospheric Research (UCAR). The package also requires the parallel HDF5 library (HDF Group 2000-2010) originally developed at the National Center for Supercomputing Applications. Full details about the system requirements and installation instructions for pbdNCDF4 are provided in the following section.

The pbdNCDF4 package is fully based on, and incorporates, the ncdf4 package, version 1.8 by David Pierce (Pierce 2012).

Warning: We have success for installing and passing tests by using the following combinations:

- HDF5-1.8.5 and NetCDF-4.1.1,
- HDF5-1.8.8 and NetCDF-4.2.0, or
- HDF5-1.8.11 and NetCDF-4.3.0.

Other versions may have parallel I/O problems even installation is correct.

1.1. System Requirements

Before installing the **pbdNCDF4** package, there is some software which must first be installed on the user's system. Additionally, **pbdNCDF4** requires the **pbdMPI** (Chen et al. 2012a) package, which itself requires some of the same dependencies that **pbdNCDF4** requires, so you are encouraged to install **pbdMPI** first. See the **pbdMPI** vignette (Chen et al. 2012b) for full details on how to install it and its dependencies.

In order to install the **pbdNCDF4** package, you must first have system installations of:

- 1. An MPI library (openmpi, mpich2, ...). This is also required by **pbdMPI**.
- 2. HDF5 (version 1.8.5) http://www.hdfgroup.org/HDF5
- 3. NetCDF4 (version 4.1.1) http://www.unidata.ucar.edu/software/netcdf/

Ideally, the user needs to install the parallel versions of the HDF5 and NetCDF4 libraries, and in such case, these libraries should be compiled with MPI. The pbdNCDF4 package functions with serial installations of these libraries, but then only serial reading is possible, obviously. In the event that the parallel versions of the HDF5 and NetCDF4 libraries are not available, **pbdNCDF4** acts as **ncdf4**. See Section 3 for details.

1.2. Installation

The remaining assumes that **pbdMPI** is installed correctly. If **pbdMPI** is not yet installed, see the **pbdMPI** vignette for installation details. We also assume nc-config, a NetCDF4 utility which provides information about installation of NetCDF4 library, is in the user's PATH. See Section 2.1 for non-default installation if nc-config is not in the user's PATH.

Users can download **pbdNCDF4** from CRAN at http://cran.r-project.org, and the installation can be done with the following commands from the shell:

Shell Command

```
tar zxvf pbdNCDF4_0.1-0.tar.gz
R CMD INSTALL pbdNCDF4 --configure-args="--enable-parallel"
```

Note that without the flag <code>-configure-args="-enable-parallel"</code>, <code>pbdNCDF4</code> compiles with NCDF4 and HDF5 in serial. In this case, it is essentially the same as the <code>ncdf4</code> package. The extra parallel-enable R functions to <code>ncdf4</code> such as <code>nc_create_par</code>, <code>nc_open_par</code>, and <code>nc_var_par_access</code> behave as their serial counterparts. The same R code with <code>pbdNCDF4</code> can run either serial or parallel depending on the configuration used. See Section 3 for details.

1.3. A Quick Example

Users can get started quickly with **pbdNCDF4** by learning from the following two examples. Issued from the shell:

Shell Command

```
### Under command mode, run the demo with 2 processors by
### (Use Rscript.exe for windows system)

mpiexec -np 2 Rscript -e "demo(ncwrite_par,'pbdNCDF4',ask=F,echo=F)"
mpiexec -np 2 Rscript -e "demo(ncread_par,'pbdNCDF4',ask=F,echo=F)"
ncdump test_par.nc
```

The examples first write a file test_par.nc, then read it back in and print the results.

In this example, each processor writes a 4×5 column-major matrix (an 8×5 matrix in total). If the demos run successfully, the user can see the following output:

Output of ncread

```
COMM.RANK = 0
n = 8 p = 5
COMM.RANK = O
     [,1] [,2] [,3] [,4] [,5]
[1,]
[2,]
         2
              3
                    4
                          5
                                6
         2
              3
                          5
                                6
[3,]
                    4
         2
              3
                          5
[4,]
```

```
COMM.RANK = 1
      [,1]
            [,2]
                   [,3] [,4] [,5]
[1,]
          3
                      5
                             6
          3
                4
                      5
                             6
                                   7
[2,]
          3
                4
                       5
                             6
                                   7
[3,]
[4,]
          3
                       5
                                   7
```

Note that NetCDF4 stores data in row-major fashion as in the C programming language. Above the data is represented in column-major fashion, as is used by R. Also, users can use the shell command ncdump (as in the third demo), a NetCDF4 utility, to show the exact contents of the test_par.nc file.

Output of ncdump

```
netcdf test_par {
dimensions:
        rows = 8;
        columns = 5;
variables:
        int rows(rows);
                rows:units = "number";
                rows:long_name = "rows" ;
        int columns(columns);
                columns:units = "number" ;
                columns:long_name = "columns";
        int testMatrix(columns, rows);
                testMatrix:units = "count"
                testMatrix:_FillValue = -1 ;
data:
rows = 1, 2, 3, 4, 5, 6, 7, 8;
columns = 1, 2, 3, 4, 5;
testMatrix =
 2, 2, 2, 2, 3, 3, 3, 3,
 3, 3, 3, 4, 4, 4, 4,
 4, 4, 4, 4, 5, 5, 5, 5,
 5, 5, 5, 5, 6, 6, 6, 6,
 6, 6, 6, 6, 7, 7, 7, 7;
```

Above, data are shown in the C, or row-major way.

2. Non-Standard System Installations

In this section we discuss a non-default method of installation for pbdNCDF4, as well as compiling the HDF5 and NetCDF4 libraries in parallel.

2.1. Special Path for NetCDF4

As the with the ncdf4 package, pbdNCDF4 allows special configuration for nc-config via the flag --with-nc_config. For example, we might issue the command:

Shell Command

```
R CMD INSTALL pbdNCDF4 \
--configure-args="--with-nc-config=/usr/local/netcdf4/bin"
```

which specifies that nc-config is in the directory /usr/local/netcdf4/bin.

2.2. Parallel HDF5 and NetCDF4

Here we assume that the MPI headers are in /usr/include/mpi and the MPI libraries are in /usr/lib.

We can install HDF5 with parallel I/O via:

Compile parallel HDF5

```
./configure \
    --prefix=/usr/local/hdf5 \
    --enable-parallel \
    --enable-shared \
    CC="mpicc -g" \
    CFLAGS="-fPIC -I/usr/include/mpi" \
    CPPFLAGS="-fPIC -I/usr/include/mpi" \
    LDFLAGS="-L/usr/lib -lmpi"
make
make install
```

For parallel NetCDF4, suppose that the parallel HDF5 library is installed in /usr/local/hdf5. Then we can install NetCDF4 with parallel I/O via:

Compile parallel NetCDF4

```
./configure \
    --prefix=/usr/local/netcdf4 \
    --enable-netcdf4 \
    --enable-shared \
    CC="mpicc -g" \
    CFLAGS="-fPIC -I/usr/include/mpi -I/usr/local/hdf5/include" \
    CPPFLAGS="-fPIC -I/usr/include/mpi -I/usr/local/hdf5/include" \
    LDFLAGS="-L/usr/lib -lmpi -L/usr/local/hdf5/lib -lhdf5"
make
make install
```

3. Collective I/O of pbdNCDF4

There are mainly three parallel functions added to **pbdNCDF4** over **ncdf4**, which enable collective I/O. Namely, we include the R functions nc_create_par(), nc_open_par(), and nc_var_par_access().

- nc_create_par() is similar to nc_create() in ncdf4, but creates a NetCDF4 file with parallel format.
- nc_open_par() is similar to nc_open() in ncdf4, but is specifically for files in the parallel
- nc_var_par_access() is used to tell the NetCDF4 library to use collective read or write for the given variable.

By default, nc_var_par_access() sets collective=TRUE, which turns on collective read and write for the given variable. If nc_var_par_access() is not called or collective=FALSE is set, then the independent method will be used.

If parallel versions of HDF5 and NetCDF4 libraries are not available or --enable-parallel is not set when compiling pbdNCDF4, then user needs to use the original ncdf4 functions such as nc_create and nc_open. For reading in parallel, it will be a little bit slower than collective reading. However, the serial version should not be used for parallel writing unless manual synchronization is used.

We can run the serial example as in the Section 1.3 next without parallel read and write capabilities. Suppose serial HDF5 and NetCDF4 are compiled and pbdNCDF4 is installed without the enable parallel flag --enable-parallel.

Shell Command

```
### Under command mode, run the demo with 2 processors by
### (Use Rscript.exe for windows system)
mpiexec -np 2 Rscript -e "demo(ncwrite_ser, 'pbdNCDF4', ask=F, echo=F)"
mpiexec -np 2 Rscript -e "demo(ncread_ser, 'pbdNCDF4', ask=F, echo=F)"
```

The first demo() uses two processors and independently writes to the file test_ser.nc in order to generate the same matrix, while the second demo reads back in and print the matrix in serial. The outputs are exactly the same as the parallel version. Note that the first demo ncwrite_ser provides an example of manual synchronization, see the source code for details.

4. Windows System

Windows system has serial HDF5 and NetCDF4 libraries available in both 32- and 64-bit systems. The pre-built (netCDF-C) libraries can be downloaded from http://www.unidata. ucar.edu/software/netcdf/docs/winbin.html. For example, the stable release (netCDF-**C 4.3.2**) has

- 32-bit library at http://www.unidata.ucar.edu/netcdf/win_netcdf/netCDF4.3.2-NC4-32.exe, and
- 64 bit library at http://www.unidata.ucar.edu/netcdf/win_netcdf/netCDF4.3.2-NC4-64.exe.

Note that both pre-built libraries contain HDF5 and NetCDF4 serial versions and can be directly linked and loaded with **pbdNCDF4** inside R.

All required *.dll files are via dyn.load() in .onLoad() at run time, and via dyn.unload() in .onUnload() when quiting the package.

With a few click on both *.exe files, we suggest users to install at the system directory

- C:/Program Files (x86)/netCDF 4.3.2/ for the 32-bit library, and
- C:/Program Files/netCDF 4.3.2/ for the 64-bit library.

Note that the default for 32-bit may be the same as 64-bit, so do the change manually since they can not be merged in general.

4.1. Install from Binary

The binary packages of **pbdNCDF4** are available on the website: "Programming with Big Data in R" at http://r-pbd.org/. The binary can be installed by

Shell Command

```
R CMD INSTALL pbdNCDF4_0.1-3.zip
```

As in Unix systems, one can start quickly with **pbdNCDF4** by learning from the following demos. There are two basic examples in serial.

Shell Command

```
demo(ncwrite_ser, 'pbdNCDF4', ask=F, echo=F)
demo(ncread_ser, 'pbdNCDF4', ask=F, echo=F)
```

4.2. Build from Source

Installation of **pbdNCDF4** in windows system requires users to set environment variables NETCDF4_ROOT_32 and NETCDF4_ROOT_64 for both pre-built libraries. By default, we suggest

Shell Command

```
### Under command mode, or save in a batch file.
SET NETCDF4_ROOT_32=C:\Program Files (x86)\netCDF 4.3.2\
SET NETCDF4_ROOT_64=C:\Program Files\netCDF 4.3.2\
SET NETCDF4_ROOT=%NETCDF4_ROOT_64%

SET R_HOME=C:\Program Files\R\R-3.0.1\
SET RTOOLS=C:\Rtools\bin\
SET MINGW=C:\Rtools\gcc-4.6.3\bin\
SET PATH=%R_HOME%;%R_HOME%bin\;%RTOOLS%;%MINGW%;%PATH%
SET PATH=%NETCDF4_ROOT%bin\;%PATH%
```

Here, we use 64-bit system for testing and set the bin directory to PATH, then some utilities such as ncdump.exe can be tested and used in pbdNCDF4.

With a correct PATH, one can use the R commands to install/build the pbdNCDF4:

Shell Command

```
### Under command mode, build and install the binary.
tar zxvf pbdNCDF4_0.1-3.tar.gz
R CMD INSTALL --build pbdNCDF4
R CMD INSTALL pbdNCDF4_0.1-3.zip
```

4.3. Detail Steps

The steps of building **pbdNCDF4** in Windwos are described next:

- 1. At configure time, I take NETCDF4_ROOT_32 and NETCDF4_ROOT_64 from environment variables, then set NETCDF4_ROOT according to architecture.
- 2. Before compile time, I check if the directories exists. If not, then I will set NETCDF4_LINKED = FALSE and feed a fake a.c to build a fake library in order to pass R CMD check. Note that this will eventually cause crashes at run time, so please check out pbdNCDF4 binary from thirteen-01 or dropbox.
- 3. At compile time, I save NETCDF4_ROOT_32, NETCDF4_ROOT_64, and NETCDF4_ROOT in pbdNCDF4/etc/i386/Makeconf and pbdNCDF4/etc/x64/Makeconf.
- 4. At installation time, both files will be copied to

```
C:/Program Files/R/R-3.0.1/library/pbdNCDF4/...,
```

with built *.dll and others. Then, pbdNCDF4/R/windows/zzz.R will be copied to pbdNCDF4/R/zzz.R to finish compiling R codes.

- 5. At load time, .onLoad() of pbdNCDF4/R/windows/zzz.R will obtain NETCDF4_ROOT_32, NETCDF4_ROOT_64, and NETCDFR_ROOT from system environment variables via Sys.getenv() first.
- 6. If environment variables were unavailable, .onLoad() will obtain them from corresponding Makeconf.
- 7. At run time, if none of *.dll were available or NETCDF4_LINKED = FALSE, then I would cast warnings. Note that any pbdNCDF4 function evokes .C() function may cause crashes in this case.

In order to load **pbdNCDF4** correctly in windows, there are several ways can solve the problem:

- There are at least two ways to avoid dynamic file loading problems if any. Either change the Makeconf files to the personal/new installation of netCDF-C or change environment variables.
- There are also at least two ways to set environment variables in windows, either from system "Control Panel" or use batch file.
- Further, inside R, Sys.setenv() can be used to set environment variables in run time.

References

- Chen WC, Ostrouchov G, Schmidt D, Patel P, Yu H (2012a). "pbdMPI: Programming with Big Data Interface to MPI." R Package, URL http://cran.r-project.org/package=pbdMPI.
- Chen WC, Ostrouchov G, Schmidt D, Patel P, Yu H (2012b). "A Quick Guide for the pbdMPI package." R Vignette, URL http://cran.r-project.org/package=pbdMPI.
- HDF Group (2000-2010). "Hierarchical data format version 5." Software package, URL http://www.hdfgroup.org/HDF5.
- NetCDF Group (2008). "Network Common Data Form." Software package, URL http://www.unidata.ucar.edu/software/netcdf/.
- Ostrouchov G, Patel P, Chen WC, Schmidt D, Pierce D (2012). "pbdNCDF4: Programming with Big Data Interface to Parallel Unidata NetCDF4 Format Data Files." R Package, URL http://cran.r-project.org/package=pbdNCDF4.
- Pierce D (2012). "ncdf4: Interface to Unidata netCDF (version 4 or earlier) format data files." R package, URL http://CRAN.R-project.org/package=ncdf4.