Standalones and HVMs

13-17 minutes : 10/17/2024

A standalone is a type of qube that is created by cloning a template. Unlike templates, however, standalones do not supply their root filesystems to other qubes. Examples of situations in which standalones can be useful include:

- Qubes used for development (dev environments often require a lot of specific packages and tools)
- Qubes used for installing untrusted packages. Normally, you install digitally signed software from Red Hat/Fedora repositories, and it's reasonable that such software has non malicious *installation* scripts (rpm pre/post scripts). However, when you would like to install some packages from less trusted sources, or unsigned, then using a dedicated (untrusted) standalone might be a better way.

Meanwhile, a Hardware-assisted Virtual Machine (HVM), also known as a "Fully-Virtualized Virtual Machine," utilizes the virtualization extensions of the host CPU. These are typically contrasted with Paravirtualized (PV) VMs.

HVMs allow you to create qubes based on any OS for which you have an installation ISO, so you can easily have qubes running Windows, *BSD, or any Linux distribution. You can also use HVMs to run "live" distros.

By default, every qube runs in PVH mode (which has security advantages over both PV and HVM), except for those with attached PCI devices, which run in HVM mode. See here for a discussion of the switch from PV to HVM and here for the announcement about the change to using PVH as default.

The standalone/template distinction and the HVM/PV/PVH distinctions are orthogonal. The former is about root filesystem inheritance, whereas the latter is about the virtualization mode. In practice, however, it is most common for standalones to be HVMs and for HVMs to be standalones. Hence, this page covers both topics.

Creating a standalone

You can create a standalone in the Qube Manager by selecting the "Type" of "Standalone qube copied from a template" or "Empty standalone qube (install your own OS)."

Alternatively, to create an empty standalone from the dom0 command line:

```
qvm-create --class StandaloneVM --label <YOUR_COLOR> --property
virt_mode=hvm <NEW_STANDALONE_NAME>
```

Or to create a standalone copied from a template:

```
qvm-create --class StandaloneVM --label <YOUR_COLOR> --property
virt_mode=hvm --template <TEMPLATE_QUBE_NAME> <NEW_STANDALONE_NAME>
```

Notes:

- Technically, virt_mode=hvm is not necessary for every standalone. However, it is needed if you want to use a kernel from within the gube.
- If you want to make software installed in a template available in your standalone, pass in the name of the template using the --template option.

Updating standalones

When you create a standalone from a template, the standalone is a complete clone of the template, including the entire filesystem. After the moment of creation, the standalone becomes completely independent from the template. Therefore, the standalone will not be updated merely by updating the template from which it was originally cloned. Rather, it must be updated as an independent qube. See How to Update.

Creating an HVM

Using the GUI

In Qube Manager, select "Create new qube" from the Qube menu, or select the "Create a new qube" button. In the "create new qube" dialog box set Type to "Empty standalone qube (install your own OS)". If "install system from device" is selected (which it is by default), then virt_mode will be set to hvm automatically. Otherwise, open the newly-created qube's Settings GUI and, in the "Advanced" tab, select HVM in the virtualization mode drop-down list. Also, make sure "Kernel" is set to (none) on the same tab.

Command line

Qubes are template-based (i.e., app qubes by default, so you must set the --class StandaloneVM option to create a standalone. The name and label color used below are for illustration purposes.

```
qvm-create my-new-vm --class StandaloneVM --property virt_mode=hvm --
property kernel='' --label=green
```

If you receive an error like this one, then you must first enable VT-x in your BIOS:

```
libvirt.libvirtError: invalid argument: could not find capabilities for
arch=x86_64
```

Make sure that you give the new qube adequate memory to install and run.

Installing an OS in an HVM

You will have to boot the qube with the installation media "attached" to it. You may either use the GUI or use command line instructions. At the command line you can do this in three ways:

1. If you have the physical CD-ROM media and an optical disc drive:

```
qvm-start <YOUR_HVM> --cdrom=/dev/cdrom
```

2. If you have an ISO image of the installation media located in dom0:

```
qvm-start <YOUR_HVM> --cdrom=dom0:/usr/local/iso/
<YOUR_INSTALLER.ISO>
```

3. If you have an ISO image of the installation media located in a qube (the qube where the media is located must be running):

```
qvm-start <YOUR_HVM> --cdrom=<YOUR_OTHER_QUBE>:/home/user/
<YOUR_INSTALLER.ISO>
```

For security reasons, you should *never* copy untrusted data to dom0.

Next, the qube will start booting from the attached installation media, and you can start installation. Whenever the installer wants to "reboot the system" it actually shuts down the qube, and Qubes won't automatically start it. You may have to restart the qube several times in order to complete installation (as is the case with Windows 7 installations). Several invocations of the qvm-start command (as shown above) might be needed.

Setting up networking for HVMs


Just like standard app qubes, an HVM gets a fixed IP addresses centrally assigned by Qubes. Normally, Qubes agent scripts (or services on Windows) running within each app qube are responsible for setting up networking within the qube according to the configuration created by Qubes (through keys exposed by dom0 to the qube). Such centrally-managed networking infrastructure allows for advanced networking configurations.

A generic HVM such as a standard Windows or Ubuntu installation, however, has no Qubes agent scripts running inside it initially and thus requires manual configuration of networking so that it matches the values assigned by Qubes.

Even though we do have a small DHCP server that runs inside the HVM's untrusted stub domain to make the manual network configuration unnecessary for many qubes, this won't work for most modern Linux distributions, which contain Xen networking PV drivers (but not Qubes tools), which bypass the stub-domain networking. (Their net frontends connect directly to the net backend in the net qube.) In this instance, our DHCP server is not useful.

In order to manually configure networking in a qube, one should first find out the IP/netmask/gateway assigned to the particular qube by Qubes. This can be seen, e.g., in the Qube Manager in the qube's

properties:



Alternatively, one can use the qvm-1s -n command to obtain the same information (IP/netmask/gateway).

The DNS IP addresses are 10.139.1.1 and 10.139.1.2. There is opt-in support for IPv6 forwarding.

Using template-based HVMs

Qubes allows HVMs to share a common root filesystem from a select template. This mode can be used for any HVM (e.g., FreeBSD running in an HVM).

In order to create an HVM template, you use the following command, suitably adapted:

```
qvm-create --class TemplateVM <YOUR_HVM_TEMPLATE_NAME> --property
virt_mode=HVM --property kernel='' -1 <YOUR_COLOR>
```

Set memory as appropriate and install the OS into this template in the same way you would install it into a normal HVM. Generally, you should install in to the first "system" disk. (Resize it as needed before starting installation.)

You can then create a new qube using the new template. If you use this Template as is, then any HVMs based on it will effectively be disposables. All file system changes will be wiped when the HVM is shut down.

Please see this page for specific advice on installing and using Windows-based templates.

Cloning HVMs

Just like normal app qubes, HVMs can also be cloned either using the command qvm-clone or via the Qube Manager's "Clone VM" option in the right-click menu.

The cloned qube will get identical root and private images and will essentially be identical to the original qube, except that it will get a different MAC address for the networking interface:

```
[joanna@dom0 ~]$ qvm-prefs my-new-vm
autostart
                   D False
backup timestamp
                   U
                   D False
debug
default_dispvm
                   D None
default_user
                   D user
gateway
                   D
gateway6
                   D
include_in_backups
                      False
installed_by_rpm
                   D False
                   D 10.137.0.122
ip
ip6
                   D fd09:24ef:4179::a89:7a
kernel
kernelopts
                   D nopat
klass
                   D StandaloneVM
label
                      red
                   D
                     00:16:3e:5e:6c:00
mac
management_dispvm
                      default-mgmt-dvm
                   D
maxmem
                    D
                      0
                      1000
memory
                      my-new-vm
name
netvm
                      sys-firewall
                   - False
provides_network
                      122
qid
grexec_timeout
                   D 60
shutdown_timeout
                      60
                   D
start time
                   D
stubdom_mem
                   U
stubdom xid
                   D -1
updateable
                   D True
uuid
                       54387f94-8617-46b0-8806-0c18bc387f34
                   D 2
vcpus
virt_mode
                      hvm
visible_gateway D 10.137.0.14
```

```
visible_gateway6
                   D fd09:24ef:4179::a89:e
visible ip
                    D 10.137.0.122
visible_ip6
                   D fd09:24ef:4179::a89:7a
visible_netmask
                   D 255.255.255.255
xid
                   D -1
[joanna@dom0 ~]$ qvm-clone my-new-vm my-new-vm-copy
/.../
[joanna@dom0 ~]$ qvm-prefs my-new-vm-copy
autostart
                    D
                      False
backup_timestamp
                      False
debug
default_dispvm
                   D None
default user
                   D user
gateway
                   D
gateway6
                    D
include_in_backups
                       False
installed_by_rpm
                   D False
ip
                    D 10.137.0.137
ip6
                    D fd09:24ef:4179::a89:89
kernel
kernelopts
                   D nopat
                    D StandaloneVM
klass
label
                       red
                      00:16:3e:5e:6c:00
mac
management_dispvm
                   D default-mgmt-dvm
                    D
                      0
maxmem
                      1000
memory
                      my-new-vm-copy
name
netvm
                      sys-firewall
provides_network
                       False
                       137
qid
qrexec_timeout
                      60
                   D
shutdown_timeout
                      60
                   D
start time
                    D
stubdom_mem
                   U
stubdom_xid
                    D -1
updateable
                      True
uuid
                      9ad109a9-d95a-4e03-b977-592f8424f42b
                    D
                      2
vcpus
virt mode
                      hvm
visible_gateway
                   D 10.137.0.14
visible_gateway6
                   D fd09:24ef:4179::a89:e
visible_ip
                   D 10.137.0.137
                   D fd09:24ef:4179::a89:89
visible_ip6
visible_netmask
                   D 255.255.255.255
```

xid D -1

Note that the MAC addresses differ between those two otherwise identical qubes. The IP addresses assigned by Qubes will also be different, of course, to allow networking to function properly:


If, for any reason, you would like to make sure that the two qubes have the same MAC address, you can use qvm-prefs to set a fixed MAC address:

[joanna@dom0 ~]\$ qvm-prefs my-new-vm-copy -s mac 00:16:3E:5E:6C:05 [joanna@dom0 ~]\$ qvm-prefs my-new-vm-copy name : my-new-vm-copy label : green : HVM type : firewallvm netvm : True updateable? installed by RPM? : False include in backups: False dir : /var/lib/qubes/appvms/my-new-vm-copy config : /var/lib/qubes/appvms/my-new-vm-copy/my-new-vmcopy.conf pcidevs : [] : /var/lib/qubes/appvms/my-new-vm-copy/root.img root img private img : /var/lib/qubes/appvms/my-new-vm-copy/private.img : 4 vcpus memory : 512 : 512 maxmem MAC : 00:16:3E:5E:6C:05 : off debug default user : user qrexec_installed : False qrexec timeout : 60 drive : None : localtime timezone

Assigning PCI devices to HVMs

HVMs (including Windows qubes) can be assigned PCI devices just like normal app qubes. For example, you can assign a USB controller to a Windows qube, and you should be able to use various devices that require Windows software, such as phones, electronic devices that are configured via FTDI, etc.

One problem at the moment, however, is that after the whole system gets suspended into S3 sleep and subsequently resumed, some attached devices may stop working and should be restarted within the qube. This can be achieved under a Windows HVM by opening the Device Manager, selecting the actual device (such as a USB controller), 'Disabling' the device, and then 'Enabling' the device again. This is illustrated in the screenshot below:



Converting VirtualBox VMs to Qubes HVMs

You can convert any VirtualBox VM to a Qubes HVM using this method.

For example, Microsoft provides free 90-day evaluation VirtualBox VMs for browser testing.

About 60 GB of disk space is required for conversion. Use an external hard drive if needed. The final root.img size is 40 GB.

In a Debian app gube, install gemu-utils and unzip:

sudo apt install qemu-utils unzip

In a Fedora app qube:

```
sudo dnf install qemu-img
```

Unzip VirtualBox zip file:

Extract OVA tar archive:

Convert vmdk to raw:

```
qemu-img convert -0 raw *.vmdk win10.raw
```

Copy the root image file from the originating qube (here called untrusted) to a temporary location in dom0, typing this in a dom0 terminal:

```
qvm-run --pass-io untrusted 'cat "/media/user/externalhd/win10.raw"' > /
home/user/win10-root.img
```

From within dom0, create a new HVM (here called win10) with the root image we just copied to dom0 (change the amount of RAM in GB as you wish):

```
qvm-create --property=virt_mode=hvm --property=memory=4096 --
property=kernel='' --label red --standalone --root-move-from /home/user/
win10-root.img win10
```

Start win10:

Optional ways to get more information

Filetype of OVA file:

List files of OVA tar archive:

List filetypes supported by qemu-img:

Further reading

Other documents related to HVMs:

- Windows VMs
- Linux HVM Tips