

Processs-in-Process (PiP)

2.0.0

Refernce Manual

January 17, 2021

Generated by Doxygen 1.8.5

Contents

1	Proc	ces-in-Process (PiP) Overview 1				
2	PiP (Comma	nds			9
	2.1	pipcc .				. 9
	2.2	pip-che	eck			. 9
	2.3	pip-exe	c			. 10
	2.4	pipfc .				. 10
	2.5	pip-ma	n			. 11
	2.6	pip-mo	de			. 11
	2.7					
	2.8	printpip	mode .			. 14
3		Functio	_	/Finalization		15 . 15
	3.1					
		3.1.1		Description		
		0.4.0	3.1.1.1	PiP Initialization/Finalization		
		3.1.2		Documentation		
			3.1.2.1	pip_init		
			3.1.2.2	pip_fin		
	3.2	Spawn	_	ask		
		3.2.1	Detailed	Description		
			3.2.1.1	PiP Spawnig PiP (ULP/BLT) task		. 18
		3.2.2	Function	Documentation		. 18
			3.2.2.1	pip_spawn_from_main		. 18
			3.2.2.2	pip_spawn_from_func		. 19
			3.2.2.3	pip_spawn_hook		. 20
			3.2.2.4	pip_task_spawn		. 21
			3.2.2.5	pip_spawn		. 22
	3.3	Export	Import Fu	unctions		. 23
		3.3.1	•	Description		
			3.3.1.1	PiP Export and Import		
		3.3.2	Function	Documentation		
			3.3.2.1	pip named export		
			3.3.2.2	pip_named_import		
			3.3.2.3	pip named tryimport		
			3.3.2.4	pip export		
			3.3.2.5	pip_import		
			3.3.2.6	pip_set_aux		
			3.3.2.7			
	2.4	Moiting		pip_get_aux		
	3.4	3.4.1	g for PiP task termination			
		3.4.1		•		
		0.4.0	3.4.1.1	Waiting for PiP task termination		
		3.4.2		Documentation		
			3.4.2.1	pip_wait		
			3.4.2.2	pip_trywait		
			3423	nin wait any		30

iv CONTENTS

		3.4.2.4 pip_trywait_any	31
3.5	PiP Qu	ery Functions	32
	3.5.1	Detailed Description	32
		3.5.1.1 PiP Query functions	32
	3.5.2	Function Documentation	32
		3.5.2.1 pip_get_pipid	32
		3.5.2.2 pip_is_initialized	33
		3.5.2.3 pip_get_ntasks	33
		3.5.2.4 pip_get_mode	34
		3.5.2.5 pip_get_mode_str	34
		3.5.2.6 pip_get_system_id	35
		3.5.2.7 pip_isa_root	35
		3.5.2.8 pip_isa_task	36
		3.5.2.9 pip_is_threaded	36
		3.5.2.10 pip is shared fd	36
3.6	PiP tas	k termination	37
	3.6.1	Detailed Description	37
			37
	3.6.2	Function Documentation	37
		3.6.2.1 pip exit	37
		3.6.2.2 pip kill all tasks	38
		3.6.2.3 pip_abort	38
		3.6.2.4 pip kill	39
3.7	PiP Sig	ganling Functions	39
	3.7.1	Detailed Description	39
		3.7.1.1 PiP signaling functions	39
	3.7.2		39
		3.7.2.1 pip sigmask	39
		3.7.2.2 pip signal wait	40
3.8	PiP Sy	nchronization Functions	41
	3.8.1	Detailed Description	41
			41
	3.8.2	Function Documentation	41
		3.8.2.1 pip yield	41
		3.8.2.2 pip_barrier_init	41
		11= =	42
		11= =	42

Index

44

Chapter 1

Proces-in-Process (PiP) Overview

Process-in-Process (PiP)

PiP is a user-level library to have the best of the both worlds of multi-process and multi-thread parallel execution models. PiP allows a process to create sub-processes into the same virtual address space where the parent process runs. The parent process and sub-processes share the same address space, however, each process has its own variable set. So, each process runs independently from the other process. If some or all processes agree, then data owned by a process can be accessed by the other processes. Those processes share the same address space, just like pthreads, but each process has its own variables like the process execution model. Hereinafter, the parent process is called PiP process and sub-processes are called PiP tasks.

PiP Versions

Currently there are three PiP library versions:

- · Version 1 Deprecated
- · Version 2 Stable version
- Version 3 Stable version supporting BLT and ULP (experimental)

Unfortunately each version has unique ABI and there is no ABI compatibility among them. The functionality of PiP-v1 is almost the same with PiP-v2, however, PiP-v2's API is a subset of the PiP-v3's API. Hereafter **NN** denotes the PiP version number.

Bi-Level Thread (BLT, from v3)

PiP also provides new thread implementation named "Bi-Level Thread (BLT)", again, to take the best of two worlds, Kernel-Level Thread (KLT) and User-Level Thread (ULT) here. A BLT is a PiP task. When a PiP task is created it runs as a KLT. At any point the KLT can becomme a ULT by decoupling the associated kernel thread from the KLT. The decoupled kernel thread becommes idle. Later, the ULT can become KLT again by coupling with the kernel thread.

User-Level Process (ULP, from v3)

As described, PiP allows PiP tasks to share the same virtual address space. This mans that a PiP task can context-switch to the other PiP task at user-level. This is called User-Level Process where processes may be derived from the same program or different programs. Threads basically share most of the kernel resources, such as address space, file descriptors, a process id, and so on whilst processes do not. Every process has its ows file descriptor

space, for example. When a ULP is scheduled by a KLT having PID 1000, then the getpid() is called by the U-LP returns 1000. Further, when the ULT is migrated to be scheduled by the other KLT, then the returned PID is different. So, when implemnting a ULP system, this systemcall consistency must be preserved. In ULP on PiP, the consistency can be maintained by utilizing the above BLT mechanism. When a ULT tries to call a system call, it is coupled with its kernel thread which was created at the beginning as a KLT. It should be note that Thread Local Storage (TLS) regions are also switched when switching ULP (and BLT) contexts.

Execution Mode

There are several PiP implementation modes which can be selected at the runtime. These implementations can be categorized into two;

- · Process and
- · (P)Thread.

In the pthread mode, although each PiP task has its own static variables unlike thread, PiP task behaves more like PThread, having a TID, having the same file descriptor space, having the same signal delivery semantics as Pthread does, and so on. In the process mode, a PiP task behaves more like a process, having a PID, having an independent file descriptor space, having the same signal delivery semantics as Linux process does, and so on. The above mentioned ULP can only work with the process mode.

When the **PIP_MODE** environment variable set to "()thread" then the PiP library runs in the pthread mode, and if it is set to "process" then it runs in the process mode. There are also three implementations in the process mode; "process:preload," "process:pipclone" and "process:got." The "process:preload" mode must be with the **LD_PRE-LOAD** environment variable setting so that the clone() system call wrapper can work with. The "process:pipclone" mode is only effective with the PIP-patched glibc library (see below).

Several function are made available by the PiP library to absorb the functional differences due to the execution modes.

License

This package is licensed under the 2-clause simplified BSD License - see the LICENSE file for details.

Installation

Basically PiP requires the following three software packages;

- PiP Process in Process (this package)
- PiP-Testsuite Testsuite for PiP
- PiP-glibc patched GNU libc for PiP
- PiP-gdb patched gdb to debug PiP root and PiP tasks.

By using PiP-glibc, users can create up to 300 PiP tasks which can be debugged by using PiP-gdb. In other words, without installing PiP-glibc, users can create up to around 10 PiP tasks (the number depends on the program) and cannot debug by using PiP-gdb.

There are several ways to install the PiP packages; Yum (RPM), Docker, Spack, and building from the source code. It is strongly recommended to use the following PiP package installation program (pip-pip):

• PiP-pip - PiP package installing program

This is the easiest way to install PiP packages in any form. Here is the example of pip-pip usage:

```
$ git clone https://github.com/RIKEN-SysSoft/PiP-pip.git
$ cd PiP-pip
$ ./pip-pip --how=HOW --pip=PIP_VERSION --work=BUILD_DIR --prefix=INSTALL_DIR
```

HOW can be one of yum, docker, spack and github, or any combination of them. pip-pip --help will show you how to use the program. yum, docker and spack include all three packages; PiP-glibc, PiP-lib, and PiP-gdb.

PiP Documents

The following PiP documents are created by using Doxygen.

Man pages

Man pages will be installed at PIP_INSTALL_DIR/share/man.

```
$ man -M PIP_INSTALL_DIR/share/man 7 libpip
```

Or, use the pip-man command (from v2).

```
$ PIP_INSTALL_DIR/bin/pip-man 7 libpip
```

The above two exammples will show you the same document you are reading.

PDF

PDF documents will be installed at PIP_INSTALL_DIR/share/pdf.

HTML

HTML documents will be installed at PIP_INSTALL_DIR/share/html.

Getting Started

Compile and link your PiP programs

• pipcc(1) command (since v2)

You can use pipcc(1) command to compile and link your PiP programs.

```
$ pipcc -Wall -O2 -g -c pip-prog.c
$ pipcc -Wall -O2 -g pip-prog.c -o pip-prog
```

Run your PiP programs

pip-exec(1) command (piprun(1) in PiP v1)

Let's assume that you have a non-PiP program(s) and wnat to run as PiP tasks. All you have to do is to compile your program by using the above pipcc(1) command and to use the pip-exec(1) command to run your program as PiP tasks.

```
$ pipcc myprog.c -o myprog
$ pip-exec -n 8 ./myprog
$ ./myprog
```

In this case, the pip-exec(1) command becomes the PiP root and your program runs as 8 PiP tasks. Note that the 'myprog.c' may or may not call any PiP functions. Your program can also run as a normal program (not as a PiP task) without using the pip-exec(1) command. In either case, your proghrams must be compiled and linked by using the pipcc(1) command described above.

You may write your own PiP programs which includes the PiP root programming. In this case, your program can run without using the pip-exec(1) command.

If you get the following message when you try to run your program;

```
PiP-ERR(19673) './myprog' is not PIE
```

Then this means that the 'myprog' (having PID 19673) is not compiled by using the pipcc(1) command properly. You may check if your program(s) can run as a PiP root and/or PiP task by using the pip-check(1) command (from v2);

```
$ pip-check a.out
a.out : Root&Task
```

Above example shows that the 'a.out' program can run as a PiP root and PiP tasks.

• pips(1) command (from v2)

Similar to the Linux ps command, you can see how your PiP program(s) is (are) running by using the pips (1) command. pips can accept 'a', 'u' and 'x' options just like the ps command.

```
$ pips [a][u][x] [PIPS-OPTIONS] [-] [PATTERN ..]
```

List the PiP tasks via the 'ps' command;

```
$ pips -ps [ PATTERN .. ]
```

or, show the activities of PiP tasks via the 'top' command;

```
$ pips –top [ PATTERN .. ]
```

Additionally you can kill all of your PiP tasks by using the same pips(1) command;

```
$ pips -s KILL [ PATTERN .. ]
```

Debugging your PiP programs by the pip-gdb command

The following procedure attaches all PiP tasks and PiP root which created those tasks. Each PiP task is treated as a GDB inferior in PiP-gdb. Note that PiP-glibc and PiP-gdb packages are required to do this.

```
$ pip-gdb
(pip-gdb) attach PID
```

The attached inferiors can be seen by the following GDB command:

```
(pip-gdb) info inferiors
Num Description Executable
4 process 6453 (pip 2) /somewhere/pip-task-2
3 process 6452 (pip 1) /somewhere/pip-task-1
2 process 6451 (pip 0) /somewhere/pip-task-0
* 1 process 6450 (pip root) /somewhere/pip-root
```

You can select and debug an inferior by the following GDB command:

```
(pip-gdb) inferior 2
[Switching to inferior 2 [process 6451 (pip 0)] (/somewhere/pip-task-0)]
```

When an already-attached program calls 'pip_spawn()' and becomes a PiP root task, the newly created PiP child tasks aren't attached automatically, but you can add empty inferiors and then attach the PiP child tasks to the inferiors. e.g.

```
.... type Control-Z to stop the root task.
Program received signal SIGTSTP, Stopped (user).
(pip-gdb) add-inferior
Added inferior 2
(pip-qdb) inferior 2
(pip-gdb) attach 1902
(pip-gdb) add-inferior
Added inferior 3
(pip-gdb) inferior 3
(pip-gdb) attach 1903
(pip-gdb) add-inferior
Added inferior 4
(pip-gdb) inferior 4
(pip-gdb) attach 1904
(pip-gdb) info inferiors
 Num Description
                                  Executable
      process 1904 (pip 2)
                                /somewhere/pip-task-2
      process 1903 (pip 1) /somewhere/pip-task-1
process 1902 (pip 0) /somewhere/pip-task-0
  3
  2
      process 1897 (pip root) /somewhere/pip-root
```

You can attach all relevant PiP tasks by:

```
$ pip-gdb -p PID-of-your-PiP-program
```

(from v2)

If the PIP_GDB_PATH environment is set to the path pointing to PiP-gdb executable file, then PiP-gdb is automatically attached when an excetion signal (SIGSEGV and SIGHUP by default) is delivered. The exception signals can also be defined by setting the PIP_GDB_SIGNALS environment. Signal names (case insensitive) can be concatenated by the '+' or '-' symbol. 'all' is reserved to specify most of the signals. For example, 'ALL-TERM' means all signals excepting SIGTERM, another example, 'PIPE+INT' means SIGPIPE and SIGINT. If one of the specified or default signals is delivered, then PiP-gdb will be attached automatically. The PiP-gdb will show backtrace by default. If users specify PIP_GDB_COMMAND, a filename containing some GDB commands, then those GDB commands will be executed by PiP-gdb in batch mode. If the PIP_STOP_ON_START environment is set, then the PiP library delivers SIGSTOP to a spawned PiP task which is about to start user program. If its value is a number in decimal, then the PiP task whose PiP-ID is the same with the specified number will be stopped. If the number is minus, then all PiP tasks will be stopped at the very beginning. Do not forget to compile your programs with a debug option.

Mailing List

```
pip@ml.riken.jp
```

Publications

Research papers

Atsushi Hori, Min Si, Balazs Gerofi, Masamichi Takagi, Jay Dayal, Pavan Balaji, and Yutaka Ishikawa. "Process-in-process: techniques for practical address-space sharing," In Proceedings of the 27th International Symposium on High-Performance Parallel and Distributed Computing (HPDC '18). ACM, New York, NY, USA, 131-143. DOI: https://doi.org/10.1145/3208040.3208045

Atsushi Hori, Balazs Gerofi, and Yuataka Ishikawa. "An Implementation of User-Level Processes using Address Space Sharing," 2020 IEEE International Parallel and Distributed Processing Symposium Workshops (IPDPSW), New Orleans, LA, USA, 2020, pp. 976-984, DOI: https://doi.org/10.1109/IPDPSW50202.2020.-00161.

Kaiming Ouyang, Min Si, Atsushi Hori, Zizhong Chen, and Pavan Balaji. 2020. "CAB-MPI: exploring interprocess work-stealing towards balanced MPI communication," In Proceedings of the International Conference for High Performance Computing, Networking, Storage and Analysis (SC '20). IEEE Press, Article 36, 1–15.

Commands

See Also

pipcc pip-check pip-exec pipfc pip-man pip-mode pips printpipmode

Functions

See Also

pip_abort pip barrier fin pip_barrier_init pip_barrier_wait pip_exit pip_export pip_fin pip_get_aux pip_get_mode pip_get_mode_str pip_get_ntasks pip_get_pipid pip_get_system_id pip_import pip_init pip_isa_root pip_isa_task pip is initialized pip_is_shared_fd pip_is_threaded pip kill pip_kill_all_tasks pip_named_export pip_named_import pip_named_tryimport pip_set_aux pip_sigmask pip_signal_wait pip_spawn pip_spawn_from_func pip_spawn_from_main pip_spawn_hook pip_task_spawn pip_trywait pip_trywait_any

pip_wait

pip_wait_any pip_yield

Author

Atsushi Hori

Riken Center for Commputational Science (R-CCS)

Japan

Proces-in-Process	(PiP)	Overview
-------------------	-------	----------

Chapter 2

PiP Commands

2.1 pipcc

C compiler driver for PiP

Synopsis

pipcc [PIP-OPTIONS] [COMPILER-OPTIONS-AND-ARGS]

Parameters

-piproot	the compile (and link) as a PiP root	
-piptask	he compile (and link) as a PiP task	
-nopip	No PiP related settings will be applied	
–where	Print the path where pipcc exists and exit	
–which	Print backend compiler and exit	

Note

The **-piproot** and **-piptask** options can be specified at the same time. In this case, the compiled object can be both of PiP root and PiP task. This is also the default behavior when none of them is specified.

Environment

\$(CC) is used to specify a C compiler

See Also

pip-exec(1), pip-mode(1)

2.2 pip-check

PiP binary checking program if a progarm can run sa a PiP root and/or PiP task

Synopsis

pip-check [OPTION] PIP-PROG [...]

10 PiP Commands

Parameters

-r	check if a.out can be PiP root		
-t	check if a.out can be PiP task		
-b	check if a.out can be PiP root and/or PiP task (default)		
-V	show reason		
-h	show this message		

See Also

pipcc

2.3 pip-exec

run program(s) as PiP tasks

Synopsis

```
\label{eq:pip-exec} \mbox{pip-exec [OPTIONS]} < \mbox{program} > \dots \mbox{ [ : ... ]}
```

Description

Run a program as PiP task(s). Mutiple programs can be specified by separating them with ':' to share the same virtual address space with the pip-exec command.

Parameters

-n N	number of tasks	
-f FUNC	unction name to start	
-c CORE	specify the CPU core number to bind core(s)	
-r	core binding in the round-robin fashion	

See Also

pipcc(1)

2.4 pipfc

Fortran compiler driver for PiP

Synopsis

pipfc [PIP-OPTIONS] [COMPILER-OPTIONS-AND-ARGS]

Parameters

-piproot	the compile (and link) as a PiP root	
-piptask	the compile (and link) as a PiP task	
-nopip	No PiP related settings will be applied	
–where	Print the path where pipfc exists and exit	
–which	Print backend compiler and exit	

2.5 pip-man 11

Note

The **-piproot** and **-piptask** options can be specified at the same time. In this case, the compiled object can be both of PiP root and PiP task. This is also the default behavior when none of them is specified.

Environment

\$(FC) is used to specify a Fortran compiler

See Also

```
pip-exec(1), pip-mode(1)
```

2.5 pip-man

show PiP man page

Synopsis

```
pip-man [MAN-OPT] MAN-TOPIC
```

Description

Show PiP man pages. It can also accept the man command options.

See Also

man(1)

2.6 pip-mode

Set PiP execution mode

Synopsis

```
pip-mode [OPTION] [PIP-COMMAND]
```

Description

The following options are avilable. If no of them specified, then the compiled output file can be used as both PiP root and PiP task.

Parameters

-P	rocess' mode	
-L	rocess:preload' mode	
-C	process:clone' mode	
-G	'process:got' mode	
-T	'thread' mode	
-u	Show usage	

See Also

pip-exec printpipmode 12 PiP Commands

2.7 pips

List or kill running PiP tasks

Synopsis

pips [a][u][x] [PIP-OPTIONS] [-] [PATTERN ..]

Parameters

a u x	similar to the aux options of the Linux ps command		
root	List PiP root(s)		
task	List PiP task(s)		
family	List PiP root(s) and PiP task(s) in family order		
kill	Send SIGTERM to PiP root(s) and task(s)		
signal	Send a signal to PiP root(s) and task(s). This option must be followed by a signal number of		
	name.		
ps	Run the ps Linux command. This option may have ps command option(s) separated by		
	comma (,)		
top	Run the top Linux command. This option may have top command option(s) separated by		
	comma (,)		
-	Simply ignored. This option can be used to avoid the ambiguity of the options.		

Description

pips is a filter to target only PiP tasks (including PiP root) to show status like the way what the ps commands does and send signals to the selected PiP tasks.

Just like the ps command, pips can take the most familiar ps options a, u, x. Here is an example;

```
$ pips
PID TID
          TT
                  TIME
                            PTP COMMAND
                 00:00:00 RT pip-exec
18741 18741 pts/0
                   00:00:00 RG pip-exec
18742 18742 pts/0
18743 18743 pts/0 00:00:00 RL pip-exec
18741 18744 pts/0
                   00:00:00 OT
18745 18745 pts/0
                   00:00:00 OG
18746 18746 pts/0
                   00:00:00 OT C
18747 18747 pts/0
                   00:00:00 1L c
18741 18748 pts/0
                   00:00:00 1T
18749 18749 pts/0
                   00:00:00 1G
                                b
18741 18750 pts/0
                   00:00:00 2T
18751 18751 pts/0
                   00:00:00 2G
                                b
18741 18752 pts/0
                   00:00:00 3T
```

here, there are 3 pip-exec root processes running. Four pip tasks running program 'a' with the ptherad mode, three PiP tasks running program 'b' with the process:got mode, and two PiP tasks running program 'c' with the process:preload mode.

Unlike the ps command, two columns 'TID' and 'PIP' are added. The 'TID' field is to identify PiP tasks in pthread execution mode. three PiP tasks running in the pthread mode. As for the 'PiP' field, if the first letter is 'R' then that pip task is running as a PiP root. If this letter is a number from '0' to '9' then this is a PiP task (not root). The number is the least-significant digit of the PiP ID of that PiP task. The second letter represents the PiP execution mode which is common with PiP root and task. 'L' is 'process:preload,' 'C' is 'process:pipclone,', 'G' is 'process:got,' and 'T' is 'thread.'

The last 'COMMAND' column of the pips output may be different from what the ps command shows, although it looks the same. It represents the command, not the command line consisting of a command and its argument(s). More precisely speaking, it is the first 14 letters of the command. This comes from the PiP's specificity. PiP tasks are not created by using the normal <code>exec</code> systemcall and the Linux assumes the same command line with the pip root process which creates the pip tasks.

If users want to have the other ps command options other than 'aux', then refer to the --ps option described below. But in this case, the command lines of PiP tasks (excepting PiP roots) are not correct.

2.7 pips 13

• --root (-r) Only the PiP root tasks will be shown.

```
$ pips --root
PID TID TT TIME PIP COMMAND
18741 18741 pts/0 00:00:00 RT pip-exec
18742 18742 pts/0 00:00:00 RG pip-exec
18743 18743 pts/0 00:00:00 RL pip-exec
```

 --task (-t) Only the PiP tasks (excluding root) will be shown. If both of --root and --task are specified, then firstly PiP roots are shown and then PiP tasks will be shown.

```
$ pips --tasks
PID TID
                  TIME
                            PIP COMMAND
          TT
18741 18744 pts/0
                   00:00:00 OT
18745 18745 pts/0
                   00:00:00 0G b
18746 18746 pts/0
                   00:00:00 OL c
18747 18747 pts/0
                   00:00:00 1L c
18741 18748 pts/0
                   00:00:00 1T
18749 18749 pts/0
                   00:00:00 1G b
18741 18750 pts/0
                    00:00:00 2T
18751 18751 pts/0
                    00:00:00 2G
18741 18752 pts/0
                    00:00:00 3T
```

 --family (-f) All PiP roots and tasks of the selected PiP tasks by the PATTERN optional argument of pips.

```
$ pips - a
    TID
           TT
                   TIME
                            PTP COMMAND
                   00:00:00 OT a
18741 18744 pts/0
18741 18748 pts/0
                   00:00:00 1T a
18741 18750 pts/0
                   00:00:00 2T
$ pips --family a
PID TID TT
                   TIME
                           PIP COMMAND
                   00:00:00 RT pip-exec
18741 18741 pts/0
18741 18744 pts/0
                    00:00:00 OT
18741 18748 pts/0
                   00:00:00 1T
18741 18750 pts/0
                   00:00:00 2T a
```

In this example, "pips - a" (the - is needed not to confused the command name a as the pips option) shows the PiP tasks which is derived from the program a. The second run, "pips --family a," shows the PiP tasks of a and their PiP root (pip-exec, in this example).

- --kill (-k) Send SIGTERM signal to the selected PiP tasks.
- \bullet --signal (-s) SIGNAL Send the specified signal to the selected PiP tasks.
- --ps (-P) This option may be followed by the ps command options. When this option is specified, the PIDs of selected PiP tasks are passed to the ps command with the specified ps command options, if given.
- --top (-T) This option may be followed by the top command options. When this option is specified, the PIDs of selected PiP tasks are passed to the top command with the specified top command options, if given.
- PATTERN The last argument is the pattern(s) to select which PiP tasks to be selected and shown. This pattern can be a command name (only the first 14 characters are effective), PID, TID, or a Unix (Linux) filename matching pattern (if the finmatch Python module is available).

```
$ pips - *-*
PID TID TT TIME PIP COMMAND
18741 18741 pts/0 00:00:00 RT pip-exec
18742 18742 pts/0 00:00:00 RG pip-exec
18743 18743 pts/0 00:00:00 RL pip-exec
```

Note

pips collects PiP tasks' status by using the Linux's ps command. When the --ps or --top option is specified, the ps or top command is invoked after invoking the ps command for information gathering. This, however, may result some PiP tasks may not appear in the invoked ps or top command when one or more PiP tasks finished after the first ps command invocation. The same situation may also happen with the --kill or --signal option.

14 PiP Commands

2.8 printpipmode

Print current PiP mode

Synopsis

printpipmode

See Also

pip-mode

Chapter 3

PiP Functions

3.1 PiP Initialization/Finalization

Functions

```
• int pip_init (int *pipidp, int *ntasks, void **root_expp, int opts)
```

```
• int pip_fin (void)
```

3.1.1 Detailed Description

3.1.1.1 PiP Initialization/Finalization

Description

PiP initialization/finalization functions

3.1.2 Function Documentation

```
3.1.2.1 int pip_init ( int * pipidp, int * ntasks, void ** root_expp, int opts )
```

Name

pip_init

Name

Initialize the PiP library

Synopsis

```
#include <pip/pip.h>
int pip_init( int *pipidp, int *ntasks, void **root_expp, uint32_t opts );
```

Description

This function initializes the PiP library. The PiP root process must call this. A PiP task is not required to call this function unless the PiP task calls any PiP functions.

Description

When this function is called by a PiP root, ntasks, and root_expp are input parameters. If this is called by a PiP task, then those parameters are output returning the same values input by the root.

Description

A PiP task may or may not call this function. If pip_init is not called by a PiP task explicitly, then pip_init is called magically and implicitly even if the PiP task program is NOT linked with the PiP library.

Parameters

out	pipidp	When this is called by the PiP root process, then this returns PIP_PIPID
		ROOT, otherwise it returns the PiP ID of the calling PiP task.
in,out	ntasks	When called by the PiP root, it specifies the maximum number of PiP tasks.
		When called by a PiP task, then it returns the number specified by the PiP root.
in,out	root_expp	If the root PiP is ready to export a memory region to any PiP task(s), then
		this parameter is to pass the exporting address. If the PiP root is not ready to
		export or has nothing to export then this variable can be NULL. When called
		by a PiP task, it returns the exported address by the PiP root, if any.
in	opts	Specifying the PiP execution mode and See below.

Execution mode option

Users may explicitly specify the PiP execution mode. This execution mode can be categorized in two; process mode and thread mode. In the process execution mode, each PiP task may have its own file descriptors, signal handlers, and so on, just like a process. Contrastingly, in the pthread execution mode, file descriptors and signal handlers are shared among PiP root and PiP tasks while maintaining the privatized variables.

To spawn a PiP task in the process mode, the PiP library modifies the **clone()** flag so that the created PiP task can exhibit the alomost same way with that of normal Linux process. There are three ways implmented; using LD_PRELOAD, modifying GLIBC, and modifying GIOT entry of the **clone()** systemcall. One of the option flag values; **PIP_MODE_PTHREAD**, **PIP_MODE_PROCESS_PIP_MODE_PROCESS_PRELOAD**, **PIP_MODE_PROCESS_GOT** can be specified as the option flag. Or, users may specify the execution mode by the **PIP_MODE** environment described below.

Returns

Zero is returned if this function succeeds. Otherwise an error number is returned.

Return values

EINVAL	ntasks is negative
EBUSY	PiP root called this function twice or more without calling pip_fin.
EPERM	opts is invalid or unacceptable
EOVERFLOW	ntasks is too large
ELIBSCN	verssion miss-match between PiP root and PiP task

Environment

- PIP_MODE Specifying the PiP execution mmode. Its value can be either thread, pthread, process, process:preload, process:pipclone, or process:got.
- LD_PRELOAD This is required to set appropriately to hold the path to the pip_preload.so file, if the PiP execution mode is PIP_MODE_PROCESS_PRELOAD (the opts in pip_init) and/or the P-IP_MODE ennvironment is set to process:preload. See also the pip-mode command to set the environment variable appropriately and easily.
- PIP_STACKSZ Sepcifying the stack size (in bytes). The KMP_STACKSIZE and OMP_STACKSIZE are also effective. The 't', 'g', 'm', 'k' and 'b' posfix character can be used.
- PIP_STOP_ON_START Specifying the PIP ID to stop on start to debug the specified PiP task from the beginning. If the before hook is specified, then the PiP task will be stopped just before calling the before hook.

- PIP_GDB_PATH If thisenvironment is set to the path pointing to the PiP-gdb executable file, then PiP-gdb is automatically attached when an excetion signal (SIGSEGV and SIGHUP by default) is delivered. The signals which triggers the PiP-gdb invokation can be specified the PIP_GDB_SIGNALS environment described below.
- PIP_GDB_COMMAND If this PIP_GDB_COMMAND is set to a filename containing some GDB commands, then those GDB commands will be executed by the GDB in batch mode, instead of backtrace.
- PIP_GDB_SIGNALS Specifying the signal(s) resulting automatic PiP-gdb attach. Signal names (case insensitive) can be concatenated by the '+' or '-' symbol. 'all' is reserved to specify most of the signals. For example, 'ALL-TERM' means all signals excepting SIGTERM, another example, 'PIPE+INT' means SIGPIPE and SIGINT. Some signals such as SIGKILL and SIGCONT cannot be specified.
- PIP_SHOW_MAPS If the value is 'on' and one of the above exection signals is delivered, then the memory map will be shown.
- **PIP_SHOW_PIPS** If the value is 'on' and one of the above exection signals is delivered, then the process status by using the pips command will be shown.

Bugs

Is is NOT guaranteed that users can spawn tasks up to the number specified by the *ntasks* argument. There are some limitations come from outside of the PiP library (from GLIBC).

See Also

```
pip_named_export
pip_export
pip_fin
pip-mode
pips

3.1.2.2 int pip_fin ( void )

Name
pip_fin

Name
Finalize the PiP library

Synopsis
#include <pip/pip.h>
```

int pip_fin(void);

Description

This function finalizes the PiP library. After calling this, most of the PiP functions will return the error code EPERM.

Returns

zero is returned if this function succeeds. On error, error number is returned.

Return values

EPERM	pip_init is not yet called
EBUSY	one or more PiP tasks are not yet terminated

Notes

The behavior of calling pip_init after calling this pip_fin is not defined and recommended not to do so.

See Also

pip_init

3.2 Spawning PiP task

Functions

void pip_spawn_from_main (pip_spawn_program_t *progp, char *prog, char **argv, char **envv, void *exp, void *aux)

Setting information to invoke a PiP task starting from the main function.

• void pip_spawn_from_func (pip_spawn_program_t *progp, char *prog, char *funcname, void *arg, char *envv, void *exp, void *aux)

Setting information to invoke a PiP task starting from a function defined in a program.

 void pip_spawn_hook (pip_spawn_hook_t *hook, pip_spawnhook_t before, pip_spawnhook_t after, void *hookarg)

Setting invocation hook information.

int pip_task_spawn (pip_spawn_program_t *progp, uint32_t coreno, uint32_t opts, int *pipidp, pip_spawn_hook_t *hookp)

Spawning a PiP task.

• int pip_spawn (char *filename, char **argv, char **envv, int coreno, int *pipidp, pip_spawnhook_t before, pip_spawnhook_t after, void *hookarg)

spawn a PiP task (PiP v1 API and deprecated)

3.2.1 Detailed Description

3.2.1.1 PiP Spawnig PiP (ULP/BLT) task

Description

Spawning PiP task or ULP/BLT task

3.2.2 Function Documentation

3.2.2.1 void pip_spawn_from_main (pip_spawn_program_t * progp, char * prog, char ** argv, char ** envv, void * exp, void * aux)

Name

pip_spawn_from_main

Synopsis

```
#include <pip/pip.h>
void pip_spawn_from_main( pip_spawn_program_t *progp, char *prog, char **argv, char **envv, void *exp,
void *aux )
```

Description

This function sets up the pip_spawn_program_t structure for spawning a PiP task, starting from the mmain function.

Parameters

out	progp	Pointer to the pip_spawn_program_t structure in which the program in-
		vokation information will be set
in	prog	Path to the executiable file.
in	argv	Argument vector.
in	envv	Environment variables. If this is NULL, then the environ variable is used for
		the spawning PiP task.
in	ехр	Export value to the spawning PiP task
in	aux	Auxiliary data to be associated with the created PiP task

See Also

```
pip_task_spawn
pip_spawn_from_func
```

3.2.2.2 void pip_spawn_from_func (pip_spawn_program_t * progp, char * prog, char * funcname, void * arg, char ** envv, void * exp, void * aux)

Name

```
pip_spawn_from_func
```

Synopsis

```
#include <pip/pip.h>
pip_spawn_from_func( pip_spawn_program_t *progp, char *prog, char *funcname, void *arg, char **envv,
void *exp, void *aux );
```

Description

This function sets the required information to invoke a program, starting from the main() function. The function should have the function prototype as shown below;

```
int start_func( void *arg )
```

This start function must be globally defined in the program. The returned integer of the start function will be treated in the same way as the main function. This implies that the pip_wait function family called from the PiP root can retrieve the return code.

Parameters

out	progp	Pointer to the pip_spawn_program_t structure in which the program in-
		vokation information will be set
in	prog	Path to the executiable file.
in	funcname	Function name to be started
in	arg	Argument which will be passed to the start function
in	envv	Environment variables. If this is NULL, then the environ variable is used for
		the spawning PiP task.

in	ехр	Export value to the spawning PiP task
in	aux	Auxiliary data to be associated with the created PiP task

See Also

```
pip_task_spawn
pip_spawn_from_main
```

3.2.2.3 void pip_spawn_hook (pip_spawn_hook_t * hook, pip_spawnhook_t before, pip_spawnhook_t after, void * hookarg)

Name

```
pip_spawn_hook
```

Synopsis

```
#include <pip/pip.h>
void pip_spawn_hook( pip_spawn_hook_t *hook, pip_spawnhook_t before, pip_spawnhook_t after, void *hookarg);
```

Description

The before and after functions are introduced to follow the programming model of the fork and exec. before function does the prologue found between the fork and exec. after function is to free the argument if it is malloc() ed, for example.

Precondition

It should be noted that the *before* and *after* functions are called in the *context* of PiP root, although they are running as a part of PiP task (i.e., having PID of the spawning PiP task). Conversely speaking, those functions cannot access the variables defined in the spawning PiP task.

The before and after hook functions should have the function prototype as shown below;

```
int hook_func( void *hookarg )
```

Parameters

out	hook	Pointer to the pip_spawn_hook_t structure in which the invocation hook information will be set
in	before	Just before the executing of the spawned PiP task, this function is called so
		that file descriptors inherited from the PiP root, for example, can deal with.
		This is only effective with the PiP process mode. This function is called with
		the argument hookarg described below.
in	after	This function is called when the PiP task terminates for the cleanup purpose.
		This function is called with the argument <i>hookarg</i> described below.
in	hookarg	The argument for the before and after function call.

Note

Note that the file descriptors and signal handlers are shared between PiP root and PiP tasks in the pthread execution mode.

See Also

pip_task_spawn

3.2 Spawning PiP task 21

3.2.2.4 int pip_task_spawn (pip_spawn_program_t * progp, uint32_t coreno, uint32_t opts, int * pipidp, pip_spawn_hook_t * hookp)

Name

pip_task_spawn

Synopsis

Description

This function spawns a PiP task specified by progp.

In the process execution mode, the file descriptors having the FD_CLOEXEC flag is closed and will not be passed to the spawned PiP task. This simulated close-on-exec will not take place in the pthread execution mode.

Parameters

out	progp	Pointer to the pip_spawn_hook_t structure in which the invocation hook
		information is set
in	coreno	CPU core number for the PiP task to be bound to. By default, coreno is set to zero, for example, then the calling task will be bound to the first core available. This is in mind that the available core numbers are not contiguous. To specify an absolute core number, coreno must be bitwise-ORed with PIP_CPUCORE_ABS. If PIP_CPUCORE_ASIS is specified, then the core binding will not take place.
in	opts	option flags
in,out	pipidp	Specify PiP ID of the spawned PiP task. If PIP_PIPID_ANY is specified,
		then the PiP ID of the spawned PiP task is up to the PiP library and the as-
		signed PiP ID will be returned.
in	hookp	Hook information to be invoked before and after the program invokation.

Returns

Zero is returned if this function succeeds. On error, an error number is returned.

Return values

EPERM	PiP library is not yet initialized
EPERM	PiP task tries to spawn child task
EINVAL	progpis NULL
EINVAL	opts is invalid and/or unacceptable
EINVAL	the value off pipidp is invalid
EINVAL	the coreno is larger than or equal to PIP_CPUCORE_CORENO_MAX
EBUSY	specified PiP ID is alredy occupied
ENOMEM	not enough memory
ENXIO	dlmopen failss

Note

In the process execution mode, each PiP task may have its own file descriptors, signal handlers, and so on, just like a process. Contrastingly, in the pthread execution mode, file descriptors and signal handlers are shared among PiP root and PiP tasks while maintaining the privatized variables.

Environment

• PIP_STOP_ON_START Specifying the PIP ID to stop on start to debug the specified PiP task from the beginning. If the before hook is specified, then the PiP task will be stopped just before calling the before hook.

Bugs

In theory, there is no reason to restrict for a PiP task to spawn another PiP task. However, the current glibc implementation does not allow to do so.

If the root process is multithreaded, only the main thread can call this function.

See Also

```
pip_task_spawn
pip_spawn_from_main
pip_spawn_from_func
pip_spawn_hook
pip_spawn
```

3.2.2.5 int pip_spawn (char * filename, char ** argv, char ** envv, int coreno, int * pipidp, pip_spawnhook_t before, pip_spawnhook_t after, void * hookarg)

Name

pip_spawn

Synopsis

```
#include <pip/pip.h>
int pip_spawn( char *filename, char **argv, char **envv, uint32_t coreno, int *pipidp, pip_spawnhook_t before, pip_spawnhook_t after, void *hookarg);
```

Description

This function spawns a PiP task.

In the process execution mode, the file descriptors having the $FD_CLOEXEC$ flag is closed and will not be passed to the spawned PiP task. This simulated close-on-exec will not take place in the pthread execution mode.

Parameters

in	filename	The executable to run as a PiP task
in	argv	Argument(s) for the spawned PiP task
in	envv	Environment variables for the spawned PiP task
in	coreno	CPU core number for the PiP task to be bound to. By default, coreno is set to
		zero, for example, then the calling task will be bound to the first core available.
		This is in mind that the available core numbers are not contiguous. To specify
		an absolute core number, coreno must be bitwise-ORed with PIP_CPUC-
		ORE_ABS. If PIP_CPUCORE_ASIS is specified, then the core binding will
		not take place.

in,out	pipidp	Specify PiP ID of the spawned PiP task. If PIP_PIPID_ANY is specified, then the PiP ID of the spawned PiP task is up to the PiP library and the as-
		signed PiP ID will be returned.
in	before	Just before the executing of the spawned PiP task, this function is called so that file descriptors inherited from the PiP root, for example, can deal with.
		This is only effective with the PiP process mode. This function is called with the argument <i>hookarg</i> described below.
in	after	This function is called when the PiP task terminates for the cleanup purpose.
		This function is called with the argument <i>hookarg</i> described below.
in	hookarg	The argument for the <i>before</i> and <i>after</i> function call.

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not yet initialized
EPERM	PiP task tries to spawn child task
EINVAL	progpis NULL
EINVAL	opts is invalid and/or unacceptable
EINVAL	the value off pipidp is invalid
EINVAL	the coreno is larger than or equal to PIP_CPUCORE_CORENO_MAX
EBUSY	specified PiP ID is alredy occupied
ENOMEM	not enough memory
ENXIO	dlmopen failss

Bugs

In theory, there is no reason to restrict for a PiP task to spawn another PiP task. However, the current glibc implementation does not allow to do so.

If the root process is multithreaded, only the main thread can call this function.

See Also

```
pip_task_spawn
pip_spawn_from_main
pip_spawn_from_func
pip_spawn_hook
pip_task_spawn
```

3.3 Export/Import Functions

Functions

- int pip_named_export (void *exp, const char *format,...) __attribute__((format(printf export an address of the calling PiP root or a PiP task to the others.
- int int pip_named_import (int pipid, void **expp, const char *format,...) __attribute__((format(printf import the named exported address
- int int int pip_named_tryimport (int pipid, void **expp, const char *format,...) __attribute__((format(printf import the named exported address (non-blocking)
- int int int pip_export (void *exp)
 export an address

```
    int pip_import (int pipid, void **expp)
```

import exported address of a PiP task

• int pip_set_aux (void *aux)

Associate user data with a PiP task.

int pip_get_aux (void **auxp)

Retrieve the user data associated with a PiP task.

3.3.1 Detailed Description

3.3.1.1 PiP Export and Import

Description

Export and import functions to exchange addresses among tasks

3.3.2 Function Documentation

```
3.3.2.1 int pip_named_export ( void * exp, const char * format, ... )
```

Name

```
pip_named_export
```

Synopsis

```
#include <pip/pip.h>
int pip_named_export( void *exp, const char *format, ... )
```

Description

Pass an address of a memory region to the other PiP task. Unlike the simmple pip_export and pip_import functions which can only export one address per task, pip_named_export and pip_named_import can associate a name with an address so that PiP root or PiP task can exchange arbitrary number of addressess.

Parameters

	in	ехр	an address to be passed to the other PiP task
Ī	in	format	a printf format to give the exported address a name. If this is NULL, then
			the name is assumed to be "".

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	pip_init is not yet called.
EBUSY	The name is already registered.
ENOMEM	Not enough memory

Note

The addresses exported by pip_named_export cannot be imported by calling pip_import, and vice versa.

See Also

```
pip_named_import
pip_named_tryimport
pip_export
pip_import
```

```
3.3.2.2 int int pip_named_import ( int pipid, void ** expp, const char * format, ... )
```

Name

```
pip_named_import
```

Synopsis

```
#include <pip/pip.h>
int pip_named_import( int pipid, void **expp, const char *format, ... )
```

Description

Import an address exported by the specified PiP task and having the specified name. If it is not exported yet, the calling task will be blocked.

Parameters

in	pipid	The PiP ID to import the exposed address
out	expp	The starting address of the exposed region of the PiP task specified by the
		pipid.
in	format	a printf format to give the exported address a name

Note

There is a possibility of deadlock when two or more tasks are mutually waiting for exported addresses.

The addresses exported by pip_export cannot be imported by calling pip_named_import, and vice versa.

Returns

zero is returned if this function succeeds. On error, an error number is returned.

Return values

EPERM	pip_init is not yet called.
EINVAL	The specified pipid is invalid
ENOMEM	Not enough memory
ECANCELED	The target task is terminated
EDEADLK	pipid is the calling task and tries to block itself

See Also

```
pip_named_export
pip_named_tryimport
pip_export
pip_import
```

```
int int int pip_named_tryimport ( int pipid, void ** expp, const char * format, ... )
```

Name

```
pip_named_tryimport
```

Synopsis

```
#include <pip/pip.h>
int pip_named_tryimport( int pipid, void **expp, const char *format, ... )
```

Description

Import an address exported by the specified PiP task and having the specified name. If it is not exported yet, this returns EAGAIN.

Parameters

in	pipid	The PiP ID to import the exposed address
out	ехрр	The starting address of the exposed region of the PiP task specified by the
		pipid.
in	format	a printf format to give the exported address a name

Note

The addresses exported by pip_export cannot be imported by calling pip_named_import, and vice versa.

Returns

Zero is returned if this function succeeds. On error, an error number is returned.

Return values

EPERM	pip_init is not yet called.
EINVAL	The specified pipid is invalid
ENOMEM	Not enough memory
ECANCELED	The target task is terminated
EAGAIN	Target is not exported yet

See Also

```
pip_named_export
     pip_named_import
     pip_export
     pip_import
3.3.2.4 int int int pip_export ( void * exp )
    pip_export
```

Synopsis

Name

```
#include <pip/pip.h>
int pip_export( void *exp );
```

Description

Pass an address of a memory region to the other PiP task. This is a very naive implementation in PiP v1 and deprecated. Once a task export an address, there is no way to change the exported address or undo export.

Parameters

in	exp	An addresss

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not initialized yet

See Also

```
pip_import
pip_named_export
pip_named_import
pip_named_tryimport
```

```
3.3.2.5 int pip_import ( int pipid, void ** expp )
```

Name

pip_import

Synopsis

```
#include <pip/pip.h>
int pip_export( void **expp );
```

Description

Get an address exported by the specified PiP task. This is a very naive implementation in PiP v1 and deprecated. If the address is not yet exported at the time of calling this function, then \mathtt{NULL} is returned.

Parameters

in	pipid	The PiP ID to import the exportedaddress
out	ехрр	The exported address

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not initialized yet

See Also

```
pip_export
pip_named_export
pip_named_import
pip_named_tryimport
```

```
3.3.2.6 int pip_set_aux ( void * aux )
```

Name

```
pip_set_aux
```

Synopsis

```
#include <pip/pip.h>
int pip_set_aux( void *aux );
```

Parameters

in	aux	Pointer to the user dats to assocate with the calling PiP task

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not yet initialized or already finalized
-------	---

See Also

```
pip_get_aux
```

```
3.3.2.7 int pip_get_aux ( void ** auxp )
```

Name

pip_get_aux

Synopsis

```
#include <pip/pip.h>
int pip_get_aux( void **auxp );
```

Parameters

out	auxp	Returned user data
-----	------	--------------------

Returns

Return 0 on success. Return an error code on error.

Return values

EINAVL	domainp is NULL or auxp is NULL
EPERM	PiP library is not yet initialized or already finalized

See Also

```
pip_set_aux
```

3.4 Waiting for PiP task termination

Functions

• int pip_wait (int pipid, int *status)

wait for the termination of a PiP task

• int pip_trywait (int pipid, int *status)

wait for the termination of a PiP task in a non-blocking way

int pip_wait_any (int *pipid, int *status)

Wait for the termination of any PiP task.

int pip_trywait_any (int *pipid, int *status)

non-blocking version of pip_wait_any

3.4.1 Detailed Description

3.4.1.1 Waiting for PiP task termination

Description

Functions to wait for PiP task termination. All functions listed here must only be called from PiP root.

3.4.2 Function Documentation

```
3.4.2.1 int pip_wait ( int pipid, int * status )
```

Name

pip_wait

Synopsis

```
#include <pip/pip.h>
int pip_wait( int pipid, int *status );
```

Description

This function can be used regardless to the PiP execution mode. This function blocks until the specified PiP task terminates. The macros such as <code>WIFEXITED</code> and so on defined in Glibc can be applied to the returned <code>status</code> value.

Parameters

in	pipid	PiP ID to wait for.
out	status	Status value of the terminated PiP task

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not initialized yet
EPERM	This function is called other than PiP root
EDEADLK	The specified pipid is the one of PiP root
ECHILD	The target PiP task does not exist or it was already terminated and waited for

See Also

```
pip_exit
pip_trywait
pip_wait_any
pip_trywait_any
wait(Linux 2)
```

```
3.4.2.2 int pip_trywait ( int pipid, int * status )

Name

pip_trywait

Synopsis

#include <pip/pip.h>
```

int pip_trywait(int pipid, int *status);

Description

This function can be used regardless to the PiP execution mode. This function behaves like the wait function of glibc and the macros such as WIFEXITED and so on can be applied to the returned status value.

Synopsis

```
#include <pip/pip.h>
int pip_trywait( int pipid, int *status );
```

Parameters

in	pipid	PiP ID to wait for.
out	status	Status value of the terminated PiP task

Note

This function can be used regardless to the PiP execution mode.

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	The PiP library is not initialized yet
EPERM	This function is called other than PiP root
EDEADLK	The specified pipid is the one of PiP root
ECHILD	The target PiP task does not exist or it was already terminated and waited for

See Also

```
pip_exit
pip_wait
pip_wait_any
pip_trywait_any
wait(Linux 2)

3.4.2.3 int pip_wait_any ( int * pipid, int * status )

Name
pip_wait_any

Synopsis
#include <pip/pip.h>
```

int pip_wait_any(int *pipid, int *status);

Description

This function can be used regardless to the PiP execution mode. This function blocks until any of PiP tasks terminates. The macros such as <code>WIFEXITED</code> and so on defined in Glibc can be applied to the returned status value.

Parameters

out	pipid	PiP ID of terminated PiP task.
out	status	Exit statusof the terminated PiP task

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	The PiP library is not initialized yet
EPERM	This function is called other than PiP root
ECHILD	The target PiP task does not exist or it was already terminated and waited for

See Also

```
pip_exit
pip_wait
pip_trywait
pip_trywait_any
wait(Linux 2)
```

```
3.4.2.4 int pip_trywait_any ( int * pipid, int * status )
```

Name

```
pip_trywait_any
```

Synopsis

```
#include <pip/pip.h>
int pip_trywait_any( int *pipid, int *status );
```

Description

This function can be used regardless to the PiP execution mode. This function blocks until any of PiP tasks terminates. The macros such as <code>WIFEXITED</code> and so on defined in Glibc can be applied to the returned status value.

Parameters

out	pipid	PiP ID of terminated PiP task.
out	status	Exit status of the terminated PiP task

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	The PiP library is not initialized yet
EPERM	This function is called other than PiP root
ECHILD	There is no PiP task to wait for

See Also

```
pip_exit
pip_wait
pip_trywait
pip_wait_any
wait(Linux 2)
```

3.5 PiP Query Functions

Functions

```
    int pip_get_pipid (int *pipidp)
    get PiP ID of the calling task
```

• int pip_is_initialized (void)

Query is PiP library is already initialized.

• int pip_get_ntasks (int *ntasksp)

get the maximum number of the PiP tasks

• int pip_get_mode (int *modep)

get the PiP execution mode

const char * pip_get_mode_str (void)

get a character string of the current execution mode

• int pip_get_system_id (int pipid, pip_id_t *idp)

deliver a process or thread ID defined by the system

int pip_isa_root (void)

check if calling PiP task is a PiP root or not

int pip_isa_task (void)

check if calling PiP task is a PiP task or not

int pip_is_threaded (int *flagp)

check if PiP execution mode is pthread or not

• int pip_is_shared_fd (int *flagp)

 $\textit{check if file descriptors are shared or not. This is equivalent with the \verb|pip_is_threaded| function. \\$

3.5.1 Detailed Description

3.5.1.1 PiP Query functions

Description

Query functions for PiP task

3.5.2 Function Documentation

```
3.5.2.1 int pip_get_pipid ( int * pipidp )
```

Name

pip_get_pipid

Synopsis

```
#include <pip/pip.h>
int pip_get_pipid( int *pipidp );
```

Parameters

out	pipidp	This parameter points to the variable which will be set to the PiP ID of the
		calling task

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not initialized yet

See Also

```
pip_init
```

```
3.5.2.2 int pip_is_initialized ( void )
```

Name

pip_is_initialized

Synopsis

```
#include <pip/pip.h>
int pip_is_initialized( void );
```

Returns

Return a non-zero value if PiP is already initialized. Otherwise this returns zero.

See Also

```
pip_init
```

```
3.5.2.3 int pip_get_ntasks ( int * ntasksp )
```

Name

```
pip_get_ntasks
```

```
#include <pip/pip.h>
int pip_get_ntasks( int *ntasksp );
```

Parameters

out	ntasksp	Maximum number of PiP tasks is returned

Returns

Return 0 on success. Return an error code on error.

Return values

```
EPERM PiP library is not yet initialized
```

See Also

```
pip_init
```

```
3.5.2.4 int pip_get_mode ( int * modep )
```

Name

```
pip_get_mode
```

Synopsis

```
#include <pip/pip.h>
int pip_get_mode( int *modep );
```

Parameters

out	modep	Returned PiP execution mode
-----	-------	-----------------------------

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM PIP library is not yet initialized
--

See Also

```
pip_get_mode_str
```

```
3.5.2.5 const char* pip_get_mode_str ( void )
```

Name

```
pip_get_mode_str
```

Synopsis

```
#include <pip/pip.h>
char *pip_get_mode_str( void );
```

Returns

Return the name string of the current execution mode. If PiP library is not initialized yet, then this returns \mathtt{NULL} .

See Also

```
pip_get_mode
```

```
3.5.2.6 int pip_get_system_id ( int pipid, pip_id_t * idp )

Name

pip_get_system_id

Synopsis

#include <pip/pip.h>
```

int pip_get_system_id(int *pipid, uintptr_t *idp);

Description

The returned object depends on the PiP execution mode. In the process mode it returns TID (Thread ID, not PID) and in the thread mode it returns thread (pthread_t) associated with the PiP task This function can be used regardless to the PiP execution mode.

Parameters

out	pipid	PiP ID of a target PiP task
out	idp	a pointer to store the ID value

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	The PiP library is not initialized yet

See Also

```
getpid(Linux 2)
pthread_self(Linux 3)
```

```
3.5.2.7 int pip_isa_root ( void )
```

Name

pip_isa_root

Synopsis

```
#include <pip/pip.h>
int pip_isa_root( void );
```

Returns

Return a non-zero value if the caller is the PiP root. Otherwise this returns zero.

See Also

pip_init

```
3.5.2.8 int pip_isa_task (void)
Name
     pip_isa_task
Synopsis
     #include <pip/pip.h>
     int pip_isa_task( void );
 Returns
       Return a non-zero value if the caller is the PiP task. Otherwise this returns zero.
See Also
       pip_init
3.5.2.9 int pip_is_threaded ( int * flagp )
Name
     pip_is_threaded
Synopsis
     #include <pip/pip.h>
     int pip_is_threaded( int *flagp );
Parameters
                                      set to a non-zero value if PiP execution mode is Pthread
      out
                              flagp
```

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM | The PiP library is not initialized yet

```
See Also
```

```
pip_init
```

```
3.5.2.10 int pip_is_shared_fd ( int * flagp )
```

Name

```
pip_is_shared_fd
```

```
#include <pip/pip.h>
int pip_is_shared_fd( int *flagp );
```

3.6 PiP task termination 37

Parameters

out	flagp	set to a non-zero value if FDs are shared
-----	-------	---

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	The PiP library is not initialized yet

See Also

pip_init

3.6 PiP task termination

Functions

```
    void pip_exit (int status)
    terminate the calling PiP task
```

• int pip_kill_all_tasks (void)

kill all PiP tasks

void pip_abort (void)

Kill all PiP tasks and then kill PiP root.

int pip_kill (int pipid, int signal)
 deliver a signal to PiP task

3.6.1 Detailed Description

3.6.1.1 Terminating PiP task

Description

Terminating PiP task(s)

3.6.2 Function Documentation

```
3.6.2.1 void pip_exit ( int status )
```

Name

pip_exit

Synopsis

```
#include <pip/pip.h>
void pip_exit( int status );
```

Description

When the main function or the start function of a PiP task returns with an integer value, then it has the same effect of calling pip_exit with the returned value.

Parameters

in	status	This status is returned to PiP root.

Note

This function can be used regardless to the PiP execution mode. exit (3) is called in the process mode and pthread_exit (3) is called in the pthread mode.

See Also

```
pip_wait
pip_trywait
pip_wait_any
pip_trywait_any
exit(Linux 3)
pthread_exit(Linux 3)

3.6.2.2 int pip_kill_all_tasks ( void )
```

Name

```
pip_kill_all_tasks
```

Synopsis

```
#include <pip/pip.h>
int pip_kill_all_tasks( void );
```

Note

This function must be called from PiP root.

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	The PiP library is not initialized yet
EPERM	Not called from root

```
3.6.2.3 void pip_abort ( void )

Name

pip_abort

Synopsis

#include <pip/pip.h>
```

void pip_abort(void);

```
3.6.2.4 int pip_kill (int pipid, int signal)
```

Name

pip_kill

Synopsis

```
#include <pip/pip.h>
int pip_kill( int pipid, int signal );
```

Parameters

out	pipid	PiP ID of a target PiP task to deliver the signal
out	signal	signal number to be delivered

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not yet initialized
EINVAL	An invalid signal number or invalid PiP ID is specified

See Also

tkill(Luinux 2)

3.7 PiP Siganling Functions

Functions

- int pip_sigmask (int how, const sigset_t *sigmask, sigset_t *oldmask)
 set signal mask of the current PiP task
- int pip_signal_wait (int signal)

wait for a signal

3.7.1 Detailed Description

3.7.1.1 PiP signaling functions

Description

Signaling functions for PiP task

3.7.2 Function Documentation

```
3.7.2.1 int pip_sigmask ( int how, const sigset_t * sigmask, sigset_t * oldmask )
```

Name

pip_sigmask

```
#include <pip/pip.h>
int pip_sigmask( int how, const sigset_t *sigmask, sigset_t *oldmask );
```

Description

This function is agnostic to the PiP execution mode.

Parameters

in	how	see sigprogmask or pthread_sigmask	
in	sigmask	signal mask	
out	oldmask	old signal mask	

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not yet initialized
EINVAL	An invalid signal number or invalid PiP ID is specified

See Also

```
sigprocmask(Linux 2)
pthread_sigmask(Linux 3)
```

```
3.7.2.2 int pip_signal_wait (int signal)
```

Name

pip_signal_wait

Synopsis

```
#include <pip/pip.h>
int pip_signal_wait( int signal );
```

Description

This function is agnostic to the PiP execution mode.

Parameters

in	signal	signal to wait

Returns

Return 0 on success. Return an error code on error.

Note

This function does NOT return the EINTR error. This case is treated as normal return;

See Also

```
sigwait(Linux 3)
sigsuspend(Linux 2)
```

3.8 PiP Synchronization Functions

Functions

```
    int pip_yield (int flag)
        Yield.
    int pip_barrier_init (pip_barrier_t *barrp, int n)
        initialize barrier synchronization structure
    int pip_barrier_wait (pip_barrier_t *barrp)
        wait on barrier synchronization in a busy-wait way
    int pip_barrier_fin (pip_barrier_t *barrp)
        finalize barrier synchronization structure
```

3.8.1 Detailed Description

3.8.1.1 PiP synchronization functions

Description

Synchronization functions for PiP tasks

3.8.2 Function Documentation

```
3.8.2.1 int pip_yield ( int flag )

Name

pip_yield

Synopsis

#include <pip/pip.h>
int pip_yield( int flag );
```

Parameters

in	flag	to specify the behavior of yielding. Unused and reserved for BLT/ULP (in PiP-
		v3)

Returns

Thuis function always succeeds and returns zero.

See Also

```
sched_yield(Linux 2)
pthread_yield(Linux 3)

3.8.2.2 int pip_barrier_init ( pip_barrier_t * barrp, int n )

Name
pip_barrier_init

Synopsis

#include <pip/pip.h>
int pip_barrier_init( pip_barrier_t *barrp, int n );
```

Parameters

in	barrp	pointer to a PiP barrier structure
in	n	number of participants of this barrier synchronization

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not yet initialized or already finalized
EINAVL	n is invalid

See Also

```
pip_barrier_wait
pip_barrier_fin
```

```
3.8.2.3 int pip_barrier_wait ( pip_barrier_t * barrp )
```

Name

pip_barrier_wait

Synopsis

```
#include <pip/pip.h>
int pip_barrier_wait( pip_barrier_t *barrp );
```

Parameters

in	barrp	pointer to a PiP barrier structure

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not yet initialized or already finalized
-------	---

See Also

```
pip_barrier_init
pip_barrier_fin
```

3.8.2.4 int pip_barrier_fin (pip_barrier_t * barrp)

Name

pip_barrier_fin

```
#include <pip/pip.h>
int pip_barrier_fin( pip_barrier_t *barrp );
```

Parameters

in	barrp	pointer to a PiP barrier structure

Returns

Return 0 on success. Return an error code on error.

Return values

EPERM	PiP library is not yet initialized or already finalized
EBUSY	there are some tasks wating for barrier synchronization

See Also

pip_barrier_init
pip_barrier_wait

Index

Export/Import Functions, 23	pip_get_aux
pip_export, 26	Export/Import Functions, 28
pip_get_aux, 28	pip get mode
pip_import, 27	PiP Query Functions, 34
pip_named_export, 24	pip_get_mode_str
pip_named_import, 25	PiP Query Functions, 34
pip_named_tryimport, 25	pip_get_ntasks
pip_set_aux, 27	PiP Query Functions, 33
F F /	pip_get_pipid
PiP Initialization/Finalization, 15	PiP Query Functions, 32
pip_fin, 17	pip_get_system_id
pip_init, 15	PiP Query Functions, 34
PiP Query Functions, 32	pip_import
pip_get_mode, 34	Export/Import Functions, 27
pip_get_mode_str, 34	·
pip_get_ntasks, 33	pip_init
pip_get_pipid, 32	PiP Initialization/Finalization, 15
pip_get_system_id, 34	pip_is_initialized
pip_is_initialized, 33	PiP Query Functions, 33
pip_is_shared_fd, 36	pip_is_shared_fd
pip_is_threaded, 36	PiP Query Functions, 36
pip_isa_root, 35	pip_is_threaded
pip_isa_task, 35	PiP Query Functions, 36
PiP Siganling Functions, 39	pip_isa_root
pip_sigmask, 39	PiP Query Functions, 35
pip_signal_wait, 40	pip_isa_task
PiP Synchronization Functions, 41	PiP Query Functions, 35
pip_barrier_fin, 42	pip_kill
pip_barrier_init, 41	PiP task termination, 38
pip_barrier_wait, 42	pip_kill_all_tasks
pip_yield, 41	PiP task termination, 38
PiP task termination, 37	pip_named_export
pip_abort, 38	Export/Import Functions, 24
pip_exit, 37	pip_named_import
pip_kill, 38	Export/Import Functions, 25
pip_kill_all_tasks, 38	pip_named_tryimport
pip_abort	Export/Import Functions, 25
PiP task termination, 38	pip_set_aux
pip_barrier_fin	Export/Import Functions, 27
PiP Synchronization Functions, 42	pip_sigmask
pip_barrier_init	PiP Siganling Functions, 39
PiP Synchronization Functions, 41	pip_signal_wait
pip_barrier_wait	PiP Siganling Functions, 40
PiP Synchronization Functions, 42	pip_spawn
	Spawning PiP task, 22
pip_exit PiP task termination, 37	pip spawn from func
	Spawning PiP task, 19
pip_export Export/Import Functions, 26	pip spawn from main
·	Spawning PiP task, 18
pip_fin PiP Initialization/Finalization, 17	pip_spawn_hook
i ii iiiiidaiization/i iiidaiization, 1/	pip_spawii_iioon

Spawning PiP task, 20 pip_task_spawn	Waiting for PiP task termination, 28 pip_trywait, 29
Spawning PiP task, 20	pip_trywait_any, 31
pip_trywait	pip_wait, 29
Waiting for PiP task termination, 29	pip_wait_any, 30
pip_trywait_any Waiting for PiP task termination, 31	
pip_wait Waiting for PiP task termination, 29	
pip_wait_any	
Waiting for PiP task termination, 30	
pip_yield	
PiP Synchronization Functions, 41	
pip_abort, 38	
pip_barrier_fin, 42	
pip_barrier_init, 41	
pip_barrier_wait, 42	
pip_exit, 37	
pip_export, 26	
pip_fin, 17	
pip_get_aux, 28	
pip_get_mode, 34	
pip_get_mode_str, 34	
pip_get_ntasks, 33	
pip_get_pipid, 32	
pip_get_system_id, 35	
pip_import, 27	
pip_init, 15	
pip_is_initialized, 33	
pip_is_shared_fd, 36	
pip_is_threaded, 36	
pip_isa_root, 35	
pip_isa_task, 36	
pip_isa_task, 50 pip_kill, 39	
pip_kill_all_tasks, 38	
pip_named_export, 24	
pip_named_import, 25	
pip_named_tryimport, 26	
pip_set_aux, 28	
pip_sigmask, 39	
pip_signal_wait, 40	
pip_spawn, 22	
pip_spawn_from_func, 19	
pip_spawn_from_main, 18	
pip_spawn_hook, 20	
pip_task_spawn, 21	
pip_trywait, 30	
pip_trywait_any, 31	
pip_wait, 29	
pip_wait_any, 30	
pip_yield, 41	
Spawning PiP task, 18	
pip_spawn, 22	
pip_spawn_from_func, 19	
pip_spawn_from_main, 18	
pip_spawn_hook, 20	
pip_spawii_nook, 20 pip_task_spawn, 20	
lark—race,—abarrerii —a	