

# OpenShift Container Platform 4.3

# **Installing on AWS**

Installing OpenShift Container Platform 4.3 on AWS

Last Updated: 2020-01-23

# OpenShift Container Platform 4.3 Installing on AWS

Installing OpenShift Container Platform 4.3 on AWS

## **Legal Notice**

Copyright © 2020 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

http://creativecommons.org/licenses/by-sa/3.0/

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java <sup>®</sup> is a registered trademark of Oracle and/or its affiliates.

XFS <sup>®</sup> is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL <sup>®</sup> is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack <sup>®</sup> Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

## **Abstract**

This document provides instructions for installing and uninstalling OpenShift Container Platform 4.3 clusters on AWS.

## **Table of Contents**

CHAPTER 1. INSTALLING ON AWS	. 5
1.1. CONFIGURING AN AWS ACCOUNT	5
1.1.1. Configuring Route53	5
1.1.2. AWS account limits	5
1.1.3. Required AWS permissions	7
1.1.4. Creating an IAM user	13
1.1.5. Supported AWS regions	14
1.2. INSTALLING A CLUSTER QUICKLY ON AWS	15
1.2.1. Internet and Telemetry access for OpenShift Container Platform	15
1.2.2. Generating an SSH private key and adding it to the agent	16
1.2.3. Obtaining the installation program	17
1.2.4. Deploy the cluster	18
1.2.5. Installing the CLI	19
1.2.6. Logging in to the cluster	20
1.3. INSTALLING A CLUSTER ON AWS WITH CUSTOMIZATIONS	20
1.3.1. Internet and Telemetry access for OpenShift Container Platform	21
1.3.2. Generating an SSH private key and adding it to the agent	21
1.3.3. Obtaining the installation program	22
1.3.4. Creating the installation configuration file	23
1.3.4.1. Installation configuration parameters	24
1.3.4.2. Sample customized install-config.yaml file for AWS	28
1.3.5. Deploy the cluster	30
1.3.6. Installing the CLI	31
1.3.7. Logging in to the cluster	32
1.4. INSTALLING A CLUSTER ON AWS WITH NETWORK CUSTOMIZATIONS	33
1.4.1. Internet and Telemetry access for OpenShift Container Platform	33
1.4.2. Generating an SSH private key and adding it to the agent	34
1.4.3. Obtaining the installation program	35
1.4.4. Creating the installation configuration file	35
1.4.4.1. Installation configuration parameters	37
1.4.4.2. Network configuration parameters	41
1.4.4.3. Sample customized install-config.yaml file for AWS	42
1.4.5. Modifying advanced network configuration parameters	44
1.4.6. Cluster Network Operator custom resource (CR)	45
1.4.6.1. Configuration parameters for OpenShift SDN	46
1.4.6.2. Configuration parameters for Open Virtual Network (OVN) SDN	47
1.4.6.3. Cluster Network Operator example CR	47
1.4.7. Deploy the cluster	47
1.4.8. Installing the CLI	48
1.4.9. Logging in to the cluster	49
1.5. INSTALLING A CLUSTER ON AWS INTO AN EXISTING VPC	49
1.5.1. About using a custom VPC	50
1.5.1.1. Requirements for using your VPC	50
1.5.1.2. VPC validation	52
1.5.1.3. Division of permissions	53
1.5.1.4. Isolation between clusters	53
1.5.2. Internet and Telemetry access for OpenShift Container Platform	53
1.5.3. Generating an SSH private key and adding it to the agent	54
1.5.4. Obtaining the installation program	55
1.5.5. Creating the installation configuration file	55
1.5.5.1. Installation configuration parameters	57

1.5.5.2. Sample customized install-config.yaml file for AWS	61
1.5.6. Deploy the cluster	63
1.5.7. Installing the CLI	64
1.5.8. Logging in to the cluster	64
1.6. INSTALLING A PRIVATE CLUSTER ON AWS	65
1.6.1. Private clusters	65
1.6.1.1. Private clusters in AWS	66
1.6.1.1.1. Limitations	66
1.6.2. About using a custom VPC	66
1.6.2.1. Requirements for using your VPC	67
1.6.2.2. VPC validation	69
1.6.2.3. Division of permissions	69
1.6.2.4. Isolation between clusters	69
1.6.3. Internet and Telemetry access for OpenShift Container Platform	70
1.6.4. Generating an SSH private key and adding it to the agent	70
1.6.5. Obtaining the installation program	71
1.6.6. Creating the installation configuration file	72
1.6.6.1. Installation configuration parameters	73
1.6.6.2. Sample customized install-config.yaml file for AWS	78
1.6.7. Deploy the cluster	80
1.6.8. Installing the CLI	81
1.6.9. Logging in to the cluster	81
1.7. INSTALLING A CLUSTER ON USER-PROVISIONED INFRASTRUCTURE IN AWS BY USING	
CLOUDFORMATION TEMPLATES	82
1.7.1. Internet and Telemetry access for OpenShift Container Platform	83
1.7.2. Required AWS infrastructure components	83
1.7.2.1. Cluster machines	83
1.7.2.2. Certificate signing requests management	85
1.7.2.3. Other infrastructure components	85
1.7.2.4. Required AWS permissions	91
1.7.3. Obtaining the installation program	97
1.7.4. Generating an SSH private key and adding it to the agent	97
1.7.5. Creating the installation files for AWS	98
1.7.5.1. Creating the installation configuration file	99
1.7.5.2. Configuring the cluster-wide proxy during installation	100
1.7.5.3. Creating the Kubernetes manifest and Ignition config files	101
1.7.6. Extracting the infrastructure name	103
1.7.7. Creating a VPC in AWS	104
1.7.7.1. CloudFormation template for the VPC	105
1.7.8. Creating networking and load balancing components in AWS	111
1.7.8.1. CloudFormation template for the network and load balancers	114
1.7.9. Creating security group and roles in AWS	121
1.7.9.1. CloudFormation template for security objects	123
1.7.10. RHCOS AMIs for the AWS infrastructure	130
1.7.11. Creating the bootstrap node in AWS	130
1.7.11.1. CloudFormation template for the bootstrap machine	134
1.7.12. Creating the control plane machines in AWS	138
1.7.12.1. CloudFormation template for control plane machines	143
1.7.13. Initializing the bootstrap node on AWS with user-provisioned infrastructure	150
1.7.13.1. Creating the worker nodes in AWS	151
1.7.13.1.1. CloudFormation template for worker machines	154
1.7.14. Installing the CLI	157
1.7.15. Logging in to the cluster	157

1.7.16. Approving the CSRs for your machines	158
1.7.17. Initial Operator configuration	159
1.7.17.1. Image registry storage configuration	160
1.7.17.1.1. Configuring registry storage for AWS with user-provisioned infrastructure	160
1.7.17.1.2. Configuring storage for the image registry in non-production clusters	161
1.7.18. Deleting the bootstrap resources	162
1.7.19. Creating the Ingress DNS Records	162
1.7.20. Completing an AWS installation on user-provisioned infrastructure	164
1.8. INSTALLING A CLUSTER ON AWS THAT USES MIRRORED INSTALLATION CONTENT	165
1.8.1. About installations in restricted networks	166
1.8.1.1. Additional limits	167
1.8.2. Internet and Telemetry access for OpenShift Container Platform	167
1.8.3. Required AWS infrastructure components	167
1.8.3.1. Cluster machines	168
1.8.3.2. Certificate signing requests management	169
1.8.3.3. Other infrastructure components	169
1.8.3.4. Required AWS permissions	175
1.8.4. Generating an SSH private key and adding it to the agent	181
1.8.5. Creating the installation files for AWS	182
1.8.5.1. Creating the installation configuration file	182
1.8.5.2. Configuring the cluster-wide proxy during installation	184
1.8.5.3. Creating the Kubernetes manifest and Ignition config files	185
1.8.6. Extracting the infrastructure name	187
1.8.7. Creating a VPC in AWS	188
1.8.7.1. CloudFormation template for the VPC	190
1.8.8. Creating networking and load balancing components in AWS	195
1.8.8.1. CloudFormation template for the network and load balancers	198
1.8.9. Creating security group and roles in AWS	205
1.8.9.1. CloudFormation template for security objects	208
1.8.10. RHCOS AMIs for the AWS infrastructure	214
1.8.11. Creating the bootstrap node in AWS	215
1.8.11.1. CloudFormation template for the bootstrap machine	219
1.8.12. Creating the control plane machines in AWS	223
1.8.12.1. CloudFormation template for control plane machines	227
1.8.13. Initializing the bootstrap node on AWS with user-provisioned infrastructure	234
1.8.13.1. Creating the worker nodes in AWS	235
1.8.13.1.1. CloudFormation template for worker machines	239
1.8.14. Logging in to the cluster	241
1.8.15. Approving the CSRs for your machines	242
1.8.16. Initial Operator configuration	243
1.8.16.1. Image registry storage configuration	244
1.8.16.1.1. Configuring registry storage for AWS with user-provisioned infrastructure	244
1.8.16.1.2. Configuring storage for the image registry in non-production clusters	245
1.8.17. Deleting the bootstrap resources	245
1.8.18. Creating the Ingress DNS Records	246
1.8.19. Completing an AWS installation on user-provisioned infrastructure	248
1.9. UNINSTALLING A CLUSTER ON AWS	249
191 Removing a cluster that uses installer-provisioned infrastructure	249

## **CHAPTER 1. INSTALLING ON AWS**

## 1.1. CONFIGURING AN AWS ACCOUNT

Before you can install OpenShift Container Platform, you must configure an Amazon Web Services (AWS) account.

## 1.1.1. Configuring Route53

To install OpenShift Container Platform, the Amazon Web Services (AWS) account you use must have a dedicated public hosted zone in your Route53 service. This zone must be authoritative for the domain. The Route53 service provides cluster DNS resolution and name lookup for external connections to the cluster.

#### **Procedure**

1. Identify your domain, or subdomain, and registrar. You can transfer an existing domain and registrar or obtain a new one through AWS or another source.



#### **NOTE**

If you purchase a new domain through AWS, it takes time for the relevant DNS changes to propagate. For more information about purchasing domains through AWS, see Registering Domain Names Using Amazon Route 53 in the AWS documentation.

- 2. If you are using an existing domain and registrar, migrate its DNS to AWS. See Making Amazon Route 53 the DNS Service for an Existing Domain in the AWS documentation.
- 3. Create a public hosted zone for your domain or subdomain. See Creating a Public Hosted Zone in the AWS documentation.
  - Use an appropriate root domain, such as **openshiftcorp.com**, or subdomain, such as **clusters.openshiftcorp.com**.
- 4. Extract the new authoritative name servers from the hosted zone records. See Getting the Name Servers for a Public Hosted Zone in the AWS documentation.
- 5. Update the registrar records for the AWS Route53 name servers that your domain uses. For example, if you registered your domain to a Route53 service in a different accounts, see the following topic in the AWS documentation: Adding or Changing Name Servers or Glue Records.
- 6. If you use a subdomain, follow your company's procedures to add its delegation records to the parent domain.

## 1.1.2. AWS account limits

The OpenShift Container Platform cluster uses a number of Amazon Web Services (AWS) components, and the default Service Limits affect your ability to install OpenShift Container Platform clusters. If you use certain cluster configurations, deploy your cluster in certain AWS regions, or run multiple clusters from your account, you might need to request additional resources for you AWS account.

The following table summarizes the AWS components whose limits can impact your ability to install and run OpenShift Container Platform clusters.

Compone nt	Number of clusters available by default	Default AWS limit	Description
Instance Limits	Varies	Varies	By default, each cluster creates the following instances:
			<ul> <li>One bootstrap machine, which is removed after installation</li> </ul>
			Three master nodes
			Three worker nodes
			These instance type counts are within a new account's default limit. To deploy more worker nodes, enable autoscaling, deploy large workloads, or use a different instance type, review your account limits to ensure that your cluster can deploy the machines that you need.
			In most regions, the bootstrap and worker machines uses an <b>m4.large</b> machines and the master machines use <b>m4.xlarge</b> instances. In some regions, including all regions that do not support these instance types, <b>m5.large</b> and <b>m5.xlarge</b> instances are used instead.
Elastic IPs (EIPs)	O to 1	5 EIPs per account	To provision the cluster in a highly available configuration, the installation program creates a public and private subnet for each availability zone within a region. Each private subnet requires aNAT Gateway, and each NAT gateway requires a separate elastic IP. Review the AWS region map to determine how many availability zones are in each region. You can install a single cluster in many regions without increasing your EIP limit, but to take advantage of the default high availability, install the cluster in a region with at least three availability zones.
			IMPORTANT  To use the us-east-1 region, you must increase the EIP limit for your account.
Virtual Private Clouds (VPCs)	5	5 VPCs per region	Each cluster creates its own VPC.

Compone nt	Number of clusters available by default	Default AWS limit	Description
Elastic Load Balancing (ELB/NLB	3	20 per region	By default, each cluster creates an internal and external network load balancers for the master API server and a single classic elastic load balancer for the router. Deploying more Kubernetes LoadBalancer Service objects will create additional load balancers.
NAT Gateways	5	5 per availability zone	The cluster deploys one NAT gateway in each availability zone.
Elastic Network Interfaces (ENIs)	At least 12	350 per region	The default installation creates 21 ENIs and an ENI for each availability zone in your region. For example, the <b>us-east-1</b> region contains six availability zones, so a cluster that is deployed in that zone uses 27 ENIs. Review the AWS region map to determine how many availability zones are in each region.  Additional ENIs are created for additional machines and elastic load balancers that are created by cluster usage and deployed workloads.
VPC Gateway	20	20 per account	Each cluster creates a single VPC Gateway for S3 access.
S3 buckets	99	100 buckets per account	Because the installation process creates a temporary bucket and the registry component in each cluster creates a bucket, you can create only 99 OpenShift Container Platform clusters per AWS account.
Security Groups	250	2,500 per account	Each cluster creates 10 distinct security groups.

## 1.1.3. Required AWS permissions

When you attach the **AdministratorAccess** policy to the IAM user that you create in Amazon Web Services (AWS), you grant that user all of the required permissions. To deploy all components of an OpenShift Container Platform cluster, the IAM user requires the following permissions:

## Required EC2 permissions for installation

- ec2:AllocateAddress
- ec2:AssociateAddress
- ec2:AuthorizeSecurityGroupEgress

- ec2:AuthorizeSecurityGroupIngress
- ec2:Copylmage
- ec2:CreateNetworkInterface
- ec2:CreateSecurityGroup
- ec2:CreateTags
- ec2:CreateVolume
- ec2:DeleteSecurityGroup
- ec2:DeleteSnapshot
- ec2:DeregisterImage
- ec2:DescribeAccountAttributes
- ec2:DescribeAddresses
- ec2:DescribeAvailabilityZones
- ec2:DescribeDhcpOptions
- ec2:DescribeImages
- ec2:DescribeInstanceAttribute
- ec2:DescribeInstanceCreditSpecifications
- ec2:DescribeInstances
- ec2:DescribeInternetGateways
- ec2:DescribeKeyPairs
- ec2:DescribeNatGateways
- ec2:DescribeNetworkAcls
- ec2:DescribeNetworkInterfaces
- ec2:DescribePrefixLists
- ec2:DescribeRegions
- ec2:DescribeRouteTables
- ec2:DescribeSecurityGroups
- ec2:DescribeSubnets
- ec2:DescribeTags
- ec2:DescribeVolumes

- ec2:DescribeVpcAttribute
- ec2:DescribeVpcClassicLink
- ec2:DescribeVpcClassicLinkDnsSupport
- ec2:DescribeVpcEndpoints
- ec2:DescribeVpcs
- ec2:ModifyInstanceAttribute
- ec2:ModifyNetworkInterfaceAttribute
- ec2:ReleaseAddress
- ec2:RevokeSecurityGroupEgress
- ec2:RevokeSecurityGroupIngress
- ec2:RunInstances
- ec2:TerminateInstances

Required permissions for creating network resources during installation

- ec2:AssociateDhcpOptions
- ec2:AssociateRouteTable
- ec2:AttachInternetGateway
- ec2:CreateDhcpOptions
- ec2:CreateInternetGateway
- ec2:CreateNatGateway
- ec2:CreateRoute
- ec2:CreateRouteTable
- ec2:CreateSubnet
- ec2:CreateVpc
- ec2:CreateVpcEndpoint
- ec2:ModifySubnetAttribute
- ec2:ModifyVpcAttribute



## **NOTE**

If you use an existing VPC, your account does not require these permissions for creating network resources.

## Required Elasticloadbalancing permissions for installation

- elasticloadbalancing:AddTags
- elasticloadbalancing:ApplySecurityGroupsToLoadBalancer
- elasticloadbalancing:AttachLoadBalancerToSubnets
- elasticloadbalancing:ConfigureHealthCheck
- elasticloadbalancing:CreateListener
- elasticloadbalancing:CreateLoadBalancer
- elasticloadbalancing:CreateLoadBalancerListeners
- elasticloadbalancing:CreateTargetGroup
- elasticloadbalancing:DeleteLoadBalancer
- elasticloadbalancing:DeregisterInstancesFromLoadBalancer
- elasticloadbalancing:DeregisterTargets
- elasticloadbalancing:DescribeInstanceHealth
- elasticloadbalancing:DescribeListeners
- elasticloadbalancing:DescribeLoadBalancerAttributes
- elasticloadbalancing:DescribeLoadBalancers
- elasticloadbalancing:DescribeTags
- elasticloadbalancing:DescribeTargetGroupAttributes
- elasticloadbalancing:DescribeTargetHealth
- elasticloadbalancing:ModifyLoadBalancerAttributes
- elasticloadbalancing:ModifyTargetGroup
- elasticloadbalancing:ModifyTargetGroupAttributes
- elasticloadbalancing:RegisterInstancesWithLoadBalancer
- elasticloadbalancing:RegisterTargets
- elasticloadbalancing:SetLoadBalancerPoliciesOfListener

## Required IAM permissions for installation

- iam:AddRoleToInstanceProfile
- iam:CreateInstanceProfile
- iam:CreateRole

- iam:DeleteInstanceProfile
- iam:DeleteRole
- iam:DeleteRolePolicy
- iam:GetInstanceProfile
- iam:GetRole
- iam:GetRolePolicy
- iam:GetUser
- iam:ListInstanceProfilesForRole
- iam:ListRoles
- iam:ListUsers
- iam:PassRole
- iam:PutRolePolicy
- iam:RemoveRoleFromInstanceProfile
- iam:SimulatePrincipalPolicy
- iam:TagRole

## Required Route53 permissions for installation

- route53:ChangeResourceRecordSets
- route53:ChangeTagsForResource
- route53:CreateHostedZone
- route53:DeleteHostedZone
- route53:GetChange
- route53:GetHostedZone
- route53:ListHostedZones
- route53:ListHostedZonesByName
- route53:ListResourceRecordSets
- route53:ListTagsForResource
- route53:UpdateHostedZoneComment

## Required S3 permissions for installation

• s3:CreateBucket

- s3:DeleteBucket
- s3:GetAccelerateConfiguration
- s3:GetBucketCors
- s3:GetBucketLocation
- s3:GetBucketLogging
- s3:GetBucketObjectLockConfiguration
- s3:GetBucketReplication
- s3:GetBucketRequestPayment
- s3:GetBucketTagging
- s3:GetBucketVersioning
- s3:GetBucketWebsite
- s3:GetEncryptionConfiguration
- s3:GetLifecycleConfiguration
- s3:GetReplicationConfiguration
- s3:ListBucket
- s3:PutBucketAcl
- s3:PutBucketTagging
- s3:PutEncryptionConfiguration

## S3 permissions that cluster Operators require

- s3:DeleteObject
- s3:GetObject
- s3:GetObjectAcl
- s3:GetObjectTagging
- s3:GetObjectVersion
- s3:PutObject
- s3:PutObjectAcl
- s3:PutObjectTagging

## Required permissions to delete base cluster resources

• autoscaling:DescribeAutoScalingGroups

- ec2:DeleteNetworkInterface
- ec2:DeleteVolume
- elasticloadbalancing:DeleteTargetGroup
- elasticloadbalancing:DescribeTargetGroups
- iam:ListInstanceProfiles
- iam:ListRolePolicies
- iam:ListUserPolicies
- s3:DeleteObject
- tag:GetResources

Required permissions to delete network resources

- ec2:DeleteDhcpOptions
- ec2:DeleteInternetGateway
- ec2:DeleteNatGateway
- ec2:DeleteRoute
- ec2:DeleteRouteTable
- ec2:DeleteSubnet
- ec2:DeleteVpc
- ec2:DeleteVpcEndpoints
- ec2:DetachInternetGateway
- ec2:DisassociateRouteTable
- ec2:ReplaceRouteTableAssociation



## **NOTE**

If you use an existing VPC, your account does not require these permissions to delete network resources.

## 1.1.4. Creating an IAM user

Each Amazon Web Services (AWS) account contains a root user account that is based on the email address you used to create the account. This is a highly-privileged account, and it is recommended to use it for only initial account and billing configuration, creating an initial set of users, and securing the account.

Before you install OpenShift Container Platform, create a secondary IAM administrative user. As you complete the Creating an IAM User in Your AWS Account procedure in the AWS documentation, set the following options:

#### **Procedure**

- 1. Specify the IAM user name and select **Programmatic access**.
- 2. Attach the **AdministratorAccess** policy to ensure that the account has sufficient permission to create the cluster. This policy provides the cluster with the ability to grant credentials to each OpenShift Container Platform component. The cluster grants the components only the credentials that they require.



#### NOTE

While it is possible to create a policy that grants the all of the required AWS permissions and attach it to the user, this is not the preferred option. The cluster will not have the ability to grant additional credentials to individual components, so the same credentials are used by all components.

- 3. Optional: Add metadata to the user by attaching tags.
- 4. Confirm that the user name that you specified is granted the **AdministratorAccess** policy.
- 5. Record the access key ID and secret access key values. You must use these values when you configure your local machine to run the installation program.



#### **IMPORTANT**

You cannot use a temporary session token that you generated while using a multi-factor authentication device to authenticate to AWS when you deploy a cluster. The cluster continues to use your current AWS credentials to create AWS resources for the entire life of the cluster, so you must use key-based, long-lived credentials.

## 1.1.5. Supported AWS regions

You can deploy an OpenShift Container Platform cluster to the following regions:

- ap-northeast-1 (Tokyo)
- ap-northeast-2 (Seoul)
- ap-south-1 (Mumbai)
- ap-southeast-1 (Singapore)
- ap-southeast-2 (Sydney)
- ca-central-1 (Central)
- eu-central-1 (Frankfurt)
- eu-north-1 (Stockholm)
- eu-west-1 (Ireland)
- eu-west-2 (London)
- eu-west-3 (Paris)

- sa-east-1 (São Paulo)
- us-east-1 (N. Virginia)
- us-east-2 (Ohio)
- us-west-1 (N. California)
- us-west-2 (Oregon)

## **Next steps**

- Install an OpenShift Container Platform cluster:
  - Quickly install a cluster with default options
  - Install a cluster with cloud customizations
  - Install a cluster with network customizations
  - Install a cluster on infrastructure that you provision

## 1.2. INSTALLING A CLUSTER QUICKLY ON AWS

In OpenShift Container Platform version 4.3, you can install a cluster on Amazon Web Services (AWS) that uses the default configuration options.

## **Prerequisites**

- Review details about the OpenShift Container Platform installation and update processes.
- Configure an AWS account to host the cluster.



#### **IMPORTANT**

If you have an AWS profile stored on your computer, it must not use a temporary session token that you generated while using a multi-factor authentication device. The cluster continues to use your current AWS credentials to create AWS resources for the entire life of the cluster, so you must use key-based, long-lived credentials. To generate appropriate keys, see Managing Access Keys for IAM Users in the AWS documentation. You can supply the keys when you run the installation program.

• If you use a firewall, you must configure it to allow the sites that your cluster requires access to.

## 1.2.1. Internet and Telemetry access for OpenShift Container Platform

In OpenShift Container Platform 4.3, you require access to the internet to install and entitle your cluster. The Telemetry service, which runs by default to provide metrics about cluster health and the success of updates, also requires internet access. If your cluster is connected to the internet, Telemetry runs automatically, and your cluster is registered to the Red Hat OpenShift Cluster Manager. From there, you can allocate entitlements to your cluster.

You must have internet access to:

- Access the Red Hat OpenShift Cluster Manager page to download the installation program and perform subscription management and entitlement. If the cluster has internet access and you do not disable Telemetry, that service automatically entitles your cluster. If the Telemetry service cannot entitle your cluster, you must manually entitle it on the Cluster registration page.
- Access Quay.io to obtain the packages that are required to install your cluster.
- Obtain the packages that are required to perform cluster updates.



#### **IMPORTANT**

If your cluster cannot have direct internet access, you can perform a restricted network installation on infrastructure that you provision. During that process, you download the content that is required and use it to populate a mirror registry with the packages that you need to install a cluster and generate the installation program. With some installation types, the environment that you install your cluster in will not require internet access. Before you update the cluster, you update the content of the mirror registry.

## 1.2.2. Generating an SSH private key and adding it to the agent

If you want to perform installation debugging or disaster recovery on your cluster, you must provide an SSH key to both your **ssh-agent** and to the installation program.



#### **NOTE**

In a production environment, you require disaster recovery and debugging.

You can use this key to SSH into the master nodes as the user **core**. When you deploy the cluster, the key is added to the **core** user's ~/.**ssh/authorized\_keys** list.



#### NOTE

You must use a local key, not one that you configured with platform-specific approaches such as AWS key pairs.

## **Procedure**

 If you do not have an SSH key that is configured for password-less authentication on your computer, create one. For example, on a computer that uses a Linux operating system, run the following command:

```
$ ssh-keygen -t rsa -b 4096 -N " \
-f <path>/<file_name> 1
```

Specify the path and file name, such as ~/.ssh/id\_rsa, of the SSH key.

Running this command generates an SSH key that does not require a password in the location that you specified.

2. Start the **ssh-agent** process as a background task:

\$ eval "\$(ssh-agent -s)"

Agent pid 31874

3. Add your SSH private key to the **ssh-agent**:

 $ssh-add < path > / < file_name > 1$ 

Identity added: /home/<you>/<path>/<file\_name> (<computer\_name>)

Specify the path and file name for your SSH private key, such as ~/.ssh/id\_rsa

#### **Next steps**

• When you install OpenShift Container Platform, provide the SSH public key to the installation program.

## 1.2.3. Obtaining the installation program

Before you install OpenShift Container Platform, download the installation file on a local computer.

## **Prerequisites**

- You must install the cluster from a computer that uses Linux or macOS.
- You need 500 MB of local disk space to download the installation program.

#### Procedure

- 1. Access the Infrastructure Provider page on the Red Hat OpenShift Cluster Manager site. If you have a Red Hat account, log in with your credentials. If you do not, create an account.
- 2. Navigate to the page for your installation type, download the installation program for your operating system, and place the file in the directory where you will store the installation configuration files.



#### **IMPORTANT**

The installation program creates several files on the computer that you use to install your cluster. You must keep both the installation program and the files that the installation program creates after you finish installing the cluster.

3. Extract the installation program. For example, on a computer that uses a Linux operating system, run the following command:

\$ tar xvf <installation\_program>.tar.gz

4. From the Pull Secret page on the Red Hat OpenShift Cluster Manager site, download your installation pull secret as a .txt file. This pull secret allows you to authenticate with the services that are provided by the included authorities, including Quay.io, which serves the container images for OpenShift Container Platform components.

## 1.2.4. Deploy the cluster

You can install OpenShift Container Platform on a compatible cloud platform.



#### **IMPORTANT**


You can run the **create cluster** command of the installation program only once, during initial installation.

## **Prerequisites**

- Configure an account with the cloud platform that hosts your cluster.
- Obtain the OpenShift Container Platform installation program and the pull secret for your cluster.

#### **Procedure**

1. Run the installation program:



- For <installation\_directory>, specify the directory name to store the files that the installation program creates.
- 2 To view different installation details, specify **warn**, **debug**, or **error** instead of **info**.



#### **IMPORTANT**

Specify an empty directory. Some installation assets, like bootstrap X.509 certificates have short expiration intervals, so you must not reuse an installation directory. If you want to reuse individual files from another cluster installation, you can copy them into your directory. However, the file names for the installation assets might change between releases. Use caution when copying installation files from an earlier OpenShift Container Platform version.

Provide values at the prompts:

a. Optional: Select an SSH key to use to access your cluster machines.



#### **NOTE**

For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your **ssh-agent** process uses.

- b. Select **aws** as the platform to target.
- c. If you do not have an Amazon Web Services (AWS) profile stored on your computer, enter the AWS access key ID and secret access key for the user that you configured to run the installation program.

- d. Select the AWS region to deploy the cluster to.
- e. Select the base domain for the Route53 service that you configured for your cluster.
- f. Enter a descriptive name for your cluster.
- g. Paste the pull secret that you obtained from the Pull Secret page on the Red Hat OpenShift Cluster Manager site.



#### **NOTE**

If the cloud provider account that you configured on your host does not have sufficient permissions to deploy the cluster, the installation process stops, and the missing permissions are displayed.

When the cluster deployment completes, directions for accessing your cluster, including a link to its web console and credentials for the **kubeadmin** user, display in your terminal.



#### **IMPORTANT**

The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.



#### **IMPORTANT**

You must not delete the installation program or the files that the installation program creates. Both are required to delete the cluster.

2. Optional: Remove or disable the **AdministratorAccess** policy from the IAM account that you used to install the cluster.

## 1.2.5. Installing the CLI

You can install the CLI in order to interact with OpenShift Container Platform using a command-line interface.



#### **IMPORTANT**

If you installed an earlier version of **oc**, you cannot use it to complete all of the commands in OpenShift Container Platform 4.3. Download and install the new version of **oc**.

## Procedure

- 1. From the Infrastructure Provider page on the Red Hat OpenShift Cluster Manager site, navigate to the page for your installation type and click **Download Command-line Tools**
- 2. Click the folder for your operating system and architecture and click the compressed file.



#### **NOTE**

You can install oc on Linux, Windows, or macOS.

- 3. Save the file to your file system.
- 4. Extract the compressed file.
- 5. Place it in a directory that is on your **PATH**.

After you install the CLI, it is available using the oc command:

\$ oc <command>

## 1.2.6. Logging in to the cluster

You can log in to your cluster as a default system user by exporting the cluster **kubeconfig** file. The **kubeconfig** file contains information about the cluster that is used by the CLI to connect a client to the correct cluster and API server. The file is specific to a cluster and is created during OpenShift Container Platform installation.

## **Prerequisites**

- Deploy an OpenShift Container Platform cluster.
- Install the oc CLI.

#### **Procedure**

- 1. Export the **kubeadmin** credentials:
  - \$ export KUBECONFIG=<installation\_directory>/auth/kubeconfig 1
  - 1 For **<installation\_directory>**, specify the path to the directory that you stored the installation files in.
- 2. Verify you can run **oc** commands successfully using the exported configuration:

\$ oc whoami system:admin

## **Next steps**

- Customize your cluster.
- If necessary, you can opt out of remote health reporting .

## 1.3. INSTALLING A CLUSTER ON AWS WITH CUSTOMIZATIONS

In OpenShift Container Platform version 4.3, you can install a customized cluster on infrastructure that the installation program provisions on Amazon Web Services (AWS). To customize the installation, you modify parameters in the **install-config.yaml** file before you install the cluster.

## **Prerequisites**

• Review details about the OpenShift Container Platform installation and update processes.

Configure an AWS account to host the cluster.



#### **IMPORTANT**

If you have an AWS profile stored on your computer, it must not use a temporary session token that you generated while using a multi-factor authentication device. The cluster continues to use your current AWS credentials to create AWS resources for the entire life of the cluster, so you must use long-lived credentials. To generate appropriate keys, see Managing Access Keys for IAM Users in the AWS documentation. You can supply the keys when you run the installation program.

• If you use a firewall, you must configure it to allow the sites that your cluster requires access to.

## 1.3.1. Internet and Telemetry access for OpenShift Container Platform

In OpenShift Container Platform 4.3, you require access to the internet to install and entitle your cluster. The Telemetry service, which runs by default to provide metrics about cluster health and the success of updates, also requires internet access. If your cluster is connected to the internet, Telemetry runs automatically, and your cluster is registered to the Red Hat OpenShift Cluster Manager. From there, you can allocate entitlements to your cluster.

You must have internet access to:

- Access the Red Hat OpenShift Cluster Manager page to download the installation program and perform subscription management and entitlement. If the cluster has internet access and you do not disable Telemetry, that service automatically entitles your cluster. If the Telemetry service cannot entitle your cluster, you must manually entitle it on the Cluster registration page.
- Access Quay.io to obtain the packages that are required to install your cluster.
- Obtain the packages that are required to perform cluster updates.



#### **IMPORTANT**

If your cluster cannot have direct internet access, you can perform a restricted network installation on infrastructure that you provision. During that process, you download the content that is required and use it to populate a mirror registry with the packages that you need to install a cluster and generate the installation program. With some installation types, the environment that you install your cluster in will not require internet access. Before you update the cluster, you update the content of the mirror registry.

## 1.3.2. Generating an SSH private key and adding it to the agent

If you want to perform installation debugging or disaster recovery on your cluster, you must provide an SSH key to both your **ssh-agent** and to the installation program.



## NOTE

In a production environment, you require disaster recovery and debugging.

You can use this key to SSH into the master nodes as the user **core**. When you deploy the cluster, the key is added to the **core** user's ~/.**ssh/authorized\_keys** list.



#### **NOTE**

You must use a local key, not one that you configured with platform-specific approaches such as AWS key pairs.

#### **Procedure**

1. If you do not have an SSH key that is configured for password-less authentication on your computer, create one. For example, on a computer that uses a Linux operating system, run the following command:

```
$ ssh-keygen -t rsa -b 4096 -N " \
-f <path>/<file_name> 1
```

Specify the path and file name, such as ~/.ssh/id\_rsa, of the SSH key.

Running this command generates an SSH key that does not require a password in the location that you specified.

2. Start the **ssh-agent** process as a background task:

```
$ eval "$(ssh-agent -s)"
Agent pid 31874
```

3. Add your SSH private key to the **ssh-agent**:

```
$ ssh-add <path>/<file_name> 1

Identity added: /home/<you>/<path>/<file_name> (<computer_name>)
```

Specify the path and file name for your SSH private key, such as ~/.ssh/id\_rsa

## Next steps

 When you install OpenShift Container Platform, provide the SSH public key to the installation program.

## 1.3.3. Obtaining the installation program

Before you install OpenShift Container Platform, download the installation file on a local computer.

## **Prerequisites**

- You must install the cluster from a computer that uses Linux or macOS.
- You need 500 MB of local disk space to download the installation program.

## **Procedure**

1. Access the Infrastructure Provider page on the Red Hat OpenShift Cluster Manager site. If you have a Red Hat account, log in with your credentials. If you do not, create an account.

2. Navigate to the page for your installation type, download the installation program for your operating system, and place the file in the directory where you will store the installation configuration files.



#### **IMPORTANT**

The installation program creates several files on the computer that you use to install your cluster. You must keep both the installation program and the files that the installation program creates after you finish installing the cluster.

- 3. Extract the installation program. For example, on a computer that uses a Linux operating system, run the following command:
  - \$ tar xvf <installation\_program>.tar.gz
- 4. From the Pull Secret page on the Red Hat OpenShift Cluster Manager site, download your installation pull secret as a .txt file. This pull secret allows you to authenticate with the services that are provided by the included authorities, including Quay.io, which serves the container images for OpenShift Container Platform components.

## 1.3.4. Creating the installation configuration file

You can customize your installation of OpenShift Container Platform on Amazon Web Services (AWS).

## **Prerequisites**

 Obtain the OpenShift Container Platform installation program and the pull secret for your cluster.

## Procedure

- 1. Create the **install-config.yaml** file.
  - a. Run the following command:
    - \$ ./openshift-install create install-config --dir=<installation\_directory> 1
    - For **<installation\_directory>**, specify the directory name to store the files that the installation program creates.



## **IMPORTANT**

Specify an empty directory. Some installation assets, like bootstrap X.509 certificates have short expiration intervals, so you must not reuse an installation directory. If you want to reuse individual files from another cluster installation, you can copy them into your directory. However, the file names for the installation assets might change between releases. Use caution when copying installation files from an earlier OpenShift Container Platform version.

b. At the prompts, provide the configuration details for your cloud:

i. Optional: Select an SSH key to use to access your cluster machines.



#### NOTE

For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your **ssh-agent** process uses.

- ii. Select **AWS** as the platform to target.
- iii. If you do not have an Amazon Web Services (AWS) profile stored on your computer, enter the AWS access key ID and secret access key for the user that you configured to run the installation program.
- iv. Select the AWS region to deploy the cluster to.
- v. Select the base domain for the Route53 service that you configured for your cluster.
- vi. Enter a descriptive name for your cluster.
- vii. Paste the pull secret that you obtained from the Pull Secret page on the Red Hat OpenShift Cluster Manager site.
- 2. Modify the **install-config.yaml** file. You can find more information about the available parameters in the **Installation configuration parameters** section.
- 3. Back up the **install-config.yaml** file so that you can use it to install multiple clusters.



## **IMPORTANT**

The **install-config.yaml** file is consumed during the installation process. If you want to reuse the file, you must back it up now.

## 1.3.4.1. Installation configuration parameters

Before you deploy an OpenShift Container Platform cluster, you provide parameter values to describe your account on the cloud platform that hosts your cluster and optionally customize your cluster's platform. When you create the **install-config.yaml** installation configuration file, you provide values for the required parameters through the command line. If you customize your cluster, you can modify the **install-config.yaml** file to provide more details about the platform.



## NOTE

You cannot modify these parameters in the **install-config.yaml** file after installation.

## Table 1.1. Required parameters

Parameter	Description	Values	

Parameter	Description	Values
baseDomain	The base domain of your cloud provider. This value is used to create routes to your OpenShift Container Platform cluster components. The full DNS name for your cluster is a combination of the baseDomain and metadata.name parameter values that uses the <metadata.name>.   &lt;</metadata.name>	A fully-qualified domain or subdomain name, such as <b>example.com</b> .
controlPlane.pla tform	The cloud provider to host the control plane machines. This parameter value must match the <b>compute.platform</b> parameter value.	aws, azure, gcp, openstack, or {}
compute.platfor m	The cloud provider to host the worker machines. This parameter value must match the <b>controlPlane.platform</b> parameter value.	aws, azure, gcp, openstack, or {}
metadata.name	The name of your cluster.	A string that contains uppercase or lowercase letters, such as <b>dev</b> .
platform. <platform>.regi on</platform>	The region to deploy your cluster in.	A valid region for your cloud, such as <b>us-east-1</b> for AWS, <b>centralus</b> for Azure, or <b>region1</b> for Red Hat OpenStack Platform (RHOSP).
pullSecret	The pull secret that you obtained from the Pull Secret page on the Red Hat OpenShift Cluster Manager site. You use this pull secret to authenticate with the services that are provided by the included authorities, including Quay.io, which serves the container images for OpenShift Container Platform components.	{     "auths":{         "cloud.openshift.com":{             "auth":"b3Blb=",             "email":"you@example.com"         },         "quay.io":{             "auth":"b3Blb=",             "email":"you@example.com"         }     } }

Table 1.2. Optional parameters

Parameter	Description	Values
sshKey	The SSH key to use to access your cluster machines.	A valid, local public SSH key that you added to the <b>ssh-agent</b> process.
	For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your ssh-agent process uses.	
fips	Whether to enable or disable FIPS mode. By default, FIPS mode is not enabled. If FIPS mode is enabled, the Red Hat Enterprise Linux CoreOS (RHCOS) machines that OpenShift Container Platform runs on bypass the default Kubernetes cryptography suite and use the FIPS validated cryptography modules that are provided with RHCOS instead.	false or true
publish	How to publish the user-facing endpoints of your cluster.	Internal or External. Set publish to Internal to deploy a private cluster, which cannot be accessed from the internet. The default value is External.
compute.hyperthrea ding	Whether to enable or disable simultaneous multithreading, or hyperthreading, on compute machines. By default, simultaneous multithreading is enabled to increase the performance of your machines' cores.	Enabled or Disabled
	IMPORTANT  If you disable simultaneous multithreading, ensure that your capacity planning accounts for the dramatically decreased machine performance.	

Parameter	Description	Values
compute.replicas	The number of compute, or worker, machines to provision.	A positive integer greater than or equal to <b>2</b> . The default value is <b>3</b> .
controlPlane.hypert hreading	Whether to enable or disable simultaneous multithreading, or hyperthreading, on control plane machines. By default, simultaneous multithreading is enabled to increase the performance of your machines' cores.  IMPORTANT  If you disable simultaneous multithreading, ensure that your capacity planning accounts for the dramatically decreased machine performance.	Enabled or Disabled
controlPlane.replica s	The number of control plane machines to provision.	A positive integer greater than or equal to <b>3</b> . The default value is <b>3</b> .

Table 1.3. Optional AWS parameters

Parameter	Description	Values
compute.platfor m.aws.rootVolu me.iops	The Input/Output Operations Per Second (IOPS) that is reserved for the root volume.	Integer, for example <b>4000</b> .
compute.platfor m.aws.rootVolu me.size	The size in GiB of the root volume.	Integer, for example <b>500</b> .
compute.platfor m.aws.rootVolu me.type	The instance type of the root volume.	Valid AWS EBS instance type, such as <b>io1</b> .
compute.platfor m.aws.type	The EC2 instance type for the compute machines.	Valid AWS instance type, such as <b>c5.9xlarge</b> .

Parameter	Description	Values
compute.platfor m.aws.zones	The availability zones where the installation program creates machines for the compute MachinePool. If you provide your own VPC, you must provide a subnet in that availability zone.	A list of valid AWS availability zones, such as <b>us-east-1c</b> , in a YAML sequence.
compute.aws.re gion	The AWS region that the installation program creates compute resources in.	Valid AWS region, such as <b>us-east-1</b> .
controlPlane.pla tform.aws.type	The EC2 instance type for the control plane machines.	Valid AWS instance type, such as <b>c5.9xlarge</b> .
controlPlane.pla tform.aws.zone s	The availability zones where the installation program creates machines for the control plane MachinePool.	A list of valid AWS availability zones, such as <b>useast-1c</b> , in a YAML sequence.
controlPlane.aw s.region	The AWS region that the installation program creates control plane resources in.	Valid AWS region, such as <b>us-east-1</b> .
platform.aws.us erTags	A map of keys and values that the installation program adds as tags to all resources that it creates.	Any valid YAML map, such as key value pairs in the <b><key>: <value></value></key></b> format. For more information about AWS tags, see Tagging Your Amazon EC2 Resources in the AWS documentation.
platform.aws.su bnets	If you provide the VPC instead of allowing the installation program to create the VPC for you, specify the subnets for the cluster to use. The subnets must be part of the same <b>machineCIDR</b> range that you specify. For a standard cluster, specify a public and a private subnet for each availability zone. For a private cluster, specify a private subnet for each availability zone.	Valid subnet range.

## 1.3.4.2. Sample customized install-config.yaml file for AWS

You can customize the **install-config.yaml** file to specify more details about your OpenShift Container Platform cluster's platform or modify the values of the required parameters.



#### **IMPORTANT**

This sample YAML file is provided for reference only. You must obtain your **install-config.yaml** file by using the installation program and modify it.

```
apiVersion: v1
baseDomain: example.com 1
controlPlane: 2
 hyperthreading: Enabled 3 4
 name: master
 platform:
  aws:
   zones:
   - us-west-2a
   - us-west-2b
   rootVolume:
    iops: 4000
    size: 500
    type: io1
   type: m5.xlarge 5
 replicas: 3
compute: 6
- hyperthreading: Enabled 7
 name: worker
 platform:
  aws:
   rootVolume:
    iops: 2000
    size: 500
    type: io1 8
   type: c5.4xlarge
   zones:
   - us-west-2c
 replicas: 3
metadata:
 name: test-cluster 9
networking:
 clusterNetwork:
 - cidr: 10.128.0.0/14
  hostPrefix: 23
 machineCIDR: 10.0.0.0/16
 networkType: OpenShiftSDN
 serviceNetwork:
 - 172.30.0.0/16
platform:
 aws:
  region: us-west-2 10
  userTags:
   adminContact: jdoe
   costCenter: 7536
pullSecret: '{"auths": ...}' 11
fips: false 12
sshKey: ssh-ed25519 AAAA... 13
```

- 1 9 10 11 Required. The installation program prompts you for this value.
- 26 If you do not provide these parameters and values, the installation program provides the default value.
- The **controlPlane** section is a single mapping, but the compute section is a sequence of mappings. To meet the requirements of the different data structures, the first line of the **compute** section must begin with a hyphen, -, and the first line of the **controlPlane** section must not. Although both sections currently define a single machine pool, it is possible that future versions of OpenShift Container Platform will support defining multiple compute pools during installation. Only one control plane pool is used.
- Whether to enable or disable simultaneous multithreading, or **hyperthreading**. By default, simultaneous multithreading is enabled to increase the performance of your machines' cores. You can disable it by setting the parameter value to **Disabled**. If you disable simultaneous multithreading in some cluster machines, you must disable it in all cluster machines.



## **IMPORTANT**

If you disable simultaneous multithreading, ensure that your capacity planning accounts for the dramatically decreased machine performance. Use larger instance types, such as **m4.2xlarge** or **m5.2xlarge**, for your machines if you disable simultaneous multithreading.

- To configure faster storage for etcd, especially for larger clusters, set the storage type as **io1** and set **iops** to **2000**.
- Whether to enable or disable FIPS mode. By default, FIPS mode is not enabled. If FIPS mode is enabled, the Red Hat Enterprise Linux CoreOS (RHCOS) machines that OpenShift Container Platform runs on bypass the default Kubernetes cryptography suite and use the FIPS validated cryptography modules that are provided with RHCOS instead.
- You can optionally provide the **sshKey** value that you use to access the machines in your cluster.



#### NOTE

For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your **ssh-agent** process uses.

## 1.3.5. Deploy the cluster

You can install OpenShift Container Platform on a compatible cloud platform.



#### **IMPORTANT**

You can run the **create cluster** command of the installation program only once, during initial installation.


#### **Prerequisites**

• Configure an account with the cloud platform that hosts your cluster.

 Obtain the OpenShift Container Platform installation program and the pull secret for your cluster.

#### **Procedure**

1. Run the installation program:



- For <installation\_directory>, specify the location of your customized ./install-config.yaml file.
- To view different installation details, specify warn, debug, or error instead of info.



## **NOTE**

If the cloud provider account that you configured on your host does not have sufficient permissions to deploy the cluster, the installation process stops, and the missing permissions are displayed.

When the cluster deployment completes, directions for accessing your cluster, including a link to its web console and credentials for the **kubeadmin** user, display in your terminal.



#### **IMPORTANT**

The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.



#### **IMPORTANT**

You must not delete the installation program or the files that the installation program creates. Both are required to delete the cluster.

2. Optional: Remove or disable the **AdministratorAccess** policy from the IAM account that you used to install the cluster.

## 1.3.6. Installing the CLI

You can install the CLI in order to interact with OpenShift Container Platform using a command-line interface.



## **IMPORTANT**

If you installed an earlier version of **oc**, you cannot use it to complete all of the commands in OpenShift Container Platform 4.3. Download and install the new version of **oc**.

## Procedure

- 1. From the Infrastructure Provider page on the Red Hat OpenShift Cluster Manager site, navigate to the page for your installation type and click **Download Command-line Tools**
- 2. Click the folder for your operating system and architecture and click the compressed file.



#### **NOTE**

You can install oc on Linux, Windows, or macOS.

- 3. Save the file to your file system.
- 4. Extract the compressed file.
- 5. Place it in a directory that is on your **PATH**.

After you install the CLI, it is available using the **oc** command:

\$ oc <command>

## 1.3.7. Logging in to the cluster

You can log in to your cluster as a default system user by exporting the cluster **kubeconfig** file. The **kubeconfig** file contains information about the cluster that is used by the CLI to connect a client to the correct cluster and API server. The file is specific to a cluster and is created during OpenShift Container Platform installation.

## **Prerequisites**

- Deploy an OpenShift Container Platform cluster.
- Install the oc CLI.

#### **Procedure**

- 1. Export the **kubeadmin** credentials:
  - \$ export KUBECONFIG=<installation\_directory>/auth/kubeconfig 1
  - For **<installation\_directory>**, specify the path to the directory that you stored the installation files in.
- 2. Verify you can run **oc** commands successfully using the exported configuration:

\$ oc whoami system:admin

## **Next steps**

- Customize your cluster.
- If necessary, you can opt out of remote health reporting.

# 1.4. INSTALLING A CLUSTER ON AWS WITH NETWORK CUSTOMIZATIONS

In OpenShift Container Platform version 4.3, you can install a cluster on Amazon Web Services (AWS) with customized network configuration options. By customizing your network configuration, your cluster can coexist with existing IP address allocations in your environment and integrate with existing MTU and VXLAN configurations.

You must set most of the network configuration parameters during installation, and you can modify only **kubeProxy** configuration parameters in a running cluster.

## **Prerequisites**

- Review details about the OpenShift Container Platform installation and update processes.
- Configure an AWS account to host the cluster.



## **IMPORTANT**

If you have an AWS profile stored on your computer, it must not use a temporary session token that you generated while using a multi-factor authentication device. The cluster continues to use your current AWS credentials to create AWS resources for the entire life of the cluster, so you must use key-based, long-lived credentials. To generate appropriate keys, see Managing Access Keys for IAM Users in the AWS documentation. You can supply the keys when you run the installation program.

• If you use a firewall, you must configure it to allow the sites that your cluster requires access to.

# 1.4.1. Internet and Telemetry access for OpenShift Container Platform

In OpenShift Container Platform 4.3, you require access to the internet to install and entitle your cluster. The Telemetry service, which runs by default to provide metrics about cluster health and the success of updates, also requires internet access. If your cluster is connected to the internet, Telemetry runs automatically, and your cluster is registered to the Red Hat OpenShift Cluster Manager. From there, you can allocate entitlements to your cluster.

You must have internet access to:

- Access the Red Hat OpenShift Cluster Manager page to download the installation program and perform subscription management and entitlement. If the cluster has internet access and you do not disable Telemetry, that service automatically entitles your cluster. If the Telemetry service cannot entitle your cluster, you must manually entitle it on the Cluster registration page.
- Access Quay.io to obtain the packages that are required to install your cluster.
- Obtain the packages that are required to perform cluster updates.



If your cluster cannot have direct internet access, you can perform a restricted network installation on infrastructure that you provision. During that process, you download the content that is required and use it to populate a mirror registry with the packages that you need to install a cluster and generate the installation program. With some installation types, the environment that you install your cluster in will not require internet access. Before you update the cluster, you update the content of the mirror registry.

# 1.4.2. Generating an SSH private key and adding it to the agent

If you want to perform installation debugging or disaster recovery on your cluster, you must provide an SSH key to both your **ssh-agent** and to the installation program.



#### NOTE

In a production environment, you require disaster recovery and debugging.

You can use this key to SSH into the master nodes as the user **core**. When you deploy the cluster, the key is added to the **core** user's ~/.**ssh/authorized\_keys** list.



#### **NOTE**

You must use a local key, not one that you configured with platform-specific approaches such as AWS key pairs.

## **Procedure**

1. If you do not have an SSH key that is configured for password-less authentication on your computer, create one. For example, on a computer that uses a Linux operating system, run the following command:

```
$ ssh-keygen -t rsa -b 4096 -N " \
-f <path>/<file_name> 1
```

Specify the path and file name, such as ~/.ssh/id\_rsa, of the SSH key.

Running this command generates an SSH key that does not require a password in the location that you specified.

2. Start the **ssh-agent** process as a background task:

```
$ eval "$(ssh-agent -s)"
Agent pid 31874
```

3. Add your SSH private key to the **ssh-agent**:

```
$ ssh-add <path>/<file_name> 1

Identity added: /home/<you>/<path>/<file_name> (<computer_name>)
```



Specify the path and file name for your SSH private key, such as ~/.ssh/id\_rsa

## **Next steps**

• When you install OpenShift Container Platform, provide the SSH public key to the installation program.

# 1.4.3. Obtaining the installation program

Before you install OpenShift Container Platform, download the installation file on a local computer.

## **Prerequisites**

- You must install the cluster from a computer that uses Linux or macOS.
- You need 500 MB of local disk space to download the installation program.

#### **Procedure**

- 1. Access the Infrastructure Provider page on the Red Hat OpenShift Cluster Manager site. If you have a Red Hat account, log in with your credentials. If you do not, create an account.
- 2. Navigate to the page for your installation type, download the installation program for your operating system, and place the file in the directory where you will store the installation configuration files.



## **IMPORTANT**

The installation program creates several files on the computer that you use to install your cluster. You must keep both the installation program and the files that the installation program creates after you finish installing the cluster.

- 3. Extract the installation program. For example, on a computer that uses a Linux operating system, run the following command:
  - \$ tar xvf <installation\_program>.tar.gz
- 4. From the Pull Secret page on the Red Hat OpenShift Cluster Manager site, download your installation pull secret as a .txt file. This pull secret allows you to authenticate with the services that are provided by the included authorities, including Quay.io, which serves the container images for OpenShift Container Platform components.

# 1.4.4. Creating the installation configuration file

You can customize your installation of OpenShift Container Platform on Amazon Web Services (AWS).

## **Prerequisites**

 Obtain the OpenShift Container Platform installation program and the pull secret for your cluster.

## **Procedure**

- 1. Create the **install-config.yaml** file.
  - a. Run the following command:
    - \$./openshift-install create install-config --dir=<installation\_directory> 1
    - For **<installation\_directory>**, specify the directory name to store the files that the installation program creates.



Specify an empty directory. Some installation assets, like bootstrap X.509 certificates have short expiration intervals, so you must not reuse an installation directory. If you want to reuse individual files from another cluster installation, you can copy them into your directory. However, the file names for the installation assets might change between releases. Use caution when copying installation files from an earlier OpenShift Container Platform version.

- b. At the prompts, provide the configuration details for your cloud:
  - i. Optional: Select an SSH key to use to access your cluster machines.



#### NOTE

For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your **ssh-agent** process uses.

- ii. Select AWS as the platform to target.
- iii. If you do not have an Amazon Web Services (AWS) profile stored on your computer, enter the AWS access key ID and secret access key for the user that you configured to run the installation program.
- iv. Select the AWS region to deploy the cluster to.
- v. Select the base domain for the Route53 service that you configured for your cluster.
- vi. Enter a descriptive name for your cluster.
- vii. Paste the pull secret that you obtained from the Pull Secret page on the Red Hat OpenShift Cluster Manager site.
- 2. Modify the **install-config.yaml** file. You can find more information about the available parameters in the **Installation configuration parameters** section.
- 3. Back up the install-config.yaml file so that you can use it to install multiple clusters.



## **IMPORTANT**

The **install-config.yaml** file is consumed during the installation process. If you want to reuse the file, you must back it up now.

# 1.4.4.1. Installation configuration parameters

Before you deploy an OpenShift Container Platform cluster, you provide parameter values to describe your account on the cloud platform that hosts your cluster and optionally customize your cluster's platform. When you create the **install-config.yaml** installation configuration file, you provide values for the required parameters through the command line. If you customize your cluster, you can modify the **install-config.yaml** file to provide more details about the platform.



## NOTE

You cannot modify these parameters in the **install-config.yaml** file after installation.

Table 1.4. Required parameters

Parameter	Description	Values
baseDomain	The base domain of your cloud provider. This value is used to create routes to your OpenShift Container Platform cluster components. The full DNS name for your cluster is a combination of the baseDomain and metadata.name parameter values that uses the <metadata.name>. <basedomain> format.</basedomain></metadata.name>	A fully-qualified domain or subdomain name, such as example.com.
controlPlane.pla tform	The cloud provider to host the control plane machines. This parameter value must match the <b>compute.platform</b> parameter value.	aws, azure, gcp, openstack, or {}
compute.platfor m	The cloud provider to host the worker machines. This parameter value must match the <b>controlPlane.platform</b> parameter value.	aws, azure, gcp, openstack, or {}
metadata.name	The name of your cluster.	A string that contains uppercase or lowercase letters, such as <b>dev</b> .
platform. <platform>.regi on</platform>	The region to deploy your cluster in.	A valid region for your cloud, such as <b>us-east-1</b> for AWS, <b>centralus</b> for Azure, or <b>region1</b> for Red Hat OpenStack Platform (RHOSP).

Parameter	Description	Values
pullSecret	The pull secret that you obtained from the Pull Secret page on the Red Hat OpenShift Cluster Manager site. You use this pull secret to authenticate with the services that are provided by the included authorities, including Quay.io, which serves the container images for OpenShift Container Platform components.	{     "auths":{         "cloud.openshift.com":{             "auth":"b3Blb=",             "email":"you@example.com"         },         "quay.io":{             "auth":"b3Blb=",             "email":"you@example.com"         }     } }

Table 1.5. Optional parameters

Parameter	Description	Values	
sshKey	The SSH key to use to access your cluster machines.  NOTE  For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your ssh-agent process uses.	A valid, local public SSH key that you added to the <b>ssh-agent</b> process.	
fips	Whether to enable or disable FIPS mode. By default, FIPS mode is not enabled. If FIPS mode is enabled, the Red Hat Enterprise Linux CoreOS (RHCOS) machines that OpenShift Container Platform runs on bypass the default Kubernetes cryptography suite and use the FIPS validated cryptography modules that are provided with RHCOS instead.	false or true	
publish	How to publish the user-facing endpoints of your cluster.	Internal or External. Set publish to Internal to deploy a private cluster, which cannot be accessed from the internet. The default value is External.	

Parameter	Description	Values
compute.hyperthrea ding	Whether to enable or disable simultaneous multithreading, or hyperthreading, on compute machines. By default, simultaneous multithreading is enabled to increase the performance of your machines' cores.	Enabled or Disabled
	IMPORTANT  If you disable simultaneous multithreading, ensure that your capacity planning accounts for the dramatically decreased machine performance.	
compute.replicas	The number of compute, or worker, machines to provision.	A positive integer greater than or equal to <b>2</b> . The default value is <b>3</b> .
controlPlane.hypert hreading	Whether to enable or disable simultaneous multithreading, or hyperthreading, on control plane machines. By default, simultaneous multithreading is enabled to increase the performance of your machines' cores.  IMPORTANT  If you disable simultaneous multithreading, ensure that your capacity planning accounts for the dramatically decreased machine performance.	Enabled or Disabled
controlPlane.replica	The number of control plane machines to provision.	A positive integer greater than or equal to <b>3</b> . The default value is <b>3</b> .

Table 1.6. Optional AWS parameters

Parameter	Description	Values
compute.platfor m.aws.rootVolu me.iops	The Input/Output Operations Per Second (IOPS) that is reserved for the root volume.	Integer, for example <b>4000</b> .
compute.platfor m.aws.rootVolu me.size	The size in GiB of the root volume.	Integer, for example <b>500</b> .
compute.platfor m.aws.rootVolu me.type	The instance type of the root volume.	Valid AWS EBS instance type, such as <b>io1</b> .
compute.platfor m.aws.type	The EC2 instance type for the compute machines.	Valid AWS instance type, such as <b>c5.9xlarge</b> .
compute.platfor m.aws.zones	The availability zones where the installation program creates machines for the compute MachinePool. If you provide your own VPC, you must provide a subnet in that availability zone.	A list of valid AWS availability zones, such as <b>useast-1c</b> , in a YAML sequence.
compute.aws.re gion	The AWS region that the installation program creates compute resources in.	Valid AWS region, such as <b>us-east-1</b> .
controlPlane.pla tform.aws.type	The EC2 instance type for the control plane machines.	Valid AWS instance type, such as <b>c5.9xlarge</b> .
controlPlane.pla tform.aws.zone s	The availability zones where the installation program creates machines for the control plane MachinePool.	A list of valid AWS availability zones, such as <b>us-east-1c</b> , in a YAML sequence.
controlPlane.aw s.region	The AWS region that the installation program creates control plane resources in.	Valid AWS region, such as <b>us-east-1</b> .
platform.aws.us erTags	A map of keys and values that the installation program adds as tags to all resources that it creates.	Any valid YAML map, such as key value pairs in the <b><key>: <value></value></key></b> format. For more information about AWS tags, see Tagging Your Amazon EC2 Resources in the AWS documentation.

Parameter	Description	Values
platform.aws.su bnets	If you provide the VPC instead of allowing the installation program to create the VPC for you, specify the subnets for the cluster to use. The subnets must be part of the same <b>machineCIDR</b> range that you specify. For a standard cluster, specify a public and a private subnet for each availability zone. For a private cluster, specify a private subnet for each availability zone.	Valid subnet range.



The Open Virtual Networking (OVN) Kubernetes network plug-in is a Technology Preview feature only. Technology Preview features are not supported with Red Hat production service level agreements (SLAs) and might not be functionally complete. Red Hat does not recommend using them in production. These features provide early access to upcoming product features, enabling customers to test functionality and provide feedback during the development process.

For more information about the support scope of the OVN Technology Preview, see https://access.redhat.com/articles/4380121.

# 1.4.4.2. Network configuration parameters

You can modify your cluster network configuration parameters in the **install-config.yaml** configuration file. The following table describes the parameters.



## NOTE

You cannot modify these parameters in the **install-config.yaml** file after installation.

Table 1.7. Required network parameters

Parameter	Description	Value
networking.net workType	The network plug-in to deploy. The <b>OpenShiftSDN</b> plug-in is the only plug-in supported in OpenShift Container Platform 4.3. The <b>OVNKubernetes</b> plug-in is available as Technology Preview in OpenShift Container Platform 4.2.	Either <b>OpenShiftSDN</b> or <b>OVNKubernetes</b> . The default value is <b>OpenShiftSDN</b> .

Parameter	Description	Value
networking.clus terNetwork.cidr	A block of IP addresses from which Pod IP addresses are allocated. The <b>OpenShiftSDN</b> network plug-in supports multiple cluster networks. The address blocks for multiple cluster networks must not overlap. Select address pools large enough to fit your anticipated workload.	An IP address allocation in CIDR format. The default value is <b>10.128.0.0/14</b> .
networking.clus terNetwork.host Prefix	The subnet prefix length to assign to each individual node. For example, if <b>hostPrefix</b> is set to <b>23</b> , then each node is assigned a <b>/23</b> subnet out of the given <b>cidr</b> , allowing for 510 (2^(32 - 23) - 2) Pod IP addresses.	A subnet prefix. The default value is <b>23</b> .
networking.serv iceNetwork	A block of IP addresses for services. <b>OpenShiftSDN</b> allows only one <b>serviceNetwork</b> block. The address block must not overlap with any other network block.	An IP address allocation in CIDR format. The default value is <b>172.30.0.0/16</b> .
networking.mac hineCIDR	A block of IP addresses used by the OpenShift Container Platform installation program while installing the cluster. The address block must not overlap with any other network block.	An IP address allocation in CIDR format. The default value is <b>10.0.0.0/16</b> .


# 1.4.4.3. Sample customized install-config.yaml file for AWS

You can customize the **install-config.yaml** file to specify more details about your OpenShift Container Platform cluster's platform or modify the values of the required parameters.



## **IMPORTANT**

This sample YAML file is provided for reference only. You must obtain your **install-config.yaml** file by using the installation program and modify it.



```
compute: 6
- hyperthreading: Enabled 7
 name: worker
 platform:
  aws:
   rootVolume:
    iops: 2000
    size: 500
    type: io1 8
   type: c5.4xlarge
   zones:
   - us-west-2c
 replicas: 3
metadata:
 name: test-cluster 9
networking: 10
 clusterNetwork:
 - cidr: 10.128.0.0/14
  hostPrefix: 23
 machineCIDR: 10.0.0.0/16
 networkType: OpenShiftSDN
 serviceNetwork:
 - 172.30.0.0/16
platform:
  region: us-west-2 111
  userTags:
   adminContact: jdoe
   costCenter: 7536
pullSecret: '{"auths": ...}' 12
fips: false 13
sshKey: ssh-ed25519 AAAA... 14
```

- 1 9 11 12 Required. The installation program prompts you for this value.
- 2 6 10 If you do not provide these parameters and values, the installation program provides the default value.
- The **controlPlane** section is a single mapping, but the compute section is a sequence of mappings. To meet the requirements of the different data structures, the first line of the **compute** section must begin with a hyphen, -, and the first line of the **controlPlane** section must not. Although both sections currently define a single machine pool, it is possible that future versions of OpenShift Container Platform will support defining multiple compute pools during installation. Only one control plane pool is used.
- Whether to enable or disable simultaneous multithreading, or **hyperthreading**. By default, simultaneous multithreading is enabled to increase the performance of your machines' cores. You can disable it by setting the parameter value to **Disabled**. If you disable simultaneous multithreading in some cluster machines, you must disable it in all cluster machines.



If you disable simultaneous multithreading, ensure that your capacity planning accounts for the dramatically decreased machine performance. Use larger instance types, such as **m4.2xlarge** or **m5.2xlarge**, for your machines if you disable simultaneous multithreading.

- To configure faster storage for etcd, especially for larger clusters, set the storage type as **io1** and set iops to 2000.
- Whether to enable or disable FIPS mode. By default, FIPS mode is not enabled. If FIPS mode is enabled, the Red Hat Enterprise Linux CoreOS (RHCOS) machines that OpenShift Container Platform runs on bypass the default Kubernetes cryptography suite and use the FIPS validated cryptography modules that are provided with RHCOS instead.
- You can optionally provide the **sshKey** value that you use to access the machines in your cluster.



#### **NOTE**

For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your sshagent process uses.

# 1.4.5. Modifying advanced network configuration parameters

You can modify the advanced network configuration parameters only before you install the cluster. Advanced configuration customization lets you integrate your cluster into your existing network environment by specifying an MTU or VXLAN port, by allowing customization of kube-proxy settings, and by specifying a different mode for the openshiftSDNConfig parameter.



## **IMPORTANT**

Modifying the OpenShift Container Platform manifest files directly is not supported.

# **Prerequisites**

• Create the **install-config.yaml** file and complete any modifications to it.

#### **Procedure**

- 1. Use the following command to create manifests:
  - ./openshift-install create manifests --dir=<installation\_directory>
  - For <installation\_directory>, specify the name of the directory that contains the installconfig.yaml file for your cluster.
- 2. Create a file that is named cluster-network-03-config.yml in the <installation\_directory>/manifests/ directory:

\$ touch <installation\_directory>/manifests/cluster-network-03-config.yml



1

For **<installation\_directory>**, specify the directory name that contains the **manifests**/ directory for your cluster.

After creating the file, several network configuration files are in the **manifests**/ directory, as shown:

\$ Is <installation\_directory>/manifests/cluster-network-\* cluster-network-01-crd.yml cluster-network-02-config.yml cluster-network-03-config.yml

3. Open the **cluster-network-03-config.yml** file in an editor and enter a CR that describes the Operator configuration you want:

apiVersion: operator.openshift.io/v1

kind: Network metadata: name: cluster spec: 1

oluotorN

clusterNetwork:

cidr: 10.128.0.0/14 hostPrefix: 23 serviceNetwork:172.30.0.0/16 defaultNetwork:

type: OpenShiftSDN openshiftSDNConfig: mode: NetworkPolicy

mtu: 1450 vxlanPort: 4789

The parameters for the **spec** parameter are only an example. Specify your configuration for the Cluster Network Operator in the CR.

The CNO provides default values for the parameters in the CR, so you must specify only the parameters that you want to change.

- 4. Save the **cluster-network-03-config.yml** file and quit the text editor.
- 5. Optional: Back up the **manifests/cluster-network-03-config.yml** file. The installation program deletes the **manifests**/ directory when creating the cluster.

# 1.4.6. Cluster Network Operator custom resource (CR)

The cluster network configuration in the **Network.operator.openshift.io** custom resource (CR) stores the configuration settings for the Cluster Network Operator (CNO). The Operator manages the cluster network.

You can specify the cluster network configuration for your OpenShift Container Platform cluster by setting the parameters for the **defaultNetwork** parameter in the CNO CR. The following CR displays the default configuration for the CNO and explains both the parameters you can configure and valid parameter values:

## Cluster Network Operator CR

apiVersion: operator.openshift.io/v1 kind: Network metadata: name: cluster spec: clusterNetwork: 1 - cidr: 10.128.0.0/14 hostPrefix: 23 serviceNetwork: 2 - 172.30.0.0/16 defaultNetwork: 3 kubeProxyConfig: 4 iptablesSyncPeriod: 30s 5 proxyArguments: iptables-min-sync-period: 6 - 30s

- Specified in the install-config.yaml file.
- Configures the software-defined networking (SDN) for the cluster network.
- The parameters for this object specify the **kube-proxy** configuration. If you do not specify the parameter values, the Network Operator applies the displayed default parameter values.
- The refresh period for **iptables** rules. The default value is **30s**. Valid suffixes include **s**, **m**, and **h** and are described in the Go time package documentation.
- The minimum duration before refreshing **iptables** rules. This parameter ensures that the refresh does not happen too frequently. Valid suffixes include **s**, **m**, and **h** and are described in the Go time package

## 1.4.6.1. Configuration parameters for OpenShift SDN

The following YAML object describes the configuration parameters for OpenShift SDN:

defaultNetwork:
type: OpenShiftSDN 1
openshiftSDNConfig: 2
mode: NetworkPolicy 3
mtu: 1450 4
vxlanPort: 4789 5

- 1 Specified in the **install-config.yaml** file.
- Specify only if you want to override part of the OpenShift SDN configuration.
- Configures the network isolation mode for **OpenShiftSDN**. The allowed values are **Multitenant**, **Subnet**, or **NetworkPolicy**. The default value is **NetworkPolicy**.
- MTU for the VXLAN overlay network. This value is normally configured automatically, but if the nodes in your cluster do not all use the same MTU, then you must set this explicitly to 50 less than the smallest node MTU value.

5

The port to use for all VXLAN packets. The default value is **4789**. If you are running in a virtualized environment with existing nodes that are part of another VXLAN network, then you might be

On Amazon Web Services (AWS), you can select an alternate port for the VXLAN between port **9000** and port **9999**.

## 1.4.6.2. Configuration parameters for Open Virtual Network (OVN) SDN

The OVN SDN does not have any configuration parameters in OpenShift Container Platform 4.3.

## 1.4.6.3. Cluster Network Operator example CR

A complete CR for the CNO is displayed in the following example:

## Cluster Network Operator example CR

```
apiVersion: operator.openshift.io/v1
kind: Network
metadata:
 name: cluster
spec:
 clusterNetwork:
 - cidr: 10.128.0.0/14
  hostPrefix: 23
 serviceNetwork:
 - 172.30.0.0/16
 defaultNetwork:
  type: OpenShiftSDN
  openshiftSDNConfig:
   mode: NetworkPolicy
   mtu: 1450
   vxlanPort: 4789
 kubeProxyConfig:
  iptablesSyncPeriod: 30s
  proxyArguments:
   iptables-min-sync-period:
   - 30s
```

# 1.4.7. Deploy the cluster

You can install OpenShift Container Platform on a compatible cloud platform.



## **IMPORTANT**


You can run the **create cluster** command of the installation program only once, during initial installation.

## **Prerequisites**

- Configure an account with the cloud platform that hosts your cluster.
- Obtain the OpenShift Container Platform installation program and the pull secret for your cluster.

#### **Procedure**

1. Run the installation program:



- For <installation\_directory>, specify the location of your customized ./install-config.yaml file.
- To view different installation details, specify warn, debug, or error instead of info.



#### NOTE

If the cloud provider account that you configured on your host does not have sufficient permissions to deploy the cluster, the installation process stops, and the missing permissions are displayed.

When the cluster deployment completes, directions for accessing your cluster, including a link to its web console and credentials for the **kubeadmin** user, display in your terminal.



#### **IMPORTANT**

The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.



## **IMPORTANT**

You must not delete the installation program or the files that the installation program creates. Both are required to delete the cluster.

2. Optional: Remove or disable the **AdministratorAccess** policy from the IAM account that you used to install the cluster.

# 1.4.8. Installing the CLI

You can install the CLI in order to interact with OpenShift Container Platform using a command-line interface.



## **IMPORTANT**

If you installed an earlier version of **oc**, you cannot use it to complete all of the commands in OpenShift Container Platform 4.3. Download and install the new version of **oc**.

## **Procedure**

- 1. From the Infrastructure Provider page on the Red Hat OpenShift Cluster Manager site, navigate to the page for your installation type and click **Download Command-line Tools**
- 2. Click the folder for your operating system and architecture and click the compressed file.



#### NOTE

You can install oc on Linux, Windows, or macOS.

- 3. Save the file to your file system.
- 4. Extract the compressed file.
- 5. Place it in a directory that is on your **PATH**.

After you install the CLI, it is available using the **oc** command:

\$ oc <command>

# 1.4.9. Logging in to the cluster

You can log in to your cluster as a default system user by exporting the cluster **kubeconfig** file. The **kubeconfig** file contains information about the cluster that is used by the CLI to connect a client to the correct cluster and API server. The file is specific to a cluster and is created during OpenShift Container Platform installation.

## **Prerequisites**

- Deploy an OpenShift Container Platform cluster.
- Install the oc CLI.

## **Procedure**

- 1. Export the **kubeadmin** credentials:
  - \$ export KUBECONFIG=<installation\_directory>/auth/kubeconfig 1
  - For **<installation\_directory>**, specify the path to the directory that you stored the installation files in.
- 2. Verify you can run **oc** commands successfully using the exported configuration:

\$ oc whoami system:admin

## **Next steps**

- Customize your cluster.
- If necessary, you can opt out of remote health reporting.

## 1.5. INSTALLING A CLUSTER ON AWS INTO AN EXISTING VPC

In OpenShift Container Platform version 4.3, you can install a cluster into an existing Amazon Virtual Private Cloud (VPC) on Amazon Web Services (AWS). The installation program provisions the rest of the required infrastructure, which you can further customize. To customize the installation, you modify

parameters in the install-config.yaml file before you install the cluster.

## **Prerequisites**

- Review details about the OpenShift Container Platform installation and update processes.
- Configure an AWS account to host the cluster.



#### **IMPORTANT**

If you have an AWS profile stored on your computer, it must not use a temporary session token that you generated while using a multi-factor authentication device. The cluster continues to use your current AWS credentials to create AWS resources for the entire life of the cluster, so you must use long-lived credentials. To generate appropriate keys, see Managing Access Keys for IAM Users in the AWS documentation. You can supply the keys when you run the installation program.

• If you use a firewall, you must configure it to allow the sites that your cluster requires access to.

# 1.5.1. About using a custom VPC

In OpenShift Container Platform 4.3, you can deploy a cluster into existing subnets in an existing Amazon Virtual Private Cloud (VPC) in Amazon Web Services (AWS). By deploying OpenShift Container Platform into an existing AWS VPC, you might be able to avoid limit constraints in new accounts or more easily abide by the operational constraints that your company's guidelines set. If you cannot obtain the infrastructure creation permissions that are required to create the VPC yourself, use this installation option.

Because the installation program cannot know what other components are also in your existing subnets, it cannot choose subnet CIDRs and so forth on your behalf. You must configure networking for the subnets that you install your cluster to yourself.

## 1.5.1.1. Requirements for using your VPC

The installation program no longer creates the following components:

- Internet gateways
- NAT gateways
- Subnets
- Route tables
- VPCs
- VPC DHCP options
- VPC endpoints

If you use a custom VPC, you must correctly configure it and its subnets for the installation program and the cluster to use. The installation program cannot subdivide network ranges for the cluster to use, set route tables for the subnets, or set VPC options like DHCP, so you must do so before you install the cluster.

Your VPC must meet the following characteristics:

- The VPC's CIDR block must contain the **Networking.MachineCIDR** range, which is the IP address pool for cluster machines.
- The VPC must not use the **kubernetes.io/cluster/.\*: owned** tag.
- You must enable the **enableDnsSupport** and **enableDnsHostnames** attributes in your VPC so that the cluster can use the Route53 zones that are attached to the VPC to resolve cluster's internal DNS records. See DNS Support in Your VPC in the AWS documentation.

If you use a cluster with public access, you must create a public and a private subnet for each availability zone that your cluster uses. The installation program modifies your subnets to add the **kubernetes.io/cluster/.\*: shared** tag, so your subnets must have at least one free tag slot available for it. Review the current Tag Restrictions in the AWS documentation to ensure that the installation program can add a tag to each subnet that you specify.

## Required VPC components

You must provide a suitable VPC and subnets that allow communication to your machines.

Compone nt	AWS type	Description
VPC	<ul><li>AWS::EC2::VPC</li><li>AWS::EC2::VPCEndpoint</li></ul>	You must provide a public VPC for the cluster to use. The VPC uses an endpoint that references the route tables for each subnet to improve communication with the registry that is hosted in S3.
Public subnets	<ul> <li>AWS::EC2::Subnet</li> <li>AWS::EC2::SubnetNetworkAclAss ociation</li> </ul>	Your VPC must have public subnets for between 1 and 3 availability zones and associate them with appropriate Ingress rules.
Internet	<ul> <li>AWS::EC2::InternetGateway</li> <li>AWS::EC2::VPCGatewayAttachme nt</li> <li>AWS::EC2::RouteTable</li> <li>AWS::EC2::Route</li> <li>AWS::EC2::SubnetRouteTableAss ociation</li> <li>AWS::EC2::NatGateway</li> <li>AWS::EC2::EIP</li> </ul>	You must have a public internet gateway, with public routes, attached to the VPC. In the provided templates, each public subnet has a NAT gateway with an EIP address. These NAT gateways allow cluster resources, like private subnet instances, to reach the internet and are not required for some restricted network or proxy scenarios.

Compone nt	AWS type	Description	
Network access control	• AWS::EC2::NetworkAcl	You must allow the VPC to access the following ports:	
00110101	AWS::EC2::NetworkAclEntry	Port	Reason
		80	Inbound HTTP traffic
		443	Inbound HTTPS traffic
		22	Inbound SSH traffic
		1024 - 65535	Inbound ephemeral traffic
		0 - 65535	Outbound ephemeral traffic
Private subnets	<ul> <li>AWS::EC2::Subnet</li> <li>AWS::EC2::RouteTable</li> <li>AWS::EC2::SubnetRouteTableAss ociation</li> </ul>	Your VPC can have provided CloudForm create private subnes. I subnets, you must proutes and tables for	nation templates can ets for between 1 and f you use private rovide appropriate

## 1.5.1.2. VPC validation

To ensure that the subnets that you provide are suitable, the installation program confirms the following data:

- All the subnets that you specify exist.
- You provide private subnets.
- The subnet CIDRs belong to the machine CIDR that you specified.
- You provide subnets for each availability zone. Each availability zone contains no more than one
  public and one private subnet. If you use a private cluster, provide only a private subnet for each
  availability zone. Otherwise, provide exactly one public and private subnet for each availability
  zone.
- You provide a public subnet for each private subnet availability zone. Machines are not provisioned in availability zones that you do not provide private subnets for.

If you destroy a cluster that uses an existing VPC, the VPC is not deleted. When you remove the OpenShift Container Platform cluster from a VPC, the **kubernetes.io/cluster/.\*: shared** tag is removed from the subnets that it used.

## 1.5.1.3. Division of permissions

Starting with OpenShift Container Platform 4.3, you do not need all of the permissions that are required for an installation program-provisioned infrastructure cluster to deploy a cluster. This change mimics the division of permissions that you might have at your company: some individuals can create different resource in your clouds than others. For example, you might be able to create application-specific items, like instances, buckets, and load balancers, but not networking-related components such as VPCs, subnets, or ingress rules.

The AWS credentials that you use when you create your cluster do not need the networking permissions that are required to make VPCs and core networking components within the VPC, such as subnets, routing tables, internet gateways, NAT, and VPN. You still need permission to make the application resources that the machines within the cluster require, such as ELBs, security groups, S3 buckets, and nodes.

#### 1.5.1.4. Isolation between clusters

If you deploy OpenShift Container Platform to an existing network, the isolation of cluster services is reduced in the following ways:

- You can install multiple OpenShift Container Platform clusters in the same VPC.
- ICMP ingress is allowed from the entire network.
- TCP 22 ingress (SSH) is allowed to the entire network.
- Control plane TCP 6443 ingress (Kubernetes API) is allowed to the entire network.
- Control plane TCP 22623 ingress (MCS) is allowed to the entire network.

# 1.5.2. Internet and Telemetry access for OpenShift Container Platform

In OpenShift Container Platform 4.3, you require access to the internet to install and entitle your cluster. The Telemetry service, which runs by default to provide metrics about cluster health and the success of updates, also requires internet access. If your cluster is connected to the internet, Telemetry runs automatically, and your cluster is registered to the Red Hat OpenShift Cluster Manager. From there, you can allocate entitlements to your cluster.

You must have internet access to:

- Access the Red Hat OpenShift Cluster Manager page to download the installation program and perform subscription management and entitlement. If the cluster has internet access and you do not disable Telemetry, that service automatically entitles your cluster. If the Telemetry service cannot entitle your cluster, you must manually entitle it on the Cluster registration page.
- Access Quay.io to obtain the packages that are required to install your cluster.
- Obtain the packages that are required to perform cluster updates.



If your cluster cannot have direct internet access, you can perform a restricted network installation on infrastructure that you provision. During that process, you download the content that is required and use it to populate a mirror registry with the packages that you need to install a cluster and generate the installation program. With some installation types, the environment that you install your cluster in will not require internet access. Before you update the cluster, you update the content of the mirror registry.

# 1.5.3. Generating an SSH private key and adding it to the agent

If you want to perform installation debugging or disaster recovery on your cluster, you must provide an SSH key to both your **ssh-agent** and to the installation program.



#### NOTE

In a production environment, you require disaster recovery and debugging.

You can use this key to SSH into the master nodes as the user **core**. When you deploy the cluster, the key is added to the **core** user's ~/.**ssh/authorized\_keys** list.




#### **NOTE**

You must use a local key, not one that you configured with platform-specific approaches such as AWS key pairs.

## **Procedure**

 If you do not have an SSH key that is configured for password-less authentication on your computer, create one. For example, on a computer that uses a Linux operating system, run the following command:

```
$ ssh-keygen -t rsa -b 4096 -N " \
-f <path>/<file_name> 1
```



Running this command generates an SSH key that does not require a password in the location that you specified.

2. Start the **ssh-agent** process as a background task:

```
$ eval "$(ssh-agent -s)"
Agent pid 31874
```

3. Add your SSH private key to the **ssh-agent**:

```
$ ssh-add <path>/<file_name> 1

Identity added: /home/<you>/<path>/<file_name> (<computer_name>)
```



Specify the path and file name for your SSH private key, such as ~/.ssh/id\_rsa

## **Next steps**

• When you install OpenShift Container Platform, provide the SSH public key to the installation program.

# 1.5.4. Obtaining the installation program

Before you install OpenShift Container Platform, download the installation file on a local computer.

## **Prerequisites**

- You must install the cluster from a computer that uses Linux or macOS.
- You need 500 MB of local disk space to download the installation program.

#### **Procedure**

- 1. Access the Infrastructure Provider page on the Red Hat OpenShift Cluster Manager site. If you have a Red Hat account, log in with your credentials. If you do not, create an account.
- 2. Navigate to the page for your installation type, download the installation program for your operating system, and place the file in the directory where you will store the installation configuration files.



## **IMPORTANT**

The installation program creates several files on the computer that you use to install your cluster. You must keep both the installation program and the files that the installation program creates after you finish installing the cluster.

- 3. Extract the installation program. For example, on a computer that uses a Linux operating system, run the following command:
  - $\$ tar \ xvf < installation\_program > .tar.gz$
- 4. From the Pull Secret page on the Red Hat OpenShift Cluster Manager site, download your installation pull secret as a .txt file. This pull secret allows you to authenticate with the services that are provided by the included authorities, including Quay.io, which serves the container images for OpenShift Container Platform components.

# 1.5.5. Creating the installation configuration file

You can customize your installation of OpenShift Container Platform on Amazon Web Services (AWS).

## **Prerequisites**

• Obtain the OpenShift Container Platform installation program and the pull secret for your cluster.

## **Procedure**

- 1. Create the **install-config.yaml** file.
  - a. Run the following command:
    - \$./openshift-install create install-config --dir=<installation\_directory> 1
    - 1 For **<installation\_directory>**, specify the directory name to store the files that the installation program creates.



Specify an empty directory. Some installation assets, like bootstrap X.509 certificates have short expiration intervals, so you must not reuse an installation directory. If you want to reuse individual files from another cluster installation, you can copy them into your directory. However, the file names for the installation assets might change between releases. Use caution when copying installation files from an earlier OpenShift Container Platform version.

- b. At the prompts, provide the configuration details for your cloud:
  - i. Optional: Select an SSH key to use to access your cluster machines.



#### NOTE

For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your **ssh-agent** process uses.

- ii. Select AWS as the platform to target.
- iii. If you do not have an Amazon Web Services (AWS) profile stored on your computer, enter the AWS access key ID and secret access key for the user that you configured to run the installation program.
- iv. Select the AWS region to deploy the cluster to.
- v. Select the base domain for the Route53 service that you configured for your cluster.
- vi. Enter a descriptive name for your cluster.
- vii. Paste the pull secret that you obtained from the Pull Secret page on the Red Hat OpenShift Cluster Manager site.
- 2. Modify the **install-config.yaml** file. You can find more information about the available parameters in the **Installation configuration parameters** section.
- 3. Back up the install-config.yaml file so that you can use it to install multiple clusters.



## **IMPORTANT**

The **install-config.yaml** file is consumed during the installation process. If you want to reuse the file, you must back it up now.

# 1.5.5.1. Installation configuration parameters

Before you deploy an OpenShift Container Platform cluster, you provide parameter values to describe your account on the cloud platform that hosts your cluster and optionally customize your cluster's platform. When you create the **install-config.yaml** installation configuration file, you provide values for the required parameters through the command line. If you customize your cluster, you can modify the **install-config.yaml** file to provide more details about the platform.



## NOTE

You cannot modify these parameters in the **install-config.yaml** file after installation.

Table 1.8. Required parameters

Parameter	Description	Values
baseDomain	The base domain of your cloud provider. This value is used to create routes to your OpenShift Container Platform cluster components. The full DNS name for your cluster is a combination of the baseDomain and metadata.name parameter values that uses the <metadata.name>. <basedomain> format.</basedomain></metadata.name>	A fully-qualified domain or subdomain name, such as example.com.
controlPlane.pla tform	The cloud provider to host the control plane machines. This parameter value must match the <b>compute.platform</b> parameter value.	aws, azure, gcp, openstack, or {}
compute.platfor m	The cloud provider to host the worker machines. This parameter value must match the <b>controlPlane.platform</b> parameter value.	aws, azure, gcp, openstack, or {}
metadata.name	The name of your cluster.	A string that contains uppercase or lowercase letters, such as <b>dev</b> .
platform. <platform>.regi on</platform>	The region to deploy your cluster in.	A valid region for your cloud, such as <b>us-east-1</b> for AWS, <b>centralus</b> for Azure, or <b>region1</b> for Red Hat OpenStack Platform (RHOSP).

Parameter	Description	Values
pullSecret	The pull secret that you obtained from the Pull Secret page on the Red Hat OpenShift Cluster Manager site. You use this pull secret to authenticate with the services that are provided by the included authorities, including Quay.io, which serves the container images for OpenShift Container Platform components.	{     "auths":{         "cloud.openshift.com":{             "auth":"b3Blb=",             "email":"you@example.com"         },         "quay.io":{             "auth":"b3Blb=",             "email":"you@example.com"         }     } }

Table 1.9. Optional parameters

Parameter	Description	Values
sshKey	The SSH key to use to access your cluster machines.  NOTE  For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your ssh-agent process uses.	A valid, local public SSH key that you added to the <b>ssh-agent</b> process.
fips	Whether to enable or disable FIPS mode. By default, FIPS mode is not enabled. If FIPS mode is enabled, the Red Hat Enterprise Linux CoreOS (RHCOS) machines that OpenShift Container Platform runs on bypass the default Kubernetes cryptography suite and use the FIPS validated cryptography modules that are provided with RHCOS instead.	false or true
publish	How to publish the user-facing endpoints of your cluster.	Internal or External. Set publish to Internal to deploy a private cluster, which cannot be accessed from the internet. The default value is External.

Parameter	Description	Values	
compute.hyperthrea ding	Whether to enable or disable simultaneous multithreading, or hyperthreading, on compute machines. By default, simultaneous multithreading is enabled to increase the performance of your machines' cores.	Enabled or Disabled	
	IMPORTANT  If you disable simultaneous multithreading, ensure that your capacity planning accounts for the dramatically decreased machine performance.		
compute.replicas	The number of compute, or worker, machines to provision.	A positive integer greater than or equal to <b>2</b> . The default value is <b>3</b> .	
controlPlane.hypert hreading	Whether to enable or disable simultaneous multithreading, or hyperthreading, on control plane machines. By default, simultaneous multithreading is enabled to increase the performance of your machines' cores.  IMPORTANT  If you disable simultaneous multithreading, ensure that your capacity planning accounts for the dramatically decreased machine performance.	Enabled or Disabled	
controlPlane.replica s	The number of control plane machines to provision.	A positive integer greater than or equal to <b>3</b> . The default value is <b>3</b> .	

Table 1.10. Optional AWS parameters

Parameter	Description	Values
compute.platfor m.aws.rootVolu me.iops	The Input/Output Operations Per Second (IOPS) that is reserved for the root volume.	Integer, for example <b>4000</b> .
compute.platfor m.aws.rootVolu me.size	The size in GiB of the root volume.	Integer, for example <b>500</b> .
compute.platfor m.aws.rootVolu me.type	The instance type of the root volume.	Valid AWS EBS instance type, such as <b>io1</b> .
compute.platfor m.aws.type	The EC2 instance type for the compute machines.	Valid AWS instance type, such as <b>c5.9xlarge</b> .
compute.platfor m.aws.zones	The availability zones where the installation program creates machines for the compute MachinePool. If you provide your own VPC, you must provide a subnet in that availability zone.	A list of valid AWS availability zones, such as <b>us-east-1c</b> , in a YAML sequence.
compute.aws.re gion	The AWS region that the installation program creates compute resources in.	Valid AWS region, such as <b>us-east-1</b> .
controlPlane.pla tform.aws.type	The EC2 instance type for the control plane machines.	Valid AWS instance type, such as <b>c5.9xlarge</b> .
controlPlane.pla tform.aws.zone s	The availability zones where the installation program creates machines for the control plane MachinePool.	A list of valid AWS availability zones, such as <b>us-east-1c</b> , in a YAML sequence.
controlPlane.aw s.region	The AWS region that the installation program creates control plane resources in.	Valid AWS region, such as <b>us-east-1</b> .
platform.aws.us erTags	A map of keys and values that the installation program adds as tags to all resources that it creates.	Any valid YAML map, such as key value pairs in the <a href="key">key</a> : <value< a="">&gt; format. For more information about AWS tags, see Tagging Your Amazon EC2 Resources in the AWS documentation.</value<>

Parameter	Description	Values
platform.aws.su bnets	If you provide the VPC instead of allowing the installation program to create the VPC for you, specify the subnets for the cluster to use. The subnets must be part of the same <b>machineCIDR</b> range that you specify. For a standard cluster, specify a public and a private subnet for each availability zone. For a private cluster, specify a private subnet for each availability zone.	Valid subnet range.


# 1.5.5.2. Sample customized install-config.yaml file for AWS

You can customize the **install-config.yaml** file to specify more details about your OpenShift Container Platform cluster's platform or modify the values of the required parameters.



## **IMPORTANT**

This sample YAML file is provided for reference only. You must obtain your **install-config.yaml** file by using the installation program and modify it.



type: c5.4xlarge zones: - us-west-2c replicas: 3 metadata: name: test-cluster 9 networkina: clusterNetwork: - cidr: 10.128.0.0/14 hostPrefix: 23 machineCIDR: 10.0.0.0/16 networkType: OpenShiftSDN serviceNetwork: - 172.30.0.0/16 platform: aws: region: us-west-2 10 userTags: adminContact: idoe costCenter: 7536 subnets: 111 - subnet-1 - subnet-2 - subnet-3 pullSecret: '{"auths": ...}' 12 fips: false 13 sshKey: ssh-ed25519 AAAA... 14

- 1 9 10 12 Required. The installation program prompts you for this value.
- 26 If you do not provide these parameters and values, the installation program provides the default value.
- The **controlPlane** section is a single mapping, but the compute section is a sequence of mappings. To meet the requirements of the different data structures, the first line of the **compute** section must begin with a hyphen, -, and the first line of the **controlPlane** section must not. Although both sections currently define a single machine pool, it is possible that future versions of OpenShift Container Platform will support defining multiple compute pools during installation. Only one control plane pool is used.
- Whether to enable or disable simultaneous multithreading, or **hyperthreading**. By default, simultaneous multithreading is enabled to increase the performance of your machines' cores. You can disable it by setting the parameter value to **Disabled**. If you disable simultaneous multithreading in some cluster machines, you must disable it in all cluster machines.



#### **IMPORTANT**

If you disable simultaneous multithreading, ensure that your capacity planning accounts for the dramatically decreased machine performance. Use larger instance types, such as **m4.2xlarge** or **m5.2xlarge**, for your machines if you disable simultaneous multithreading.

To configure faster storage for etcd, especially for larger clusters, set the storage type as **io1** and set **iops** to **2000**.

- If you provide your own VPC, specify subnets for each availability zone that your cluster uses.
- Whether to enable or disable FIPS mode. By default, FIPS mode is not enabled. If FIPS mode is enabled, the Red Hat Enterprise Linux CoreOS (RHCOS) machines that OpenShift Container Platform runs on bypass the default Kubernetes cryptography suite and use the FIPS validated cryptography modules that are provided with RHCOS instead.
- You can optionally provide the **sshkey** value that you use to access the machines in your cluster.



#### **NOTE**

For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your **ssh-agent** process uses.

# 1.5.6. Deploy the cluster

You can install OpenShift Container Platform on a compatible cloud platform.



#### **IMPORTANT**

You can run the **create cluster** command of the installation program only once, during initial installation.

## **Prerequisites**

- Configure an account with the cloud platform that hosts your cluster.
- Obtain the OpenShift Container Platform installation program and the pull secret for your cluster.

#### **Procedure**

- 1. Run the installation program:
  - \$ ./openshift-install create cluster --dir=<installation\_directory> \ 1 --log-level=info 2
  - For <installation\_directory>, specify the location of your customized ./install-config.yaml file.
  - 2 To view different installation details, specify warn, debug, or error instead of info.



#### NOTE

If the cloud provider account that you configured on your host does not have sufficient permissions to deploy the cluster, the installation process stops, and the missing permissions are displayed.

When the cluster deployment completes, directions for accessing your cluster, including a link to its web console and credentials for the **kubeadmin** user, display in your terminal.



The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.



## **IMPORTANT**

You must not delete the installation program or the files that the installation program creates. Both are required to delete the cluster.

2. Optional: Remove or disable the **AdministratorAccess** policy from the IAM account that you used to install the cluster.

# 1.5.7. Installing the CLI

You can install the CLI in order to interact with OpenShift Container Platform using a command-line interface.



#### **IMPORTANT**

If you installed an earlier version of **oc**, you cannot use it to complete all of the commands in OpenShift Container Platform 4.3. Download and install the new version of **oc**.

#### **Procedure**

- 1. From the Infrastructure Provider page on the Red Hat OpenShift Cluster Manager site, navigate to the page for your installation type and click **Download Command-line Tools**
- 2. Click the folder for your operating system and architecture and click the compressed file.



#### **NOTE**

You can install oc on Linux, Windows, or macOS.

- 3. Save the file to your file system.
- 4. Extract the compressed file.
- 5. Place it in a directory that is on your **PATH**.

After you install the CLI, it is available using the oc command:

\$ oc <command>

# 1.5.8. Logging in to the cluster

You can log in to your cluster as a default system user by exporting the cluster **kubeconfig** file. The **kubeconfig** file contains information about the cluster that is used by the CLI to connect a client to the correct cluster and API server. The file is specific to a cluster and is created during OpenShift Container Platform installation.

### **Prerequisites**

- Deploy an OpenShift Container Platform cluster.
- Install the oc CLI.

#### **Procedure**

- 1. Export the **kubeadmin** credentials:
  - \$ export KUBECONFIG=<installation\_directory>/auth/kubeconfig 1
- For **<installation\_directory>**, specify the path to the directory that you stored the installation files in.
- 2. Verify you can run **oc** commands successfully using the exported configuration:

\$ oc whoami system:admin

### **Next steps**

- Customize your cluster.
- If necessary, you can opt out of remote health reporting .

# 1.6. INSTALLING A PRIVATE CLUSTER ON AWS

In OpenShift Container Platform version 4.3, you can install a private cluster into an existing VPC on Amazon Web Services (AWS). The installation program provisions the rest of the required infrastructure, which you can further customize. To customize the installation, you modify parameters in the **install-config.yaml** file before you install the cluster.

## **Prerequisites**

- Review details about the OpenShift Container Platform installation and update processes.
- Configure an AWS account to host the cluster.



#### **IMPORTANT**

If you have an AWS profile stored on your computer, it must not use a temporary session token that you generated while using a multi-factor authentication device. The cluster continues to use your current AWS credentials to create AWS resources for the entire life of the cluster, so you must use long-lived credentials. To generate appropriate keys, see Managing Access Keys for IAM Users in the AWS documentation. You can supply the keys when you run the installation program.

• If you use a firewall, you must configure it to allow the sites that your cluster requires access to.

## 1.6.1. Private clusters

If your environment does not require an external internet connection, you can deploy a private OpenShift Container Platform cluster that does not expose external endpoints. Private clusters are accessible from only an internal network and are not visible to the Internet.

By default, OpenShift Container Platform is provisioned to use publicly-accessible DNS and endpoints. A private cluster sets the DNS, Ingress Controller, and API server to private when you deploy your cluster. This means that the cluster resources are only accessible from your internal network and are not visible to the internet.

To deploy a private cluster, you must use existing networking that meets your requirements. Your cluster resources might be shared between other clusters on the network.

Additionally, you must deploy a private cluster from a machine that has access the API services for the cloud you provision to, the hosts on the network that you provision, and to the internet to obtain installation media. You can use any machine that meets these access requirements and follows your company's guidelines. For example, this machine can be a bastion host on your cloud network or a machine that has access to the network through a VPN.

#### 1.6.1.1. Private clusters in AWS

To create a private cluster on Amazon Web Services (AWS), you must provide an existing private VPC and subnets to host the cluster. The installation program must also be able to resolve the DNS records that the cluster requires. The installation program configures the Ingress Operator and API server for access from only the private network.

The cluster still requires access to Internet to access the AWS APIs.

The following items are not required or created when you install a private cluster:

- Public subnets
- Public load balancers, which support public ingress
- A public Route 53 Zone that matches the **baseDomain** for the cluster

The installation program does use the **baseDomain** that you specify to create a private Route 53 Zone and the required records for the cluster. The cluster is configured so that the Operators do not create public records for the cluster and all cluster machines are placed in the private subnets that you specify.

## 1.6.1.1.1 Limitations

The ability to add public functionality to a private cluster is limited.

- You cannot make the Kubernetes API endpoints public after installation without taking additional actions, including creating public subnets in the VPC for each availablity zone in use, creating a public load balancer, and configuring the control plane security groups to allow traffic from Internet on 6443 (Kubernetes API port).
- If you use a public Service type load balancer, you must tag a public subnet in each availability zone with **kubernetes.io/cluster/<cluster-infra-id>: shared** so that AWS can use them to create public load balancers.

# 1.6.2. About using a custom VPC

In OpenShift Container Platform 4.3, you can deploy a cluster into existing subnets in an existing Amazon Virtual Private Cloud (VPC) in Amazon Web Services (AWS). By deploying OpenShift

Container Platform into an existing AWS VPC, you might be able to avoid limit constraints in new accounts or more easily abide by the operational constraints that your company's guidelines set. If you cannot obtain the infrastructure creation permissions that are required to create the VPC yourself, use this installation option.

Because the installation program cannot know what other components are also in your existing subnets, it cannot choose subnet CIDRs and so forth on your behalf. You must configure networking for the subnets that you install your cluster to yourself.

# 1.6.2.1. Requirements for using your VPC

The installation program no longer creates the following components:

- Internet gateways
- NAT gateways
- Subnets
- Route tables
- VPCs
- VPC DHCP options
- VPC endpoints

If you use a custom VPC, you must correctly configure it and its subnets for the installation program and the cluster to use. The installation program cannot subdivide network ranges for the cluster to use, set route tables for the subnets, or set VPC options like DHCP, so you must do so before you install the cluster.

Your VPC must meet the following characteristics:

- The VPC's CIDR block must contain the **Networking.MachineCIDR** range, which is the IP address pool for cluster machines.
- The VPC must not use the **kubernetes.io/cluster/.\*: owned** tag.
- You must enable the **enableDnsSupport** and **enableDnsHostnames** attributes in your VPC so that the cluster can use the Route53 zones that are attached to the VPC to resolve cluster's internal DNS records. See DNS Support in Your VPC in the AWS documentation.

If you use a cluster with public access, you must create a public and a private subnet for each availability zone that your cluster uses. The installation program modifies your subnets to add the **kubernetes.io/cluster/.\*: shared** tag, so your subnets must have at least one free tag slot available for it. Review the current Tag Restrictions in the AWS documentation to ensure that the installation program can add a tag to each subnet that you specify.

# Required VPC components

You must provide a suitable VPC and subnets that allow communication to your machines.

Compone nt	AWS type	Description	
VPC	AWS::EC2::VPC     AWS::EC2::VPCEndpoint	You must provide a public VPC for the cluster to use. The VPC uses an endpoint that references the route tables for each subnet to improve communication with the registry that is hosted in S3.	
Public subnets	<ul> <li>AWS::EC2::Subnet</li> <li>AWS::EC2::SubnetNetworkAclAss ociation</li> </ul>	Your VPC must have public subnets for between 1 and 3 availability zones and associate them with appropriate Ingress rules.	
Internet	<ul> <li>AWS::EC2::InternetGateway</li> <li>AWS::EC2::VPCGatewayAttachme nt</li> <li>AWS::EC2::RouteTable</li> <li>AWS::EC2::Route</li> <li>AWS::EC2::SubnetRouteTableAss ociation</li> <li>AWS::EC2::NatGateway</li> <li>AWS::EC2::EIP</li> </ul>	You must have a public internet gateway, with public routes, attached to the VPC. In the provided templates, each public subnet has a NAT gateway with an EIP address. These NAT gateways allow cluster resources, like private subnet instances, to reach the internet and are not required for some restricted network or proxy scenarios.	
Network access control	AWS::EC2::NetworkAclEntry	You must allow the VPC to access the following ports:	
00110101		Port	Reason
		80	Inbound HTTP traffic
		443	Inbound HTTPS traffic
		22	Inbound SSH traffic
		1024 - 65535	Inbound ephemeral traffic
		0 - 65535	Outbound ephemeral traffic

Compone nt	AWS type	Description
Private subnets	<ul> <li>AWS::EC2::Subnet</li> <li>AWS::EC2::RouteTable</li> <li>AWS::EC2::SubnetRouteTableAss ociation</li> </ul>	Your VPC can have private subnets. The provided CloudFormation templates can create private subnets for between 1 and 3 availability zones. If you use private subnets, you must provide appropriate routes and tables for them.

# 1.6.2.2. VPC validation

To ensure that the subnets that you provide are suitable, the installation program confirms the following data:

- All the subnets that you specify exist.
- You provide private subnets.
- The subnet CIDRs belong to the machine CIDR that you specified.
- You provide subnets for each availability zone. Each availability zone contains no more than one public and one private subnet. If you use a private cluster, provide only a private subnet for each availability zone. Otherwise, provide exactly one public and private subnet for each availability zone.
- You provide a public subnet for each private subnet availability zone. Machines are not
  provisioned in availability zones that you do not provide private subnets for.

If you destroy a cluster that uses an existing VPC, the VPC is not deleted. When you remove the OpenShift Container Platform cluster from a VPC, the **kubernetes.io/cluster/.\*: shared** tag is removed from the subnets that it used.

# 1.6.2.3. Division of permissions

Starting with OpenShift Container Platform 4.3, you do not need all of the permissions that are required for an installation program-provisioned infrastructure cluster to deploy a cluster. This change mimics the division of permissions that you might have at your company: some individuals can create different resource in your clouds than others. For example, you might be able to create application-specific items, like instances, buckets, and load balancers, but not networking-related components such as VPCs, subnets, or ingress rules.

The AWS credentials that you use when you create your cluster do not need the networking permissions that are required to make VPCs and core networking components within the VPC, such as subnets, routing tables, internet gateways, NAT, and VPN. You still need permission to make the application resources that the machines within the cluster require, such as ELBs, security groups, S3 buckets, and nodes.

### 1.6.2.4. Isolation between clusters

If you deploy OpenShift Container Platform to an existing network, the isolation of cluster services is reduced in the following ways:

- You can install multiple OpenShift Container Platform clusters in the same VPC.
- ICMP ingress is allowed from the entire network.
- TCP 22 ingress (SSH) is allowed to the entire network.
- Control plane TCP 6443 ingress (Kubernetes API) is allowed to the entire network.
- Control plane TCP 22623 ingress (MCS) is allowed to the entire network.

# 1.6.3. Internet and Telemetry access for OpenShift Container Platform

In OpenShift Container Platform 4.3, you require access to the internet to install and entitle your cluster. The Telemetry service, which runs by default to provide metrics about cluster health and the success of updates, also requires internet access. If your cluster is connected to the internet, Telemetry runs automatically, and your cluster is registered to the Red Hat OpenShift Cluster Manager. From there, you can allocate entitlements to your cluster.

You must have internet access to:

- Access the Red Hat OpenShift Cluster Manager page to download the installation program and perform subscription management and entitlement. If the cluster has internet access and you do not disable Telemetry, that service automatically entitles your cluster. If the Telemetry service cannot entitle your cluster, you must manually entitle it on the Cluster registration page.
- Access Quay.io to obtain the packages that are required to install your cluster.
- Obtain the packages that are required to perform cluster updates.



# **IMPORTANT**

If your cluster cannot have direct internet access, you can perform a restricted network installation on infrastructure that you provision. During that process, you download the content that is required and use it to populate a mirror registry with the packages that you need to install a cluster and generate the installation program. With some installation types, the environment that you install your cluster in will not require internet access. Before you update the cluster, you update the content of the mirror registry.

# 1.6.4. Generating an SSH private key and adding it to the agent

If you want to perform installation debugging or disaster recovery on your cluster, you must provide an SSH key to both your **ssh-agent** and to the installation program.



### NOTE

In a production environment, you require disaster recovery and debugging.

You can use this key to SSH into the master nodes as the user **core**. When you deploy the cluster, the key is added to the **core** user's ~/.**ssh/authorized\_keys** list.



# NOTE

You must use a local key, not one that you configured with platform-specific approaches such as AWS key pairs.

### **Procedure**

1. If you do not have an SSH key that is configured for password-less authentication on your computer, create one. For example, on a computer that uses a Linux operating system, run the following command:

```
$ ssh-keygen -t rsa -b 4096 -N " \
-f <path>/<file_name> 1
```

Specify the path and file name, such as ~/.ssh/id\_rsa, of the SSH key.

Running this command generates an SSH key that does not require a password in the location that you specified.

2. Start the **ssh-agent** process as a background task:

```
$ eval "$(ssh-agent -s)"
Agent pid 31874
```

3. Add your SSH private key to the **ssh-agent**:

```
$ ssh-add <path>/<file_name> 1

Identity added: /home/<you>/<path>/<file_name> (<computer_name>)
```

Specify the path and file name for your SSH private key, such as ~/.ssh/id\_rsa

# **Next steps**

• When you install OpenShift Container Platform, provide the SSH public key to the installation program.

# 1.6.5. Obtaining the installation program

Before you install OpenShift Container Platform, download the installation file on a local computer.

# Prerequisites

- You must install the cluster from a computer that uses Linux or macOS.
- You need 500 MB of local disk space to download the installation program.

# Procedure

- 1. Access the Infrastructure Provider page on the Red Hat OpenShift Cluster Manager site. If you have a Red Hat account, log in with your credentials. If you do not, create an account.
- 2. Navigate to the page for your installation type, download the installation program for your operating system, and place the file in the directory where you will store the installation configuration files.



# **IMPORTANT**

The installation program creates several files on the computer that you use to install your cluster. You must keep both the installation program and the files that the installation program creates after you finish installing the cluster.

- 3. Extract the installation program. For example, on a computer that uses a Linux operating system, run the following command:
  - \$ tar xvf <installation\_program>.tar.gz
- 4. From the Pull Secret page on the Red Hat OpenShift Cluster Manager site, download your installation pull secret as a .txt file. This pull secret allows you to authenticate with the services that are provided by the included authorities, including Quay.io, which serves the container images for OpenShift Container Platform components.

# 1.6.6. Creating the installation configuration file

You can customize your installation of OpenShift Container Platform on

# **Prerequisites**

• Obtain the OpenShift Container Platform installation program and the pull secret for your cluster.

### **Procedure**

- 1. Create the **install-config.yaml** file.
  - a. Run the following command:
    - \$ ./openshift-install create install-config --dir=<installation\_directory> 1
    - For **<installation\_directory>**, specify the directory name to store the files that the installation program creates.



### **IMPORTANT**

Specify an empty directory. Some installation assets, like bootstrap X.509 certificates have short expiration intervals, so you must not reuse an installation directory. If you want to reuse individual files from another cluster installation, you can copy them into your directory. However, the file names for the installation assets might change between releases. Use caution when copying installation files from an earlier OpenShift Container Platform version.

- b. At the prompts, provide the configuration details for your cloud:
  - i. Optional: Select an SSH key to use to access your cluster machines.



### NOTE

For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your **ssh-agent** process uses.

- ii. Enter a descriptive name for your cluster.
- iii. Paste the pull secret that you obtained from the Pull Secret page on the Red Hat OpenShift Cluster Manager site.
- 2. Modify the **install-config.yaml** file. You can find more information about the available parameters in the **Installation configuration parameters** section.
- 3. Back up the **install-config.yaml** file so that you can use it to install multiple clusters.



### **IMPORTANT**

The **install-config.yaml** file is consumed during the installation process. If you want to reuse the file, you must back it up now.

# 1.6.6.1. Installation configuration parameters

Before you deploy an OpenShift Container Platform cluster, you provide parameter values to describe your account on the cloud platform that hosts your cluster and optionally customize your cluster's platform. When you create the **install-config.yaml** installation configuration file, you provide values for the required parameters through the command line. If you customize your cluster, you can modify the **install-config.yaml** file to provide more details about the platform.



# **NOTE**

You cannot modify these parameters in the **install-config.yaml** file after installation.

Table 1.11. Required parameters

Parameter	Description	Values
baseDomain	The base domain of your cloud provider. This value is used to create routes to your OpenShift Container Platform cluster components. The full DNS name for your cluster is a combination of the baseDomain and metadata.name parameter values that uses the <metadata.name>. <basedomain> format.</basedomain></metadata.name>	A fully-qualified domain or subdomain name, such as example.com.

Parameter	Description	Values	
controlPlane.pla tform	The cloud provider to host the control plane machines. This parameter value must match the <b>compute.platform</b> parameter value.	aws, azure, gcp, openstack, or {}	
compute.platfor m	The cloud provider to host the worker machines. This parameter value must match the <b>controlPlane.platform</b> parameter value.	aws, azure, gcp, openstack, or {}	
metadata.name	The name of your cluster.	A string that contains uppercase or lowercase letters, such as <b>dev</b> .	
platform. <platform>.regi on</platform>	The region to deploy your cluster in.	A valid region for your cloud, such as <b>us-east-1</b> for AWS, <b>centralus</b> for Azure, or <b>region1</b> for Red Hat OpenStack Platform (RHOSP).	
pullSecret	The pull secret that you obtained from the Pull Secret page on the Red Hat OpenShift Cluster Manager site. You use this pull secret to authenticate with the services that are provided by the included authorities, including Quay.io, which serves the container images for OpenShift Container Platform components.	{     "auths":{         "cloud.openshift.com":{             "auth":"b3Blb=",             "email":"you@example.com"         },         "quay.io":{             "auth":"b3Blb=",             "email":"you@example.com"         }     } }	

Table 1.12. Optional parameters

Parameter	Description	Values	
-----------	-------------	--------	--

Parameter	Description	Values
sshKey	The SSH key to use to access your cluster machines.  NOTE  For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your ssh-agent process uses.	A valid, local public SSH key that you added to the <b>ssh-agent</b> process.
fips	Whether to enable or disable FIPS mode. By default, FIPS mode is not enabled. If FIPS mode is enabled, the Red Hat Enterprise Linux CoreOS (RHCOS) machines that OpenShift Container Platform runs on bypass the default Kubernetes cryptography suite and use the FIPS validated cryptography modules that are provided with RHCOS instead.	false or true
publish	How to publish the user-facing endpoints of your cluster.	Internal or External. Set publish to Internal to deploy a private cluster, which cannot be accessed from the internet. The default value is External.

Parameter	Description	Values
compute.hyperthrea ding	Whether to enable or disable simultaneous multithreading, or hyperthreading, on compute machines. By default, simultaneous multithreading is enabled to increase the performance of your machines' cores.  IMPORTANT  If you disable simultaneous multithreading, ensure that your capacity planning accounts for the dramatically decreased machine performance.	Enabled or Disabled
compute.replicas	The number of compute, or worker, machines to provision.	A positive integer greater than or equal to <b>2</b> . The default value is <b>3</b> .
controlPlane.hypert hreading	Whether to enable or disable simultaneous multithreading, or hyperthreading, on control plane machines. By default, simultaneous multithreading is enabled to increase the performance of your machines' cores.	Enabled or Disabled
	IMPORTANT  If you disable simultaneous multithreading, ensure that your capacity planning accounts for the dramatically decreased machine performance.	
controlPlane.replica s	The number of control plane machines to provision.	A positive integer greater than or equal to <b>3</b> . The default value is <b>3</b> .

Table 1.13. Optional AWS parameters

Parameter	Description	Values
compute.platfor m.aws.rootVolu me.iops	The Input/Output Operations Per Second (IOPS) that is reserved for the root volume.	Integer, for example <b>4000</b> .
compute.platfor m.aws.rootVolu me.size	The size in GiB of the root volume.	Integer, for example <b>500</b> .
compute.platfor m.aws.rootVolu me.type	The instance type of the root volume.	Valid AWS EBS instance type, such as <b>io1</b> .
compute.platfor m.aws.type	The EC2 instance type for the compute machines.	Valid AWS instance type, such as <b>c5.9xlarge</b> .
compute.platfor m.aws.zones	The availability zones where the installation program creates machines for the compute MachinePool. If you provide your own VPC, you must provide a subnet in that availability zone.	A list of valid AWS availability zones, such as <b>us-east-1c</b> , in a YAML sequence.
compute.aws.re gion	The AWS region that the installation program creates compute resources in.	Valid AWS region, such as <b>us-east-1</b> .
controlPlane.pla tform.aws.type	The EC2 instance type for the control plane machines.	Valid AWS instance type, such as <b>c5.9xlarge</b> .
controlPlane.pla tform.aws.zone s	The availability zones where the installation program creates machines for the control plane MachinePool.	A list of valid AWS availability zones, such as <b>us-east-1c</b> , in a YAML sequence.
controlPlane.aw s.region	The AWS region that the installation program creates control plane resources in.	Valid AWS region, such as <b>us-east-1</b> .
platform.aws.us erTags	A map of keys and values that the installation program adds as tags to all resources that it creates.	Any valid YAML map, such as key value pairs in the <b><key>: <value></value></key></b> format. For more information about AWS tags, see Tagging Your Amazon EC2 Resources in the AWS documentation.

Parameter	Description	Values
platform.aws.su bnets	If you provide the VPC instead of allowing the installation program to create the VPC for you, specify the subnets for the cluster to use. The subnets must be part of the same <b>machineCIDR</b> range that you specify. For a standard cluster, specify a public and a private subnet for each availability zone. For a private cluster, specify a private subnet for each availability zone.	Valid subnet range.

# 1.6.6.2. Sample customized install-config.yaml file for AWS

You can customize the **install-config.yaml** file to specify more details about your OpenShift Container Platform cluster's platform or modify the values of the required parameters.



# **IMPORTANT**

This sample YAML file is provided for reference only. You must obtain your **install-config.yaml** file by using the installation program and modify it.

```
apiVersion: v1
baseDomain: example.com 1
controlPlane: 2
 hyperthreading: Enabled 3 4
 name: master
 platform:
  aws:
   zones:
   - us-west-2a
   - us-west-2b
   rootVolume:
    iops: 4000
    size: 500
    type: io1
   type: m5.xlarge 5
 replicas: 3
compute: 6
- hyperthreading: Enabled 7
 name: worker
 platform:
  aws:
   rootVolume:
    iops: 2000
    size: 500
    type: io1 8
```

```
type: c5.4xlarge
   zones:
   - us-west-2c
 replicas: 3
metadata:
 name: test-cluster 9
networkina:
 clusterNetwork:
 - cidr: 10.128.0.0/14
  hostPrefix: 23
 machineCIDR: 10.0.0.0/16
 networkType: OpenShiftSDN
 serviceNetwork:
 - 172.30.0.0/16
platform:
 aws:
  region: us-west-2 10
  userTags:
   adminContact: idoe
   costCenter: 7536
  subnets: 111
  - subnet-1
  - subnet-2
  - subnet-3
pullSecret: '{"auths": ...}' 12
fips: false 13
sshKey: ssh-ed25519 AAAA... 14
publish: Internal 15
```

- 1 9 10 12 Required. The installation program prompts you for this value.
- 26 If you do not provide these parameters and values, the installation program provides the default value.
- The **controlPlane** section is a single mapping, but the compute section is a sequence of mappings. To meet the requirements of the different data structures, the first line of the **compute** section must begin with a hyphen, -, and the first line of the **controlPlane** section must not. Although both sections currently define a single machine pool, it is possible that future versions of OpenShift Container Platform will support defining multiple compute pools during installation. Only one control plane pool is used.
- Whether to enable or disable simultaneous multithreading, or **hyperthreading**. By default, simultaneous multithreading is enabled to increase the performance of your machines' cores. You can disable it by setting the parameter value to **Disabled**. If you disable simultaneous multithreading in some cluster machines, you must disable it in all cluster machines.



# **IMPORTANT**

If you disable simultaneous multithreading, ensure that your capacity planning accounts for the dramatically decreased machine performance. Use larger instance types, such as **m4.2xlarge** or **m5.2xlarge**, for your machines if you disable simultaneous multithreading.

8 To configure faster storage for etcd, especially for larger clusters, set the storage type as **io1** and

- If you provide your own VPC, specify subnets for each availability zone that your cluster uses.
- Whether to enable or disable FIPS mode. By default, FIPS mode is not enabled. If FIPS mode is enabled, the Red Hat Enterprise Linux CoreOS (RHCOS) machines that OpenShift Container Platform runs on bypass the default Kubernetes cryptography suite and use the FIPS validated cryptography modules that are provided with RHCOS instead.
- You can optionally provide the **sshKey** value that you use to access the machines in your cluster.



### **NOTE**

For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your **ssh-agent** process uses.

How to publish the user-facing endpoints of your cluster. Set **publish** to **Internal** to deploy a private cluster, which cannot be accessed from the internet. The default value is **External**.

# 1.6.7. Deploy the cluster

You can install OpenShift Container Platform on a compatible cloud platform.



# **IMPORTANT**


You can run the **create cluster** command of the installation program only once, during initial installation.

# **Prerequisites**

- Configure an account with the cloud platform that hosts your cluster.
- Obtain the OpenShift Container Platform installation program and the pull secret for your cluster.

# **Procedure**

1. Run the installation program:



- For <installation\_directory>, specify the
- To view different installation details, specify warn, debug, or error instead of info.



# **NOTE**

If the cloud provider account that you configured on your host does not have sufficient permissions to deploy the cluster, the installation process stops, and the missing permissions are displayed.

When the cluster deployment completes, directions for accessing your cluster, including a link to its web console and credentials for the **kubeadmin** user, display in your terminal.



### **IMPORTANT**

The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.



# **IMPORTANT**

You must not delete the installation program or the files that the installation program creates. Both are required to delete the cluster.

# 1.6.8. Installing the CLI

You can install the CLI in order to interact with OpenShift Container Platform using a command-line interface.



### **IMPORTANT**

If you installed an earlier version of **oc**, you cannot use it to complete all of the commands in OpenShift Container Platform 4.3. Download and install the new version of **oc**.

### **Procedure**

- 1. From the Infrastructure Provider page on the Red Hat OpenShift Cluster Manager site, navigate to the page for your installation type and click **Download Command-line Tools**
- 2. Click the folder for your operating system and architecture and click the compressed file.



### **NOTE**

You can install oc on Linux, Windows, or macOS.

- 3. Save the file to your file system.
- 4. Extract the compressed file.
- 5. Place it in a directory that is on your **PATH**.

After you install the CLI, it is available using the oc command:

\$ oc <command>

# 1.6.9. Logging in to the cluster

You can log in to your cluster as a default system user by exporting the cluster **kubeconfig** file. The **kubeconfig** file contains information about the cluster that is used by the CLI to connect a client to the correct cluster and API server. The file is specific to a cluster and is created during OpenShift Container Platform installation.

# **Prerequisites**

- Deploy an OpenShift Container Platform cluster.
- Install the oc CLI.

### **Procedure**

- 1. Export the **kubeadmin** credentials:
  - \$ export KUBECONFIG=<installation\_directory>/auth/kubeconfig 1
  - For **<installation\_directory>**, specify the path to the directory that you stored the installation files in.
- 2. Verify you can run **oc** commands successfully using the exported configuration:

\$ oc whoami system:admin

### **Next steps**

- Customize your cluster.
- If necessary, you can opt out of remote health reporting .

# 1.7. INSTALLING A CLUSTER ON USER-PROVISIONED INFRASTRUCTURE IN AWS BY USING CLOUDFORMATION TEMPLATES

In OpenShift Container Platform version 4.3, you can install a cluster on Amazon Web Services (AWS) by using infrastructure that you provide.

One way to create this infrastructure is to use the provided CloudFormation templates. You can modify the templates to customize your infrastructure or use the information that they contain to create AWS objects according to your company's policies.

# **Prerequisites**

- Review details about the OpenShift Container Platform installation and update processes.
- Configure an AWS account to host the cluster.



### **IMPORTANT**

If you have an AWS profile stored on your computer, it must not use a temporary session token that you generated while using a multi-factor authentication device. The cluster continues to use your current AWS credentials to create AWS resources for the entire life of the cluster, so you must use key-based, long-lived credentials. To generate appropriate keys, see Managing Access Keys for IAM Users in the AWS documentation. You can supply the keys when you run the installation program.

- Download the AWS CLI and install it on your computer. See Install the AWS CLI Using the Bundled Installer (Linux, macOS, or Unix) in the AWS documentation.
- If you use a firewall, you must configure it to allow the sites that your cluster requires access to.



# **NOTE**

Be sure to also review this site list if you are configuring a proxy.

# 1.7.1. Internet and Telemetry access for OpenShift Container Platform

In OpenShift Container Platform 4.3, you require access to the internet to install and entitle your cluster. The Telemetry service, which runs by default to provide metrics about cluster health and the success of updates, also requires internet access. If your cluster is connected to the internet, Telemetry runs automatically, and your cluster is registered to the Red Hat OpenShift Cluster Manager. From there, you can allocate entitlements to your cluster.

You must have internet access to:

- Access the Red Hat OpenShift Cluster Manager page to download the installation program and perform subscription management and entitlement. If the cluster has internet access and you do not disable Telemetry, that service automatically entitles your cluster. If the Telemetry service cannot entitle your cluster, you must manually entitle it on the Cluster registration page.
- Access Quay.io to obtain the packages that are required to install your cluster.
- Obtain the packages that are required to perform cluster updates.



### **IMPORTANT**

If your cluster cannot have direct internet access, you can perform a restricted network installation on infrastructure that you provision. During that process, you download the content that is required and use it to populate a mirror registry with the packages that you need to install a cluster and generate the installation program. With some installation types, the environment that you install your cluster in will not require internet access. Before you update the cluster, you update the content of the mirror registry.

# 1.7.2. Required AWS infrastructure components

To install OpenShift Container Platform on user-provisioned infrastructure in Amazon Web Services (AWS), you must manually create both the machines and their supporting infrastructure.

For more information about the integration testing for different platforms, see the OpenShift Container Platform 4.x Tested Integrations page.

You can use the provided CloudFormation templates to create this infrastructure, you can manually create the components, or you can reuse existing infrastructure that meets the cluster requirements. Review the CloudFormation templates for more details about how the components interrelate.

### 1.7.2.1. Cluster machines

You need AWS::EC2::Instance objects for the following machines:

• A bootstrap machine. This machine is required during installation, but you can remove it after your cluster deploys.

- At least three control plane machines. The control plane machines are not governed by a MachineSet.
- Compute machines. You must create at least two compute, or worker, machines during installation. These machines are not governed by a MachineSet.

You can use the following instance types for the cluster machines with the provided CloudFormation templates.



# **IMPORTANT**

If **m4** instance types are not available in your region, such as with **eu-west-3**, use **m5** types instead.

Table 1.14. Instance types for machines

Instance type	Bootstrap	Control plane	Compute
i3.large	х		
m4.large or m5.large			х
m4.xlarge or m5.xlarge		X	X
m4.2xlarge		х	х
m4.4xlarge		х	х
m4.8xlarge		х	х
m4.10xlarge		х	х
m4.16xlarge		х	х
c4.large			х
c4.xlarge			х
c4.2xlarge		х	х
c4.4xlarge		х	х
c4.8xlarge		х	х
r4.large			х
r4.xlarge		х	х

Instance type	Bootstrap	Control plane	Compute
r4.2xlarge		х	х
r4.4xlarge		х	x
r4.8xlarge		х	x
r4.16xlarge		х	х

You might be able to use other instance types that meet the specifications of these instance types.

# 1.7.2.2. Certificate signing requests management

Because your cluster has limited access to automatic machine management when you use infrastructure that you provision, you must provide a mechanism for approving cluster certificate signing requests (CSRs) after installation. The **kube-controller-manager** only approves the kubelet client CSRs. The **machine-approver** cannot guarantee the validity of a serving certificate that is requested by using kubelet credentials because it cannot confirm that the correct machine issued the request. You must determine and implement a method of verifying the validity of the kubelet serving certificate requests and approving them.

# 1.7.2.3. Other infrastructure components

- A VPC
- DNS entries
- Load balancers (classic or network) and listeners
- A public and a private Route53 zone
- Security groups
- IAM roles
- S3 buckets

# Required VPC components

You must provide a suitable VPC and subnets that allow communication to your machines.

Compone nt	AWS type	Description
VPC	<ul><li>AWS::EC2::VPC</li><li>AWS::EC2::VPCEndpoint</li></ul>	You must provide a public VPC for the cluster to use. The VPC uses an endpoint that references the route tables for each subnet to improve communication with the registry that is hosted in S3.

Compone nt	AWS type	Description	
Public subnets	<ul> <li>AWS::EC2::Subnet</li> <li>AWS::EC2::SubnetNetworkAclAss ociation</li> </ul>	Your VPC must have public subnets for between 1 and 3 availability zones and associate them with appropriate Ingress rules.	
Internet	<ul> <li>AWS::EC2::InternetGateway</li> <li>AWS::EC2::VPCGatewayAttachme nt</li> <li>AWS::EC2::RouteTable</li> <li>AWS::EC2::Route</li> <li>AWS::EC2::SubnetRouteTableAss ociation</li> <li>AWS::EC2::NatGateway</li> <li>AWS::EC2::EIP</li> </ul>	You must have a public internet gateway with public routes, attached to the VPC. In the provided templates, each public subnet has a NAT gateway with an EIP address. These NAT gateways allow cluster resources, like private subnet instances, to reach the internet and are not required for some restricted network or proxy scenarios.	
Network access control	AWS::EC2::NetworkAclEntry	You must allow the VPC to access the following ports:	
Control		Port	Reason
		80	Inbound HTTP traffic
		443	Inbound HTTPS traffic
		22	Inbound SSH traffic
		1024 - 65535	Inbound ephemeral traffic
		0 - 65535	Outbound ephemeral traffic

Compone nt	AWS type	Description
Private subnets	<ul> <li>AWS::EC2::Subnet</li> <li>AWS::EC2::RouteTable</li> <li>AWS::EC2::SubnetRouteTableAss ociation</li> </ul>	Your VPC can have private subnets. The provided CloudFormation templates can create private subnets for between 1 and 3 availability zones. If you use private subnets, you must provide appropriate routes and tables for them.

# Required DNS and load balancing components

Your DNS and load balancer configuration needs to use a public hosted zone and can use a private hosted zone similar to the one that the installation program uses if it provisions the cluster's infrastructure. You must create a DNS entry that resolves to your load balancer. An entry for **api.** <cluster\_name>.<domain> must point to the external load balancer, and an entry for **api-int.** <cluster\_name>.<domain> must point to the internal load balancer.

The cluster also requires load balancers and listeners for port 6443, which are required for the Kubernetes API and its extensions, and port 22623, which are required for the Ignition config files for new machines. The targets will be the master nodes. Port 6443 must be accessible to both clients external to the cluster and nodes within the cluster. Port 22623 must be accessible to nodes within the cluster.

Component	AWS type	Description
DNS	AWS::Route 53::HostedZ one	The hosted zone for your internal DNS.
etcd record sets	AWS::Route 53::RecordS et	The registration records for etcd for your control plane machines.
Public load balancer	AWS::Elastic LoadBalanci ngV2::LoadB alancer	The load balancer for your public subnets.
External API server record	AWS::Route 53::RecordS etGroup	Alias records for the external API server.
External listener	AWS::Elastic LoadBalanci ngV2::Listen er	A listener on port 6443 for the external load balancer.

Component	AWS type	Description
External target group	AWS::Elastic LoadBalanci ngV2::Target Group	The target group for the external load balancer.
Private load balancer	AWS::Elastic LoadBalanci ngV2::LoadB alancer	The load balancer for your private subnets.
Internal API server record	AWS::Route 53::RecordS etGroup	Alias records for the internal API server.
Internal listener	AWS::Elastic LoadBalanci ngV2::Listen er	A listener on port 22623 for the internal load balancer.
Internal target group	AWS::Elastic LoadBalanci ngV2::Target Group	The target group for the Internal load balancer.
Internal listener	AWS::Elastic LoadBalanci ngV2::Listen er	A listener on port 6443 for the internal load balancer.
Internal target group	AWS::Elastic LoadBalanci ngV2::Target Group	The target group for the internal load balancer.

# Security groups

The control plane and worker machines require access to the following ports:

0
22
6443
22623

Group	Туре	IP Protocol	Port range
WorkerSecurityGroup	AWS::EC2::Security Group	icmp	0
		tcp	22
BootstrapSecurityGroup	AWS::EC2::Security Group	tcp	22
		tcp	19531

# **Control plane Ingress**

The control plane machines require the following Ingress groups. Each Ingress group is a **AWS::EC2::SecurityGroupIngress** resource.

Ingress group	Description	IP protocol	Port range
MasterIngress Etcd	etcd	tcp	2379- 2380
MasterIngress Vxlan	Vxlan packets	udp	4789
MasterIngress WorkerVxIan	Vxlan packets	udp	4789
MasterIngress Internal	Internal cluster communication	tcp	9000 - 9999
MasterIngress WorkerInterna I	Internal cluster communication	tcp	9000 - 9999
MasterIngress Kube	Kubernetes kubelet, scheduler and controller manager	tcp	10250 - 10259
MasterIngress WorkerKube	Kubernetes kubelet, scheduler and controller manager	tcp	10250 - 10259
MasterIngress IngressServic es	Kubernetes Ingress services	tcp	30000 - 32767
MasterIngress WorkerIngress Services	Kubernetes Ingress services	tcp	30000 - 32767

# **Worker Ingress**

The worker machines require the following Ingress groups. Each Ingress group is a **AWS::EC2::SecurityGroupIngress** resource.

Ingress group	Description	IP protocol	Port range
WorkerIngress Vxlan	Vxlan packets	udp	4789
WorkerIngress WorkerVxIan	Vxlan packets	udp	4789
WorkerIngress Internal	Internal cluster communication	tcp	9000 - 9999
WorkerIngress WorkerInterna I	Internal cluster communication	tcp	9000 - 9999
WorkerIngress Kube	Kubernetes kubelet, scheduler and controller manager	tcp	10250
WorkerIngress WorkerKube	Kubernetes kubelet, scheduler and controller manager	tcp	10250
WorkerIngress IngressServic es	Kubernetes Ingress services	tcp	30000 - 32767
WorkerIngress WorkerIngress Services	Kubernetes Ingress services	tcp	30000 - 32767

# Roles and instance profiles

You must grant the machines permissions in AWS. The provided CloudFormation templates grant the machines permission the following **AWS::IAM::Role** objects and provide a **AWS::IAM::InstanceProfile** for each set of roles. If you do not use the templates, you can grant the machines the following broad permissions or the following individual permissions.

Role	Effect	Action	Resource
Master	Allow	ec2:*	*
	Allow	elasticloadbalancing :*	*
	Allow	iam:PassRole	*
	Allow	s3:GetObject	*

Role	Effect	Action	Resource
Worker	Allow	ec2:Describe*	*
Bootstrap	Allow	ec2:Describe*	*
	Allow	ec2:AttachVolume	*
	Allow	ec2:DetachVolume	*

# 1.7.2.4. Required AWS permissions

When you attach the **AdministratorAccess** policy to the IAM user that you create in Amazon Web Services (AWS), you grant that user all of the required permissions. To deploy all components of an OpenShift Container Platform cluster, the IAM user requires the following permissions:

# Required EC2 permissions for installation

- ec2:AllocateAddress
- ec2:AssociateAddress
- ec2:AuthorizeSecurityGroupEgress
- ec2:AuthorizeSecurityGroupIngress
- ec2:Copylmage
- ec2:CreateNetworkInterface
- ec2:CreateSecurityGroup
- ec2:CreateTags
- ec2:CreateVolume
- ec2:DeleteSecurityGroup
- ec2:DeleteSnapshot
- ec2:DeregisterImage
- ec2:DescribeAccountAttributes
- ec2:DescribeAddresses
- ec2:DescribeAvailabilityZones
- ec2:DescribeDhcpOptions
- ec2:Describelmages
- ec2:DescribeInstanceAttribute

- ec2:DescribeInstanceCreditSpecifications
- ec2:DescribeInstances
- ec2:DescribeInternetGateways
- ec2:DescribeKeyPairs
- ec2:DescribeNatGateways
- ec2:DescribeNetworkAcls
- ec2:DescribeNetworkInterfaces
- ec2:DescribePrefixLists
- ec2:DescribeRegions
- ec2:DescribeRouteTables
- ec2:DescribeSecurityGroups
- ec2:DescribeSubnets
- ec2:DescribeTags
- ec2:DescribeVolumes
- ec2:DescribeVpcAttribute
- ec2:DescribeVpcClassicLink
- ec2:DescribeVpcClassicLinkDnsSupport
- ec2:DescribeVpcEndpoints
- ec2:DescribeVpcs
- ec2:ModifyInstanceAttribute
- ec2:ModifyNetworkInterfaceAttribute
- ec2:ReleaseAddress
- ec2:RevokeSecurityGroupEgress
- ec2:RevokeSecurityGroupIngress
- ec2:RunInstances
- ec2:TerminateInstances

Required permissions for creating network resources during installation

- ec2:AssociateDhcpOptions
- ec2:AssociateRouteTable

- ec2:AttachInternetGateway
- ec2:CreateDhcpOptions
- ec2:CreateInternetGateway
- ec2:CreateNatGateway
- ec2:CreateRoute
- ec2:CreateRouteTable
- ec2:CreateSubnet
- ec2:CreateVpc
- ec2:CreateVpcEndpoint
- ec2:ModifySubnetAttribute
- ec2:ModifyVpcAttribute



### NOTE

If you use an existing VPC, your account does not require these permissions for creating network resources.

# Required Elasticloadbalancing permissions for installation

- elasticloadbalancing:AddTags
- elasticloadbalancing:ApplySecurityGroupsToLoadBalancer
- elasticloadbalancing:AttachLoadBalancerToSubnets
- elasticloadbalancing:ConfigureHealthCheck
- elasticloadbalancing:CreateListener
- elasticloadbalancing:CreateLoadBalancer
- elasticloadbalancing:CreateLoadBalancerListeners
- elasticloadbalancing:CreateTargetGroup
- elasticloadbalancing:DeleteLoadBalancer
- elasticloadbalancing:DeregisterInstancesFromLoadBalancer
- elasticloadbalancing:DeregisterTargets
- elasticloadbalancing:DescribeInstanceHealth
- elasticloadbalancing:DescribeListeners
- elasticloadbalancing:DescribeLoadBalancerAttributes

- elasticloadbalancing:DescribeLoadBalancers
- elasticloadbalancing:DescribeTags
- elasticloadbalancing:DescribeTargetGroupAttributes
- elasticloadbalancing:DescribeTargetHealth
- elasticloadbalancing:ModifyLoadBalancerAttributes
- elasticloadbalancing:ModifyTargetGroup
- elasticloadbalancing:ModifyTargetGroupAttributes
- elasticloadbalancing:RegisterInstancesWithLoadBalancer
- elasticloadbalancing:RegisterTargets
- elasticloadbalancing:SetLoadBalancerPoliciesOfListener

# Required IAM permissions for installation

- iam:AddRoleToInstanceProfile
- iam:CreateInstanceProfile
- iam:CreateRole
- iam:DeleteInstanceProfile
- iam:DeleteRole
- iam:DeleteRolePolicy
- iam:GetInstanceProfile
- iam:GetRole
- iam:GetRolePolicy
- iam:GetUser
- iam:ListInstanceProfilesForRole
- iam:ListRoles
- iam:ListUsers
- iam:PassRole
- iam:PutRolePolicy
- iam:RemoveRoleFromInstanceProfile
- iam:SimulatePrincipalPolicy
- iam:TagRole

# Required Route53 permissions for installation

- route53:ChangeResourceRecordSets
- route53:ChangeTagsForResource
- route53:CreateHostedZone
- route53:DeleteHostedZone
- route53:GetChange
- route53:GetHostedZone
- route53:ListHostedZones
- route53:ListHostedZonesByName
- route53:ListResourceRecordSets
- route53:ListTagsForResource
- route53:UpdateHostedZoneComment

# Required S3 permissions for installation

- s3:CreateBucket
- s3:DeleteBucket
- s3:GetAccelerateConfiguration
- s3:GetBucketCors
- s3:GetBucketLocation
- s3:GetBucketLogging
- s3:GetBucketObjectLockConfiguration
- s3:GetBucketReplication
- s3:GetBucketRequestPayment
- s3:GetBucketTagging
- s3:GetBucketVersioning
- s3:GetBucketWebsite
- s3:GetEncryptionConfiguration
- s3:GetLifecycleConfiguration
- s3:GetReplicationConfiguration
- s3:ListBucket

- s3:PutBucketAcl
- s3:PutBucketTagging
- s3:PutEncryptionConfiguration

# S3 permissions that cluster Operators require

- s3:DeleteObject
- s3:GetObject
- s3:GetObjectAcl
- s3:GetObjectTagging
- s3:GetObjectVersion
- s3:PutObject
- s3:PutObjectAcl
- s3:PutObjectTagging

# Required permissions to delete base cluster resources

- autoscaling:DescribeAutoScalingGroups
- ec2:DeleteNetworkInterface
- ec2:DeleteVolume
- elasticloadbalancing:DeleteTargetGroup
- elasticloadbalancing:DescribeTargetGroups
- iam:ListInstanceProfiles
- iam:ListRolePolicies
- iam:ListUserPolicies
- s3:DeleteObject
- tag:GetResources

# Required permissions to delete network resources

- ec2:DeleteDhcpOptions
- ec2:DeleteInternetGateway
- ec2:DeleteNatGateway
- ec2:DeleteRoute
- ec2:DeleteRouteTable

- ec2:DeleteSubnet
- ec2:DeleteVpc
- ec2:DeleteVpcEndpoints
- ec2:DetachInternetGateway
- ec2:DisassociateRouteTable
- ec2:ReplaceRouteTableAssociation



### NOTE

If you use an existing VPC, your account does not require these permissions to delete network resources.

# 1.7.3. Obtaining the installation program

Before you install OpenShift Container Platform, download the installation file on a local computer.

# **Prerequisites**

- You must install the cluster from a computer that uses Linux or macOS.
- You need 500 MB of local disk space to download the installation program.

### Procedure

- 1. Access the Infrastructure Provider page on the Red Hat OpenShift Cluster Manager site. If you have a Red Hat account, log in with your credentials. If you do not, create an account.
- 2. Navigate to the page for your installation type, download the installation program for your operating system, and place the file in the directory where you will store the installation configuration files.



# **IMPORTANT**

The installation program creates several files on the computer that you use to install your cluster. You must keep both the installation program and the files that the installation program creates after you finish installing the cluster.

- 3. Extract the installation program. For example, on a computer that uses a Linux operating system, run the following command:
  - \$ tar xvf <installation\_program>.tar.gz
- 4. From the Pull Secret page on the Red Hat OpenShift Cluster Manager site, download your installation pull secret as a .txt file. This pull secret allows you to authenticate with the services that are provided by the included authorities, including Quay.io, which serves the container images for OpenShift Container Platform components.

# 1.7.4. Generating an SSH private key and adding it to the agent

If you want to perform installation debugging or disaster recovery on your cluster, you must provide an SSH key to both your **ssh-agent** and to the installation program.



# **NOTE**

In a production environment, you require disaster recovery and debugging.

You can use this key to SSH into the master nodes as the user **core**. When you deploy the cluster, the key is added to the **core** user's ~/.**ssh/authorized\_keys** list.



# **NOTE**

You must use a local key, not one that you configured with platform-specific approaches such as AWS key pairs.

# Procedure

1. If you do not have an SSH key that is configured for password-less authentication on your computer, create one. For example, on a computer that uses a Linux operating system, run the following command:

```
$ ssh-keygen -t rsa -b 4096 -N " \
-f <path>/<file_name> 1
```

Specify the path and file name, such as ~/.ssh/id\_rsa, of the SSH key.

Running this command generates an SSH key that does not require a password in the location that you specified.

2. Start the **ssh-agent** process as a background task:

```
$ eval "$(ssh-agent -s)"

Agent pid 31874
```

3. Add your SSH private key to the **ssh-agent**:

Specify the path and file name for your SSH private key, such as ~/.ssh/id\_rsa

### **Next steps**

 When you install OpenShift Container Platform, provide the SSH public key to the installation program. If you install a cluster on infrastructure that you provision, you must provide this key to your cluster's machines.

# 1.7.5. Creating the installation files for AWS

To install OpenShift Container Platform on Amazon Web Services (AWS) using user-provisioned infrastructure, you must generate the files that the installation program needs to deploy your cluster and modify them so that the cluster creates only the machines that it will use. You generate and customize the **install-config.yaml** file, Kubernetes manifests, and Ignition config files.

# 1.7.5.1. Creating the installation configuration file

Generate and customize the installation configuration file that the installation program needs to deploy your cluster.

# **Prerequisites**

 Obtain the OpenShift Container Platform installation program and the pull secret for your cluster.

### **Procedure**

- 1. Obtain the install-config.yaml file.
  - a. Run the following command:
    - \$ ./openshift-install create install-config --dir=<installation\_directory> 1
    - For **<installation\_directory>**, specify the directory name to store the files that the installation program creates.



# **IMPORTANT**

Specify an empty directory. Some installation assets, like bootstrap X.509 certificates have short expiration intervals, so you must not reuse an installation directory. If you want to reuse individual files from another cluster installation, you can copy them into your directory. However, the file names for the installation assets might change between releases. Use caution when copying installation files from an earlier OpenShift Container Platform version.

- b. At the prompts, provide the configuration details for your cloud:
  - i. Optional: Select an SSH key to use to access your cluster machines.



### NOTE

For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your **ssh-agent** process uses.

- ii. Select aws as the platform to target.
- iii. If you do not have an AWS profile stored on your computer, enter the AWS access key ID and secret access key for the user that you configured to run the installation program.
- iv. Select the AWS region to deploy the cluster to.

- v. Select the base domain for the Route53 service that you configured for your cluster.
- vi. Enter a descriptive name for your cluster.
- vii. Paste the pull secret that you obtained from the Pull Secret page on the Red Hat OpenShift Cluster Manager site.
- 2. Edit the **install-config.yaml** file to set the number of compute, or worker, replicas to **0**, as shown in the following **compute** stanza:

# compute:

- hyperthreading: Enabled

name: worker platform: {} replicas: 0

3. Optional: Back up the **install-config.yaml** file.



### **IMPORTANT**

The **install-config.yaml** file is consumed during the installation process. If you want to reuse the file, you must back it up now.

# 1.7.5.2. Configuring the cluster-wide proxy during installation

Production environments can deny direct access to the Internet and instead have an HTTP or HTTPS proxy available. You can configure a new OpenShift Container Platform cluster to use a proxy by configuring the proxy settings in the **install-config.yaml** file.

# **Prerequisites**

- An existing install-config.yaml file.
- Review the sites that your cluster requires access to and determine whether any need to bypass
  the proxy. By default, all cluster egress traffic is proxied, including calls to hosting cloud provider
  APIs. Add sites to the Proxy object's **spec.noProxy** field to bypass the proxy if necessary.



# NOTE

The Proxy object's **status.noProxy** field is populated by default with the instance metadata endpoint (**169.254.169.254**) and with the values of the **networking.machineCIDR**, **networking.clusterNetwork.cidr**, and **networking.serviceNetwork** fields from your installation configuration.

# **Procedure**

1. Edit your **install-config.yaml** file and add the proxy settings. For example:

apiVersion: v1

baseDomain: my.domain.com

proxy:

httpProxy: http://<username>:<pswd>@<ip>:<port> 1

httpsProxy: http://<username>:<pswd>@<ip>:<port> 2

noProxy: example.com 3

```
additionalTrustBundle: | 4
----BEGIN CERTIFICATE-----
<MY_TRUSTED_CA_CERT>
-----END CERTIFICATE-----
```

- A proxy URL to use for creating HTTP connections outside the cluster. The URL scheme must be **http**.
- A proxy URL to use for creating HTTPS connections outside the cluster. If this field is not specified, then **httpProxy** is used for both HTTP and HTTPS connections. The URL scheme must be **http**; **https** is currently not supported.
- A comma-separated list of destination domain names, domains, IP addresses, or other network CIDRs to exclude proxying. Preface a domain with . to include all subdomains of that domain. Use \* to bypass proxy for all destinations.
- If provided, the installation program generates a ConfigMap that is named **user-ca-bundle** in the **openshift-config** namespace that contains one or more additional CA certificates that are required for proxying HTTPS connections. The Cluster Network Operator then creates a **trusted-ca-bundle** ConfigMap that merges these contents with the Red Hat Enterprise Linux CoreOS (RHCOS) trust bundle, and this ConfigMap is referenced in the Proxy object's **trustedCA** field. The **additionalTrustBundle** field is required unless the proxy's identity certificate is signed by an authority from the RHCOS trust bundle.



### **NOTE**

The installation program does not support the proxy **readinessEndpoints** field.

2. Save the file and reference it when installing OpenShift Container Platform.

The installation program creates a cluster-wide proxy that is named **cluster** that uses the proxy settings in the provided **install-config.yaml** file. If no proxy settings are provided, a **cluster** Proxy object is still created, but it will have a nil **spec**.



### NOTE

Only the Proxy object named **cluster** is supported, and no additional proxies can be created.

# 1.7.5.3. Creating the Kubernetes manifest and Ignition config files

Because you must modify some cluster definition files and manually start the cluster machines, you must generate the Kubernetes manifest and Ignition config files that the cluster needs to make its machines.



# **IMPORTANT**

The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must complete your cluster installation and keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.

# **Prerequisites**

- Obtain the OpenShift Container Platform installation program.
- Create the **install-config.yaml** installation configuration file.

### **Procedure**

1. Generate the Kubernetes manifests for the cluster:

\$ ./openshift-install create manifests --dir=<installation\_directory>

WARNING There are no compute nodes specified. The cluster will not fully initialize without compute nodes.

INFO Consuming "Install Config" from target directory

For <installation\_directory>, specify the installation directory that contains the install-config.yaml file you created.

Because you create your own compute machines later in the installation process, you can safely ignore this warning.

- 2. Remove the Kubernetes manifest files that define the control plane machines:
  - \$ rm -f openshift/99\_openshift-cluster-api\_master-machines-\*.yaml

By removing these files, you prevent the cluster from automatically generating control plane machines.

3. Remove the Kubernetes manifest files that define the worker machines:

\$ rm -f openshift/99\_openshift-cluster-api\_worker-machineset-\*.yaml

Because you create and manage the worker machines yourself, you do not need to initialize these machines.

- 4. Modify the **manifests**/**cluster-scheduler-02-config.yml** Kubernetes manifest file to prevent Pods from being scheduled on the control plane machines:
  - a. Open the manifests/cluster-scheduler-02-config.yml file.
  - b. Locate the **mastersSchedulable** parameter and set its value to **False**.
  - c. Save and exit the file.



### NOTE

Currently, due to a Kubernetes limitation, router Pods running on control plane machines will not be reachable by the ingress load balancer. This step might not be required in a future minor version of OpenShift Container Platform.

5. Optional: If you do not want the Ingress Operator to create DNS records on your behalf, remove the privateZone and publicZone sections from the manifests/cluster-dns-02-config.yml DNS configuration file:

apiVersion: config.openshift.io/v1


```
kind: DNS
metadata:
    creationTimestamp: null
    name: cluster
spec:
    baseDomain: example.openshift.com
    privateZone: 1
    id: mycluster-100419-private-zone
    publicZone: 2
    id: example.openshift.com
status: {}
```

1 2 Remove these sections completely.

If you do so, you must add ingress DNS records manually in a later step.

- 6. Obtain the Ignition config files:
  - \$ ./openshift-install create ignition-configs --dir=<installation\_directory> 1
  - For **<installation\_directory>**, specify the same installation directory.

The following files are generated in the directory:



# 1.7.6. Extracting the infrastructure name

The Ignition configs contain a unique cluster identifier that you can use to uniquely identify your cluster in Amazon Web Services (AWS). The provided CloudFormation templates contain references to this infrastructure name, so you must extract it.

# **Prerequisites**

- Obtain the OpenShift Container Platform installation program and the pull secret for your cluster.
- Generate the Ignition config files for your cluster.
- Install the **jq** package.

### **Procedure**

 To extract and view the infrastructure name from the Ignition config file metadata, run the following command: \$ jq -r .infraID /<installation\_directory>/metadata.json 1 openshift-vw9j6 2

- For **<installation\_directory>**, specify the path to the directory that you stored the installation files in.
- The output of this command is your cluster name and a random string.

# 1.7.7. Creating a VPC in AWS

You must create a VPC in Amazon Web Services (AWS) for your OpenShift Container Platform cluster to use. You can customize the VPC to meet your requirements, including VPN and route tables. The easiest way to create the VPC is to modify the provided CloudFormation template.



# **NOTE**

If you do not use the provided CloudFormation template to create your AWS infrastructure, you must review the provided information and manually create the infrastructure. If your cluster does not initialize correctly, you might have to contact Red Hat support with your installation logs.

# **Prerequisites**

- Configure an AWS account.
- Generate the Ignition config files for your cluster.

## Procedure

1. Create a JSON file that contains the parameter values that the template requires:

- 1 The CIDR block for the VPC.
- Specify a CIDR block in the format x.x.x.x/16-24.
- 3 The number of availability zones to deploy the VPC in.

- 4 Specify an integer between **1** and **3**.
- The size of each subnet in each availability zone.
- 6 Specify an integer between **5** and **13**, where **5** is /**27** and **13** is /**19**.
- 2. Copy the template from the **CloudFormation template for the VPC**section of this topic and save it as a YAML file on your computer. This template describes the VPC that your cluster requires.
- 3. Launch the template:



#### **IMPORTANT**

You must enter the command on a single line.

\$ aws cloudformation create-stack --stack-name < name > 1

- --template-body file://<template>.yaml 2
- --parameters file://<parameters>.json 3
- <name> is the name for the CloudFormation stack, such as cluster-vpc. You need the name of this stack if you remove the cluster.
- **<template>** is the relative path to and name of the CloudFormation template YAML file that you saved.
- <parameters> is the relative path to and name of the CloudFormation parameters JSON file.
- 4. Confirm that the template components exist:
  - \$ aws cloudformation describe-stacks --stack-name <name>

After the **StackStatus** displays **CREATE\_COMPLETE**, the output displays values for the following parameters. You must provide these parameter values to the other CloudFormation templates that you run to create your cluster:

Vpcld	The ID of your VPC.
PublicSub netIds	The IDs of the new public subnets.
PrivateSu bnetIds	The IDs of the new private subnets.

### 1.7.7.1. CloudFormation template for the VPC

You can use the following CloudFormation template to deploy the VPC that you need for your OpenShift Container Platform cluster.

```
AWSTemplateFormatVersion: 2010-09-09
Description: Template for Best Practice VPC with 1-3 AZs
Parameters:
   VpcCidr:
      Allowed Pattern: \land (([0-9]|[1-9][0-9]|1[0-9]\{2\}|2[0-4][0-9]|25[0-5]) \land .) \\ \{3\}([0-9]|[1-9][0-9]|1[0-9]\{2\}|2[0-4]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9
[0-9]|25[0-5])(\lor(1[6-9]|2[0-4]))$
      ConstraintDescription: CIDR block parameter must be in the form x.x.x.x/16-24.
      Default: 10.0.0.0/16
      Description: CIDR block for VPC.
      Type: String
   AvailabilityZoneCount:
      ConstraintDescription: "The number of availability zones. (Min: 1, Max: 3)"
      MinValue: 1
      MaxValue: 3
      Default: 1
      Description: "How many AZs to create VPC subnets for. (Min: 1, Max: 3)"
      Type: Number
   SubnetBits:
      ConstraintDescription: CIDR block parameter must be in the form x.x.x.x/19-27.
      MinValue: 5
      MaxValue: 13
      Default: 12
      Description: "Size of each subnet to create within the availability zones. (Min: 5 = /27, Max: 13 =
/19)"
      Type: Number
Metadata:
   AWS::CloudFormation::Interface:
      ParameterGroups:
      - Label:
           default: "Network Configuration"
         Parameters:
         - VpcCidr
         - SubnetBits
      - Label:
           default: "Availability Zones"
         Parameters:
         - AvailabilityZoneCount
      ParameterLabels:
         AvailabilityZoneCount:
           default: "Availability Zone Count"
         VpcCidr:
           default: "VPC CIDR"
         SubnetBits:
            default: "Bits Per Subnet"
Conditions:
   DoAz3: !Equals [3, !Ref AvailabilityZoneCount]
   DoAz2: !Or [!Equals [2, !Ref AvailabilityZoneCount], Condition: DoAz3]
Resources:
   VPC:
      Type: "AWS::EC2::VPC"
      Properties:
         EnableDnsSupport: "true"
```

EnableDnsHostnames: "true" CidrBlock: !Ref VpcCidr PublicSubnet: Type: "AWS::EC2::Subnet" Properties: VpcId: !Ref VPC CidrBlock: !Select [0, !Cidr [!Ref VpcCidr, 6, !Ref SubnetBits]] AvailabilityZone: !Select - 0 - Fn::GetAZs: !Ref "AWS::Region" PublicSubnet2: Type: "AWS::EC2::Subnet" Condition: DoAz2 Properties: Vpcld: !Ref VPC CidrBlock: !Select [1, !Cidr [!Ref VpcCidr, 6, !Ref SubnetBits]] AvailabilityZone: !Select - 1 - Fn::GetAZs: !Ref "AWS::Region" PublicSubnet3: Type: "AWS::EC2::Subnet" Condition: DoAz3 Properties: Vpcld: !Ref VPC CidrBlock: !Select [2, !Cidr [!Ref VpcCidr, 6, !Ref SubnetBits]] AvailabilityZone: !Select - Fn::GetAZs: !Ref "AWS::Region" InternetGateway: Type: "AWS::EC2::InternetGateway" GatewayToInternet: Type: "AWS::EC2::VPCGatewayAttachment" Properties: VpcId: !Ref VPC InternetGatewayld: !Ref InternetGateway PublicRouteTable: Type: "AWS::EC2::RouteTable" Properties: Vpcld: !Ref VPC PublicRoute: Type: "AWS::EC2::Route" DependsOn: GatewayToInternet Properties: RouteTableId: !Ref PublicRouteTable DestinationCidrBlock: 0.0.0.0/0 Gatewayld: !Ref InternetGateway PublicSubnetRouteTableAssociation: Type: "AWS::EC2::SubnetRouteTableAssociation" Properties: SubnetId: !Ref PublicSubnet RouteTableId: !Ref PublicRouteTable PublicSubnetRouteTableAssociation2: Type: "AWS::EC2::SubnetRouteTableAssociation" Condition: DoAz2 Properties: SubnetId: !Ref PublicSubnet2

```
RouteTableId: !Ref PublicRouteTable
PublicSubnetRouteTableAssociation3:
 Condition: DoAz3
 Type: "AWS::EC2::SubnetRouteTableAssociation"
 Properties:
  SubnetId: !Ref PublicSubnet3
  RouteTableId: !Ref PublicRouteTable
PrivateSubnet:
 Type: "AWS::EC2::Subnet"
 Properties:
  Vpcld: !Ref VPC
  CidrBlock: !Select [3, !Cidr [!Ref VpcCidr, 6, !Ref SubnetBits]]
  AvailabilityZone: !Select
  - 0
  - Fn::GetAZs: !Ref "AWS::Region"
PrivateRouteTable:
 Type: "AWS::EC2::RouteTable"
 Properties:
  Vpcld: !Ref VPC
PrivateSubnetRouteTableAssociation:
 Type: "AWS::EC2::SubnetRouteTableAssociation"
 Properties:
  SubnetId: !Ref PrivateSubnet
  RouteTableId: !Ref PrivateRouteTable
NAT:
 DependsOn:
 - GatewayToInternet
 Type: "AWS::EC2::NatGateway"
 Properties:
  AllocationId:
   "Fn::GetAtt":
   - EIP
   - AllocationId
  SubnetId: !Ref PublicSubnet
EIP:
 Type: "AWS::EC2::EIP"
 Properties:
  Domain: vpc
Route:
 Type: "AWS::EC2::Route"
 Properties:
  RouteTableId:
   Ref: PrivateRouteTable
  DestinationCidrBlock: 0.0.0.0/0
  NatGatewayld:
   Ref: NAT
PrivateSubnet2:
 Type: "AWS::EC2::Subnet"
 Condition: DoAz2
 Properties:
  Vpcld: !Ref VPC
  CidrBlock: !Select [4, !Cidr [!Ref VpcCidr, 6, !Ref SubnetBits]]
  AvailabilityZone: !Select
  - Fn::GetAZs: !Ref "AWS::Region"
PrivateRouteTable2:
```

Type: "AWS::EC2::RouteTable" Condition: DoAz2 Properties: Vpcld: !Ref VPC PrivateSubnetRouteTableAssociation2: Type: "AWS::EC2::SubnetRouteTableAssociation" Condition: DoAz2 Properties: SubnetId: !Ref PrivateSubnet2 RouteTableId: !Ref PrivateRouteTable2 NAT2: DependsOn: - GatewayToInternet Type: "AWS::EC2::NatGateway" Condition: DoAz2 Properties: AllocationId: "Fn::GetAtt": - EIP2 - AllocationId SubnetId: !Ref PublicSubnet2 EIP2: Type: "AWS::EC2::EIP" Condition: DoAz2 Properties: Domain: vpc Route2: Type: "AWS::EC2::Route" Condition: DoAz2 Properties: RouteTableId: Ref: PrivateRouteTable2 DestinationCidrBlock: 0.0.0.0/0 NatGatewayld: Ref: NAT2 PrivateSubnet3: Type: "AWS::EC2::Subnet" Condition: DoAz3 Properties: Vpcld: !Ref VPC CidrBlock: !Select [5, !Cidr [!Ref VpcCidr, 6, !Ref SubnetBits]] AvailabilityZone: !Select - 2 - Fn::GetAZs: !Ref "AWS::Region" PrivateRouteTable3: Type: "AWS::EC2::RouteTable" Condition: DoAz3 Properties: Vpcld: !Ref VPC PrivateSubnetRouteTableAssociation3: Type: "AWS::EC2::SubnetRouteTableAssociation" Condition: DoAz3 Properties: SubnetId: !Ref PrivateSubnet3 RouteTableId: !Ref PrivateRouteTable3

NAT3:

```
DependsOn:
  - GatewayToInternet
  Type: "AWS::EC2::NatGateway"
  Condition: DoAz3
  Properties:
   AllocationId:
    "Fn::GetAtt":
    - EIP3
    - AllocationId
   SubnetId: !Ref PublicSubnet3
 EIP3:
  Type: "AWS::EC2::EIP"
  Condition: DoAz3
  Properties:
   Domain: vpc
 Route3:
  Type: "AWS::EC2::Route"
  Condition: DoAz3
  Properties:
   RouteTableId:
    Ref: PrivateRouteTable3
   DestinationCidrBlock: 0.0.0.0/0
   NatGatewayld:
    Ref: NAT3
 S3Endpoint:
  Type: AWS::EC2::VPCEndpoint
  Properties:
   PolicyDocument:
    Version: 2012-10-17
    Statement:
    - Effect: Allow
      Principal: '*'
      Action:
      Resource:
   RouteTableIds:
   - !Ref PublicRouteTable
   - !Ref PrivateRouteTable
   - !If [DoAz2, !Ref PrivateRouteTable2, !Ref "AWS::NoValue"]
   - !If [DoAz3, !Ref PrivateRouteTable3, !Ref "AWS::NoValue"]
   ServiceName: !Join
   _ "
   - - com.amazonaws.
    - !Ref 'AWS::Region'
    - .s3
   Vpcld: !Ref VPC
Outputs:
 Vpcld:
  Description: ID of the new VPC.
  Value: !Ref VPC
 PublicSubnetIds:
  Description: Subnet IDs of the public subnets.
  Value:
   !Join [
```

```
",",
    [!Ref PublicSubnet, !If [DoAz2, !Ref PublicSubnet2, !Ref "AWS::NoValue"], !If [DoAz3, !Ref
PublicSubnet3, !Ref "AWS::NoValue"]]
    ]
    PrivateSubnetIds:
    Description: Subnet IDs of the private subnets.
    Value:
    !Join [
        ",",
        [!Ref PrivateSubnet, !If [DoAz2, !Ref PrivateSubnet2, !Ref "AWS::NoValue"], !If [DoAz3, !Ref
PrivateSubnet3, !Ref "AWS::NoValue"]]
    ]
```

# 1.7.8. Creating networking and load balancing components in AWS

You must configure networking and load balancing (classic or network) in Amazon Web Services (AWS) for your OpenShift Container Platform cluster to use. The easiest way to create these components is to modify the provided CloudFormation template, which also creates a hosted zone and subnet tags.

You can run the template multiple times within a single VPC.



#### NOTE

If you do not use the provided CloudFormation template to create your AWS infrastructure, you must review the provided information and manually create the infrastructure. If your cluster does not initialize correctly, you might have to contact Red Hat support with your installation logs.

# **Prerequisites**

- Configure an AWS account.
- Generate the Ignition config files for your cluster.
- Create and configure a VPC and associated subnets in AWS.

#### **Procedure**

1. Obtain the Hosted Zone ID for the Route53 zone that you specified in the **install-config.yaml** file for your cluster. You can obtain this ID from the AWS console or by running the following command:



#### **IMPORTANT**

You must enter the command on a single line.

\$ aws route53 list-hosted-zones-by-name |
 jq --arg name "<route53\_domain>." \
 -r '.HostedZones | .[] | select(.Name=="\(\$name)") | .ld'

For the **<route53\_domain>**, specify the Route53 base domain that you used when you generated the **install-config.yaml** file for the cluster.

2. Create a JSON file that contains the parameter values that the template requires:

```
"ParameterKey": "ClusterName", 1
 "ParameterValue": "mycluster" (2)
 "ParameterKey": "InfrastructureName", 3
 "ParameterValue": "mycluster-<random_string>" 4
 "ParameterKey": "HostedZoneId", 5
 "ParameterValue": "<random_string>" 6
 "ParameterKey": "HostedZoneName", 7
 "ParameterValue": "example.com" (8)
 "ParameterKey": "PublicSubnets", 9
 "ParameterValue": "subnet-<random_string>" 10
},
 "ParameterKey": "PrivateSubnets", 11
 "ParameterValue": "subnet-<random_string>" 12
 "ParameterKey": "VpcId", 13
 "ParameterValue": "vpc-<random_string>" 14
```

- A short, representative cluster name to use for host names, etc.
- 2 Specify the cluster name that you used when you generated the **install-config.yaml** file for the cluster.
- 3 The name for your cluster infrastructure that is encoded in your Ignition config files for the cluster.
- Specify the infrastructure name that you extracted from the Ignition config file metadata, which has the format **<cluster-name>-<random-string>**.
- The Route53 public zone ID to register the targets with.
- Specify the Route53 public zone ID, which as a format similar to **Z21IXYZABCZ2A4**. You can obtain this value from the AWS console.
- 7 The Route53 zone to register the targets with.
- Specify the Route53 base domain that you used when you generated the **install-config.yaml** file for the cluster. Do not include the trailing period (.) that is displayed in the AWS console.

- The public subnets that you created for your VPC.
- Specify the PublicSubnetIds value from the output of the CloudFormation template for the VPC.
- The private subnets that you created for your VPC.
- Specify the PrivateSubnetIds value from the output of the CloudFormation template for the VPC.
- The VPC that you created for the cluster.
- Specify the **VpcId** value from the output of the CloudFormation template for the VPC.
- 3. Copy the template from the CloudFormation template for the network and load balancers section of this topic and save it as a YAML file on your computer. This template describes the networking and load balancing objects that your cluster requires.
- 4. Launch the template:



#### **IMPORTANT**

You must enter the command on a single line.

\$ aws cloudformation create-stack --stack-name < name > 1

- --template-body file://<template>.yaml 2
- --parameters file://<parameters>.json 3
- --capabilities CAPABILITY NAMED IAM
- <name> is the name for the CloudFormation stack, such as cluster-dns. You need the name of this stack if you remove the cluster.
- <template> is the relative path to and name of the CloudFormation template YAML file that you saved.
- <parameters> is the relative path to and name of the CloudFormation parameters JSON file.
- 5. Confirm that the template components exist:
  - \$ aws cloudformation describe-stacks --stack-name <name>

After the StackStatus displays CREATE\_COMPLETE, the output displays values for the following parameters. You must provide these parameter values to the other CloudFormation templates that you run to create your cluster:

PrivateHo stedZonel d	Hosted zone ID for the private DNS.
-----------------------------	-------------------------------------

ExternalA piLoadBal ancerNam e	Full name of the external API load balancer.
InternalAp iLoadBala ncerName	Full name of the internal API load balancer.
ApiServer DnsName	Full host name of the API server.
RegisterN lblpTarget sLambda	Lambda ARN useful to help register/deregister IP targets for these load balancers.
ExternalA piTargetG roupArn	ARN of external API target group.
InternalAp iTargetGr oupArn	ARN of internal API target group.
InternalSe rviceTarg etGroupA rn	ARN of internal service target group.

### 1.7.8.1. CloudFormation template for the network and load balancers

You can use the following CloudFormation template to deploy the networking objects and load balancers that you need for your OpenShift Container Platform cluster.

AWSTemplateFormatVersion: 2010-09-09

Description: Template for OpenShift Cluster Network Elements (Route53 & LBs)

Parameters:

ClusterName:

AllowedPattern: ^([a-zA-Z][a-zA-Z0-9\-]{0,26})\$

MaxLength: 27 MinLength: 1

ConstraintDescription: Cluster name must be alphanumeric, start with a letter, and have a maximum of 27 characters.

Description: A short, representative cluster name to use for host names and other identifying

names.

Type: String InfrastructureName:

AllowedPattern: ([a-zA-Z][a-zA-Z0-9]-](0,26))

MaxLength: 27 MinLength: 1

ConstraintDescription: Infrastructure name must be alphanumeric, start with a letter, and have a

maximum of 27 characters.

Description: A short, unique cluster ID used to tag cloud resources and identify items owned or used by the cluster.

Type: String HostedZoneld:

Description: The Route53 public zone ID to register the targets with, such as Z21IXYZABCZ2A4.

Type: String HostedZoneName:

Description: The Route53 zone to register the targets with, such as example.com. Omit the trailing period.

Type: String

Default: "example.com"

PublicSubnets:

Description: The internet-facing subnets. Type: List<AWS::EC2::Subnet::Id>

PrivateSubnets:

Description: The internal subnets. Type: List<AWS::EC2::Subnet::Id>

Vpcld:

Description: The VPC-scoped resources will belong to this VPC.

Type: AWS::EC2::VPC::Id

#### Metadata:

AWS::CloudFormation::Interface:

ParameterGroups:

- Label:

default: "Cluster Information"

Parameters:

- ClusterName
- InfrastructureName
- Label:

default: "Network Configuration"

Parameters:

- Vpcld
- PublicSubnets
- PrivateSubnets
- Label

default: "DNS"

Parameters:

- HostedZoneName
- HostedZoneId

ParameterLabels:

ClusterName:

default: "Cluster Name" InfrastructureName:

default: "Infrastructure Name"

Vpcld:

default: "VPC ID" PublicSubnets:

default: "Public Subnets"

PrivateSubnets:

default: "Private Subnets"

HostedZoneName:

default: "Public Hosted Zone Name"

HostedZoneId:

default: "Public Hosted Zone ID"

```
Resources:
 ExtApiElb:
  Type: AWS::ElasticLoadBalancingV2::LoadBalancer
  Properties:
   Name: !Join ["-", [!Ref InfrastructureName, "ext"]]
   IpAddressType: ipv4
   Subnets: !Ref PublicSubnets
   Type: network
 IntApiElb:
  Type: AWS::ElasticLoadBalancingV2::LoadBalancer
  Properties:
   Name: !Join ["-", [!Ref InfrastructureName, "int"]]
   Scheme: internal
   IpAddressType: ipv4
   Subnets: !Ref PrivateSubnets
   Type: network
 IntDns:
  Type: "AWS::Route53::HostedZone"
  Properties:
   HostedZoneConfig:
    Comment: "Managed by CloudFormation"
   Name: !Join [".", [!Ref ClusterName, !Ref HostedZoneName]]
   HostedZoneTags:
   - Key: Name
    Value: !Join ["-", [!Ref InfrastructureName, "int"]]
   - Key: !Join ["", ["kubernetes.io/cluster/", !Ref InfrastructureName]]
    Value: "owned"
   VPCs:
   - VPCId: !Ref VpcId
    VPCRegion: !Ref "AWS::Region"
 ExternalApiServerRecord:
  Type: AWS::Route53::RecordSetGroup
   Comment: Alias record for the API server
   HostedZoneld: !Ref HostedZoneld
   RecordSets:
   - Name:
      !Join [
       ["api", !Ref ClusterName, !Join ["", [!Ref HostedZoneName, "."]]],
     ]
    Type: A
    AliasTarget:
      HostedZoneld: !GetAtt ExtApiElb.CanonicalHostedZoneID
      DNSName: !GetAtt ExtApiElb.DNSName
 InternalApiServerRecord:
  Type: AWS::Route53::RecordSetGroup
  Properties:
   Comment: Alias record for the API server
   HostedZoneId: !Ref IntDns
   RecordSets:
```

```
- Name:
    !Join [
     ".",
     ["api", !Ref ClusterName, !Join ["", [!Ref HostedZoneName, "."]]],
   Type: A
   AliasTarget:
    HostedZoneId: !GetAtt IntApiElb.CanonicalHostedZoneID
    DNSName: !GetAtt IntApiElb.DNSName
  - Name:
    !Join [
     ".",
      ["api-int", !Ref ClusterName, !Join ["", [!Ref HostedZoneName, "."]]],
   Type: A
   AliasTarget:
    HostedZoneld: !GetAtt IntApiElb.CanonicalHostedZoneID
    DNSName: !GetAtt IntApiElb.DNSName
ExternalApiListener:
 Type: AWS::ElasticLoadBalancingV2::Listener
 Properties:
  DefaultActions:
  - Type: forward
   TargetGroupArn:
    Ref: ExternalApiTargetGroup
  LoadBalancerArn:
   Ref: ExtApiElb
  Port: 6443
  Protocol: TCP
ExternalApiTargetGroup:
 Type: AWS::ElasticLoadBalancingV2::TargetGroup
 Properties:
  Port: 6443
  Protocol: TCP
  TargetType: ip
  Vpcld:
   Ref: Vpcld
  TargetGroupAttributes:
  - Key: deregistration_delay.timeout_seconds
   Value: 60
InternalApiListener:
 Type: AWS::ElasticLoadBalancingV2::Listener
 Properties:
  DefaultActions:
  - Type: forward
   TargetGroupArn:
    Ref: InternalApiTargetGroup
  LoadBalancerArn:
   Ref: IntApiElb
  Port: 6443
  Protocol: TCP
InternalApiTargetGroup:
```

```
Type: AWS::ElasticLoadBalancingV2::TargetGroup
 Properties:
  Port: 6443
  Protocol: TCP
  TargetType: ip
  Vpcld:
   Ref: Vpcld
  TargetGroupAttributes:
  - Key: deregistration_delay.timeout_seconds
   Value: 60
InternalServiceInternalListener:
 Type: AWS::ElasticLoadBalancingV2::Listener
 Properties:
  DefaultActions:
  - Type: forward
   TargetGroupArn:
     Ref: InternalServiceTargetGroup
  LoadBalancerArn:
   Ref: IntApiElb
  Port: 22623
  Protocol: TCP
InternalServiceTargetGroup:
 Type: AWS::ElasticLoadBalancingV2::TargetGroup
 Properties:
  Port: 22623
  Protocol: TCP
  TargetType: ip
  Vpcld:
   Ref: Vpcld
  TargetGroupAttributes:
  - Key: deregistration delay.timeout seconds
   Value: 60
RegisterTargetLambdalamRole:
 Type: AWS::IAM::Role
 Properties:
  RoleName: !Join ["-", [!Ref InfrastructureName, "nlb", "lambda", "role"]]
  AssumeRolePolicyDocument:
   Version: "2012-10-17"
   Statement:
   - Effect: "Allow"
    Principal:
      Service:
      - "lambda.amazonaws.com"
     - "sts:AssumeRole"
  Path: "/"
  Policies:
  - PolicyName: !Join ["-", [!Ref InfrastructureName, "master", "policy"]]
   PolicyDocument:
     Version: "2012-10-17"
     Statement:
     - Effect: "Allow"
      Action:
```

```
"elasticloadbalancing:RegisterTargets",
          "elasticloadbalancing:DeregisterTargets",
       Resource: !Ref InternalApiTargetGroup
      - Effect: "Allow"
       Action:
          "elasticloadbalancing:RegisterTargets",
          "elasticloadbalancing:DeregisterTargets",
       Resource: !Ref InternalServiceTargetGroup
      - Effect: "Allow"
       Action:
          "elasticloadbalancing:RegisterTargets",
          "elasticloadbalancing:DeregisterTargets",
       Resource: !Ref ExternalApiTargetGroup
 RegisterNlblpTargets:
  Type: "AWS::Lambda::Function"
  Properties:
   Handler: "index.handler"
   Role:
     Fn::GetAtt:
     - "RegisterTargetLambdalamRole"
     - "Arn"
   Code:
     ZipFile: |
      import json
      import boto3
      import cfnresponse
      def handler(event, context):
       elb = boto3.client('elbv2')
       if event['RequestType'] == 'Delete':
        elb.deregister targets(TargetGroupArn=event['ResourceProperties']['TargetArn'],Targets=
[{'Id': event['ResourceProperties']['TargetIp']}])
       elif event['RequestType'] == 'Create':
        elb.register_targets(TargetGroupArn=event['ResourceProperties']['TargetArn'],Targets=[{'Id':
event['ResourceProperties']['TargetIp']}])
       responseData = {}
       cfnresponse.send(event, context, cfnresponse.SUCCESS, responseData,
event['ResourceProperties']['TargetArn']+event['ResourceProperties']['TargetIp'])
   Runtime: "python3.7"
   Timeout: 120
 RegisterSubnetTagsLambdalamRole:
  Type: AWS::IAM::Role
  Properties:
   RoleName: !Join ["-", [!Ref InfrastructureName, "subnet-tags-lambda-role"]]
   AssumeRolePolicyDocument:
     Version: "2012-10-17"
     Statement:
     - Effect: "Allow"
      Principal:
```

```
Service:
       - "lambda.amazonaws.com"
      Action:
      - "sts:AssumeRole"
   Path: "/"
   Policies:
   - PolicyName: !Join ["-", [!Ref InfrastructureName, "subnet-tagging-policy"]]
     PolicyDocument:
      Version: "2012-10-17"
      Statement:
      - Effect: "Allow"
       Action:
          "ec2:DeleteTags",
          "ec2:CreateTags"
       Resource: "arn:aws:ec2:*:*:subnet/*"
      - Effect: "Allow"
       Action:
          "ec2:DescribeSubnets",
          "ec2:DescribeTags"
       Resource: "*"
 RegisterSubnetTags:
  Type: "AWS::Lambda::Function"
  Properties:
   Handler: "index.handler"
   Role:
     Fn::GetAtt:
     - "RegisterSubnetTagsLambdalamRole"
     - "Arn"
   Code:
     ZipFile: |
      import json
      import boto3
      import cfnresponse
      def handler(event, context):
       ec2_client = boto3.client('ec2')
       if event['RequestType'] == 'Delete':
        for subnet id in event['ResourceProperties']['Subnets']:
          ec2_client.delete_tags(Resources=[subnet_id], Tags=[{'Key': 'kubernetes.io/cluster/' +
event['ResourceProperties']['InfrastructureName']}]);
       elif event['RequestType'] == 'Create':
        for subnet id in event['ResourceProperties']['Subnets']:
          ec2 client.create tags(Resources=[subnet id], Tags=[{'Key': 'kubernetes.io/cluster/' +
event['ResourceProperties']['InfrastructureName'], 'Value': 'shared'}]);
       responseData = {}
       cfnresponse.send(event, context, cfnresponse.SUCCESS, responseData,
event['ResourceProperties']['InfrastructureName']+event['ResourceProperties']['Subnets'][0])
   Runtime: "python3.7"
   Timeout: 120
 RegisterPublicSubnetTags:
  Type: Custom::SubnetRegister
```

Properties:

ServiceToken: !GetAtt RegisterSubnetTags.Arn InfrastructureName: !Ref InfrastructureName

Subnets: !Ref PublicSubnets

RegisterPrivateSubnetTags: Type: Custom::SubnetRegister

Properties:

ServiceToken: !GetAtt RegisterSubnetTags.Arn InfrastructureName: !Ref InfrastructureName

Subnets: !Ref PrivateSubnets

### Outputs:

PrivateHostedZoneId:

Description: Hosted zone ID for the private DNS, which is required for private records.

Value: !Ref IntDns

ExternalApiLoadBalancerName:

Description: Full name of the External API load balancer created.

Value: !GetAtt ExtApiElb.LoadBalancerFullName

InternalApiLoadBalancerName:

Description: Full name of the Internal API load balancer created.

Value: !GetAtt IntApiElb.LoadBalancerFullName

ApiServerDnsName:

Description: Full hostname of the API server, which is required for the Ignition config files.

Value: !Join [".", ["api-int", !Ref ClusterName, !Ref HostedZoneName]]

RegisterNlblpTargetsLambda:

Description: Lambda ARN useful to help register or deregister IP targets for these load balancers.

Value: !GetAtt RegisterNlblpTargets.Arn

ExternalApiTargetGroupArn:

Description: ARN of External API target group.

Value: !Ref ExternalApiTargetGroup

InternalApiTargetGroupArn:

Description: ARN of Internal API target group.

Value: !Ref InternalApiTargetGroup InternalServiceTargetGroupArn:

Description: ARN of internal service target group.

Value: !Ref InternalServiceTargetGroup

# 1.7.9. Creating security group and roles in AWS

You must create security groups and roles in Amazon Web Services (AWS) for your OpenShift Container Platform cluster to use. The easiest way to create these components is to modify the provided CloudFormation template.



### NOTE

If you do not use the provided CloudFormation template to create your AWS infrastructure, you must review the provided information and manually create the infrastructure. If your cluster does not initialize correctly, you might have to contact Red Hat support with your installation logs.

### **Prerequisites**

Configure an AWS account.

- Generate the Ignition config files for your cluster.
- Create and configure a VPC and associated subnets in AWS.

#### **Procedure**

1. Create a JSON file that contains the parameter values that the template requires:

- The name for your cluster infrastructure that is encoded in your Ignition config files for the cluster.
- 2 Specify the infrastructure name that you extracted from the Ignition config file metadata, which has the format **<cluster-name>-<random-string>**.
- The CIDR block for the VPC.
- Specify the CIDR block parameter that you used for the VPC that you defined in the form **x.x.x.x/16-24**.
- The private subnets that you created for your VPC.
- Specify the **PrivateSubnetIds** value from the output of the CloudFormation template for the VPC.
- 7 The VPC that you created for the cluster.
- 8 Specify the **VpcId** value from the output of the CloudFormation template for the VPC.
- 2. Copy the template from the **CloudFormation template for security objects**section of this topic and save it as a YAML file on your computer. This template describes the security groups and roles that your cluster requires.
- 3. Launch the template:



#### **IMPORTANT**

You must enter the command on a single line.

\$ aws cloudformation create-stack --stack-name < name > 1

- --template-body file://<template>.yaml 2
- --parameters file://<parameters>.json 3
- --capabilities CAPABILITY\_NAMED\_IAM
- <name> is the name for the CloudFormation stack, such as cluster-sec. You need the name of this stack if you remove the cluster.
- <template> is the relative path to and name of the CloudFormation template YAML file that you saved.
- <parameters> is the relative path to and name of the CloudFormation parameters JSON
- 4. Confirm that the template components exist:
  - \$ aws cloudformation describe-stacks --stack-name <name>

After the StackStatus displays CREATE\_COMPLETE, the output displays values for the following parameters. You must provide these parameter values to the other CloudFormation templates that you run to create your cluster:

MasterSec urityGrou pld	Master Security Group ID
WorkerSe curityGro upId	Worker Security Group ID
MasterIns tanceProfi le	Master IAM Instance Profile
Workerins tanceProfi le	Worker IAM Instance Profile

### 1.7.9.1. CloudFormation template for security objects

You can use the following CloudFormation template to deploy the security objects that you need for your OpenShift Container Platform cluster.

AWSTemplateFormatVersion: 2010-09-09

Description: Template for OpenShift Cluster Security Elements (Security Groups & IAM)

Parameters:

InfrastructureName:

AllowedPattern: ^([a-zA-Z][a-zA-Z0-9\-]{0,26})\$

MaxLength: 27 MinLength: 1

ConstraintDescription: Infrastructure name must be alphanumeric, start with a letter, and have a maximum of 27 characters.

Description: A short, unique cluster ID used to tag cloud resources and identify items owned or used by the cluster.

Type: String VpcCidr:

AllowedPattern: ^(([0-9]|[1-9][0-9]|1[0-9]{2}|2[0-4][0-9]|25[0-5])\.){3}([0-9]|[1-9][0-9]|1[0-9]{2}|2[0-4]

 $[0-9]|25[0-5])(\forall (1[6-9]|2[0-4]))$ \$

ConstraintDescription: CIDR block parameter must be in the form x.x.x.x/16-24.

Default: 10.0.0.0/16

Description: CIDR block for VPC.

Type: String VpcId:

Description: The VPC-scoped resources will belong to this VPC.

Type: AWS::EC2::VPC::Id

PrivateSubnets:

Description: The internal subnets. Type: List<AWS::EC2::Subnet::Id>

#### Metadata:

AWS::CloudFormation::Interface:

ParameterGroups:

- Label:

default: "Cluster Information"

Parameters:

- InfrastructureName

- Label:

default: "Network Configuration"

Parameters:

- Vpcld

- VpcCidr

- PrivateSubnets

ParameterLabels:

InfrastructureName:

default: "Infrastructure Name"

Vpcld:

default: "VPC ID"

VpcCidr:

default: "VPC CIDR"

PrivateSubnets:

default: "Private Subnets"

#### Resources:

MasterSecurityGroup:

Type: AWS::EC2::SecurityGroup

Properties:

GroupDescription: Cluster Master Security Group

SecurityGroupIngress:
- IpProtocol: icmp

FromPort: 0
ToPort: 0

Cidrlp: !Ref VpcCidr

IpProtocol: tcp FromPort: 22 ToPort: 22

Cidrlp: !Ref VpcCidr
- lpProtocol: tcp
ToPort: 6443
FromPort: 6443
Cidrlp: !Ref VpcCidr
- lpProtocol: tcp

FromPort: 22623 ToPort: 22623 Cidrlp: !Ref VpcCidr VpcId: !Ref VpcId

### WorkerSecurityGroup:

Type: AWS::EC2::SecurityGroup

Properties:

GroupDescription: Cluster Worker Security Group

SecurityGroupIngress:
- IpProtocol: icmp
FromPort: 0
ToPort: 0

Cidrlp: !Ref VpcCidr
- lpProtocol: tcp
FromPort: 22
ToPort: 22

Cidrlp: !Ref VpcCidr VpcId: !Ref VpcId

### MasterIngressEtcd:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId

Description: etcd FromPort: 2379 ToPort: 2380 IpProtocol: tcp

# MasterIngressVxlan:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId

Description: Vxlan packets

FromPort: 4789 ToPort: 4789 IpProtocol: udp

### MasterIngressWorkerVxlan:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt WorkerSecurityGroup.GroupId

Description: Vxlan packets

FromPort: 4789

ToPort: 4789 IpProtocol: udp

MasterIngressInternal:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId

Description: Internal cluster communication

FromPort: 9000 ToPort: 9999 IpProtocol: tcp

MasterIngressWorkerInternal:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt WorkerSecurityGroup.GroupId

Description: Internal cluster communication

FromPort: 9000 ToPort: 9999 IpProtocol: tcp

MasterIngressKube:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId Description: Kubernetes kubelet, scheduler and controller manager

FromPort: 10250 ToPort: 10259 IpProtocol: tcp

MasterIngressWorkerKube:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt WorkerSecurityGroup.GroupId Description: Kubernetes kubelet, scheduler and controller manager

FromPort: 10250 ToPort: 10259 IpProtocol: tcp

MasterIngressIngressServices:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId

Description: Kubernetes ingress services

FromPort: 30000 ToPort: 32767 IpProtocol: tcp

MasterIngressWorkerIngressServices:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt WorkerSecurityGroup.GroupId

Description: Kubernetes ingress services

FromPort: 30000 ToPort: 32767 IpProtocol: tcp

#### WorkerIngressVxlan:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt WorkerSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt WorkerSecurityGroup.GroupId

Description: Vxlan packets

FromPort: 4789 ToPort: 4789 IpProtocol: udp

#### WorkerIngressWorkerVxlan:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt WorkerSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId

Description: Vxlan packets

FromPort: 4789 ToPort: 4789 IpProtocol: udp

### WorkerIngressInternal:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt WorkerSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt WorkerSecurityGroup.GroupId

Description: Internal cluster communication

FromPort: 9000 ToPort: 9999 IpProtocol: tcp

#### WorkerIngressWorkerInternal:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt WorkerSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId

Description: Internal cluster communication

FromPort: 9000 ToPort: 9999 IpProtocol: tcp

# WorkerIngressKube:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt WorkerSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt WorkerSecurityGroup.GroupId

Description: Kubernetes secure kubelet port

FromPort: 10250 ToPort: 10250 IpProtocol: tcp WorkerIngressWorkerKube:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt WorkerSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId

Description: Internal Kubernetes communication

FromPort: 10250 ToPort: 10250 IpProtocol: tcp

WorkerIngressIngressServices:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt WorkerSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt WorkerSecurityGroup.GroupId

Description: Kubernetes ingress services

FromPort: 30000 ToPort: 32767 IpProtocol: tcp

WorkerIngressWorkerIngressServices:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt WorkerSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId

Description: Kubernetes ingress services

FromPort: 30000 ToPort: 32767 IpProtocol: tcp

MasterlamRole:

Type: AWS::IAM::Role

Properties:

AssumeRolePolicyDocument:

Version: "2012-10-17"

Statement:
- Effect: "Allow"
Principal:
Service:

- "ec2.amazonaws.com"

Action:

- "sts:AssumeRole"

Policies:

- PolicyName: !Join ["-", [!Ref InfrastructureName, "master", "policy"]]

PolicyDocument: Version: "2012-10-17"

Statement:
- Effect: "Allow"
Action: "ec2:\*"
Resource: "\*"
- Effect: "Allow"

Action: "elasticloadbalancing:\*"

Resource: "\*"
- Effect: "Allow"

Action: "iam:PassRole"

Resource: "\*"
- Effect: "Allow"

Action: "s3:GetObject"

Resource: "\*"

#### MasterInstanceProfile:

Type: "AWS::IAM::InstanceProfile"

Properties: Roles:

- Ref: "MasterlamRole"

#### WorkerlamRole:

Type: AWS::IAM::Role

Properties:

### AssumeRolePolicyDocument:

Version: "2012-10-17"

Statement:
- Effect: "Allow"
Principal:
Service:

- "ec2.amazonaws.com"

Action:

- "sts:AssumeRole"

#### Policies:

- PolicyName: !Join ["-", [!Ref InfrastructureName, "worker", "policy"]]

PolicyDocument: Version: "2012-10-17"

Statement:
- Effect: "Allow"

Action: "ec2:Describe\*"

Resource: "\*"

### WorkerInstanceProfile:

Type: "AWS::IAM::InstanceProfile"

Properties: Roles:

- Ref: "WorkerlamRole"

#### Outputs:

MasterSecurityGroupId:

Description: Master Security Group ID

Value: !GetAtt MasterSecurityGroup.GroupId

### WorkerSecurityGroupId:

Description: Worker Security Group ID

Value: !GetAtt WorkerSecurityGroup.GroupId

#### MasterInstanceProfile:

Description: Master IAM Instance Profile

Value: !Ref MasterInstanceProfile

# WorkerInstanceProfile:

Description: Worker IAM Instance Profile

Value: !Ref WorkerInstanceProfile

## 1.7.10. RHCOS AMIs for the AWS infrastructure

You must use a valid Red Hat Enterprise Linux CoreOS (RHCOS) AMI for your Amazon Web Services (AWS) zone for your OpenShift Container Platform nodes.

Table 1.15. RHCOS AMIs

AWS zone	AWS AMI
ap-northeast-1	ami-023d0452866845125
ap-northeast-2	ami-0ba4f9a0358bcb44a
ap-south-1	ami-0bf62e963a473068e"
ap-southeast-1	ami-086b93722336bd1d9
ap-southeast-2	ami-08929f33bfab49b83
ca-central-1	ami-0f6d943a1fa9172fd
eu-central-1	ami-0ceea534b63224411
eu-north-1	ami-06b7087b2768f644a
eu-west-1	ami-0e95125b57fa63b0d
eu-west-2	ami-0eef98c447b85ffcd
eu-west-3	ami-0049e16104f360df6
me-south-1	ami-0b03ea038629fd02e
sa-east-1	ami-0c80d785b30eef121
us-east-1	ami-06f85a7940faa3217
us-east-2	ami-04a79d8d7cfa540cc
us-west-1	ami-0633b392e8eff25e7
us-west-2	ami-0d231993dddc5cd2e

# 1.7.11. Creating the bootstrap node in AWS

You must create the bootstrap node in Amazon Web Services (AWS) to use during OpenShift Container Platform cluster initialization. The easiest way to create this node is to modify the provided CloudFormation template.



#### **NOTE**

If you do not use the provided CloudFormation template to create your bootstrap node, you must review the provided information and manually create the infrastructure. If your cluster does not initialize correctly, you might have to contact Red Hat support with your installation logs.

### **Prerequisites**

- Configure an AWS account.
- Generate the Ignition config files for your cluster.
- Create and configure a VPC and assocated subnets in AWS.
- Create and configure DNS, load balancers, and listeners in AWS.
- Create control plane and compute roles.

#### **Procedure**

1. Provide a location to serve the **bootstrap.ign** Ignition config file to your cluster. This file is located in your installation directory. One way to do this is to create an S3 bucket in your cluster's region and upload the Ignition config file to it.



#### **IMPORTANT**

The provided CloudFormation Template assumes that the Ignition config files for your cluster are served from an S3 bucket. If you choose to serve the files from another location, you must modify the templates.



### **NOTE**

The bootstrap Ignition config file does contain secrets, like X.509 keys. The following steps provide basic security for the S3 bucket. To provide additional security, you can enable an S3 bucket policy to allow only certain users, such as the OpenShift IAM user, to access objects that the bucket contains. You can avoid S3 entirely and serve your bootstrap Ignition config file from any address that the bootstrap machine can reach.

- a. Create the bucket:
  - \$ aws s3 mb s3://<cluster-name>-infra
  - <cluster-name>-infra is the bucket name.
- b. Upload the **bootstrap.ign** Ignition config file to the bucket:
  - \$ aws s3 cp bootstrap.ign s3://<cluster-name>-infra/bootstrap.ign
- c. Verify that the file uploaded:

```
$ aws s3 ls s3://<cluster-name>-infra/
2019-04-03 16:15:16 314878 bootstrap.ign
```

2. Create a JSON file that contains the parameter values that the template requires:

```
"ParameterKey": "InfrastructureName", 1
 "ParameterValue": "mycluster-<random_string>" 2
  "ParameterKey": "RhcosAmi", 3
 "ParameterValue": "ami-<random_string>" 4
  "ParameterKey": "AllowedBootstrapSshCidr", 5
  "ParameterValue": "0.0.0.0/0" 6
  "ParameterKey": "PublicSubnet", 7
  "ParameterValue": "subnet-<random_string>" 8
  "ParameterKey": "MasterSecurityGroupId", 9
  "ParameterValue": "sg-<random string>" 10
 "ParameterKey": "VpcId", 111
  "ParameterValue": "vpc-<random_string>" 12
  "ParameterKey": "BootstrapIgnitionLocation", 13
  "ParameterValue": "s3://<bucket_name>/bootstrap.ign" 14
  "ParameterKey": "AutoRegisterELB", 15
  "ParameterValue": "yes" 16
  "ParameterKey": "RegisterNlblpTargetsLambdaArn", 17
  "ParameterValue": "arn:aws:lambda:<region>:<account number>:function:
<dns_stack_name>-RegisterNlblpTargets-<random_string>" 18
  "ParameterKey": "ExternalApiTargetGroupArn", 19
  "ParameterValue": "arn:aws:elasticloadbalancing:<region>:
<account_number>:targetgroup/<dns_stack_name>-Exter-<random_string>" 20
},
  "ParameterKey": "InternalApiTargetGroupArn", 21
  "ParameterValue": "arn:aws:elasticloadbalancing:<region>:
```

```
<account_number>:targetgroup/<dns_stack_name>-Inter-<random_string>" 22
},
{
   "ParameterKey": "InternalServiceTargetGroupArn", 23
   "ParameterValue": "arn:aws:elasticloadbalancing:<region>:
<account_number>:targetgroup/<dns_stack_name>-Inter-<random_string>" 24
}
]
```

- The name for your cluster infrastructure that is encoded in your Ignition config files for the cluster.
- Specify the infrastructure name that you extracted from the Ignition config file metadata, which has the format **<cluster-name>-<random-string>**.
- Current Red Hat Enterprise Linux CoreOS (RHCOS) AMI to use for the bootstrap node.
- Specify a valid **AWS::EC2::Image::Id** value.
- CIDR block to allow SSH access to the bootstrap node.
- Specify a CIDR block in the format x.x.x.x/16-24.
- The public subnet that is associated with your VPC to launch the bootstrap node into.
- Specify the **PublicSubnetIds** value from the output of the CloudFormation template for the VPC.
- The master security group ID (for registering temporary rules)
- Specify the **MasterSecurityGroupId** value from the output of the CloudFormation template for the security group and roles.
- The VPC created resources will belong to.
- Specify the **VpcId** value from the output of the CloudFormation template for the VPC.
- Location to fetch bootstrap Ignition config file from.
- Specify the S3 bucket and file name in the form s3://<bucket\_name>/bootstrap.ign.
- Whether or not to register a network load balancer (NLB).
- Specify **yes** or **no**. If you specify **yes**, you must provide a Lambda Amazon Resource Name (ARN) value.
- 7 The ARN for NLB IP target registration lambda group.
- Specify the **RegisterNlblpTargetsLambda** value from the output of the CloudFormation template for DNS and load balancing.
- 19 The ARN for external API load balancer target group.
- Specify the **ExternalApiTargetGroupArn** value from the output of the CloudFormation template for DNS and load balancing.
- The ARN for internal API load balancer target group.

- Specify the **InternalApiTargetGroupArn** value from the output of the CloudFormation template for DNS and load balancing.
- The ARN for internal service load balancer target group.
- Specify the **InternalServiceTargetGroupArn** value from the output of the CloudFormation template for DNS and load balancing.
- 3. Copy the template from the **CloudFormation template for the bootstrap machine**section of this topic and save it as a YAML file on your computer. This template describes the bootstrap machine that your cluster requires.
- 4. Launch the template:



#### **IMPORTANT**

You must enter the command on a single line.

\$ aws cloudformation create-stack --stack-name < name > 1

- --template-body file://<template>.yaml 2
- --parameters file://<parameters>.json 3
- --capabilities CAPABILITY NAMED IAM
- <name> is the name for the CloudFormation stack, such as cluster-bootstrap. You need the name of this stack if you remove the cluster.
- 2 <template> is the relative path to and name of the CloudFormation template YAML file that you saved.
- **<parameters>** is the relative path to and name of the CloudFormation parameters JSON file
- 5. Confirm that the template components exist:
  - \$ aws cloudformation describe-stacks --stack-name <name>

After the **StackStatus** displays **CREATE\_COMPLETE**, the output displays values for the following parameters. You must provide these parameter values to the other CloudFormation templates that you run to create your cluster:

Bootstrap InstanceId	The bootstrap Instance ID.
Bootstrap PublicIp	The bootstrap node public IP address.
Bootstrap Privatelp	The bootstrap node private IP address.

### 1.7.11.1. CloudFormation template for the bootstrap machine

You can use the following CloudFormation template to deploy the bootstrap machine that you need for your OpenShift Container Platform cluster.

AWSTemplateFormatVersion: 2010-09-09

Description: Template for OpenShift Cluster Bootstrap (EC2 Instance, Security Groups and IAM)

Parameters:

InfrastructureName:

AllowedPattern: ^([a-zA-Z][a-zA-Z0-9\-]{0,26})\$

MaxLength: 27 MinLength: 1

ConstraintDescription: Infrastructure name must be alphanumeric, start with a letter, and have a maximum of 27 characters.

Description: A short, unique cluster ID used to tag cloud resources and identify items owned or used by the cluster.

Type: String RhcosAmi:

Description: Current Red Hat Enterprise Linux CoreOS AMI to use for bootstrap.

Type: AWS::EC2::Image::Id AllowedBootstrapSshCidr:

 $Allowed Pattern: \land (([0-9]|[1-9][0-9]|1[0-9]\{2\}|2[0-4][0-9]|25[0-5]) \land ([0-9]|[1-9][0-9]|1[0-9]\{2\}|2[0-4][0-9]|25[0-5]) \land ([0-9]|1[0-9]|2[0-9]|3[0-2])) \Leftrightarrow ([0-9]|25[0-5]) \land ([0-9]|2[0-9]|3[0-2])) \Leftrightarrow ([0-9]|25[0-5]) \land ([0-9]|2[0-9]|3[0-9]|3[0-2])) \Leftrightarrow ([0-9]|25[0-5]) \land ([0-9]|2[0-9]|3[0-9]|3[0-2])) \Leftrightarrow ([0-9]|25[0-5]) \land ([0-9]|2[0-9]|3[0-2])) \Leftrightarrow ([0-9]|25[0-5]) \land ([0-9]|2[0-9]|3[0-2])) \Leftrightarrow ([0-9]|25[0-5]) \land ([0-9]|2[0-9]|3[0-2])) \Leftrightarrow ([0-9]|2[0-9]|3[0-2]) \Leftrightarrow ([0-9]|2[0-9]|3[0-2])) \Leftrightarrow ([0-9]|2[0-9]|3[0-2]) \Leftrightarrow ([0-9]|2[0-9]|3[0-9]|3[0-9]) \Leftrightarrow ([0-9]|2[0-9]|3[0-9]|3[0-9]) \Leftrightarrow ([0-9]|2[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3[0-9]|3$ 

ConstraintDescription: CIDR block parameter must be in the form x.x.x.x/0-32.

Default: 0.0.0.0/0

Description: CIDR block to allow SSH access to the bootstrap node.

Type: String PublicSubnet:

Description: The public subnet to launch the bootstrap node into.

Type: AWS::EC2::Subnet::ld MasterSecurityGroupId:

Description: The master security group ID for registering temporary rules.

Type: AWS::EC2::SecurityGroup::Id

Vpcld:

Description: The VPC-scoped resources will belong to this VPC.

Type: AWS::EC2::VPC::ld BootstrapIgnitionLocation:

Default: s3://my-s3-bucket/bootstrap.ign Description: Ignition config file location.

Type: String
AutoRegisterELB:
Default: "yes"
AllowedValues:

- "yes" - "no"

Description: Do you want to invoke NLB registration, which requires a Lambda ARN parameter?

Type: String

RegisterNlblpTargetsLambdaArn:

Description: ARN for NLB IP target registration lambda.

Type: String

ExternalApiTargetGroupArn:

Description: ARN for external API load balancer target group.

Type: String

InternalApiTargetGroupArn:

Description: ARN for internal API load balancer target group.

Type: String

InternalServiceTargetGroupArn:

Description: ARN for internal service load balancer target group.

Type: String

#### Metadata:

AWS::CloudFormation::Interface:

ParameterGroups:

- Label:

default: "Cluster Information"

Parameters:

- InfrastructureName
- Label:

default: "Host Information"

Parameters:

- RhcosAmi
- BootstrapIgnitionLocation
- MasterSecurityGroupId
- Label:

default: "Network Configuration"

Parameters:

- Vpcld
- AllowedBootstrapSshCidr
- PublicSubnet
- Label:

default: "Load Balancer Automation"

Parameters:

- AutoRegisterELB
- RegisterNlbIpTargetsLambdaArn
- ExternalApiTargetGroupArn
- InternalApiTargetGroupArn
- InternalServiceTargetGroupArn

### ParameterLabels:

InfrastructureName:

default: "Infrastructure Name"

Vpcld:

default: "VPC ID"

AllowedBootstrapSshCidr:

default: "Allowed SSH Source"

PublicSubnet:

default: "Public Subnet"

RhcosAmi:

default: "Red Hat Enterprise Linux CoreOS AMI ID"

BootstraplgnitionLocation:

default: "Bootstrap Ignition Source"

MasterSecurityGroupId:

default: "Master Security Group ID"

AutoRegisterELB:

default: "Use Provided ELB Automation"

#### Conditions:

DoRegistration: !Equals ["yes", !Ref AutoRegisterELB]

Resources:

BootstraplamRole:

Type: AWS::IAM::Role

Properties:

AssumeRolePolicyDocument:

Version: "2012-10-17"

Statement:
- Effect: "Allow"
Principal:
Service:

- "ec2.amazonaws.com"

Action:

- "sts:AssumeRole"

Path: "/" Policies:

- PolicyName: !Join ["-", [!Ref InfrastructureName, "bootstrap", "policy"]]

PolicyDocument:

Version: "2012-10-17"

Statement:
- Effect: "Allow"

Action: "ec2:Describe\*"

Resource: "\*"
- Effect: "Allow"

Action: "ec2:AttachVolume"

Resource: "\*"
- Effect: "Allow"

Action: "ec2:DetachVolume"

Resource: "\*"
- Effect: "Allow"

Action: "s3:GetObject"

Resource: "\*"

### BootstrapInstanceProfile:

Type: "AWS::IAM::InstanceProfile"

Properties: Path: "/" Roles:

- Ref: "BootstraplamRole"

## BootstrapSecurityGroup:

Type: AWS::EC2::SecurityGroup

Properties:

GroupDescription: Cluster Bootstrap Security Group

SecurityGroupIngress:

IpProtocol: tcp FromPort: 22 ToPort: 22

Cidrlp: !Ref AllowedBootstrapSshCidr

- IpProtocol: tcp ToPort: 19531 FromPort: 19531 Cidrlp: 0.0.0.0/0 Vpcld: !Ref Vpcld

### BootstrapInstance:

Type: AWS::EC2::Instance

Properties:

Imageld: !Ref RhcosAmi

lamInstanceProfile: !Ref BootstrapInstanceProfile

InstanceType: "i3.large" NetworkInterfaces:

```
- AssociatePublicIpAddress: "true"
     DeviceIndex: "0"
     GroupSet:
     - !Ref "BootstrapSecurityGroup"
     - !Ref "MasterSecurityGroupId"
     SubnetId: !Ref "PublicSubnet"
   UserData:
     Fn::Base64: !Sub
     - '{"ignition":{"config":{"replace":{"source":"${S3Loc}","verification":{}}},"timeouts":
{},"version":"2.1.0"},"networkd":{},"passwd":{},"storage":{},"systemd":{}}'
      S3Loc: !Ref BootstrapIgnitionLocation
    }
 RegisterBootstrapApiTarget:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref ExternalApiTargetGroupArn
   Targetlp: !GetAtt BootstrapInstance.Privatelp
 RegisterBootstrapInternalApiTarget:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref InternalApiTargetGroupArn
   Targetlp: !GetAtt BootstrapInstance.Privatelp
 RegisterBootstrapInternalServiceTarget:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref InternalServiceTargetGroupArn
   Targetlp: !GetAtt BootstrapInstance.Privatelp
Outputs:
 BootstrapInstanceld:
  Description: Bootstrap Instance ID.
  Value: !Ref BootstrapInstance
 BootstrapPubliclp:
  Description: The bootstrap node public IP address.
  Value: !GetAtt BootstrapInstance.PublicIp
 BootstrapPrivatelp:
  Description: The bootstrap node private IP address.
  Value: !GetAtt BootstrapInstance.Privatelp
```

# 1.7.12. Creating the control plane machines in AWS

You must create the control plane machines in Amazon Web Services (AWS) for your cluster to use. The easiest way to create these nodes is to modify the provided CloudFormation template.



### **NOTE**

If you do not use the provided CloudFormation template to create your control plane nodes, you must review the provided information and manually create the infrastructure. If your cluster does not initialize correctly, you might have to contact Red Hat support with your installation logs.

### **Prerequisites**

- Configure an AWS account.
- Generate the Ignition config files for your cluster.
- Create and configure a VPC and assocated subnets in AWS.
- Create and configure DNS, load balancers, and listeners in AWS.
- Create control plane and compute roles.
- Create the bootstrap machine.

#### **Procedure**

1. Create a JSON file that contains the parameter values that the template requires:

```
[
{
    "ParameterKey": "InfrastructureName", 1
    "ParameterValue": "mycluster-<random_string>" 2
},
{
    "ParameterKey": "RhcosAmi", 3
    "ParameterValue": "ami-<random_string>" 4
},
{
    "ParameterKey": "AutoRegisterDNS", 5
    "ParameterValue": "yes" 6
},
{
    "ParameterValue": "yes" 6
},
{
    "ParameterValue": "random_string>" 8
},
{
    "ParameterValue": "random_string>" 8
},
{
    "ParameterValue": "mycluster.example.com" 10
},
{
    "ParameterKey": "Master0Subnet", 11
    "ParameterValue": "subnet-<random_string>" 12
},
{
    "ParameterKey": "Master1Subnet", 13
    "ParameterValue": "subnet-<random_string>" 14
},
```

```
"ParameterKey": "Master2Subnet", 15
  "ParameterValue": "subnet-<random string>" 16
  "ParameterKey": "MasterSecurityGroupId", 17
  "ParameterValue": "sg-<random_string>" 18
  "ParameterKey": "IgnitionLocation", 19
 "ParameterValue": "https://api-int.<cluster_name>.<domain_name>:22623/config/master"
20
},
  "ParameterKey": "CertificateAuthorities", 21
  "ParameterValue": "data:text/plain;charset=utf-8;base64,ABC...xYz==" 22
  "ParameterKey": "MasterInstanceProfileName", 23
  "ParameterValue": "<roles_stack>-MasterInstanceProfile-<random_string>" 24
  "ParameterKey": "MasterInstanceType", 25
  "ParameterValue": "m4.xlarge" 26
  "ParameterKey": "AutoRegisterELB", 27
  "ParameterValue": "yes" 28
  "ParameterKey": "RegisterNlblpTargetsLambdaArn", 29
  "ParameterValue": "arn:aws:lambda:<region>:<account_number>:function:
<dns_stack_name>-RegisterNlblpTargets-<random_string>" 30
},
  "ParameterKey": "ExternalApiTargetGroupArn", 31
 "ParameterValue": "arn:aws:elasticloadbalancing:<region>:
<account_number>:targetgroup/<dns_stack_name>-Exter-<random_string>" 32
},
  "ParameterKey": "InternalApiTargetGroupArn", 33
  "ParameterValue": "arn:aws:elasticloadbalancing:<region>:
<account_number>:targetgroup/<dns_stack_name>-Inter-<random_string>" 34
},
  "ParameterKey": "InternalServiceTargetGroupArn", 35
  "ParameterValue": "arn:aws:elasticloadbalancing:<region>:
<account_number>:targetgroup/<dns_stack_name>-Inter-<random_string>" 36
```

The name for your cluster infrastructure that is encoded in your Ignition config files for the cluster.

- 2 Specify the infrastructure name that you extracted from the Ignition config file metadata, which has the format **<cluster-name>-<random-string>**.
- 3 CurrentRed Hat Enterprise Linux CoreOS (RHCOS) AMI to use for the control plane machines.
- Specify an AWS::EC2::Image::Id value.
- Whether or not to perform DNS etcd registration.
- 6 Specify **yes** or **no**. If you specify **yes**, you must provide Hosted Zone information.
- The Route53 private zone ID to register the etcd targets with.
- 8 Specify the **PrivateHostedZoneld** value from the output of the CloudFormation template for DNS and load balancing.
- The Route53 zone to register the targets with.
- Specify **<cluster\_name>.<domain\_name>** where **<domain\_name>** is the Route53 base domain that you used when you generated **install-config.yaml** file for the cluster. Do not include the trailing period (.) that is displayed in the AWS console.
- 11 13 15 A subnet, preferably private, to launch the control plane machines on.
- 12 14 16 Specify a subnet from the **PrivateSubnets** value from the output of the CloudFormation template for DNS and load balancing.
- The master security group ID to associate with master nodes.
- Specify the **MasterSecurityGroupId** value from the output of the CloudFormation template for the security group and roles.
- The location to fetch control plane Ignition config file from.
- Specify the generated Ignition config file location, https://api-int.<cluster\_name>. <domain\_name>:22623/config/master.
- The base64 encoded certificate authority string to use.
- Specify the value from the **master.ign** file that is in the installation directory. This value is the long string with the format **data:text/plain;charset=utf-8;base64,ABC...xYz==**.
- The IAM profile to associate with master nodes.
- Specify the **MasterInstanceProfile** parameter value from the output of the CloudFormation template for the security group and roles.
- The type of AWS instance to use for the control plane machines.
- 26 Allowed values:
  - m4.xlarge
  - m4.2xlarge
  - m4.4xlarge

- m4.8xlarge
- m4.10xlarge
- m4.16xlarge
- c4.2xlarge
- c4.4xlarge
- c4.8xlarge
- r4.xlarge
- r4.2xlarge
- r4.4xlarge
- r4.8xlarge
- r4.16xlarge



#### **IMPORTANT**

If **m4** instance types are not available in your region, such as with **euwest-3**, specify an **m5** type, such as **m5.xlarge**, instead.

- Whether or not to register a network load balancer (NLB).
- Specify **yes** or **no**. If you specify **yes**, you must provide a Lambda Amazon Resource Name (ARN) value.
- The ARN for NLB IP target registration lambda group.
- Specify the **RegisterNlblpTargetsLambda** value from the output of the CloudFormation template for DNS and load balancing.
- 31 The ARN for external API load balancer target group.
- Specify the **ExternalApiTargetGroupArn** value from the output of the CloudFormation template for DNS and load balancing.
- The ARN for internal API load balancer target group.
- Specify the **InternalApiTargetGroupArn** value from the output of the CloudFormation template for DNS and load balancing.
- The ARN for internal service load balancer target group.
- Specify the **InternalServiceTargetGroupArn** value from the output of the CloudFormation template for DNS and load balancing.
- 2. Copy the template from the **CloudFormation template for control plane machines** section of this topic and save it as a YAML file on your computer. This template describes the control plane machines that your cluster requires.

- 3. If you specified an **m5** instance type as the value for **MasterInstanceType**, add that instance type to the MasterInstanceType.AllowedValues parameter in the CloudFormation template.
- 4. Launch the template:



#### **IMPORTANT**

You must enter the command on a single line.

\$ aws cloudformation create-stack --stack-name <name> 1

- --template-body file://<template>.yaml 2
- --parameters file://<parameters>.json 3
- <name> is the name for the CloudFormation stack, such as cluster-control-plane. You need the name of this stack if you remove the cluster.
- <template> is the relative path to and name of the CloudFormation template YAML file that you saved.
- <parameters> is the relative path to and name of the CloudFormation parameters JSON file.
- 5. Confirm that the template components exist:

\$ aws cloudformation describe-stacks --stack-name <name>

# 1.7.12.1. CloudFormation template for control plane machines

You can use the following CloudFormation template to deploy the control plane machines that you need for your OpenShift Container Platform cluster.

AWSTemplateFormatVersion: 2010-09-09

Description: Template for OpenShift Cluster Node Launch (EC2 master instances)

#### Parameters:

InfrastructureName:

AllowedPattern: ^([a-zA-Z][a-zA-Z0-9\-]{0,26})\$

MaxLength: 27 MinLength: 1

ConstraintDescription: Infrastructure name must be alphanumeric, start with a letter, and have a maximum of 27 characters.

Description: A short, unique cluster ID used to tag nodes for the kubelet cloud provider.

Type: String RhcosAmi:

Description: Current Red Hat Enterprise Linux CoreOS AMI to use for bootstrap.

Type: AWS::EC2::Image::Id

AutoRegisterDNS: Default: "yes" AllowedValues:

- "ves"

- "no"

Description: Do you want to invoke DNS etcd registration, which requires Hosted Zone information?

Type: String

PrivateHostedZoneId:

Description: The Route53 private zone ID to register the etcd targets with, such as

Z21IXYZABCZ2A4. Type: String

PrivateHostedZoneName:

Description: The Route53 zone to register the targets with, such as cluster.example.com. Omit the

trailing period.

Type: String

Description: The subnets, recommend private, to launch the master nodes into.

Type: AWS::EC2::Subnet::Id

Master1Subnet:

Master0Subnet:

Description: The subnets, recommend private, to launch the master nodes into.

Type: AWS::EC2::Subnet::Id

Master2Subnet:

Description: The subnets, recommend private, to launch the master nodes into.

Type: AWS::EC2::Subnet::Id

MasterSecurityGroupId:

Description: The master security group ID to associate with master nodes.

Type: AWS::EC2::SecurityGroup::Id

IgnitionLocation:

Default: https://api-int.\$CLUSTER\_NAME.\$DOMAIN:22623/config/master

Description: Ignition config file location.

Type: String

CertificateAuthorities:

Default: data:text/plain;charset=utf-8;base64,ABC...xYz== Description: Base64 encoded certificate authority string to use.

Type: String

MasterInstanceProfileName:

Description: IAM profile to associate with master nodes.

Type: String

MasterInstanceType:

Default: m4.xlarge

Type: String AllowedValues:

- "m4.xlarge"
- "m4.2xlarge"
- "m4.4xlarge"
- "m4.8xlarge"
- "m4.10xlarge"
- "m4.16xlarge"
- "c4.2xlarge"
- "c4.4xlarge"
- "c4.8xlarge"
- "r4.xlarge"
- "r4.2xlarge"
- "r4.4xlarge"
- "r4.8xlarge"
- "r4.16xlarge"

# AutoRegisterELB:

Default: "yes"

AllowedValues:

- "yes"
- "no"

Description: Do you want to invoke NLB registration, which requires a Lambda ARN parameter?

Type: String

RegisterNlblpTargetsLambdaArn:

Description: ARN for NLB IP target registration lambda. Supply the value from the cluster infrastructure or select "no" for AutoRegisterELB.

Type: String

ExternalApiTargetGroupArn:

Description: ARN for external API load balancer target group. Supply the value from the cluster infrastructure or select "no" for AutoRegisterELB.

Type: String

InternalApiTargetGroupArn:

Description: ARN for internal API load balancer target group. Supply the value from the cluster infrastructure or select "no" for AutoRegisterELB.

Type: String

InternalServiceTargetGroupArn:

Description: ARN for internal service load balancer target group. Supply the value from the cluster infrastructure or select "no" for AutoRegisterELB.

Type: String

#### Metadata:

AWS::CloudFormation::Interface:

ParameterGroups:

- Label:

default: "Cluster Information"

Parameters:

- InfrastructureName
- Label:

default: "Host Information"

Parameters:

- MasterInstanceType
- RhcosAmi
- IgnitionLocation
- CertificateAuthorities
- MasterSecurityGroupId
- MasterInstanceProfileName
- Label:

default: "Network Configuration"

Parameters:

- Vpcld
- AllowedBootstrapSshCidr
- Master0Subnet
- Master1Subnet
- Master2Subnet
- Label:

default: "DNS"

Parameters:

- AutoRegisterDNS
- PrivateHostedZoneName
- PrivateHostedZoneId
- Label:

default: "Load Balancer Automation"

Parameters:

- AutoRegisterELB
- RegisterNlbIpTargetsLambdaArn
- ExternalApiTargetGroupArn
- InternalApiTargetGroupArn
- InternalServiceTargetGroupArn

ParameterLabels:

InfrastructureName:

default: "Infrastructure Name"

Vpcld:

default: "VPC ID" Master0Subnet:

default: "Master-0 Subnet"

Master1Subnet:

default: "Master-1 Subnet"

Master2Subnet:

default: "Master-2 Subnet"

MasterInstanceType:

default: "Master Instance Type" MasterInstanceProfileName:

default: "Master Instance Profile Name"

RhcosAmi:

default: "Red Hat Enterprise Linux CoreOS AMI ID"

BootstrapIgnitionLocation:

default: "Master Ignition Source"

CertificateAuthorities:

default: "Ignition CA String"

MasterSecurityGroupId:

default: "Master Security Group ID"

AutoRegisterDNS:

default: "Use Provided DNS Automation"

AutoRegisterELB:

default: "Use Provided ELB Automation"

PrivateHostedZoneName:

default: "Private Hosted Zone Name"

PrivateHostedZoneId:

default: "Private Hosted Zone ID"

Conditions:

DoRegistration: !Equals ["yes", !Ref AutoRegisterELB]

DoDns: !Equals ["yes", !Ref AutoRegisterDNS]

Resources:

Master0:

Type: AWS::EC2::Instance

Properties:

Imageld: !Ref RhcosAmi BlockDeviceMappings: - DeviceName: /dev/xvda

Ebs:

VolumeSize: "120" VolumeType: "gp2"

lamInstanceProfile: !Ref MasterInstanceProfileName

InstanceType: !Ref MasterInstanceType

NetworkInterfaces:

- AssociatePublicIpAddress: "false"

DeviceIndex: "0" GroupSet:

- !Ref "MasterSecurityGroupId" SubnetId: !Ref "Master0Subnet"

UserData:

Fn::Base64: !Sub

```
- '{"ignition":{"config":{"append":[{"source":"${SOURCE}}","verification":{}}]},"security":{"tls":
{"certificateAuthorities":[{"source":"${CA_BUNDLE}","verification":{}}]}},"timeouts":
{},"version":"2.2.0"},"networkd":{},"passwd":{},"storage":{},"systemd":{}}'
      SOURCE: !Ref IgnitionLocation,
      CA BUNDLE: !Ref CertificateAuthorities,
   Tags:
   - Key: !Join ["", ["kubernetes.io/cluster/", !Ref InfrastructureName]]
     Value: "shared"
 RegisterMaster0:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref ExternalApiTargetGroupArn
   Targetlp: !GetAtt Master0.Privatelp
 RegisterMaster0InternalApiTarget:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref InternalApiTargetGroupArn
   Targetlp: !GetAtt Master0.Privatelp
 RegisterMaster0InternalServiceTarget:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref InternalServiceTargetGroupArn
   Targetlp: !GetAtt Master0.Privatelp
 Master1:
  Type: AWS::EC2::Instance
  Properties:
   Imageld: !Ref RhcosAmi
   BlockDeviceMappings:
   - DeviceName: /dev/xvda
      VolumeSize: "120"
      VolumeType: "gp2"
   lamInstanceProfile: !Ref MasterInstanceProfileName
   InstanceType: !Ref MasterInstanceType
   NetworkInterfaces:
   - AssociatePublicIpAddress: "false"
     DeviceIndex: "0"
     GroupSet:
     - !Ref "MasterSecurityGroupId"
     SubnetId: !Ref "Master1Subnet"
   UserData:
     Fn::Base64: !Sub
     - '{"ignition":{"config":{"append":[{"source":"${SOURCE}}","verification":{}}]},"security":{"tls":
 'certificateAuthorities":[{"source":"${CA_BUNDLE}","verification":{}}]}},"timeouts":
```

```
{},"version":"2.2.0"},"networkd":{},"passwd":{},"storage":{},"systemd":{}}'
      SOURCE: !Ref IgnitionLocation,
      CA BUNDLE: !Ref CertificateAuthorities,
   Tags:
   - Key: !Join ["", ["kubernetes.io/cluster/", !Ref InfrastructureName]]
     Value: "shared"
 RegisterMaster1:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref ExternalApiTargetGroupArn
   Targetlp: !GetAtt Master1.Privatelp
 RegisterMaster1InternalApiTarget:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref InternalApiTargetGroupArn
   Targetlp: !GetAtt Master1.Privatelp
 RegisterMaster1InternalServiceTarget:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref InternalServiceTargetGroupArn
   Targetlp: !GetAtt Master1.Privatelp
 Master2:
  Type: AWS::EC2::Instance
  Properties:
   ImageId: !Ref RhcosAmi
   BlockDeviceMappings:
   - DeviceName: /dev/xvda
     Ebs:
      VolumeSize: "120"
      VolumeType: "gp2"
   lamInstanceProfile: !Ref MasterInstanceProfileName
   InstanceType: !Ref MasterInstanceType
   NetworkInterfaces:
   - AssociatePublicIpAddress: "false"
     DeviceIndex: "0"
     GroupSet:
     - !Ref "MasterSecurityGroupId"
     SubnetId: !Ref "Master2Subnet"
   UserData:
     Fn::Base64: !Sub
     - '{"ignition":{"config":{"append":[{"source":"${SOURCE}}","verification":{}}]},"security":{"tls":
{"certificateAuthorities":[{"source":"${CA_BUNDLE}","verification":{}}]}},"timeouts":
{},"version":"2.2.0"},"networkd":{},"passwd":{},"storage":{},"systemd":{}}'
     - {
```

```
SOURCE: !Ref IgnitionLocation,
    CA_BUNDLE: !Ref CertificateAuthorities,
   }
  Tags:
  - Key: !Join ["", ["kubernetes.io/cluster/", !Ref InfrastructureName]]
   Value: "shared"
RegisterMaster2:
 Condition: DoRegistration
 Type: Custom::NLBRegister
 Properties:
  ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
  TargetArn: !Ref ExternalApiTargetGroupArn
  Targetlp: !GetAtt Master2.Privatelp
RegisterMaster2InternalApiTarget:
 Condition: DoRegistration
 Type: Custom::NLBRegister
 Properties:
  ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
  TargetArn: !Ref InternalApiTargetGroupArn
  Targetlp: !GetAtt Master2.Privatelp
RegisterMaster2InternalServiceTarget:
 Condition: DoRegistration
 Type: Custom::NLBRegister
 Properties:
  ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
  TargetArn: !Ref InternalServiceTargetGroupArn
  Targetlp: !GetAtt Master2.Privatelp
EtcdSrvRecords:
 Condition: DoDns
 Type: AWS::Route53::RecordSet
 Properties:
  HostedZoneld: !Ref PrivateHostedZoneld
  Name: !Join [".", [" etcd-server-ssl. tcp", !Ref PrivateHostedZoneName]]
  ResourceRecords:
  - !Join [
   " ".
   ["0 10 2380", !Join [".", ["etcd-0", !Ref PrivateHostedZoneName]]],
  ]
  - !Join [
   ["0 10 2380", !Join [".", ["etcd-1", !Ref PrivateHostedZoneName]]],
  - !Join [
   ["0 10 2380", !Join [".", ["etcd-2", !Ref PrivateHostedZoneName]]],
  TTL: 60
  Type: SRV
Etcd0Record:
 Condition: DoDns
 Type: AWS::Route53::RecordSet
```

```
Properties:
   HostedZoneld: !Ref PrivateHostedZoneld
   Name: !Join [".", ["etcd-0", !Ref PrivateHostedZoneName]]
   ResourceRecords:
   - !GetAtt Master0.PrivateIp
   TTL: 60
   Type: A
 Etcd1Record:
  Condition: DoDns
  Type: AWS::Route53::RecordSet
  Properties:
   HostedZoneld: !Ref PrivateHostedZoneld
   Name: !Join [".", ["etcd-1", !Ref PrivateHostedZoneName]]
   ResourceRecords:
   - !GetAtt Master1.Privatelp
   TTL: 60
   Type: A
 Etcd2Record:
  Condition: DoDns
  Type: AWS::Route53::RecordSet
  Properties:
   HostedZoneld: !Ref PrivateHostedZoneld
   Name: !Join [".", ["etcd-2", !Ref PrivateHostedZoneName]]
   ResourceRecords:
   - !GetAtt Master2.Privatelp
   TTL: 60
   Type: A
Outputs:
 PrivateIPs:
  Description: The control-plane node private IP addresses.
  Value:
   !Join [
    [!GetAtt Master0.Privatelp, !GetAtt Master1.Privatelp, !GetAtt Master2.Privatelp]
```

# 1.7.13. Initializing the bootstrap node on AWS with user-provisioned infrastructure

After you create all of the required infrastructure in Amazon Web Services (AWS), you can install the cluster.

## **Prerequisites**

- Configure an AWS account.
- Generate the Ignition config files for your cluster.
- Create and configure a VPC and assocated subnets in AWS.
- Create and configure DNS, load balancers, and listeners in AWS.
- Create control plane and compute roles.

- Create the bootstrap machine.
- Create the control plane machines.
- If you plan to manually manage the worker machines, create the worker machines.

#### Procedure

- 1. Change to the directory that contains the installation program and run the following command:
  - \$ ./openshift-install wait-for bootstrap-complete --dir=<installation\_directory> \ 1 --log-level=info 2
  - For **<installation\_directory>**, specify the path to the directory that you stored the installation files in.
  - To view different installation details, specify warn, debug, or error instead of info.

If the command exits without a **FATAL** warning, your production control plane has initialized.

# 1.7.13.1. Creating the worker nodes in AWS

You can create worker nodes in Amazon Web Services (AWS) for your cluster to use. The easiest way to manually create these nodes is to modify the provided CloudFormation template.



#### **IMPORTANT**

The CloudFormation template creates a stack that represents one worker machine. You must create a stack for each worker machine.



## NOTE

If you do not use the provided CloudFormation template to create your worker nodes, you must review the provided information and manually create the infrastructure. If your cluster does not initialize correctly, you might have to contact Red Hat support with your installation logs.

## **Prerequisites**

- Configure an AWS account.
- Generate the Ignition config files for your cluster.
- Create and configure a VPC and assocated subnets in AWS.
- Create and configure DNS, load balancers, and listeners in AWS.
- Create control plane and compute roles.
- Create the bootstrap machine.
- Create the control plane machines.

#### Procedure

1. Create a JSON file that contains the parameter values that the CloudFormation template requires:

```
"ParameterKey": "InfrastructureName", 1
  "ParameterValue": "mycluster-<random_string>" 2
  "ParameterKey": "RhcosAmi", 3
 "ParameterValue": "ami-<random_string>" 4
},
  "ParameterKey": "Subnet", 5
 "ParameterValue": "subnet-<random_string>" 6
  "ParameterKey": "WorkerSecurityGroupId", 7
 "ParameterValue": "sg-<random_string>" 8
},
  "ParameterKey": "IgnitionLocation", 9
  "ParameterValue": "https://api-int.<cluster_name>.<domain_name>:22623/config/worker"
10
  "ParameterKey": "CertificateAuthorities", 11
  "ParameterValue": "" 12
  "ParameterKey": "WorkerInstanceProfileName", 13
  "ParameterValue": "" 14
  "ParameterKey": "WorkerInstanceType", 15
  "ParameterValue": "m4.large" 16
```

- The name for your cluster infrastructure that is encoded in your Ignition config files for the cluster.
- Specify the infrastructure name that you extracted from the Ignition config file metadata, which has the format **<cluster-name>-<random-string>**.
- Current Red Hat Enterprise Linux CoreOS (RHCOS) AMI to use for the worker nodes.
- A Specify an AWS::EC2::Image::Id value.
- A subnet, preferably private, to launch the worker nodes on.
- 6 Specify a subnet from the **PrivateSubnets** value from the output of the CloudFormation template for DNS and load balancing.

- 7 The worker security group ID to associate with worker nodes.
- 8 Specify the **WorkerSecurityGroupId** value from the output of the CloudFormation template for the security group and roles.
- The location to fetch bootstrap Ignition config file from.
- Specify the generated Ignition config location, https://api-int.<cluster\_name>. <domain\_name>:22623/config/worker.
- Base64 encoded certificate authority string to use.
- Specify the value from the **worker.ign** file that is in the installation directory. This value is the long string with the format **data:text/plain;charset=utf-8;base64,ABC...xYz==**.
- The IAM profile to associate with worker nodes.
- Specify the **WorkerInstanceProfile** parameter value from the output of the CloudFormation template for the security group and roles.
- The type of AWS instance to use for the control plane machines.
- 16 Allowed values:
  - m4.large
  - m4.xlarge
  - m4.2xlarge
  - m4.4xlarge
  - m4.8xlarge
  - m4.10xlarge
  - m4.16xlarge
  - c4.large
  - c4.xlarge
  - c4.2xlarge
  - c4.4xlarge
  - c4.8xlarge
  - r4.large
  - r4.xlarge
  - r4.2xlarge
  - r4.4xlarge
  - r4.8xlarge

### r4.16xlarge



#### **IMPORTANT**

If **m4** instance types are not available in your region, such as with **eu**west-3, use m5 types instead.

- 2. Copy the template from the CloudFormation template for worker machines section of this topic and save it as a YAML file on your computer. This template describes the networking objects and load balancers that your cluster requires.
- 3. If you specified an m5 instance type as the value for WorkerInstanceType, add that instance type to the WorkerInstanceType.AllowedValues parameter in the CloudFormation template.
- 4. Create a worker stack.
  - a. Launch the template:



#### **IMPORTANT**

You must enter the command on a single line.

\$ aws cloudformation create-stack --stack-name < name > 1



- --template-body file://<template>.yaml \ 2
- --parameters file://<parameters>.json 3
- <name> is the name for the CloudFormation stack, such as cluster-workers. You need the name of this stack if you remove the cluster.
- <template> is the relative path to and name of the CloudFormation template YAML file that you saved.
- <parameters> is the relative path to and name of the CloudFormation parameters JSON file.
- b. Confirm that the template components exist:
  - \$ aws cloudformation describe-stacks --stack-name <name>
- 5. Continue to create worker stacks until you have created enough worker Machines for your cluster.



#### **IMPORTANT**

You must create at least two worker machines, so you must create at least two stacks that use this CloudFormation template.

#### 1.7.13.1.1. CloudFormation template for worker machines

You can use the following CloudFormation template to deploy the worker machines that you need for your OpenShift Container Platform cluster.

AWSTemplateFormatVersion: 2010-09-09

Description: Template for OpenShift Cluster Node Launch (EC2 worker instance)

#### Parameters:

InfrastructureName:

AllowedPattern: ^([a-zA-Z][a-zA-Z0-9\-]{0,26})\$

MaxLength: 27 MinLength: 1

ConstraintDescription: Infrastructure name must be alphanumeric, start with a letter, and have a maximum of 27 characters.

Description: A short, unique cluster ID used to tag nodes for the kubelet cloud provider.

Type: String RhcosAmi:

Description: Current Red Hat Enterprise Linux CoreOS AMI to use for bootstrap.

Type: AWS::EC2::Image::Id

Subnet:

Description: The subnets, recommend private, to launch the master nodes into.

Type: AWS::EC2::Subnet::Id WorkerSecurityGroupId:

Description: The master security group ID to associate with master nodes.

Type: AWS::EC2::SecurityGroup::ld

IgnitionLocation:

Default: https://api-int.\$CLUSTER\_NAME.\$DOMAIN:22623/config/worker

Description: Ignition config file location.

Type: String

CertificateAuthorities:

Default: data:text/plain;charset=utf-8;base64,ABC...xYz== Description: Base64 encoded certificate authority string to use.

Type: String

WorkerInstanceProfileName:

Description: IAM profile to associate with master nodes.

Type: String

WorkerInstanceType:

Default: m4.large

Type: String

## AllowedValues:

- "m4.large"
- "m4.xlarge"
- "m4.2xlarge"
- "m4.4xlarge"
- "m4.8xlarge"
- "m4.10xlarge"
- "m4.16xlarge"
- "c4.large"
- "c4.xlarge"
- "c4.2xlarge"
- "c4.4xlarge"
- "c4.8xlarge"
- "r4.large"
- "r4.xlarge"
- "r4.2xlarge"
- "r4.4xlarge"
- "r4.8xlarge"
- "r4.16xlarge"

### Metadata:

AWS::CloudFormation::Interface:

ParameterGroups:

- Label:

default: "Cluster Information"

Parameters:

- InfrastructureName
- Label:

default: "Host Information"

Parameters:

- WorkerInstanceType
- RhcosAmi
- IgnitionLocation
- CertificateAuthorities
- WorkerSecurityGroupId
- WorkerInstanceProfileName
- Label:

default: "Network Configuration"

Parameters:

- Subnet

ParameterLabels:

Subnet:

default: "Subnet" InfrastructureName:

default: "Infrastructure Name"

WorkerInstanceType:

default: "Worker Instance Type" WorkerInstanceProfileName:

default: "Worker Instance Profile Name"

RhcosAmi:

default: "Red Hat Enterprise Linux CoreOS AMI ID"

IgnitionLocation:

default: "Worker Ignition Source"

CertificateAuthorities:

default: "Ignition CA String" WorkerSecurityGroupId:

default: "Worker Security Group ID"

#### Resources:

Worker0:

Type: AWS::EC2::Instance

Properties:

Imageld: !Ref RhcosAmi BlockDeviceMappings: - DeviceName: /dev/xvda

Ebs:

VolumeSize: "120" VolumeType: "gp2"

lamInstanceProfile: !Ref WorkerInstanceProfileName

InstanceType: !Ref WorkerInstanceType

NetworkInterfaces:

- AssociatePublicIpAddress: "false"

DeviceIndex: "0" GroupSet:

- !Ref "WorkerSecurityGroupId"

SubnetId: !Ref "Subnet"

UserData:

```
Fn::Base64: !Sub
- '{"ignition":{"config":{"append":[{"source":"${SOURCE}","verification":{}}]},"security":{"tls":
{"certificateAuthorities":[{"source":"${CA_BUNDLE}","verification":{}}]},"timeouts":
{},"version":"2.2.0"},"networkd":{},"passwd":{},"storage":{},"systemd":{}}'
- {
    SOURCE: !Ref IgnitionLocation,
    CA_BUNDLE: !Ref CertificateAuthorities,
    }
    Tags:
- Key: !Join ["", ["kubernetes.io/cluster/", !Ref InfrastructureName]]
    Value: "shared"

Outputs:
    PrivateIP:
    Description: The compute node private IP address.
    Value: !GetAtt Worker0.PrivateIp
```

# 1.7.14. Installing the CLI

You can install the CLI in order to interact with OpenShift Container Platform using a command-line interface.



#### **IMPORTANT**

If you installed an earlier version of **oc**, you cannot use it to complete all of the commands in OpenShift Container Platform 4.3. Download and install the new version of **oc**.

## Procedure

- 1. From the Infrastructure Provider page on the Red Hat OpenShift Cluster Manager site, navigate to the page for your installation type and click **Download Command-line Tools**
- 2. Click the folder for your operating system and architecture and click the compressed file.



#### **NOTE**

You can install **oc** on Linux, Windows, or macOS.

- 3. Save the file to your file system.
- 4. Extract the compressed file.
- 5. Place it in a directory that is on your **PATH**.

After you install the CLI, it is available using the oc command:

\$ oc <command>

# 1.7.15. Logging in to the cluster

You can log in to your cluster as a default system user by exporting the cluster **kubeconfig** file. The **kubeconfig** file contains information about the cluster that is used by the CLI to connect a client to the correct cluster and API server. The file is specific to a cluster and is created during OpenShift Container

Platform installation.


## **Prerequisites**

- Deploy an OpenShift Container Platform cluster.
- Install the oc CLI.

#### Procedure

1. Export the **kubeadmin** credentials:





2. Verify you can run **oc** commands successfully using the exported configuration:

\$ oc whoami system:admin

# 1.7.16. Approving the CSRs for your machines

When you add machines to a cluster, two pending certificates signing request (CSRs) are generated for each machine that you added. You must confirm that these CSRs are approved or, if necessary, approve them yourself.

#### **Prerequisites**

- You added machines to your cluster.
- Install the jq package.

### Procedure

1. Confirm that the cluster recognizes the machines:

```
$ oc get nodes

NAME STATUS ROLES AGE VERSION
master-0 Ready master 63m v1.16.2
master-1 Ready master 63m v1.16.2
master-2 Ready master 64m v1.16.2
worker-0 NotReady worker 76s v1.16.2
worker-1 NotReady worker 70s v1.16.2
```

The output lists all of the machines that you created.

2. Review the pending certificate signing requests (CSRs) and ensure that the you see a client and server request with **Pending** or **Approved** status for each machine that you added to the cluster:

\$ oc get csr

NAME AGE REQUESTOR CONDITION csr-8b2br 15m system:serviceaccount:openshift-machine-config-operator:node-bootstrapper Pending 1 csr-8vnps 15m system:serviceaccount:openshift-machine-config-operator:node-bootstrapper Pending csr-bfd72 5m26s system:node:ip-10-0-50-126.us-east-2.compute.internal Pending 2 csr-c57lv 5m26s system:node:ip-10-0-95-157.us-east-2.compute.internal Pending ...

- A client request CSR.
- A server request CSR.

In this example, two machines are joining the cluster. You might see more approved CSRs in the list.

3. If the CSRs were not approved, after all of the pending CSRs for the machines you added are in **Pending** status, approve the CSRs for your cluster machines:



#### **NOTE**

Because the CSRs rotate automatically, approve your CSRs within an hour of adding the machines to the cluster. If you do not approve them within an hour, the certificates will rotate, and more than two certificates will be present for each node. You must approve all of these certificates. After you approve the initial CSRs, the subsequent node client CSRs are automatically approved by the cluster **kube-controller-manager**. You must implement a method of automatically approving the kubelet serving certificate requests.

- To approve them individually, run the following command for each valid CSR:
  - \$ oc adm certificate approve <csr\_name> 1
  - **csr\_name>** is the name of a CSR from the list of current CSRs.
- If all the CSRs are valid, approve them all by running the following command:

## 1.7.17. Initial Operator configuration

After the control plane initializes, you must immediately configure some Operators so that they all become available.

## **Prerequisites**

Your control plane has initialized.

#### **Procedure**

1. Watch the cluster components come online:

\$ watch -n5 oc get clusteroperators

NAME SINCE	VERSION AV	'AILABLE F	PROGRESSING	DEGRADED
authentication	4.3.0 True	False	False 69s	
cloud-credential			False 12r	
cluster-autoscaler	4.3.0 True		False 11	• •
console	4.3.0 True	False	False 46s	111
	4.3.0 True		False 11m	
	4.3.0 True		False 5m2	260
image-registry	4.3.0 True	False	False 5m36s	
ingress				
kube-apiserver	4.3.0 True			153s
kube-controller-manager	4.3.0		lse False	
kube-scheduler	4.3.0 True		False 12	
machine-api	4.3.0 True			
machine-config		e False		
marketplace			False 7m	
monitoring			False 7h54	·S
network	4.3.0 True			
node-tuning	4.3.0 True	False	False 11m	1
openshift-apiserver	4.3.0 Tru	e False	False 1	1 m
openshift-controller-mana	ıger 4.3.0	True F	alse False	5m943s
openshift-samples	4.3.0 Tru	ie False	False 3	m55s
operator-lifecycle-manage	er 4.3.0	True Fa	ılse False	11m
operator-lifecycle-manage	er-catalog 4.3.0	True	False False	e 11m
service-ca	4.3.0 True	False		
service-catalog-apiserver	4.3.0 T	rue Fal	se False	5m26s
service-catalog-controller				
storage	4.3.0 True		False 5m30s	
<b>3</b> -				

2. Configure the Operators that are not available.

# 1.7.17.1. Image registry storage configuration

If the **image-registry** Operator is not available, you must configure storage for it. Instructions for both configuring a PersistentVolume, which is required for production clusters, and for configuring an empty directory as the storage location, which is available for only non-production clusters, are shown.

# 1.7.17.1.1. Configuring registry storage for AWS with user-provisioned infrastructure

During installation, your cloud credentials are sufficient to create an S3 bucket and the Registry Operator will automatically configure storage.

If the Registry Operator cannot create an S3 bucket, and automatically configure storage, you can create an S3 bucket and configure storage with the following procedure.

## **Prerequisites**

- A cluster on AWS with user-provisioned infrastructure.
- For S3 on AWS storage the secret is expected to contain two keys:

- REGISTRY\_STORAGE\_S3\_ACCESSKEY
- REGISTRY\_STORAGE\_S3\_SECRETKEY

#### **Procedure**

Use the following procedure if the Registry Operator cannot create an S3 bucket and automatically configure storage.

- 1. Set up a Bucket Lifecycle Policy to abort incomplete multipart uploads that are one day old.
- 2. Fill in the storage configuration in **configs.imageregistry.operator.openshift.io/cluster**:

\$ oc edit configs.imageregistry.operator.openshift.io/cluster

storage:

s3:

bucket: <bucket-name>
region: <region-name>



#### **WARNING**

To secure your registry images in AWS, block public access to the S3 bucket.

## 1.7.17.1.2. Configuring storage for the image registry in non-production clusters

You must configure storage for the image registry Operator. For non-production clusters, you can set the image registry to an empty directory. If you do so, all images are lost if you restart the registry.

## Procedure

• To set the image registry storage to an empty directory:

\$ oc patch configs.imageregistry.operator.openshift.io cluster --type merge --patch '{"spec": {"storage":{"emptyDir":{}}}}'



#### **WARNING**

Configure this option for only non-production clusters.

If you run this command before the Image Registry Operator initializes its components, the **oc patch** command fails with the following error:

Error from server (NotFound): configs.imageregistry.operator.openshift.io "cluster" not found

Wait a few minutes and run the command again.

## 1.7.18. Deleting the bootstrap resources

After you complete the initial Operator configuration for the cluster, remove the bootstrap resources from Amazon Web Services (AWS).

## **Prerequisites**

• You completed the initial Operator configuration for your cluster.

#### **Procedure**

- 1. Delete the bootstrap resources. If you used the CloudFormation template, delete its stack:
  - \$ aws cloudformation delete-stack --stack-name <name> 1
- <name> is the name of your bootstrap stack.

# 1.7.19. Creating the Ingress DNS Records

If you removed the DNS Zone configuration, manually create DNS records that point to the Ingress load balancer. You can create either a wildcard record or specific records. While the following procedure uses A records, you can use other record types that you require, such as CNAME or alias.

# **Prerequisites**

- You deployed an OpenShift Container Platform cluster on Amazon Web Services (AWS) by using infrastructure that you provisioned.
- Install the OpenShift Command-line Interface (CLI), commonly known as oc.
- Install the **jq** package.
- Download the AWS CLI and install it on your computer. See Install the AWS CLI Using the Bundled Installer (Linux, macOS, or Unix).

#### Procedure

- 1. Determine the routes to create.
  - To create a wildcard record, use \*.apps.<cluster\_name>.<domain\_name>, where
     <cluster\_name> is your cluster name, and <domain\_name> is the Route53 base domain for your OpenShift Container Platform cluster.
  - To create specific records, you must create a record for each route that your cluster uses, as shown in the output of the following command:

\$ oc get --all-namespaces -o jsonpath='{range .items[\*]}{range .status.ingress[\*]}{.host} {\"\n"}{end}{end}' routes
oauth-openshift.apps.<cluster\_name>.<domain\_name>
console-openshift-console.apps.<cluster\_name>.<domain\_name>
downloads-openshift-console.apps.<cluster\_name>.<domain\_name>

alertmanager-main-openshift-monitoring.apps.<cluster\_name>.<domain\_name> grafana-openshift-monitoring.apps.<cluster\_name>.<domain\_name> prometheus-k8s-openshift-monitoring.apps.<cluster\_name>.<domain\_name>

2. Retrieve the Ingress Operator load balancer status and note the value of the external IP address that it uses, which is shown in the **EXTERNAL-IP** column:

```
$ oc -n openshift-ingress get service router-default

NAME TYPE CLUSTER-IP EXTERNAL-IP PORT(S)

AGE

router-default LoadBalancer 172.30.62.215 ab3...28.us-east-2.elb.amazonaws.com
80:31499/TCP,443:30693/TCP 5m
```

3. Locate the hosted zone ID for the load balancer:

#### Z3AADJGX6KTTL2

for **<external\_ip>**, specify the value of the external IP address of the Ingress Operator load balancer that you obtained.

The output of this command is the load balancer hosted zone ID.

4. Obtain the public hosted zone ID for your cluster's domain:

/hostedzone/Z3URY6TWQ91KVV

For **<domain\_name>**, specify the Route53 base domain for your OpenShift Container Platform cluster.

The public hosted zone ID for your domain is shown in the command output. In this example, it is **Z3URY6TWQ91KVV**.

5. Add the alias records to your private zone:

```
$ aws route53 change-resource-record-sets --hosted-zone-id "<private_hosted_zone_id>" --
change-batch '{
> "Changes": [
> {
> "Action": "CREATE",
> "ResourceRecordSet": {
> "Name": "\\052.apps.<cluster_domain>", 2
> "Type": "A",
> "AliasTarget":{
> "HostedZoneId": "<hosted_zone_id>", 3
```

```
> "DNSName": "<external_ip>.", 4
> "EvaluateTargetHealth": false
>     }
>     }
>     }
>     }
>     }
>     }
>     }
```

- For reprivate\_hosted\_zone\_id>, specify the value from the output of the CloudFormation template for DNS and load balancing.
- 2 For **<cluster\_domain>**, specify the domain or subdomain that you use with your OpenShift Container Platform cluster.
- For **<hosted\_zone\_id>**, specify the public hosted zone ID for the load balancer that you obtained.
- For **<external\_ip>**, specify the value of the external IP address of the Ingress Operator load balancer. Ensure that you include the trailing period (.) in this parameter value.
- 6. Add the records to your public zone:

```
$ aws route53 change-resource-record-sets --hosted-zone-id "<public hosted zone id>"" --
change-batch '{
   "Changes": [
   {
>
     "Action": "CREATE".
>
     "ResourceRecordSet": {
      "Name": "\\052.apps.<cluster_domain>", 2
>
      "Type": "A",
>
      "AliasTarget":{
       "HostedZoneId": "<hosted_zone_id>", 3
       "DNSName": "<external ip>.", 4
       "EvaluateTargetHealth": false
>
      }
>
    }
>
   }
```

- For **<public\_hosted\_zone\_id>**, specify the public hosted zone for your domain.
- For **<cluster\_domain>**, specify the domain or subdomain that you use with your OpenShift Container Platform cluster.
- For <hosted\_zone\_id>, specify the public hosted zone ID for the load balancer that you obtained.
- For **<external\_ip>**, specify the value of the external IP address of the Ingress Operator load balancer. Ensure that you include the trailing period (.) in this parameter value.

# 1.7.20. Completing an AWS installation on user-provisioned infrastructure

After you start the OpenShift Container Platform installation on Amazon Web Service (AWS) userprovisioned infrastructure, monitor the deployment to completion.

## **Prerequisites**

- Removed the bootstrap node for an OpenShift Container Platform cluster on user-provisioned AWS infrastructure.
- Install the **oc** CLI and log in.

#### **Procedure**

• Complete the cluster installation:

\$ ./openshift-install --dir=<installation\_directory> wait-for install-complete



INFO Waiting up to 30m0s for the cluster to initialize...

For <installation\_directory>, specify the path to the directory that you stored the installation files in.



#### **IMPORTANT**

The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.

## **Next steps**

- Customize your cluster.
- If necessary, you can opt out of remote health reporting.

# 1.8. INSTALLING A CLUSTER ON AWS THAT USES MIRRORED INSTALLATION CONTENT

In OpenShift Container Platform version 4.3, you can install a cluster on Amazon Web Services (AWS) using infrastructure that you provide and an internal mirror of the installation release content.



#### **IMPORTANT**

While you can install an OpenShift Container Platform cluster by using mirrored installation release content, your cluster still requires internet access to use the AWS APIs.

One way to create this infrastructure is to use the provided CloudFormation templates. You can modify the templates to customize your infrastructure or use the information that they contain to create AWS objects according to your company's policies.

# **Prerequisites**

 Create a mirror registry on your bastion host and obtain the imageContentSources data for your version of OpenShift Container Platform.



#### **IMPORTANT**

Because the installation media is on the bastion host, use that computer to complete all installation steps.

- Review details about the OpenShift Container Platform installation and update processes.
- Configure an AWS account to host the cluster.



#### **IMPORTANT**

If you have an AWS profile stored on your computer, it must not use a temporary session token that you generated while using a multi-factor authentication device. The cluster continues to use your current AWS credentials to create AWS resources for the entire life of the cluster, so you must use key-based, long-lived credentials. To generate appropriate keys, see Managing Access Keys for IAM Users in the AWS documentation. You can supply the keys when you run the installation program.

- Download the AWS CLI and install it on your computer. See Install the AWS CLI Using the Bundled Installer (Linux, macOS, or Unix) in the AWS documentation.
- If you use a firewall and plan to use telemetry, you must configure it to allow the sites that your cluster requires access to.



## NOTE

Be sure to also review this site list if you are configuring a proxy.

## 1.8.1. About installations in restricted networks

In OpenShift Container Platform 4.3, you can perform an installation that does not require an active connection to the internet to obtain software components. You complete an installation in a restricted network on only infrastructure that you provision, not infrastructure that the installation program provisions, so your platform selection is limited.

If you choose to perform a restricted network installation on a cloud platform, you still require access to its cloud APIs. Some cloud functions, like Amazon Web Service's IAM service, require internet access, so you might still require internet access. Depending on your network, you might require less internet access for an installation on bare metal hardware or on VMware vSphere.

To complete a restricted network installation, you must create a registry that mirrors the contents of the OpenShift Container Platform registry and contains the installation media. You can create this mirror on a bastion host, which can access both the internet and your closed network, or by using other methods that meet your restrictions.



### **IMPORTANT**

Restricted network installations always use user-provisioned infrastructure. Because of the complexity of the configuration for user-provisioned installations, consider completing a standard user-provisioned infrastructure installation before you attempt a restricted network installation. Completing this test installation might make it easier to isolate and troubleshoot any issues that might arise during your installation in a restricted network.

#### 1.8.1.1. Additional limits

Clusters in restricted networks have the following additional limitations and restrictions:

- The ClusterVersion status includes an **Unable to retrieve available updates** error.
- By default, you cannot use the contents of the Developer Catalog because you cannot access the required ImageStreamTags.

# 1.8.2. Internet and Telemetry access for OpenShift Container Platform

In OpenShift Container Platform 4.3, you require access to the internet to install and entitle your cluster. The Telemetry service, which runs by default to provide metrics about cluster health and the success of updates, also requires internet access. If your cluster is connected to the internet, Telemetry runs automatically, and your cluster is registered to the Red Hat OpenShift Cluster Manager. From there, you can allocate entitlements to your cluster.

You must have internet access to:

- Access the Red Hat OpenShift Cluster Manager page to download the installation program and perform subscription management and entitlement. If the cluster has internet access and you do not disable Telemetry, that service automatically entitles your cluster. If the Telemetry service cannot entitle your cluster, you must manually entitle it on the Cluster registration page.
- Access Quay.io to obtain the packages that are required to install your cluster.
- Obtain the packages that are required to perform cluster updates.



## **IMPORTANT**

If your cluster cannot have direct internet access, you can perform a restricted network installation on infrastructure that you provision. During that process, you download the content that is required and use it to populate a mirror registry with the packages that you need to install a cluster and generate the installation program. With some installation types, the environment that you install your cluster in will not require internet access. Before you update the cluster, you update the content of the mirror registry.

# 1.8.3. Required AWS infrastructure components

To install OpenShift Container Platform on user-provisioned infrastructure in Amazon Web Services (AWS), you must manually create both the machines and their supporting infrastructure.

For more information about the integration testing for different platforms, see the OpenShift Container Platform 4.x Tested Integrations page.

You can use the provided CloudFormation templates to create this infrastructure, you can manually create the components, or you can reuse existing infrastructure that meets the cluster requirements. Review the CloudFormation templates for more details about how the components interrelate.

#### 1.8.3.1. Cluster machines

You need AWS::EC2::Instance objects for the following machines:

- A bootstrap machine. This machine is required during installation, but you can remove it after your cluster deploys.
- At least three control plane machines. The control plane machines are not governed by a MachineSet.
- Compute machines. You must create at least two compute, or worker, machines during installation. These machines are not governed by a MachineSet.

You can use the following instance types for the cluster machines with the provided CloudFormation templates.



### **IMPORTANT**

If **m4** instance types are not available in your region, such as with **eu-west-3**, use **m5** types instead.

Table 1.16. Instance types for machines

Instance type	Bootstrap	Control plane	Compute
i3.large	х		
m4.large or m5.large			х
m4.xlarge or m5.xlarge		X	X
m4.2xlarge		х	х
m4.4xlarge		х	х
m4.8xlarge		х	х
m4.10xlarge		х	х
m4.16xlarge		х	х
c4.large			х
c4.xlarge			х
c4.2xlarge		х	х

Instance type	Bootstrap	Control plane	Compute
c4.4xlarge		х	х
c4.8xlarge		х	х
r4.large			х
r4.xlarge		х	х
r4.2xlarge		х	х
r4.4xlarge		х	х
r4.8xlarge		х	х
r4.16xlarge		х	х

You might be able to use other instance types that meet the specifications of these instance types.

# 1.8.3.2. Certificate signing requests management

Because your cluster has limited access to automatic machine management when you use infrastructure that you provision, you must provide a mechanism for approving cluster certificate signing requests (CSRs) after installation. The **kube-controller-manager** only approves the kubelet client CSRs. The **machine-approver** cannot guarantee the validity of a serving certificate that is requested by using kubelet credentials because it cannot confirm that the correct machine issued the request. You must determine and implement a method of verifying the validity of the kubelet serving certificate requests and approving them.

## 1.8.3.3. Other infrastructure components

- A VPC
- DNS entries
- Load balancers (classic or network) and listeners
- A public and a private Route53 zone
- Security groups
- IAM roles
- S3 buckets

## Required VPC components

You must provide a suitable VPC and subnets that allow communication to your machines.

Compone nt	AWS type	Description	
VPC	<ul><li>AWS::EC2::VPC</li><li>AWS::EC2::VPCEndpoint</li></ul>	You must provide a public VPC for the cluster to use. The VPC uses an endpoint that references the route tables for each subnet to improve communication with the registry that is hosted in S3.	
Public subnets	<ul> <li>AWS::EC2::Subnet</li> <li>AWS::EC2::SubnetNetworkAclAss ociation</li> </ul>	Your VPC must have public subnets for between 1 and 3 availability zones and associate them with appropriate Ingress rules.	
Internet gateway	<ul> <li>AWS::EC2::InternetGateway</li> <li>AWS::EC2::VPCGatewayAttachme nt</li> <li>AWS::EC2::RouteTable</li> <li>AWS::EC2::Route</li> <li>AWS::EC2::SubnetRouteTableAss ociation</li> <li>AWS::EC2::NatGateway</li> <li>AWS::EC2::EIP</li> </ul>	subnet has a NAT gateway with an EIP address. These NAT gateways allow cluster resources, like private subnet instances, to reach the internet and are not required for some restricted networ	
Network access control	AWS::EC2::NetworkAcl	You must allow the VPC to access the following ports:	
COILLOI	AWS::EC2::NetworkAclEntry	Port	Reason
		80	Inbound HTTP traffic
		443	Inbound HTTPS traffic
		22	Inbound SSH traffic
		1024 - 65535	Inbound ephemeral traffic
		0 - 65535	Outbound ephemeral traffic

Compone nt	AWS type	Description
Private subnets	<ul> <li>AWS::EC2::Subnet</li> <li>AWS::EC2::RouteTable</li> <li>AWS::EC2::SubnetRouteTableAss ociation</li> </ul>	Your VPC can have private subnets. The provided CloudFormation templates can create private subnets for between 1 and 3 availability zones. If you use private subnets, you must provide appropriate routes and tables for them.

## Required DNS and load balancing components

Your DNS and load balancer configuration needs to use a public hosted zone and can use a private hosted zone similar to the one that the installation program uses if it provisions the cluster's infrastructure. You must create a DNS entry that resolves to your load balancer. An entry for **api.** <cluster\_name>.<domain> must point to the external load balancer, and an entry for **api-int.** <cluster\_name>.<domain> must point to the internal load balancer.

The cluster also requires load balancers and listeners for port 6443, which are required for the Kubernetes API and its extensions, and port 22623, which are required for the Ignition config files for new machines. The targets will be the master nodes. Port 6443 must be accessible to both clients external to the cluster and nodes within the cluster. Port 22623 must be accessible to nodes within the cluster.

Component	AWS type	Description
DNS	AWS::Route 53::HostedZ one	The hosted zone for your internal DNS.
etcd record sets	AWS::Route 53::RecordS et	The registration records for etcd for your control plane machines.
Public load balancer	AWS::Elastic LoadBalanci ngV2::LoadB alancer	The load balancer for your public subnets.
External API server record	AWS::Route 53::RecordS etGroup	Alias records for the external API server.
External listener	AWS::Elastic LoadBalanci ngV2::Listen er	A listener on port 6443 for the external load balancer.

Component	AWS type	Description
External target group	AWS::Elastic LoadBalanci ngV2::Target Group	The target group for the external load balancer.
Private load balancer	AWS::Elastic LoadBalanci ngV2::LoadB alancer	The load balancer for your private subnets.
Internal API server record	AWS::Route 53::RecordS etGroup	Alias records for the internal API server.
Internal listener	AWS::Elastic LoadBalanci ngV2::Listen er	A listener on port 22623 for the internal load balancer.
Internal target group	AWS::Elastic LoadBalanci ngV2::Target Group	The target group for the Internal load balancer.
Internal listener	AWS::Elastic LoadBalanci ngV2::Listen er	A listener on port 6443 for the internal load balancer.
Internal target group	AWS::Elastic LoadBalanci ngV2::Target Group	The target group for the internal load balancer.

# Security groups

The control plane and worker machines require access to the following ports:

Group	Туре	IP Protocol	Port range
MasterSecurityGroup	AWS::EC2::Security Group	icmp	0
		tcp	22
		tcp	6443

Group	Туре	IP Protocol	Port range
		tcp	22623
WorkerSecurityGroup	AWS::EC2::Security Group	icmp	0
	G. Gup	tcp	22
BootstrapSecurityGroup	AWS::EC2::Security Group	tcp	22
	опоцр	tcp	19531

# **Control plane Ingress**

The control plane machines require the following Ingress groups. Each Ingress group is a **AWS::EC2::SecurityGroupIngress** resource.

Ingress group	Description	IP protocol	Port range
MasterIngress Etcd	etcd	tcp	2379- 2380
MasterIngress Vxlan	Vxlan packets	udp	4789
MasterIngress WorkerVxIan	Vxlan packets	udp	4789
MasterIngress Internal	Internal cluster communication	tcp	9000 - 9999
MasterIngress WorkerInterna I	Internal cluster communication	tcp	9000 - 9999
MasterIngress Kube	Kubernetes kubelet, scheduler and controller manager	tcp	10250 - 10259
MasterIngress WorkerKube	Kubernetes kubelet, scheduler and controller manager	tcp	10250 - 10259
MasterIngress IngressServic es	Kubernetes Ingress services	tcp	30000 - 32767
MasterIngress WorkerIngress Services	Kubernetes Ingress services	tcp	30000 - 32767

# **Worker Ingress**

The worker machines require the following Ingress groups. Each Ingress group is a **AWS::EC2::SecurityGroupIngress** resource.

Ingress group	Description	IP protocol	Port range
WorkerIngress Vxlan	Vxlan packets	udp	4789
WorkerIngress WorkerVxIan	Vxlan packets	udp	4789
WorkerIngress Internal	Internal cluster communication	tcp	9000 - 9999
WorkerIngress WorkerInterna I	Internal cluster communication	tcp	9000 - 9999
WorkerIngress Kube	Kubernetes kubelet, scheduler and controller manager	tcp	10250
WorkerIngress WorkerKube	Kubernetes kubelet, scheduler and controller manager	tcp	10250
WorkerIngress IngressServic es	Kubernetes Ingress services	tcp	30000 - 32767
WorkerIngress WorkerIngress Services	Kubernetes Ingress services	tcp	30000 - 32767

# Roles and instance profiles

You must grant the machines permissions in AWS. The provided CloudFormation templates grant the machines permission the following **AWS::IAM::Role** objects and provide a **AWS::IAM::InstanceProfile** for each set of roles. If you do not use the templates, you can grant the machines the following broad permissions or the following individual permissions.

Role	Effect	Action	Resource
Master	Allow	ec2:*	*
	Allow	elasticloadbalancing :*	*
	Allow	iam:PassRole	*

Role	Effect	Action	Resource
	Allow	s3:GetObject	*
Worker	Allow	ec2:Describe*	*
Bootstrap	Allow	ec2:Describe*	*
	Allow	ec2:AttachVolume	*
	Allow	ec2:DetachVolume	*

# 1.8.3.4. Required AWS permissions

When you attach the **AdministratorAccess** policy to the IAM user that you create in Amazon Web Services (AWS), you grant that user all of the required permissions. To deploy all components of an OpenShift Container Platform cluster, the IAM user requires the following permissions:

# Required EC2 permissions for installation

- ec2:AllocateAddress
- ec2:AssociateAddress
- ec2:AuthorizeSecurityGroupEgress
- ec2:AuthorizeSecurityGroupIngress
- ec2:Copylmage
- ec2:CreateNetworkInterface
- ec2:CreateSecurityGroup
- ec2:CreateTags
- ec2:CreateVolume
- ec2:DeleteSecurityGroup
- ec2:DeleteSnapshot
- ec2:DeregisterImage
- ec2:DescribeAccountAttributes
- ec2:DescribeAddresses
- ec2:DescribeAvailabilityZones
- ec2:DescribeDhcpOptions
- ec2:Describelmages

- ec2:DescribeInstanceAttribute
- ec2:DescribeInstanceCreditSpecifications
- ec2:DescribeInstances
- ec2:DescribeInternetGateways
- ec2:DescribeKeyPairs
- ec2:DescribeNatGateways
- ec2:DescribeNetworkAcIs
- ec2:DescribeNetworkInterfaces
- ec2:DescribePrefixLists
- ec2:DescribeRegions
- ec2:DescribeRouteTables
- ec2:DescribeSecurityGroups
- ec2:DescribeSubnets
- ec2:DescribeTags
- ec2:DescribeVolumes
- ec2:DescribeVpcAttribute
- ec2:DescribeVpcClassicLink
- ec2:DescribeVpcClassicLinkDnsSupport
- ec2:DescribeVpcEndpoints
- ec2:DescribeVpcs
- ec2:ModifyInstanceAttribute
- ec2:ModifyNetworkInterfaceAttribute
- ec2:ReleaseAddress
- ec2:RevokeSecurityGroupEgress
- ec2:RevokeSecurityGroupIngress
- ec2:RunInstances
- ec2:TerminateInstances

Required permissions for creating network resources during installation

ec2:AssociateDhcpOptions

- ec2:AssociateRouteTable
- ec2:AttachInternetGateway
- ec2:CreateDhcpOptions
- ec2:CreateInternetGateway
- ec2:CreateNatGateway
- ec2:CreateRoute
- ec2:CreateRouteTable
- ec2:CreateSubnet
- ec2:CreateVpc
- ec2:CreateVpcEndpoint
- ec2:ModifySubnetAttribute
- ec2:ModifyVpcAttribute



## NOTE

If you use an existing VPC, your account does not require these permissions for creating network resources.

# Required Elasticloadbalancing permissions for installation

- elasticloadbalancing:AddTags
- elasticloadbalancing:ApplySecurityGroupsToLoadBalancer
- elasticloadbalancing:AttachLoadBalancerToSubnets
- elasticloadbalancing:ConfigureHealthCheck
- elasticloadbalancing:CreateListener
- elasticloadbalancing:CreateLoadBalancer
- elasticloadbalancing:CreateLoadBalancerListeners
- elasticloadbalancing:CreateTargetGroup
- elasticloadbalancing:DeleteLoadBalancer
- elasticloadbalancing:DeregisterInstancesFromLoadBalancer
- elasticloadbalancing:DeregisterTargets
- elasticloadbalancing:DescribeInstanceHealth
- elasticloadbalancing:DescribeListeners

- elasticloadbalancing:DescribeLoadBalancerAttributes
- elasticloadbalancing:DescribeLoadBalancers
- elasticloadbalancing:DescribeTags
- elasticloadbalancing:DescribeTargetGroupAttributes
- elasticloadbalancing:DescribeTargetHealth
- elasticloadbalancing:ModifyLoadBalancerAttributes
- elasticloadbalancing:ModifyTargetGroup
- elasticloadbalancing:ModifyTargetGroupAttributes
- elasticloadbalancing:RegisterInstancesWithLoadBalancer
- elasticloadbalancing:RegisterTargets
- elasticloadbalancing:SetLoadBalancerPoliciesOfListener

# Required IAM permissions for installation

- iam:AddRoleToInstanceProfile
- iam:CreateInstanceProfile
- iam:CreateRole
- iam:DeleteInstanceProfile
- iam:DeleteRole
- iam:DeleteRolePolicy
- iam:GetInstanceProfile
- iam:GetRole
- iam:GetRolePolicy
- iam:GetUser
- iam:ListInstanceProfilesForRole
- iam:ListRoles
- iam:ListUsers
- iam:PassRole
- iam:PutRolePolicy
- iam:RemoveRoleFromInstanceProfile
- iam:SimulatePrincipalPolicy

## • iam:TagRole

# Required Route53 permissions for installation

- route53:ChangeResourceRecordSets
- route53:ChangeTagsForResource
- route53:CreateHostedZone
- route53:DeleteHostedZone
- route53:GetChange
- route53:GetHostedZone
- route53:ListHostedZones
- route53:ListHostedZonesByName
- route53:ListResourceRecordSets
- route53:ListTagsForResource
- route53:UpdateHostedZoneComment

## Required S3 permissions for installation

- s3:CreateBucket
- s3:DeleteBucket
- s3:GetAccelerateConfiguration
- s3:GetBucketCors
- s3:GetBucketLocation
- s3:GetBucketLogging
- s3:GetBucketObjectLockConfiguration
- s3:GetBucketReplication
- s3:GetBucketRequestPayment
- s3:GetBucketTagging
- s3:GetBucketVersioning
- s3:GetBucketWebsite
- s3:GetEncryptionConfiguration
- s3:GetLifecycleConfiguration
- s3:GetReplicationConfiguration

- s3:ListBucket
- s3:PutBucketAcl
- s3:PutBucketTagging
- s3:PutEncryptionConfiguration

# S3 permissions that cluster Operators require

- s3:DeleteObject
- s3:GetObject
- s3:GetObjectAcl
- s3:GetObjectTagging
- s3:GetObjectVersion
- s3:PutObject
- s3:PutObjectAcl
- s3:PutObjectTagging

## Required permissions to delete base cluster resources

- autoscaling:DescribeAutoScalingGroups
- ec2:DeleteNetworkInterface
- ec2:DeleteVolume
- elasticloadbalancing:DeleteTargetGroup
- elasticloadbalancing:DescribeTargetGroups
- iam:ListInstanceProfiles
- iam:ListRolePolicies
- iam:ListUserPolicies
- s3:DeleteObject
- tag:GetResources

# Required permissions to delete network resources

- ec2:DeleteDhcpOptions
- ec2:DeleteInternetGateway
- ec2:DeleteNatGateway
- ec2:DeleteRoute

- ec2:DeleteRouteTable
- ec2:DeleteSubnet
- ec2:DeleteVpc
- ec2:DeleteVpcEndpoints
- ec2:DetachInternetGateway
- ec2:DisassociateRouteTable
- ec2:ReplaceRouteTableAssociation



#### NOTE

If you use an existing VPC, your account does not require these permissions to delete network resources.

# 1.8.4. Generating an SSH private key and adding it to the agent

If you want to perform installation debugging or disaster recovery on your cluster, you must provide an SSH key to both your **ssh-agent** and to the installation program.



#### **NOTE**

In a production environment, you require disaster recovery and debugging.

You can use this key to SSH into the master nodes as the user **core**. When you deploy the cluster, the key is added to the **core** user's ~/.**ssh/authorized\_keys** list.



#### **NOTE**

You must use a local key, not one that you configured with platform-specific approaches such as AWS key pairs.

#### **Procedure**

1. If you do not have an SSH key that is configured for password-less authentication on your computer, create one. For example, on a computer that uses a Linux operating system, run the following command:

```
$ ssh-keygen -t rsa -b 4096 -N " \
-f <path>/<file_name> 1
```

Specify the path and file name, such as ~/.ssh/id\_rsa, of the SSH key.

Running this command generates an SSH key that does not require a password in the location that you specified.

2. Start the **ssh-agent** process as a background task:

\$ eval "\$(ssh-agent -s)"

Agent pid 31874

3. Add your SSH private key to the **ssh-agent**:

\$ ssh-add <path>/<file\_name> 1

Identity added: /home/<you>/<path>/<file\_name> (<computer\_name>)

Specify the path and file name for your SSH private key, such as ~/.ssh/id\_rsa

# Next steps

 When you install OpenShift Container Platform, provide the SSH public key to the installation program. If you install a cluster on infrastructure that you provision, you must provide this key to your cluster's machines.

# 1.8.5. Creating the installation files for AWS

To install OpenShift Container Platform on Amazon Web Services (AWS) using user-provisioned infrastructure, you must generate the files that the installation program needs to deploy your cluster and modify them so that the cluster creates only the machines that it will use. You generate and customize the **install-config.yaml** file, Kubernetes manifests, and Ignition config files.

# 1.8.5.1. Creating the installation configuration file

Generate and customize the installation configuration file that the installation program needs to deploy your cluster.

### **Prerequisites**

• Obtain the OpenShift Container Platform installation program and the pull secret for your cluster. For a restricted network installation, these files are on your bastion host.

#### **Procedure**

- 1. Obtain the **install-config.yaml** file.
  - a. Run the following command:
    - \$ ./openshift-install create install-config --dir=<installation\_directory>
    - 1 For **<installation\_directory>**, specify the directory name to store the files that the installation program creates.



Specify an empty directory. Some installation assets, like bootstrap X.509 certificates have short expiration intervals, so you must not reuse an installation directory. If you want to reuse individual files from another cluster installation, you can copy them into your directory. However, the file names for the installation assets might change between releases. Use caution when copying installation files from an earlier OpenShift Container Platform version.

- b. At the prompts, provide the configuration details for your cloud:
  - i. Optional: Select an SSH key to use to access your cluster machines.



#### NOTE

For production OpenShift Container Platform clusters on which you want to perform installation debugging or disaster recovery on, specify an SSH key that your **ssh-agent** process uses.

- ii. Select aws as the platform to target.
- iii. If you do not have an AWS profile stored on your computer, enter the AWS access key ID and secret access key for the user that you configured to run the installation program.
- iv. Select the AWS region to deploy the cluster to.
- v. Select the base domain for the Route53 service that you configured for your cluster.
- vi. Enter a descriptive name for your cluster.
- vii. Paste the pull secret that you obtained from the Pull Secret page on the Red Hat OpenShift Cluster Manager site.
- 2. Edit the **install-config.yaml** file to set the number of compute, or worker, replicas to **0**, as shown in the following **compute** stanza:

#### compute:

- hyperthreading: Enabled

name: worker platform: {} replicas: 0

- 3. Edit the **install-config.yaml** file to provide the additional information that is required for an installation in a restricted network.
  - a. Update the **pullSecret** value to contain the authentication information for your registry:

pullSecret: '{"auths":{"<bastion\_host\_name>:5000": {"auth": "<credentials>","email":
 "you@example.com"}}}'

For **bastion\_host\_name**, specify the registry domain name that you specified in the certificate for your mirror registry, and for **<credentials>**, specify the base64-encoded user name and password for your mirror registry.

b. Add the **additionalTrustBundle** parameter and value. The value must be the contents of the certificate file that you used for your mirror registry, which can be an exiting, trusted certificate authority or the self-signed certificate that you generated for the mirror registry.

c. Add the image content resources:

imageContentSources:

- mirrors:
- <bastion\_host\_name>:5000/<repo\_name>/release source: quay.io/openshift-release-dev/ocp-release
- mirrors:
- <bastion\_host\_name>:5000/<repo\_name>/release source: registry.svc.ci.openshift.org/ocp/release

Use the **imageContentSources** section from the output of the command to mirror the repository.

4. Optional: Back up the install-config.yaml file.



#### **IMPORTANT**

The **install-config.yaml** file is consumed during the installation process. If you want to reuse the file, you must back it up now.

# 1.8.5.2. Configuring the cluster-wide proxy during installation

Production environments can deny direct access to the Internet and instead have an HTTP or HTTPS proxy available. You can configure a new OpenShift Container Platform cluster to use a proxy by configuring the proxy settings in the **install-config.yaml** file.

# **Prerequisites**

- An existing install-config.yaml file.
- Review the sites that your cluster requires access to and determine whether any need to bypass
  the proxy. By default, all cluster egress traffic is proxied, including calls to hosting cloud provider
  APIs. Add sites to the Proxy object's **spec.noProxy** field to bypass the proxy if necessary.



#### NOTE

The Proxy object's **status.noProxy** field is populated by default with the instance metadata endpoint (**169.254.169.254**) and with the values of the **networking.machineCIDR**, **networking.clusterNetwork.cidr**, and **networking.serviceNetwork** fields from your installation configuration.

#### **Procedure**

1. Edit your **install-config.yaml** file and add the proxy settings. For example:

```
apiVersion: v1
baseDomain: my.domain.com
proxy:
httpProxy: http://<username>:<pswd>@<ip>:<port> 1
httpsProxy: http://<username>:<pswd>@<ip>:<port> 2
noProxy: example.com 3
additionalTrustBundle: | 4
-----BEGIN CERTIFICATE-----
<MY_TRUSTED_CA_CERT>
-----END CERTIFICATE-----
...
```

- 1 A proxy URL to use for creating HTTP connections outside the cluster. The URL scheme must be **http**.
- A proxy URL to use for creating HTTPS connections outside the cluster. If this field is not specified, then **httpProxy** is used for both HTTP and HTTPS connections. The URL scheme must be **http**; **https** is currently not supported.
- A comma-separated list of destination domain names, domains, IP addresses, or other network CIDRs to exclude proxying. Preface a domain with . to include all subdomains of that domain. Use \* to bypass proxy for all destinations.
- If provided, the installation program generates a ConfigMap that is named **user-ca-bundle** in the **openshift-config** namespace that contains one or more additional CA certificates that are required for proxying HTTPS connections. The Cluster Network Operator then creates a **trusted-ca-bundle** ConfigMap that merges these contents with the Red Hat Enterprise Linux CoreOS (RHCOS) trust bundle, and this ConfigMap is referenced in the Proxy object's **trustedCA** field. The **additionalTrustBundle** field is required unless the proxy's identity certificate is signed by an authority from the RHCOS trust bundle.



#### **NOTE**

The installation program does not support the proxy **readinessEndpoints** field.

2. Save the file and reference it when installing OpenShift Container Platform.

The installation program creates a cluster-wide proxy that is named **cluster** that uses the proxy settings in the provided **install-config.yaml** file. If no proxy settings are provided, a **cluster** Proxy object is still created, but it will have a nil **spec**.



### NOTE

Only the Proxy object named **cluster** is supported, and no additional proxies can be created.

## 1.8.5.3. Creating the Kubernetes manifest and Ignition config files

Because you must modify some cluster definition files and manually start the cluster machines, you must generate the Kubernetes manifest and Ignition config files that the cluster needs to make its machines.



The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must complete your cluster installation and keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.

## **Prerequisites**

- Obtain the OpenShift Container Platform installation program. For a restricted network installation, these files are on your bastion host.
- Create the **install-config.yaml** installation configuration file.

#### **Procedure**

1. Generate the Kubernetes manifests for the cluster:



WARNING There are no compute nodes specified. The cluster will not fully initialize without compute nodes.

INFO Consuming "Install Config" from target directory

For <installation\_directory>, specify the installation directory that contains the install-config.yaml file you created.

Because you create your own compute machines later in the installation process, you can safely ignore this warning.

2. Remove the Kubernetes manifest files that define the control plane machines:

\$ rm -f openshift/99\_openshift-cluster-api\_master-machines-\*.yaml

By removing these files, you prevent the cluster from automatically generating control plane machines.

3. Remove the Kubernetes manifest files that define the worker machines:

\$ rm -f openshift/99\_openshift-cluster-api\_worker-machineset-\*.yaml

Because you create and manage the worker machines yourself, you do not need to initialize these machines.

- 4. Modify the **manifests**/**cluster-scheduler-02-config.yml** Kubernetes manifest file to prevent Pods from being scheduled on the control plane machines:
  - a. Open the manifests/cluster-scheduler-02-config.yml file.
  - b. Locate the **mastersSchedulable** parameter and set its value to **False**.
  - c. Save and exit the file.



## NOTE

Currently, due to a Kubernetes limitation, router Pods running on control plane machines will not be reachable by the ingress load balancer. This step might not be required in a future minor version of OpenShift Container Platform.

5. Optional: If you do not want the Ingress Operator to create DNS records on your behalf, remove the **privateZone** and **publicZone** sections from the **manifests/cluster-dns-02-config.yml** DNS configuration file:


```
apiVersion: config.openshift.io/v1
kind: DNS
metadata:
    creationTimestamp: null
    name: cluster
spec:
    baseDomain: example.openshift.com
    privateZone: 1
    id: mycluster-100419-private-zone
    publicZone: 2
    id: example.openshift.com
status: {}
```

1 2 Remove these sections completely.

If you do so, you must add ingress DNS records manually in a later step.

- 6. Obtain the Ignition config files:
  - \$./openshift-install create ignition-configs --dir=<installation\_directory> 1
  - For **<installation\_directory>**, specify the same installation directory.

The following files are generated in the directory:



# 1.8.6. Extracting the infrastructure name

The Ignition configs contain a unique cluster identifier that you can use to uniquely identify your cluster in Amazon Web Services (AWS). The provided CloudFormation templates contain references to this infrastructure name, so you must extract it.

## **Prerequisites**

- Obtain the OpenShift Container Platform installation program and the pull secret for your cluster.
- Generate the Ignition config files for your cluster.
- Install the jq package.

#### **Procedure**

 To extract and view the infrastructure name from the Ignition config file metadata, run the following command:

```
$ jq -r .infraID /<installation_directory>/metadata.json 1 openshift-vw9j6 2
```

- For **<installation\_directory>**, specify the path to the directory that you stored the installation files in.
- The output of this command is your cluster name and a random string.

# 1.8.7. Creating a VPC in AWS

You must create a VPC in Amazon Web Services (AWS) for your OpenShift Container Platform cluster to use. You can customize the VPC to meet your requirements, including VPN and route tables. The easiest way to create the VPC is to modify the provided CloudFormation template.



## NOTE

If you do not use the provided CloudFormation template to create your AWS infrastructure, you must review the provided information and manually create the infrastructure. If your cluster does not initialize correctly, you might have to contact Red Hat support with your installation logs.

# **Prerequisites**

- Configure an AWS account.
- Generate the Ignition config files for your cluster.

#### **Procedure**

1. Create a JSON file that contains the parameter values that the template requires:

```
"ParameterKey": "SubnetBits", 5
"ParameterValue": "12" 6
```

- The CIDR block for the VPC.
- Specify a CIDR block in the format x.x.x.x/16-24.
- The number of availability zones to deploy the VPC in.
- Specify an integer between 1 and 3.
- The size of each subnet in each availability zone.
- Specify an integer between 5 and 13, where 5 is /27 and 13 is /19.
- 2. Copy the template from the CloudFormation template for the VPC section of this topic and save it as a YAML file on your computer. This template describes the VPC that your cluster requires.
- 3. Launch the template:



You must enter the command on a single line.

\$ aws cloudformation create-stack --stack-name <name> 1



- --template-body file://<template>.yaml 2
- --parameters file://<parameters>.json 3
- <name> is the name for the CloudFormation stack, such as cluster-vpc. You need the name of this stack if you remove the cluster.
- <template> is the relative path to and name of the CloudFormation template YAML file that you saved.
- <parameters> is the relative path to and name of the CloudFormation parameters JSON file.
- 4. Confirm that the template components exist:

\$ aws cloudformation describe-stacks --stack-name <name>

After the StackStatus displays CREATE COMPLETE, the output displays values for the following parameters. You must provide these parameter values to the other CloudFormation templates that you run to create your cluster:

Vpcld	The ID of your VPC.
-------	---------------------

PublicSub netIds	The IDs of the new public subnets.
PrivateSu bnetIds	The IDs of the new private subnets.

# 1.8.7.1. CloudFormation template for the VPC

You can use the following CloudFormation template to deploy the VPC that you need for your OpenShift Container Platform cluster.

AWSTemplateFormatVersion: 2010-09-09

Description: Template for Best Practice VPC with 1-3 AZs

#### Parameters:

VpcCidr:

 $Allowed Pattern: \land (([0-9]|[1-9][0-9]|1[0-9]\{2\}|2[0-4][0-9]|25[0-5]) \land .) \{3\}([0-9]|[1-9][0-9]|1[0-9]\{2\}|2[0-4]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|1[0-9]|$ 

 $[0-9]|25[0-5])(\forall (1[6-9]|2[0-4]))$ \$

ConstraintDescription: CIDR block parameter must be in the form x.x.x.x/16-24.

Default: 10.0.0.0/16

Description: CIDR block for VPC.

Type: String

AvailabilityZoneCount:

ConstraintDescription: "The number of availability zones. (Min: 1, Max: 3)"

MinValue: 1 MaxValue: 3 Default: 1

Description: "How many AZs to create VPC subnets for. (Min: 1, Max: 3)"

Type: Number SubnetBits:

ConstraintDescription: CIDR block parameter must be in the form x.x.x.x/19-27.

MinValue: 5 MaxValue: 13 Default: 12

Description: "Size of each subnet to create within the availability zones. (Min: 5 = /27, Max: 13 =

/19)"

Type: Number

#### Metadata:

AWS::CloudFormation::Interface:

ParameterGroups:

- Label:

default: "Network Configuration"

Parameters:

- VpcCidr
- SubnetBits
- Label:

default: "Availability Zones"

Parameters:

- AvailabilityZoneCount

ParameterLabels:

AvailabilityZoneCount:

default: "Availability Zone Count"

VpcCidr:

```
default: "VPC CIDR"
   SubnetBits:
    default: "Bits Per Subnet"
Conditions:
 DoAz3: !Equals [3, !Ref AvailabilityZoneCount]
 DoAz2: !Or [!Equals [2, !Ref AvailabilityZoneCount], Condition: DoAz3]
Resources:
 VPC:
  Type: "AWS::EC2::VPC"
  Properties:
   EnableDnsSupport: "true"
   EnableDnsHostnames: "true"
   CidrBlock: !Ref VpcCidr
 PublicSubnet:
  Type: "AWS::EC2::Subnet"
  Properties:
   VpcId: !Ref VPC
   CidrBlock: !Select [0, !Cidr [!Ref VpcCidr, 6, !Ref SubnetBits]]
   AvailabilityZone: !Select
   - Fn::GetAZs: !Ref "AWS::Region"
 PublicSubnet2:
  Type: "AWS::EC2::Subnet"
  Condition: DoAz2
  Properties:
   Vpcld: !Ref VPC
   CidrBlock: !Select [1, !Cidr [!Ref VpcCidr, 6, !Ref SubnetBits]]
   AvailabilityZone: !Select
   - 1
   - Fn::GetAZs: !Ref "AWS::Region"
 PublicSubnet3:
  Type: "AWS::EC2::Subnet"
  Condition: DoAz3
  Properties:
   Vpcld: !Ref VPC
   CidrBlock: !Select [2, !Cidr [!Ref VpcCidr, 6, !Ref SubnetBits]]
   AvailabilityZone: !Select
   - 2
   - Fn::GetAZs: !Ref "AWS::Region"
 InternetGateway:
  Type: "AWS::EC2::InternetGateway"
 GatewayToInternet:
  Type: "AWS::EC2::VPCGatewayAttachment"
  Properties:
   VpcId: !Ref VPC
   InternetGatewayld: !Ref InternetGateway
 PublicRouteTable:
  Type: "AWS::EC2::RouteTable"
  Properties:
   Vpcld: !Ref VPC
 PublicRoute:
  Type: "AWS::EC2::Route"
  DependsOn: GatewayToInternet
  Properties:
```

RouteTableId: !Ref PublicRouteTable DestinationCidrBlock: 0.0.0.0/0 GatewayId: !Ref InternetGateway PublicSubnetRouteTableAssociation:

Type: "AWS::EC2::SubnetRouteTableAssociation"

Properties:

SubnetId: !Ref PublicSubnet

RouteTableId: !Ref PublicRouteTable PublicSubnetRouteTableAssociation2:

Type: "AWS::EC2::SubnetRouteTableAssociation"

Condition: DoAz2

Properties:

SubnetId: !Ref PublicSubnet2

RouteTableId: !Ref PublicRouteTable PublicSubnetRouteTableAssociation3:

Condition: DoAz3

Type: "AWS::EC2::SubnetRouteTableAssociation"

Properties:

SubnetId: !Ref PublicSubnet3

RouteTableId: !Ref PublicRouteTable

PrivateSubnet:

Type: "AWS::EC2::Subnet"

Properties:

VpcId: !Ref VPC

CidrBlock: !Select [3, !Cidr [!Ref VpcCidr, 6, !Ref SubnetBits]]

AvailabilityZone: !Select

- (

- Fn::GetAZs: !Ref "AWS::Region"

PrivateRouteTable:

Type: "AWS::EC2::RouteTable"

Properties:

Vpcld: !Ref VPC

PrivateSubnetRouteTableAssociation:

Type: "AWS::EC2::SubnetRouteTableAssociation"

Properties:

SubnetId: !Ref PrivateSubnet

RouteTableId: !Ref PrivateRouteTable

NAT:

DependsOn:

- GatewayToInternet

Type: "AWS::EC2::NatGateway"

Properties:

AllocationId:

"Fn::GetAtt":

- EIP

- AllocationId

SubnetId: !Ref PublicSubnet

EIP:

Type: "AWS::EC2::EIP"

Properties: Domain: vpc

Route:

Type: "AWS::EC2::Route"

Properties: RouteTableId:

Ref: PrivateRouteTable

DestinationCidrBlock: 0.0.0.0/0 NatGatewayld: Ref: NAT PrivateSubnet2: Type: "AWS::EC2::Subnet" Condition: DoAz2 Properties: Vpcld: !Ref VPC CidrBlock: !Select [4, !Cidr [!Ref VpcCidr, 6, !Ref SubnetBits]] AvailabilityZone: !Select - 1 - Fn::GetAZs: !Ref "AWS::Region" PrivateRouteTable2: Type: "AWS::EC2::RouteTable" Condition: DoAz2 Properties: Vpcld: !Ref VPC PrivateSubnetRouteTableAssociation2: Type: "AWS::EC2::SubnetRouteTableAssociation" Condition: DoAz2 Properties: SubnetId: !Ref PrivateSubnet2 RouteTableId: !Ref PrivateRouteTable2 NAT2: DependsOn: - GatewayToInternet Type: "AWS::EC2::NatGateway" Condition: DoAz2 Properties: AllocationId: "Fn::GetAtt": - EIP2 - AllocationId SubnetId: !Ref PublicSubnet2 EIP2: Type: "AWS::EC2::EIP" Condition: DoAz2 Properties: Domain: vpc Route2: Type: "AWS::EC2::Route" Condition: DoAz2 Properties: RouteTableId: Ref: PrivateRouteTable2 DestinationCidrBlock: 0.0.0.0/0 NatGatewayld: Ref: NAT2 PrivateSubnet3: Type: "AWS::EC2::Subnet" Condition: DoAz3 Properties: Vpcld: !Ref VPC CidrBlock: !Select [5, !Cidr [!Ref VpcCidr, 6, !Ref SubnetBits]] AvailabilityZone: !Select - 2

```
- Fn::GetAZs: !Ref "AWS::Region"
PrivateRouteTable3:
 Type: "AWS::EC2::RouteTable"
 Condition: DoAz3
 Properties:
  Vpcld: !Ref VPC
PrivateSubnetRouteTableAssociation3:
 Type: "AWS::EC2::SubnetRouteTableAssociation"
 Condition: DoAz3
 Properties:
  SubnetId: !Ref PrivateSubnet3
  RouteTableId: !Ref PrivateRouteTable3
NAT3:
 DependsOn:
 - GatewayToInternet
 Type: "AWS::EC2::NatGateway"
 Condition: DoAz3
 Properties:
  AllocationId:
   "Fn::GetAtt":
   - EIP3
   - AllocationId
  SubnetId: !Ref PublicSubnet3
EIP3:
 Type: "AWS::EC2::EIP"
 Condition: DoAz3
 Properties:
  Domain: vpc
Route3:
 Type: "AWS::EC2::Route"
 Condition: DoAz3
 Properties:
  RouteTableId:
   Ref: PrivateRouteTable3
  DestinationCidrBlock: 0.0.0.0/0
  NatGatewayld:
   Ref: NAT3
S3Endpoint:
 Type: AWS::EC2::VPCEndpoint
 Properties:
  PolicyDocument:
   Version: 2012-10-17
   Statement:
   - Effect: Allow
    Principal: '*'
    Action:
    Resource:
  RouteTableIds:
  - !Ref PublicRouteTable
  - !Ref PrivateRouteTable
  - !If [DoAz2, !Ref PrivateRouteTable2, !Ref "AWS::NoValue"]
  - !If [DoAz3, !Ref PrivateRouteTable3, !Ref "AWS::NoValue"]
  ServiceName: !Join
```

```
- - com.amazonaws.
    - !Ref 'AWS::Region'
    - .s3
   Vpcld: !Ref VPC
Outputs:
 Vpcld:
  Description: ID of the new VPC.
  Value: !Ref VPC
 PublicSubnetIds:
  Description: Subnet IDs of the public subnets.
  Value:
   !Join [
     [!Ref PublicSubnet, !If [DoAz2, !Ref PublicSubnet2, !Ref "AWS::NoValue"], !If [DoAz3, !Ref
PublicSubnet3, !Ref "AWS::NoValue"]]
 PrivateSubnetIds:
  Description: Subnet IDs of the private subnets.
  Value:
   !Join [
    " ",
     [!Ref PrivateSubnet, !If [DoAz2, !Ref PrivateSubnet2, !Ref "AWS::NoValue"], !If [DoAz3, !Ref
PrivateSubnet3, !Ref "AWS::NoValue"]]
```

# 1.8.8. Creating networking and load balancing components in AWS

You must configure networking and load balancing (classic or network) in Amazon Web Services (AWS) for your OpenShift Container Platform cluster to use. The easiest way to create these components is to modify the provided CloudFormation template, which also creates a hosted zone and subnet tags.

You can run the template multiple times within a single VPC.



## NOTE

If you do not use the provided CloudFormation template to create your AWS infrastructure, you must review the provided information and manually create the infrastructure. If your cluster does not initialize correctly, you might have to contact Red Hat support with your installation logs.

# **Prerequisites**

- Configure an AWS account.
- Generate the Ignition config files for your cluster.
- Create and configure a VPC and associated subnets in AWS.

#### **Procedure**

Obtain the Hosted Zone ID for the Route53 zone that you specified in the install-config.yaml
file for your cluster. You can obtain this ID from the AWS console or by running the following
command:



You must enter the command on a single line.

```
$ aws route53 list-hosted-zones-by-name |
jq --arg name "<route53_domain>." \
-r '.HostedZones | .[] | select(.Name=="\($name)") | .ld'
```

- For the **<route53\_domain>**, specify the Route53 base domain that you used when you generated the **install-config.yaml** file for the cluster.
- 2. Create a JSON file that contains the parameter values that the template requires:

```
"ParameterKey": "ClusterName", 1
"ParameterValue": "mycluster" (2)
"ParameterKey": "InfrastructureName", 3
"ParameterValue": "mycluster-<random_string>" 4
"ParameterKey": "HostedZoneId", 5
"ParameterValue": "<random_string>" 6
"ParameterKey": "HostedZoneName", 7
"ParameterValue": "example.com" 8
"ParameterKey": "PublicSubnets", 9
"ParameterValue": "subnet-<random_string>" 10
"ParameterKey": "PrivateSubnets", 11
"ParameterValue": "subnet-<random_string>" 12
"ParameterKey": "VpcId", 13
"ParameterValue": "vpc-<random_string>" 14
```

- A short, representative cluster name to use for host names, etc.
- 2 Specify the cluster name that you used when you generated the **install-config.yaml** file for the cluster.
- The name for your cluster infrastructure that is encoded in your Ignition config files for the cluster.

- Specify the infrastructure name that you extracted from the Ignition config file metadata, which has the format <cluster-name>-<random-string>.
- The Route53 public zone ID to register the targets with.
- Specify the Route53 public zone ID, which as a format similar to Z21IXYZABCZ2A4. You can obtain this value from the AWS console.
- The Route53 zone to register the targets with.
- Specify the Route53 base domain that you used when you generated the installconfig.yaml file for the cluster. Do not include the trailing period (.) that is displayed in the AWS console.
- The public subnets that you created for your VPC.
- Specify the PublicSubnetIds value from the output of the CloudFormation template for the VPC.
- The private subnets that you created for your VPC.
- Specify the **PrivateSubnetIds** value from the output of the CloudFormation template for the VPC.
- The VPC that you created for the cluster.
- Specify the **VpcId** value from the output of the CloudFormation template for the VPC.
- 3. Copy the template from the CloudFormation template for the network and load balancers section of this topic and save it as a YAML file on your computer. This template describes the networking and load balancing objects that your cluster requires.
- 4. Launch the template:



You must enter the command on a single line.

\$ aws cloudformation create-stack --stack-name < name > 1



- --template-body file://<template>.yaml 2
- --parameters file://<parameters>.json 3
- --capabilities CAPABILITY NAMED IAM
- <name> is the name for the CloudFormation stack, such as cluster-dns. You need the name of this stack if you remove the cluster.
- <template> is the relative path to and name of the CloudFormation template YAML file that you saved.
- <parameters> is the relative path to and name of the CloudFormation parameters JSON file.
- 5. Confirm that the template components exist:

\$ aws cloudformation describe-stacks --stack-name <name>

After the **StackStatus** displays **CREATE\_COMPLETE**, the output displays values for the following parameters. You must provide these parameter values to the other CloudFormation templates that you run to create your cluster:

PrivateHo stedZonel d	Hosted zone ID for the private DNS.
ExternalA piLoadBal ancerNam e	Full name of the external API load balancer.
InternalAp iLoadBala ncerName	Full name of the internal API load balancer.
ApiServer DnsName	Full host name of the API server.
RegisterN IblpTarget sLambda	Lambda ARN useful to help register/deregister IP targets for these load balancers.
ExternalA piTargetG roupArn	ARN of external API target group.
InternalAp iTargetGr oupArn	ARN of internal API target group.
InternalSe rviceTarg etGroupA rn	ARN of internal service target group.

# 1.8.8.1. CloudFormation template for the network and load balancers

You can use the following CloudFormation template to deploy the networking objects and load balancers that you need for your OpenShift Container Platform cluster.

AWSTemplateFormatVersion: 2010-09-09

Description: Template for OpenShift Cluster Network Elements (Route53 & LBs)

Parameters: ClusterName:

AllowedPattern: ([a-zA-Z][a-zA-Z0-9]-](0,26))

MaxLength: 27 MinLength: 1

ConstraintDescription: Cluster name must be alphanumeric, start with a letter, and have a maximum of 27 characters.

Description: A short, representative cluster name to use for host names and other identifying names.

Type: String

InfrastructureName:

AllowedPattern: ^([a-zA-Z][a-zA-Z0-9\-]{0,26})\$

MaxLength: 27 MinLength: 1

ConstraintDescription: Infrastructure name must be alphanumeric, start with a letter, and have a maximum of 27 characters.

Description: A short, unique cluster ID used to tag cloud resources and identify items owned or used by the cluster.

Type: String

HostedZoneId:

Description: The Route53 public zone ID to register the targets with, such as Z21IXYZABCZ2A4.

Type: String HostedZoneName:

Description: The Route53 zone to register the targets with, such as example.com. Omit the trailing period.

Type: String

Default: "example.com"

PublicSubnets:

Description: The internet-facing subnets.

Type: List<AWS::EC2::Subnet::Id>

PrivateSubnets:

Description: The internal subnets. Type: List<AWS::EC2::Subnet::Id>

Vncld:

Description: The VPC-scoped resources will belong to this VPC.

Type: AWS::EC2::VPC::Id

### Metadata:

AWS::CloudFormation::Interface:

ParameterGroups:

- Label:

default: "Cluster Information"

Parameters:

- ClusterName
- InfrastructureName
- Label:

default: "Network Configuration"

Parameters:

- Vpcld
- PublicSubnets
- PrivateSubnets
- Label:

default: "DNS"

Parameters:

- HostedZoneName
- HostedZoneId

ParameterLabels:

ClusterName:

default: "Cluster Name"

InfrastructureName:

default: "Infrastructure Name"

```
Vpcld:
    default: "VPC ID"
   PublicSubnets:
    default: "Public Subnets"
   PrivateSubnets:
    default: "Private Subnets"
   HostedZoneName:
    default: "Public Hosted Zone Name"
   HostedZoneId:
    default: "Public Hosted Zone ID"
Resources:
 ExtApiElb:
  Type: AWS::ElasticLoadBalancingV2::LoadBalancer
  Properties:
   Name: !Join ["-", [!Ref InfrastructureName, "ext"]]
   IpAddressType: ipv4
   Subnets: !Ref PublicSubnets
   Type: network
 IntApiElb:
  Type: AWS::ElasticLoadBalancingV2::LoadBalancer
  Properties:
   Name: !Join ["-", [!Ref InfrastructureName, "int"]]
   Scheme: internal
   IpAddressType: ipv4
   Subnets: !Ref PrivateSubnets
   Type: network
 IntDns:
  Type: "AWS::Route53::HostedZone"
  Properties:
   HostedZoneConfig:
    Comment: "Managed by CloudFormation"
   Name: !Join [".", [!Ref ClusterName, !Ref HostedZoneName]]
   HostedZoneTags:
   - Key: Name
    Value: !Join ["-", [!Ref InfrastructureName, "int"]]
   - Key: !Join ["", ["kubernetes.io/cluster/", !Ref InfrastructureName]]
    Value: "owned"
   VPCs:
   - VPCId: !Ref VpcId
    VPCRegion: !Ref "AWS::Region"
 ExternalApiServerRecord:
  Type: AWS::Route53::RecordSetGroup
  Properties:
   Comment: Alias record for the API server
   HostedZoneld: !Ref HostedZoneld
   RecordSets:
   - Name:
      !Join [
       ["api", !Ref ClusterName, !Join ["", [!Ref HostedZoneName, "."]]],
     1
    Type: A
```

```
AliasTarget:
    HostedZoneId: !GetAtt ExtApiElb.CanonicalHostedZoneID
    DNSName: !GetAtt ExtApiElb.DNSName
InternalApiServerRecord:
 Type: AWS::Route53::RecordSetGroup
 Properties:
  Comment: Alias record for the API server
  HostedZoneId: !Ref IntDns
  RecordSets:
  - Name:
    !Join [
      ".",
     ["api", !Ref ClusterName, !Join ["", [!Ref HostedZoneName, "."]]],
   Type: A
   AliasTarget:
    HostedZoneId: !GetAtt IntApiElb.CanonicalHostedZoneID
    DNSName: !GetAtt IntApiElb.DNSName
  - Name:
    !Join [
     ".",
      ["api-int", !Ref ClusterName, !Join ["", [!Ref HostedZoneName, "."]]],
   Type: A
   AliasTarget:
    HostedZoneld: !GetAtt IntApiElb.CanonicalHostedZoneID
    DNSName: !GetAtt IntApiElb.DNSName
ExternalApiListener:
 Type: AWS::ElasticLoadBalancingV2::Listener
 Properties:
  DefaultActions:
  - Type: forward
   TargetGroupArn:
    Ref: ExternalApiTargetGroup
  LoadBalancerArn:
   Ref: ExtApiElb
  Port: 6443
  Protocol: TCP
ExternalApiTargetGroup:
 Type: AWS::ElasticLoadBalancingV2::TargetGroup
 Properties:
  Port: 6443
  Protocol: TCP
  TargetType: ip
  Vpcld:
   Ref: Vpcld
  TargetGroupAttributes:
  - Key: deregistration delay.timeout seconds
   Value: 60
InternalApiListener:
 Type: AWS::ElasticLoadBalancingV2::Listener
 Properties:
```

```
DefaultActions:
- Type: forward
 TargetGroupArn:
  Ref: InternalApiTargetGroup
LoadBalancerArn:
 Ref: IntApiElb
Port: 6443
Protocol: TCP
```

InternalApiTargetGroup:

Type: AWS::ElasticLoadBalancingV2::TargetGroup

Properties: Port: 6443 Protocol: TCP TargetType: ip Vpcld: Ref: VpcId

TargetGroupAttributes:

- Key: deregistration\_delay.timeout\_seconds

Value: 60

InternalServiceInternalListener:

Type: AWS::ElasticLoadBalancingV2::Listener

Properties: DefaultActions: - Type: forward TargetGroupArn:

Ref: InternalServiceTargetGroup

LoadBalancerArn: Ref: IntApiElb Port: 22623 Protocol: TCP

InternalServiceTargetGroup:

Type: AWS::ElasticLoadBalancingV2::TargetGroup

Properties: Port: 22623 Protocol: TCP TargetType: ip Vpcld: Ref: Vpcld

TargetGroupAttributes:

- Key: deregistration\_delay.timeout\_seconds

Value: 60

RegisterTargetLambdalamRole:

Type: AWS::IAM::Role

Properties:

RoleName: !Join ["-", [!Ref InfrastructureName, "nlb", "lambda", "role"]]

AssumeRolePolicyDocument: Version: "2012-10-17"

Statement: - Effect: "Allow" Principal: Service:

- "lambda.amazonaws.com"

```
Action:
      - "sts:AssumeRole"
   Path: "/"
   Policies:
   - PolicyName: !Join ["-", [!Ref InfrastructureName, "master", "policy"]]
     PolicyDocument:
      Version: "2012-10-17"
      Statement:
      - Effect: "Allow"
       Action:
          "elasticloadbalancing:RegisterTargets",
          "elasticloadbalancing:DeregisterTargets",
       Resource: !Ref InternalApiTargetGroup
      - Effect: "Allow"
       Action:
          "elasticloadbalancing:RegisterTargets",
          "elasticloadbalancing:DeregisterTargets",
       Resource: !Ref InternalServiceTargetGroup
      - Effect: "Allow"
       Action:
          "elasticloadbalancing:RegisterTargets",
          "elasticloadbalancing:DeregisterTargets",
       Resource: !Ref ExternalApiTargetGroup
 RegisterNlblpTargets:
  Type: "AWS::Lambda::Function"
  Properties:
   Handler: "index.handler"
   Role:
     Fn::GetAtt:
     - "RegisterTargetLambdalamRole"
     - "Arn"
   Code:
     ZipFile: |
      import json
      import boto3
      import cfnresponse
      def handler(event, context):
       elb = boto3.client('elbv2')
       if event['RequestType'] == 'Delete':
        elb.deregister targets(TargetGroupArn=event['ResourceProperties']['TargetArn'],Targets=
[{'Id': event['ResourceProperties']['TargetIp']}])
       elif event['RequestType'] == 'Create':
        elb.register targets(TargetGroupArn=event['ResourceProperties']['TargetArn'],Targets=[{'Id':
event['ResourceProperties']['Targetlp']}])
       responseData = {}
       cfnresponse.send(event, context, cfnresponse.SUCCESS, responseData,
event['ResourceProperties']['TargetArn']+event['ResourceProperties']['TargetIp'])
   Runtime: "python3.7"
   Timeout: 120
```

```
RegisterSubnetTagsLambdalamRole:
  Type: AWS::IAM::Role
  Properties:
   RoleName: !Join ["-", [!Ref InfrastructureName, "subnet-tags-lambda-role"]]
   AssumeRolePolicyDocument:
     Version: "2012-10-17"
     Statement:
     - Effect: "Allow"
      Principal:
       Service:
       - "lambda.amazonaws.com"
      - "sts:AssumeRole"
   Path: "/"
   Policies:
   - PolicyName: !Join ["-", [!Ref InfrastructureName, "subnet-tagging-policy"]]
     PolicyDocument:
      Version: "2012-10-17"
      Statement:
      - Effect: "Allow"
       Action:
          "ec2:DeleteTags",
          "ec2:CreateTags"
       Resource: "arn:aws:ec2:*:*:subnet/*"
      - Effect: "Allow"
       Action:
          "ec2:DescribeSubnets",
          "ec2:DescribeTags"
       Resource: "*"
 RegisterSubnetTags:
  Type: "AWS::Lambda::Function"
  Properties:
   Handler: "index.handler"
   Role:
     Fn::GetAtt:
     - "RegisterSubnetTagsLambdalamRole"
     - "Arn"
   Code:
     ZipFile: |
      import ison
      import boto3
      import cfnresponse
      def handler(event, context):
       ec2 client = boto3.client('ec2')
       if event['RequestType'] == 'Delete':
        for subnet_id in event['ResourceProperties']['Subnets']:
          ec2_client.delete_tags(Resources=[subnet_id], Tags=[{'Key': 'kubernetes.io/cluster/' +
event['ResourceProperties']['InfrastructureName']}]);
       elif event['RequestType'] == 'Create':
        for subnet_id in event['ResourceProperties']['Subnets']:
```

ec2\_client.create\_tags(Resources=[subnet\_id], Tags=[{'Key': 'kubernetes.io/cluster/' + event['ResourceProperties']['InfrastructureName'], 'Value': 'shared'}]);

responseData = {}

cfnresponse.send(event, context, cfnresponse.SUCCESS, responseData,

event['ResourceProperties']['InfrastructureName']+event['ResourceProperties']['Subnets'][0])

Runtime: "python3.7"

Timeout: 120

RegisterPublicSubnetTags:
Type: Custom::SubnetRegister

Properties:

ServiceToken: !GetAtt RegisterSubnetTags.Arn InfrastructureName: !Ref InfrastructureName

Subnets: !Ref PublicSubnets

RegisterPrivateSubnetTags: Type: Custom::SubnetRegister

Properties:

ServiceToken: !GetAtt RegisterSubnetTags.Arn InfrastructureName: !Ref InfrastructureName

Subnets: !Ref PrivateSubnets

#### Outputs:

PrivateHostedZoneId:

Description: Hosted zone ID for the private DNS, which is required for private records.

Value: !Ref IntDns

ExternalApiLoadBalancerName:

Description: Full name of the External API load balancer created.

Value: !GetAtt ExtApiElb.LoadBalancerFullName

InternalApiLoadBalancerName:

Description: Full name of the Internal API load balancer created.

Value: !GetAtt IntApiElb.LoadBalancerFullName

ApiServerDnsName:

Description: Full hostname of the API server, which is required for the Ignition config files.

Value: !Join [".", ["api-int", !Ref ClusterName, !Ref HostedZoneName]]

RegisterNlblpTargetsLambda:

Description: Lambda ARN useful to help register or deregister IP targets for these load balancers.

Value: !GetAtt RegisterNlblpTargets.Arn

ExternalApiTargetGroupArn:

Description: ARN of External API target group.

Value: !Ref ExternalApiTargetGroup

InternalApiTargetGroupArn:

Description: ARN of Internal API target group.

Value: !Ref InternalApiTargetGroup InternalServiceTargetGroupArn:

Description: ARN of internal service target group.

Value: !Ref InternalServiceTargetGroup

# 1.8.9. Creating security group and roles in AWS

You must create security groups and roles in Amazon Web Services (AWS) for your OpenShift Container Platform cluster to use. The easiest way to create these components is to modify the provided CloudFormation template.



#### NOTE

If you do not use the provided CloudFormation template to create your AWS infrastructure, you must review the provided information and manually create the infrastructure. If your cluster does not initialize correctly, you might have to contact Red Hat support with your installation logs.

## **Prerequisites**

- Configure an AWS account.
- Generate the Ignition config files for your cluster.
- Create and configure a VPC and associated subnets in AWS.

#### **Procedure**

1. Create a JSON file that contains the parameter values that the template requires:

- 1 The name for your cluster infrastructure that is encoded in your Ignition config files for the cluster.
- Specify the infrastructure name that you extracted from the Ignition config file metadata, which has the format **<cluster-name>-<random-string>**.
- The CIDR block for the VPC.
- Specify the CIDR block parameter that you used for the VPC that you defined in the form **x.x.x.x/16-24**.
- The private subnets that you created for your VPC.
- Specify the **PrivateSubnetIds** value from the output of the CloudFormation template for the VPC.
- 7 The VPC that you created for the cluster.

- Specify the **VpcId** value from the output of the CloudFormation template for the VPC.
- 2. Copy the template from the CloudFormation template for security objects section of this topic and save it as a YAML file on your computer. This template describes the security groups and roles that your cluster requires.
- 3. Launch the template:



You must enter the command on a single line.

\$ aws cloudformation create-stack --stack-name < name > 1



- --template-body file://<template>.yaml 2
- --parameters file://<parameters>.json 3
- --capabilities CAPABILITY NAMED IAM
- <name> is the name for the CloudFormation stack, such as cluster-sec. You need the name of this stack if you remove the cluster.
- <template> is the relative path to and name of the CloudFormation template YAML file that you saved.
- <parameters> is the relative path to and name of the CloudFormation parameters JSON file.
- 4. Confirm that the template components exist:
  - \$ aws cloudformation describe-stacks --stack-name <name>

After the StackStatus displays CREATE COMPLETE, the output displays values for the following parameters. You must provide these parameter values to the other CloudFormation templates that you run to create your cluster:

MasterSec urityGrou pld	Master Security Group ID
WorkerSe curityGro upId	Worker Security Group ID
MasterIns tanceProfi le	Master IAM Instance Profile
WorkerIns tanceProfi le	Worker IAM Instance Profile

# 1.8.9.1. CloudFormation template for security objects

You can use the following CloudFormation template to deploy the security objects that you need for your OpenShift Container Platform cluster.

AWSTemplateFormatVersion: 2010-09-09

Description: Template for OpenShift Cluster Security Elements (Security Groups & IAM)

#### Parameters:

InfrastructureName:

AllowedPattern: ^([a-zA-Z][a-zA-Z0-9\-]{0,26})\$

MaxLength: 27 MinLength: 1

ConstraintDescription: Infrastructure name must be alphanumeric, start with a letter, and have a maximum of 27 characters.

Description: A short, unique cluster ID used to tag cloud resources and identify items owned or used by the cluster.

Type: String VpcCidr:

AllowedPattern: ^(([0-9]|[1-9][0-9]|1[0-9]{2}|2[0-4][0-9]|25[0-5])\.){3}([0-9]|[1-9][0-9]|1[0-9]{2}|2[0-4]

 $[0-9]|25[0-5])(\forall (1[6-9]|2[0-4]))$ \$

ConstraintDescription: CIDR block parameter must be in the form x.x.x.x/16-24.

Default: 10.0.0.0/16

Description: CIDR block for VPC.

Type: String VpcId:

Description: The VPC-scoped resources will belong to this VPC.

Type: AWS::EC2::VPC::Id

PrivateSubnets:

Description: The internal subnets. Type: List<AWS::EC2::Subnet::Id>

## Metadata:

AWS::CloudFormation::Interface:

ParameterGroups:

- Label:

default: "Cluster Information"

Parameters:

- InfrastructureName

- Label:

default: "Network Configuration"

Parameters:

- Vpcld

- VpcCidr

- PrivateSubnets

ParameterLabels:

InfrastructureName:

default: "Infrastructure Name"

Vpcld:

default: "VPC ID"

VpcCidr:

default: "VPC CIDR"

PrivateSubnets:

default: "Private Subnets"

Resources:

MasterSecurityGroup:

Type: AWS::EC2::SecurityGroup

Properties:

GroupDescription: Cluster Master Security Group

SecurityGroupIngress:
- IpProtocol: icmp
FromPort: 0
ToPort: 0

Cidrlp: !Ref VpcCidr
- lpProtocol: tcp
FromPort: 22
ToPort: 22

Cidrlp: !Ref VpcCidr
- lpProtocol: tcp
ToPort: 6443
FromPort: 6443
Cidrlp: !Ref VpcCidr
- lpProtocol: tcp
FromPort: 22623
ToPort: 22623
Cidrlp: !Ref VpcCidr

Vpcld: !Ref Vpcld

# WorkerSecurityGroup:

Type: AWS::EC2::SecurityGroup

Properties:

GroupDescription: Cluster Worker Security Group

SecurityGroupIngress:
- IpProtocol: icmp
FromPort: 0
ToPort: 0

Cidrlp: !Ref VpcCidr
- lpProtocol: tcp
FromPort: 22
ToPort: 22

Cidrlp: !Ref VpcCidr VpcId: !Ref VpcId

# MasterIngressEtcd:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId

Description: etcd FromPort: 2379 ToPort: 2380 IpProtocol: tcp

# MasterIngressVxlan:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId

Description: Vxlan packets

FromPort: 4789 ToPort: 4789 IpProtocol: udp

MasterIngressWorkerVxlan:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt WorkerSecurityGroup.GroupId

Description: Vxlan packets

FromPort: 4789 ToPort: 4789 IpProtocol: udp

MasterIngressInternal:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId

Description: Internal cluster communication

FromPort: 9000 ToPort: 9999 IpProtocol: tcp

MasterIngressWorkerInternal:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt WorkerSecurityGroup.GroupId

Description: Internal cluster communication

FromPort: 9000 ToPort: 9999 IpProtocol: tcp

MasterIngressKube:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId Description: Kubernetes kubelet, scheduler and controller manager

FromPort: 10250 ToPort: 10259 IpProtocol: tcp

MasterIngressWorkerKube:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt WorkerSecurityGroup.GroupId Description: Kubernetes kubelet, scheduler and controller manager

FromPort: 10250 ToPort: 10259 IpProtocol: tcp

MasterIngressIngressServices:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId

Description: Kubernetes ingress services

FromPort: 30000 ToPort: 32767 IpProtocol: tcp

MasterIngressWorkerIngressServices:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt MasterSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt WorkerSecurityGroup.GroupId

Description: Kubernetes ingress services

FromPort: 30000 ToPort: 32767 IpProtocol: tcp

WorkerIngressVxlan:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt WorkerSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt WorkerSecurityGroup.GroupId

Description: Vxlan packets

FromPort: 4789 ToPort: 4789 IpProtocol: udp

WorkerIngressWorkerVxlan:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt WorkerSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId

Description: Vxlan packets

FromPort: 4789 ToPort: 4789 IpProtocol: udp

WorkerIngressInternal:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt WorkerSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt WorkerSecurityGroup.GroupId

Description: Internal cluster communication

FromPort: 9000 ToPort: 9999 IpProtocol: tcp

WorkerIngressWorkerInternal:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt WorkerSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId

Description: Internal cluster communication

FromPort: 9000 ToPort: 9999 IpProtocol: tcp WorkerIngressKube:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt WorkerSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt WorkerSecurityGroup.GroupId

Description: Kubernetes secure kubelet port

FromPort: 10250 ToPort: 10250 IpProtocol: tcp

WorkerIngressWorkerKube:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt WorkerSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId

Description: Internal Kubernetes communication

FromPort: 10250 ToPort: 10250 IpProtocol: tcp

WorkerIngressIngressServices:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt WorkerSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt WorkerSecurityGroup.GroupId

Description: Kubernetes ingress services

FromPort: 30000 ToPort: 32767 IpProtocol: tcp

WorkerIngressWorkerIngressServices:

Type: AWS::EC2::SecurityGroupIngress

Properties:

GroupId: !GetAtt WorkerSecurityGroup.GroupId

SourceSecurityGroupId: !GetAtt MasterSecurityGroup.GroupId

Description: Kubernetes ingress services

FromPort: 30000 ToPort: 32767 IpProtocol: tcp

MasterlamRole:

Type: AWS::IAM::Role

Properties:

AssumeRolePolicyDocument:

Version: "2012-10-17"

Statement:
- Effect: "Allow"
Principal:
Service:

- "ec2.amazonaws.com"

Action:

- "sts:AssumeRole"

Policies:

- PolicyName: !Join ["-", [!Ref InfrastructureName, "master", "policy"]]

PolicyDocument: Version: "2012-10-17"

#### Statement:

- Effect: "Allow" Action: "ec2:\*" Resource: "\*" - Effect: "Allow"

Action: "elasticloadbalancing:\*"

Resource: "\*"
- Effect: "Allow"

Action: "iam:PassRole"

Resource: "\*"
- Effect: "Allow"

Action: "s3:GetObject"

Resource: "\*"

### MasterInstanceProfile:

Type: "AWS::IAM::InstanceProfile"

Properties: Roles:

- Ref: "MasterlamRole"

### WorkerlamRole:

Type: AWS::IAM::Role

Properties:

## AssumeRolePolicyDocument:

Version: "2012-10-17"

Statement:
- Effect: "Allow"
Principal:
Service:

- "ec2.amazonaws.com"

Action:

- "sts:AssumeRole"

### Policies:

- PolicyName: !Join ["-", [!Ref InfrastructureName, "worker", "policy"]]

PolicyDocument: Version: "2012-10-17" Statement: - Effect: "Allow"

Action: "ec2:Describe\*"

Resource: "\*"

## WorkerInstanceProfile:

Type: "AWS::IAM::InstanceProfile"

Properties: Roles:

- Ref: "WorkerlamRole"

### Outputs:

MasterSecurityGroupId:

Description: Master Security Group ID

Value: !GetAtt MasterSecurityGroup.GroupId

## WorkerSecurityGroupId:

Description: Worker Security Group ID

Value: !GetAtt WorkerSecurityGroup.GroupId

MasterInstanceProfile:

Description: Master IAM Instance Profile Value: !Ref MasterInstanceProfile

WorkerInstanceProfile:

Description: Worker IAM Instance Profile Value: !Ref WorkerInstanceProfile

# 1.8.10. RHCOS AMIs for the AWS infrastructure

You must use a valid Red Hat Enterprise Linux CoreOS (RHCOS) AMI for your Amazon Web Services (AWS) zone for your OpenShift Container Platform nodes.

Table 1.17. RHCOS AMIs

AWS zone	AWS AMI
ap-northeast-1	ami-023d0452866845125
ap-northeast-2	ami-0ba4f9a0358bcb44a
ap-south-1	ami-0bf62e963a473068e"
ap-southeast-1	ami-086b93722336bd1d9
ap-southeast-2	ami-08929f33bfab49b83
ca-central-1	ami-0f6d943a1fa9172fd
eu-central-1	ami-0ceea534b63224411
eu-north-1	ami-06b7087b2768f644a
eu-west-1	ami-0e95125b57fa63b0d
eu-west-2	ami-0eef98c447b85ffcd
eu-west-3	ami-0049e16104f360df6
me-south-1	ami-0b03ea038629fd02e
sa-east-1	ami-0c80d785b30eef121
us-east-1	ami-06f85a7940faa3217
us-east-2	ami-04a79d8d7cfa540cc
us-west-1	ami-0633b392e8eff25e7

AWS zone	AWS AMI
us-west-2	ami-0d231993dddc5cd2e

# 1.8.11. Creating the bootstrap node in AWS

You must create the bootstrap node in Amazon Web Services (AWS) to use during OpenShift Container Platform cluster initialization. The easiest way to create this node is to modify the provided CloudFormation template.



#### **NOTE**

If you do not use the provided CloudFormation template to create your bootstrap node, you must review the provided information and manually create the infrastructure. If your cluster does not initialize correctly, you might have to contact Red Hat support with your installation logs.

### **Prerequisites**

- Configure an AWS account.
- Generate the Ignition config files for your cluster.
- Create and configure a VPC and assocated subnets in AWS.
- Create and configure DNS, load balancers, and listeners in AWS.
- Create control plane and compute roles.

#### Procedure

1. Provide a location to serve the **bootstrap.ign** Ignition config file to your cluster. This file is located in your installation directory. One way to do this is to create an S3 bucket in your cluster's region and upload the Ignition config file to it.



## **IMPORTANT**

The provided CloudFormation Template assumes that the Ignition config files for your cluster are served from an S3 bucket. If you choose to serve the files from another location, you must modify the templates.



## NOTE

The bootstrap Ignition config file does contain secrets, like X.509 keys. The following steps provide basic security for the S3 bucket. To provide additional security, you can enable an S3 bucket policy to allow only certain users, such as the OpenShift IAM user, to access objects that the bucket contains. You can avoid S3 entirely and serve your bootstrap Ignition config file from any address that the bootstrap machine can reach.

a. Create the bucket:

- \$ aws s3 mb s3://<cluster-name>-infra 1
- <cluster-name>-infra is the bucket name.
- b. Upload the **bootstrap.ign** Ignition config file to the bucket:
  - \$ aws s3 cp bootstrap.ign s3://<cluster-name>-infra/bootstrap.ign
- c. Verify that the file uploaded:
  - \$ aws s3 ls s3://<cluster-name>-infra/ 2019-04-03 16:15:16 314878 bootstrap.ign
- 2. Create a JSON file that contains the parameter values that the template requires:

```
"ParameterKey": "InfrastructureName", 1
 "ParameterValue": "mycluster-<random_string>" 2
 "ParameterKey": "RhcosAmi", 3
 "ParameterValue": "ami-<random_string>" 4
},
 "ParameterKey": "AllowedBootstrapSshCidr", 5
 "ParameterValue": "0.0.0.0/0" 6
 "ParameterKey": "PublicSubnet", 7
 "ParameterValue": "subnet-<random_string>" 8
 "ParameterKey": "MasterSecurityGroupId", 9
 "ParameterValue": "sg-<random_string>" 10
 "ParameterKey": "VpcId", 111
 "ParameterValue": "vpc-<random_string>" 12
 "ParameterKey": "BootstrapIgnitionLocation", 13
 "ParameterValue": "s3://<bucket_name>/bootstrap.ign" 14
 "ParameterKey": "AutoRegisterELB", 15
 "ParameterValue": "yes" 16
 "ParameterKey": "RegisterNlbIpTargetsLambdaArn", 17
```

```
"ParameterValue": "arn:aws:lambda:<region>:<account_number>:function:
<dns_stack_name>-RegisterNlblpTargets-<random_string>" 18
},
{
   "ParameterKey": "ExternalApiTargetGroupArn", 19
   "ParameterValue": "arn:aws:elasticloadbalancing:<region>:
<account_number>:targetgroup/<dns_stack_name>-Exter-<random_string>" 20
},
{
   "ParameterKey": "InternalApiTargetGroupArn", 21
   "ParameterValue": "arn:aws:elasticloadbalancing:<region>:
<account_number>:targetgroup/<dns_stack_name>-Inter-<random_string>" 22
},
{
   "ParameterKey": "InternalServiceTargetGroupArn", 23
   "ParameterValue": "arn:aws:elasticloadbalancing:<region>:
<account_number>:targetgroup/<dns_stack_name>-Inter-<random_string>" 24
}
]
```

- The name for your cluster infrastructure that is encoded in your Ignition config files for the cluster.
- Specify the infrastructure name that you extracted from the Ignition config file metadata, which has the format **<cluster-name>-<random-string>**.
- Current Red Hat Enterprise Linux CoreOS (RHCOS) AMI to use for the bootstrap node.
- Specify a valid AWS::EC2::Image::Id value.
- CIDR block to allow SSH access to the bootstrap node.
- 6 Specify a CIDR block in the format **x.x.x.x/16-24**.
- 7 The public subnet that is associated with your VPC to launch the bootstrap node into.
- Specify the **PublicSubnetIds** value from the output of the CloudFormation template for the VPC.
- The master security group ID (for registering temporary rules)
- Specify the **MasterSecurityGroupId** value from the output of the CloudFormation template for the security group and roles.
- 11 The VPC created resources will belong to.
- Specify the **VpcId** value from the output of the CloudFormation template for the VPC.
- 13 Location to fetch bootstrap Ignition config file from.
- Specify the S3 bucket and file name in the form s3://<bucket\_name>/bootstrap.ign.
- Whether or not to register a network load balancer (NLB).
- Specify **yes** or **no**. If you specify **yes**, you must provide a Lambda Amazon Resource Name (ARN) value.

- The ARN for NLB IP target registration lambda group.
- Specify the **RegisterNIblpTargetsLambda** value from the output of the CloudFormation template for DNS and load balancing.
- 19 The ARN for external API load balancer target group.
- Specify the **ExternalApiTargetGroupArn** value from the output of the CloudFormation template for DNS and load balancing.
- The ARN for internal API load balancer target group.
- Specify the **InternalApiTargetGroupArn** value from the output of the CloudFormation template for DNS and load balancing.
- The ARN for internal service load balancer target group.
- Specify the **InternalServiceTargetGroupArn** value from the output of the CloudFormation template for DNS and load balancing.
- 3. Copy the template from the **CloudFormation template for the bootstrap machine**section of this topic and save it as a YAML file on your computer. This template describes the bootstrap machine that your cluster requires.
- 4. Launch the template:



#### **IMPORTANT**

You must enter the command on a single line.

\$ aws cloudformation create-stack --stack-name <name> 1

- --template-body file://<template>.yaml 2
- --parameters file://<parameters>.json 3
- --capabilities CAPABILITY\_NAMED\_IAM
- <name> is the name for the CloudFormation stack, such as cluster-bootstrap. You need the name of this stack if you remove the cluster.
- **<template>** is the relative path to and name of the CloudFormation template YAML file that you saved.
- <parameters> is the relative path to and name of the CloudFormation parameters JSON file.
- 5. Confirm that the template components exist:
  - \$ aws cloudformation describe-stacks --stack-name <name>

After the **StackStatus** displays **CREATE\_COMPLETE**, the output displays values for the following parameters. You must provide these parameter values to the other CloudFormation templates that you run to create your cluster:

Bootstrap InstanceId	The bootstrap Instance ID.
Bootstrap PublicIp	The bootstrap node public IP address.
Bootstrap Privatelp	The bootstrap node private IP address.

# 1.8.11.1. CloudFormation template for the bootstrap machine

You can use the following CloudFormation template to deploy the bootstrap machine that you need for your OpenShift Container Platform cluster.

AWSTemplateFormatVersion: 2010-09-09

Description: Template for OpenShift Cluster Bootstrap (EC2 Instance, Security Groups and IAM)

Parameters:

InfrastructureName:

AllowedPattern: ^([a-zA-Z][a-zA-Z0-9\-]{0,26})\$

MaxLength: 27 MinLength: 1

ConstraintDescription: Infrastructure name must be alphanumeric, start with a letter, and have a maximum of 27 characters.

Description: A short, unique cluster ID used to tag cloud resources and identify items owned or used by the cluster.

Type: String RhcosAmi:

Description: Current Red Hat Enterprise Linux CoreOS AMI to use for bootstrap.

Type: AWS::EC2::Image::Id AllowedBootstrapSshCidr:

AllowedPattern: ^(([0-9]|[1-9][0-9]|1[0-9]{2}|2[0-4][0-9]|25[0-5])\.){3}([0-9]|[1-9][0-9]|1[0-9]{2}|2[0-4]

 $[0-9]|25[0-5])(\lor([0-9]|1[0-9]|2[0-9]|3[0-2]))$ \$

 $Constraint Description: CIDR \ block \ parameter \ must \ be \ in \ the \ form \ x.x.x.x/0-32.$ 

Default: 0.0.0.0/0

Description: CIDR block to allow SSH access to the bootstrap node.

Type: String PublicSubnet:

Description: The public subnet to launch the bootstrap node into.

Type: AWS::EC2::Subnet::Id MasterSecurityGroupId:

Description: The master security group ID for registering temporary rules.

Type: AWS::EC2::SecurityGroup::Id

Vpcld:

Description: The VPC-scoped resources will belong to this VPC.

Type: AWS::EC2::VPC::ld BootstrapIgnitionLocation:

Default: s3://my-s3-bucket/bootstrap.ign Description: Ignition config file location.

Type: String
AutoRegisterELB:
Default: "yes"
AllowedValues:

- "yes"

- "no"

Description: Do you want to invoke NLB registration, which requires a Lambda ARN parameter?

Type: String

RegisterNlblpTargetsLambdaArn:

Description: ARN for NLB IP target registration lambda.

Type: String

ExternalApiTargetGroupArn:

Description: ARN for external API load balancer target group.

Type: String

InternalApiTargetGroupArn:

Description: ARN for internal API load balancer target group.

Type: String

InternalServiceTargetGroupArn:

Description: ARN for internal service load balancer target group.

Type: String

#### Metadata:

AWS::CloudFormation::Interface:

ParameterGroups:

- Label:

default: "Cluster Information"

Parameters:

- InfrastructureName
- Label:

default: "Host Information"

Parameters:

- RhcosAmi
- BootstrapIgnitionLocation
- MasterSecurityGroupId
- Label:

default: "Network Configuration"

Parameters:

- Vpcld
- AllowedBootstrapSshCidr
- PublicSubnet
- Label:

default: "Load Balancer Automation"

Parameters:

- AutoRegisterELB
- RegisterNlbIpTargetsLambdaArn
- ExternalApiTargetGroupArn
- InternalApiTargetGroupArn
- InternalServiceTargetGroupArn

ParameterLabels:

InfrastructureName:

default: "Infrastructure Name"

Vpcld:

default: "VPC ID"

AllowedBootstrapSshCidr:

default: "Allowed SSH Source"

PublicSubnet:

default: "Public Subnet"

RhcosAmi:

default: "Red Hat Enterprise Linux CoreOS AMI ID"

BootstraplgnitionLocation:

default: "Bootstrap Ignition Source"

MasterSecurityGroupId:

default: "Master Security Group ID"

AutoRegisterELB:

default: "Use Provided ELB Automation"

### Conditions:

DoRegistration: !Equals ["yes", !Ref AutoRegisterELB]

### Resources:

BootstraplamRole: Type: AWS::IAM::Role

Properties:

AssumeRolePolicyDocument:

Version: "2012-10-17"

Statement:
- Effect: "Allow"
Principal:
Service:

- "ec2.amazonaws.com"

Action:

- "sts:AssumeRole"

Path: "/" Policies:

- PolicyName: !Join ["-", [!Ref InfrastructureName, "bootstrap", "policy"]]

PolicyDocument: Version: "2012-10-17"

Statement:
- Effect: "Allow"

Action: "ec2:Describe\*"

Resource: "\*"
- Effect: "Allow"

Action: "ec2:AttachVolume"

Resource: "\*"
- Effect: "Allow"

Action: "ec2:DetachVolume"

Resource: "\*" - Effect: "Allow"

Action: "s3:GetObject"

Resource: "\*"

## BootstrapInstanceProfile:

Type: "AWS::IAM::InstanceProfile"

Properties: Path: "/" Roles:

- Ref: "BootstraplamRole"

## BootstrapSecurityGroup:

Type: AWS::EC2::SecurityGroup

Properties:

GroupDescription: Cluster Bootstrap Security Group

SecurityGroupIngress:

IpProtocol: tcp FromPort: 22 ToPort: 22

```
Cidrlp: !Ref AllowedBootstrapSshCidr
   - IpProtocol: tcp
     ToPort: 19531
     FromPort: 19531
     Cidrlp: 0.0.0.0/0
   Vpcld: !Ref Vpcld
 BootstrapInstance:
  Type: AWS::EC2::Instance
  Properties:
   Imageld: !Ref RhcosAmi
   lamInstanceProfile: !Ref BootstrapInstanceProfile
   InstanceType: "i3.large"
   NetworkInterfaces:
   - AssociatePublicIpAddress: "true"
     DeviceIndex: "0"
     GroupSet:
     - !Ref "BootstrapSecurityGroup"
     - !Ref "MasterSecurityGroupId"
     SubnetId: !Ref "PublicSubnet"
   UserData:
     Fn::Base64: !Sub
     - '{"ignition":{"config":{"replace":{"source":"${S3Loc}","verification":{}}},"timeouts":
{},"version":"2.1.0"},"networkd":{},"passwd":{},"storage":{},"systemd":{}}'
      S3Loc: !Ref BootstrapIgnitionLocation
    }
 RegisterBootstrapApiTarget:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref ExternalApiTargetGroupArn
   Targetlp: !GetAtt BootstrapInstance.Privatelp
 RegisterBootstrapInternalApiTarget:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref InternalApiTargetGroupArn
   Targetlp: !GetAtt BootstrapInstance.Privatelp
 RegisterBootstrapInternalServiceTarget:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref InternalServiceTargetGroupArn
   Targetlp: !GetAtt BootstrapInstance.Privatelp
Outputs:
 BootstrapInstanceld:
  Description: Bootstrap Instance ID.
  Value: !Ref BootstrapInstance
```

## BootstrapPubliclp:

Description: The bootstrap node public IP address.

Value: !GetAtt BootstrapInstance.PublicIp

## BootstrapPrivatelp:

Description: The bootstrap node private IP address.

Value: !GetAtt BootstrapInstance.PrivateIp

# 1.8.12. Creating the control plane machines in AWS

You must create the control plane machines in Amazon Web Services (AWS) for your cluster to use. The easiest way to create these nodes is to modify the provided CloudFormation template.



#### **NOTE**

If you do not use the provided CloudFormation template to create your control plane nodes, you must review the provided information and manually create the infrastructure. If your cluster does not initialize correctly, you might have to contact Red Hat support with your installation logs.

# **Prerequisites**

- Configure an AWS account.
- Generate the Ignition config files for your cluster.
- Create and configure a VPC and assocated subnets in AWS.
- Create and configure DNS, load balancers, and listeners in AWS.
- Create control plane and compute roles.
- Create the bootstrap machine.

## Procedure

1. Create a JSON file that contains the parameter values that the template requires:

```
"ParameterValue": "<random_string>" 8
  "ParameterKey": "PrivateHostedZoneName", 9
  "ParameterValue": "mycluster.example.com" 10
  "ParameterKey": "Master0Subnet", 11
  "ParameterValue": "subnet-<random_string>" 12
  "ParameterKey": "Master1Subnet", 13
  "ParameterValue": "subnet-<random_string>" 14
  "ParameterKey": "Master2Subnet", 15
  "ParameterValue": "subnet-<random_string>" 16
  "ParameterKey": "MasterSecurityGroupId", 17
  "ParameterValue": "sg-<random_string>" 18
  "ParameterKey": "IgnitionLocation", 19
  "ParameterValue": "https://api-int.<cluster_name>.<domain_name>:22623/config/master"
20
},
  "ParameterKey": "CertificateAuthorities", 21
  "ParameterValue": "data:text/plain;charset=utf-8;base64,ABC...xYz==" 22
  "ParameterKey": "MasterInstanceProfileName", 23
  "ParameterValue": "<roles_stack>-MasterInstanceProfile-<random_string>" 24
  "ParameterKey": "MasterInstanceType", 25
  "ParameterValue": "m4.xlarge" 26
  "ParameterKey": "AutoRegisterELB", 27
  "ParameterValue": "yes" 28
  "ParameterKey": "RegisterNlblpTargetsLambdaArn", 29
  "ParameterValue": "arn:aws:lambda:<region>:<account_number>:function:
<dns_stack_name>-RegisterNlblpTargets-<random_string>" 30
},
  "ParameterKey": "ExternalApiTargetGroupArn", 31
  "ParameterValue": "arn:aws:elasticloadbalancing:<region>:
<account_number>:targetgroup/<dns_stack_name>-Exter-<random_string>" 32
```

```
{
    "ParameterKey": "InternalApiTargetGroupArn", 33
    "ParameterValue": "arn:aws:elasticloadbalancing:<region>:
    <account_number>:targetgroup/<dns_stack_name>-Inter-<random_string>" 34
    },
    {
        "ParameterKey": "InternalServiceTargetGroupArn", 35
        "ParameterValue": "arn:aws:elasticloadbalancing:<region>:
        <account_number>:targetgroup/<dns_stack_name>-Inter-<random_string>" 36
    }
}
```

- The name for your cluster infrastructure that is encoded in your Ignition config files for the cluster.
- 2 Specify the infrastructure name that you extracted from the Ignition config file metadata, which has the format **<cluster-name>-<random-string>**.
- 3 CurrentRed Hat Enterprise Linux CoreOS (RHCOS) AMI to use for the control plane machines.
- A Specify an AWS::EC2::Image::Id value.
- Whether or not to perform DNS etcd registration.
- Specify **yes** or **no**. If you specify **yes**, you must provide Hosted Zone information.
- 7 The Route53 private zone ID to register the etcd targets with.
- 8 Specify the **PrivateHostedZoneld** value from the output of the CloudFormation template for DNS and load balancing.
- The Route53 zone to register the targets with.
- Specify **<cluster\_name>.<domain\_name>** where **<domain\_name>** is the Route53 base domain that you used when you generated **install-config.yaml** file for the cluster. Do not include the trailing period (.) that is displayed in the AWS console.
- 11,13,15 A subnet, preferably private, to launch the control plane machines on.
- 12 14 16 Specify a subnet from the **PrivateSubnets** value from the output of the CloudFormation template for DNS and load balancing.
- The master security group ID to associate with master nodes.
- Specify the **MasterSecurityGroupId** value from the output of the CloudFormation template for the security group and roles.
- 19 The location to fetch control plane Ignition config file from.
- Specify the generated Ignition config file location, https://api-int.<cluster\_name>. <a href="https://api-int.eduster\_name">domain\_name</a>:22623/config/master.
- The base64 encoded certificate authority string to use.
- Specify the value from the **master.ign** file that is in the installation directory. This value is the long string with the format **data:text/plain;charset=utf-8;base64,ABC...xYz==**.

- The IAM profile to associate with master nodes.
- Specify the **MasterInstanceProfile** parameter value from the output of the CloudFormation template for the security group and roles.
- The type of AWS instance to use for the control plane machines.
- Allowed values:
  - m4.xlarge
  - m4.2xlarge
  - m4.4xlarge
  - m4.8xlarge
  - m4.10xlarge
  - m4.16xlarge
  - c4.2xlarge
  - c4.4xlarge
  - c4.8xlarge
  - r4.xlarge
  - r4.2xlarge
  - r4.4xlarge
  - r4.8xlarge
  - r4.16xlarge



#### **IMPORTANT**

If **m4** instance types are not available in your region, such as with **euwest-3**, specify an **m5** type, such as **m5.xlarge**, instead.

- Whether or not to register a network load balancer (NLB).
- Specify **yes** or **no**. If you specify **yes**, you must provide a Lambda Amazon Resource Name (ARN) value.
- The ARN for NLB IP target registration lambda group.
- Specify the **RegisterNIblpTargetsLambda** value from the output of the CloudFormation template for DNS and load balancing.
- 31 The ARN for external API load balancer target group.
- Specify the **ExternalApiTargetGroupArn** value from the output of the CloudFormation template for DNS and load balancing.

- The ARN for internal API load balancer target group.
- Specify the InternalApiTargetGroupArn value from the output of the CloudFormation template for DNS and load balancing.
- The ARN for internal service load balancer target group.
- Specify the InternalServiceTargetGroupArn value from the output of the CloudFormation template for DNS and load balancing.
- 2. Copy the template from the CloudFormation template for control plane machines section of this topic and save it as a YAML file on your computer. This template describes the control plane machines that your cluster requires.
- 3. If you specified an m5 instance type as the value for MasterInstanceType, add that instance type to the **MasterInstanceType.AllowedValues** parameter in the CloudFormation template.
- 4. Launch the template:



#### **IMPORTANT**

You must enter the command on a single line.

\$ aws cloudformation create-stack --stack-name < name > 1



- --template-body file://<template>.yaml 2
- --parameters file://<parameters>.json 3
- <name> is the name for the CloudFormation stack, such as cluster-control-plane. You need the name of this stack if you remove the cluster.
- <template> is the relative path to and name of the CloudFormation template YAML file that you saved.
- <parameters> is the relative path to and name of the CloudFormation parameters JSON file.
- 5. Confirm that the template components exist:

\$ aws cloudformation describe-stacks --stack-name <name>

## 1.8.12.1. CloudFormation template for control plane machines

You can use the following CloudFormation template to deploy the control plane machines that you need for your OpenShift Container Platform cluster.

AWSTemplateFormatVersion: 2010-09-09

Description: Template for OpenShift Cluster Node Launch (EC2 master instances)

Parameters:

InfrastructureName:

AllowedPattern: ^([a-zA-Z][a-zA-Z0-9\-]{0,26})\$

MaxLength: 27

MinLength: 1

ConstraintDescription: Infrastructure name must be alphanumeric, start with a letter, and have a maximum of 27 characters.

Description: A short, unique cluster ID used to tag nodes for the kubelet cloud provider.

Type: String RhcosAmi:

Description: Current Red Hat Enterprise Linux CoreOS AMI to use for bootstrap.

Type: AWS::EC2::Image::Id

AutoRegisterDNS:

Default: "yes" AllowedValues:

- "yes" - "no"

Description: Do you want to invoke DNS etcd registration, which requires Hosted Zone

information?
Type: String

PrivateHostedZoneId:

Description: The Route53 private zone ID to register the etcd targets with, such as

Z21IXYZABCZ2A4.

Type: String

PrivateHostedZoneName:

Description: The Route53 zone to register the targets with, such as cluster.example.com. Omit the trailing period.

Type: String Master0Subnet:

Description: The subnets, recommend private, to launch the master nodes into.

Type: AWS::EC2::Subnet::Id

Master1Subnet:

Description: The subnets, recommend private, to launch the master nodes into.

Type: AWS::EC2::Subnet::Id

Master2Subnet:

Description: The subnets, recommend private, to launch the master nodes into.

Type: AWS::EC2::Subnet::Id MasterSecurityGroupId:

Description: The master security group ID to associate with master nodes.

Type: AWS::EC2::SecurityGroup::Id

IgnitionLocation:

Default: https://api-int.\$CLUSTER NAME.\$DOMAIN:22623/config/master

Description: Ignition config file location.

Type: String

CertificateAuthorities:

Default: data:text/plain;charset=utf-8;base64,ABC...xYz== Description: Base64 encoded certificate authority string to use.

Type: String

MasterInstanceProfileName:

Description: IAM profile to associate with master nodes.

Type: String

MasterInstanceType:

Default: m4.xlarge

Type: String Allowed Values:

- "m4.xlarge"

- III4.xiaiye
- "m4.2xlarge"
- "m4.4xlarge"
- "m4.8xlarge"
- "m4.10xlarge"

- "m4.16xlarge"
- "c4.2xlarge"
- "c4.4xlarge"
- "c4.8xlarge"
- "r4.xlarge"
- "r4.2xlarge"
- "r4.4xlarge"
- "r4.8xlarge"
- "r4.16xlarge"

### AutoRegisterELB:

Default: "yes"

## AllowedValues:

- "yes"
- "no"

Description: Do you want to invoke NLB registration, which requires a Lambda ARN parameter?

Type: String

RegisterNlblpTargetsLambdaArn:

Description: ARN for NLB IP target registration lambda. Supply the value from the cluster infrastructure or select "no" for AutoRegisterELB.

Type: String

ExternalApiTargetGroupArn:

Description: ARN for external API load balancer target group. Supply the value from the cluster infrastructure or select "no" for AutoRegisterELB.

Type: String

InternalApiTargetGroupArn:

Description: ARN for internal API load balancer target group. Supply the value from the cluster infrastructure or select "no" for AutoRegisterELB.

Type: String

InternalServiceTargetGroupArn:

Description: ARN for internal service load balancer target group. Supply the value from the cluster infrastructure or select "no" for AutoRegisterELB.

Type: String

#### Metadata:

AWS::CloudFormation::Interface:

ParameterGroups:

- Label:

default: "Cluster Information"

Parameters:

- InfrastructureName
- Label:

default: "Host Information"

Parameters:

- MasterInstanceType
- RhcosAmi
- IgnitionLocation
- CertificateAuthorities
- MasterSecurityGroupId
- MasterInstanceProfileName
- Label:

default: "Network Configuration"

Parameters:

- Vpcld
- AllowedBootstrapSshCidr
- Master0Subnet
- Master1Subnet

- Master2Subnet
- Label:

default: "DNS"

### Parameters:

- AutoRegisterDNS
- PrivateHostedZoneName
- PrivateHostedZoneId
- Label:

default: "Load Balancer Automation"

#### Parameters:

- AutoRegisterELB
- RegisterNlbIpTargetsLambdaArn
- ExternalApiTargetGroupArn
- InternalApiTargetGroupArn
- InternalServiceTargetGroupArn

#### ParameterLabels:

InfrastructureName:

default: "Infrastructure Name"

Vpcld:

default: "VPC ID"

Master0Subnet:

default: "Master-0 Subnet"

Master1Subnet:

default: "Master-1 Subnet"

Master2Subnet:

default: "Master-2 Subnet"

MasterInstanceType:

default: "Master Instance Type"

MasterInstanceProfileName:

default: "Master Instance Profile Name"

RhcosAmi:

default: "Red Hat Enterprise Linux CoreOS AMI ID"

BootstraplgnitionLocation:

default: "Master Ignition Source"

CertificateAuthorities:

default: "Ignition CA String"

MasterSecurityGroupId:

default: "Master Security Group ID"

AutoRegisterDNS:

default: "Use Provided DNS Automation"

AutoRegisterELB:

default: "Use Provided ELB Automation"

PrivateHostedZoneName:

default: "Private Hosted Zone Name"

PrivateHostedZoneId:

default: "Private Hosted Zone ID"

#### Conditions:

DoRegistration: !Equals ["yes", !Ref AutoRegisterELB]

DoDns: !Equals ["yes", !Ref AutoRegisterDNS]

Resources:

Master0:

Type: AWS::EC2::Instance

Properties:

Imageld: !Ref RhcosAmi

```
BlockDeviceMappings:
   - DeviceName: /dev/xvda
     Ebs:
      VolumeSize: "120"
      VolumeType: "gp2"
   lamInstanceProfile: !Ref MasterInstanceProfileName
   InstanceType: !Ref MasterInstanceType
   NetworkInterfaces:
   - AssociatePublicIpAddress: "false"
     DeviceIndex: "0"
     GroupSet:
     - !Ref "MasterSecurityGroupId"
     SubnetId: !Ref "Master0Subnet"
   UserData:
     Fn::Base64: !Sub
     - '{"ignition":{"config":{"append":[{"source":"${SOURCE}}","verification":{}}]},"security":{"tls":
{"certificateAuthorities":[{"source":"${CA_BUNDLE}","verification":{}}]}},"timeouts":
{},"version":"2.2.0"},"networkd":{},"passwd":{},"storage":{},"systemd":{}}'
      SOURCE: !Ref IgnitionLocation,
      CA BUNDLE: !Ref CertificateAuthorities,
    }
   Tags:
   - Key: !Join ["", ["kubernetes.io/cluster/", !Ref InfrastructureName]]
     Value: "shared"
 RegisterMaster0:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref ExternalApiTargetGroupArn
   Targetlp: !GetAtt Master0.Privatelp
 RegisterMaster0InternalApiTarget:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref InternalApiTargetGroupArn
   Targetlp: !GetAtt Master0.Privatelp
 RegisterMaster0InternalServiceTarget:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref InternalServiceTargetGroupArn
   Targetlp: !GetAtt Master0.Privatelp
 Master1:
  Type: AWS::EC2::Instance
  Properties:
   Imageld: !Ref RhcosAmi
   BlockDeviceMappings:
   - DeviceName: /dev/xvda
```

```
Ebs:
      VolumeSize: "120"
      VolumeType: "gp2"
   lamInstanceProfile: !Ref MasterInstanceProfileName
   InstanceType: !Ref MasterInstanceType
   NetworkInterfaces:
   - AssociatePublicIpAddress: "false"
     DeviceIndex: "0"
     GroupSet:
     - !Ref "MasterSecurityGroupId"
     SubnetId: !Ref "Master1Subnet"
   UserData:
     Fn::Base64: !Sub
     - '{"ignition":{"config":{"append":[{"source":"${SOURCE}}","verification":{}}]},"security":{"tls":
{"certificateAuthorities":[{"source":"${CA_BUNDLE}","verification":{}}]}},"timeouts":
{},"version":"2.2.0"},"networkd":{},"passwd":{},"storage":{},"systemd":{}}'
      SOURCE: !Ref IgnitionLocation,
      CA BUNDLE: !Ref CertificateAuthorities,
   Tags:
   - Key: !Join ["", ["kubernetes.io/cluster/", !Ref InfrastructureName]]
     Value: "shared"
 RegisterMaster1:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref ExternalApiTargetGroupArn
   Targetlp: !GetAtt Master1.Privatelp
 RegisterMaster1InternalApiTarget:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref InternalApiTargetGroupArn
   Targetlp: !GetAtt Master1.Privatelp
 RegisterMaster1InternalServiceTarget:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref InternalServiceTargetGroupArn
   Targetlp: !GetAtt Master1.Privatelp
 Master2:
  Type: AWS::EC2::Instance
  Properties:
   Imageld: !Ref RhcosAmi
   BlockDeviceMappings:
   - DeviceName: /dev/xvda
      VolumeSize: "120"
```

```
VolumeType: "gp2"
   lamInstanceProfile: !Ref MasterInstanceProfileName
   InstanceType: !Ref MasterInstanceType
   NetworkInterfaces:
   - AssociatePublicIpAddress: "false"
     DeviceIndex: "0"
     GroupSet:
     - !Ref "MasterSecurityGroupId"
     SubnetId: !Ref "Master2Subnet"
   UserData:
     Fn::Base64: !Sub
     - '{"ignition":{"config":{"append":[{"source":"${SOURCE}}","verification":{}}]},"security":{"tls":
{"certificateAuthorities":[{"source":"${CA_BUNDLE}","verification":{}}]}},"timeouts":
{},"version":"2.2.0"},"networkd":{},"passwd":{},"storage":{},"systemd":{}}'
      SOURCE: !Ref IgnitionLocation,
      CA_BUNDLE: !Ref CertificateAuthorities,
    }
   Tags:
   - Key: !Join ["", ["kubernetes.io/cluster/", !Ref InfrastructureName]]
     Value: "shared"
 RegisterMaster2:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref ExternalApiTargetGroupArn
   Targetlp: !GetAtt Master2.Privatelp
 RegisterMaster2InternalApiTarget:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref InternalApiTargetGroupArn
   Targetlp: !GetAtt Master2.Privatelp
 RegisterMaster2InternalServiceTarget:
  Condition: DoRegistration
  Type: Custom::NLBRegister
  Properties:
   ServiceToken: !Ref RegisterNlblpTargetsLambdaArn
   TargetArn: !Ref InternalServiceTargetGroupArn
   Targetlp: !GetAtt Master2.Privatelp
 EtcdSrvRecords:
  Condition: DoDns
  Type: AWS::Route53::RecordSet
  Properties:
   HostedZoneld: !Ref PrivateHostedZoneld
   Name: !Join [".", ["_etcd-server-ssl._tcp", !Ref PrivateHostedZoneName]]
   ResourceRecords:
   - !Join [
    " ",
     ["0 10 2380", !Join [".", ["etcd-0", !Ref PrivateHostedZoneName]]],
```

```
- !Join [
    " "
    ["0 10 2380", !Join [".", ["etcd-1", !Ref PrivateHostedZoneName]]],
   - !Join [
    " ".
    ["0 10 2380", !Join [".", ["etcd-2", !Ref PrivateHostedZoneName]]],
   TTL: 60
   Type: SRV
 Etcd0Record:
  Condition: DoDns
  Type: AWS::Route53::RecordSet
  Properties:
   HostedZoneld: !Ref PrivateHostedZoneld
   Name: !Join [".", ["etcd-0", !Ref PrivateHostedZoneName]]
   ResourceRecords:
   - !GetAtt Master0.Privatelp
   TTL: 60
   Type: A
 Etcd1Record:
  Condition: DoDns
  Type: AWS::Route53::RecordSet
  Properties:
   HostedZoneld: !Ref PrivateHostedZoneld
   Name: !Join [".", ["etcd-1", !Ref PrivateHostedZoneName]]
   ResourceRecords:
   - !GetAtt Master1.Privatelp
   TTL: 60
   Type: A
 Etcd2Record:
  Condition: DoDns
  Type: AWS::Route53::RecordSet
  Properties:
   HostedZoneld: !Ref PrivateHostedZoneld
   Name: !Join [".", ["etcd-2", !Ref PrivateHostedZoneName]]
   ResourceRecords:
   - !GetAtt Master2.PrivateIp
   TTL: 60
   Type: A
Outputs:
 PrivateIPs:
  Description: The control-plane node private IP addresses.
  Value:
   !Join [
    [!GetAtt Master0.Privatelp, !GetAtt Master1.Privatelp, !GetAtt Master2.Privatelp]
   1
```

# 1.8.13. Initializing the bootstrap node on AWS with user-provisioned infrastructure

After you create all of the required infrastructure in Amazon Web Services (AWS), you can install the cluster.

# **Prerequisites**

- Configure an AWS account.
- Generate the Ignition config files for your cluster.
- Create and configure a VPC and assocated subnets in AWS.
- Create and configure DNS, load balancers, and listeners in AWS.
- Create control plane and compute roles.
- Create the bootstrap machine.
- Create the control plane machines.
- If you plan to manually manage the worker machines, create the worker machines.

#### Procedure

- 1. Change to the directory that contains the installation program and run the following command:
  - \$ ./openshift-install wait-for bootstrap-complete --dir=<installation\_directory> \ 1 --log-level=info 2
  - For **<installation\_directory>**, specify the path to the directory that you stored the installation files in.
  - 2 To view different installation details, specify **warn**, **debug**, or **error** instead of **info**.

If the command exits without a **FATAL** warning, your production control plane has initialized.

# 1.8.13.1. Creating the worker nodes in AWS

You can create worker nodes in Amazon Web Services (AWS) for your cluster to use. The easiest way to manually create these nodes is to modify the provided CloudFormation template.



#### **IMPORTANT**

The CloudFormation template creates a stack that represents one worker machine. You must create a stack for each worker machine.



#### NOTE

If you do not use the provided CloudFormation template to create your worker nodes, you must review the provided information and manually create the infrastructure. If your cluster does not initialize correctly, you might have to contact Red Hat support with your installation logs.

# Prerequisites

- Configure an AWS account.
- Generate the Ignition config files for your cluster.
- Create and configure a VPC and assocated subnets in AWS.
- Create and configure DNS, load balancers, and listeners in AWS.
- Create control plane and compute roles.
- Create the bootstrap machine.
- Create the control plane machines.

### Procedure

1. Create a JSON file that contains the parameter values that the CloudFormation template requires:

```
"ParameterKey": "InfrastructureName", 1
 "ParameterValue": "mycluster-<random_string>" 2
 "ParameterKey": "RhcosAmi", 3
 "ParameterValue": "ami-<random_string>" 4
 "ParameterKey": "Subnet", 5
 "ParameterValue": "subnet-<random_string>" 6
},
 "ParameterKey": "WorkerSecurityGroupId", 7
 "ParameterValue": "sg-<random_string>" 8
 "ParameterKey": "IgnitionLocation", 9
 "ParameterValue": "https://api-int.<cluster_name>.<domain_name>:22623/config/worker"
 "ParameterKey": "CertificateAuthorities", 11
 "ParameterValue": "" 12
 "ParameterKey": "WorkerInstanceProfileName", 13
 "ParameterValue": "" 14
},
 "ParameterKey": "WorkerInstanceType", 15
 "ParameterValue": "m4.large" 16
```

- The name for your cluster infrastructure that is encoded in your Ignition config files for the cluster.
- Specify the infrastructure name that you extracted from the Ignition config file metadata, which has the format **<cluster-name>-<random-string>**.
- Current Red Hat Enterprise Linux CoreOS (RHCOS) AMI to use for the worker nodes.
- Specify an AWS::EC2::Image::Id value.
- A subnet, preferably private, to launch the worker nodes on.
- Specify a subnet from the **PrivateSubnets** value from the output of the CloudFormation template for DNS and load balancing.
- 7 The worker security group ID to associate with worker nodes.
- Specify the **WorkerSecurityGroupId** value from the output of the CloudFormation template for the security group and roles.
- The location to fetch bootstrap Ignition config file from.
- Specify the generated Ignition config location, https://api-int.<cluster\_name>. <domain\_name>:22623/config/worker.
- Base64 encoded certificate authority string to use.
- Specify the value from the **worker.ign** file that is in the installation directory. This value is the long string with the format **data:text/plain;charset=utf-8;base64,ABC...xYz==**.
- The IAM profile to associate with worker nodes.
- Specify the **WorkerInstanceProfile** parameter value from the output of the CloudFormation template for the security group and roles.
- The type of AWS instance to use for the control plane machines.
- 16 Allowed values:
  - m4.large
  - m4.xlarge
  - m4.2xlarge
  - m4.4xlarge
  - m4.8xlarge
  - m4.10xlarge
  - m4.16xlarge
  - c4.large
  - c4.xlarge
  - c4.2xlarge

- c4.4xlarge
- c4.8xlarge
- r4.large
- r4.xlarge
- r4.2xlarge
- r4.4xlarge
- r4.8xlarge
- r4.16xlarge



#### **IMPORTANT**

If **m4** instance types are not available in your region, such as with **euwest-3**, use **m5** types instead.

- 2. Copy the template from the **CloudFormation template for worker machines** section of this topic and save it as a YAML file on your computer. This template describes the networking objects and load balancers that your cluster requires.
- 3. If you specified an **m5** instance type as the value for **WorkerInstanceType**, add that instance type to the **WorkerInstanceType.AllowedValues** parameter in the CloudFormation template.
- 4. Create a worker stack.
  - a. Launch the template:



### **IMPORTANT**

You must enter the command on a single line.

\$ aws cloudformation create-stack --stack-name <name> 1

- --template-body file://<template>.yaml \ 2
- --parameters file://<parameters>.json 3
- <name> is the name for the CloudFormation stack, such as cluster-workers. You need the name of this stack if you remove the cluster.
- **<template>** is the relative path to and name of the CloudFormation template YAML file that you saved.
- **<parameters>** is the relative path to and name of the CloudFormation parameters JSON file.
- b. Confirm that the template components exist:
  - \$ aws cloudformation describe-stacks --stack-name <name>

5. Continue to create worker stacks until you have created enough worker Machines for your cluster.



### **IMPORTANT**

You must create at least two worker machines, so you must create at least two stacks that use this CloudFormation template.

### 1.8.13.1.1. CloudFormation template for worker machines

You can use the following CloudFormation template to deploy the worker machines that you need for your OpenShift Container Platform cluster.

AWSTemplateFormatVersion: 2010-09-09

Description: Template for OpenShift Cluster Node Launch (EC2 worker instance)

Parameters:

InfrastructureName:

AllowedPattern:  $([a-zA-Z][a-zA-Z0-9]\{0,26\})$ 

MaxLength: 27 MinLength: 1

ConstraintDescription: Infrastructure name must be alphanumeric, start with a letter, and have a maximum of 27 characters.

Description: A short, unique cluster ID used to tag nodes for the kubelet cloud provider.

Type: String RhcosAmi:

Description: Current Red Hat Enterprise Linux CoreOS AMI to use for bootstrap.

Type: AWS::EC2::Image::Id

Subnet:

Description: The subnets, recommend private, to launch the master nodes into.

Type: AWS::EC2::Subnet::Id WorkerSecurityGroupId:

Description: The master security group ID to associate with master nodes.

Type: AWS::EC2::SecurityGroup::Id

IgnitionLocation:

Default: https://api-int.\$CLUSTER\_NAME.\$DOMAIN:22623/config/worker

Description: Ignition config file location.

Type: String

CertificateAuthorities:

Default: data:text/plain;charset=utf-8;base64,ABC...xYz== Description: Base64 encoded certificate authority string to use.

Type: String

WorkerInstanceProfileName:

Description: IAM profile to associate with master nodes.

Type: String

WorkerInstanceType: Default: m4.large

Type: String AllowedValues:

- "m4.large"

- in thialge
- "m4.xlarge"
- "m4.2xlarge"
- "m4.4xlarge"
- "m4.8xlarge"
- "m4.10xlarge"

- "m4.16xlarge"
- "c4.large"
- "c4.xlarge"
- "c4.2xlarge"
- "c4.4xlarge"
- "c4.8xlarge"
- "r4.large"
- "r4.xlarge"
- "r4.2xlarge"
- "r4.4xlarge"
- "r4.8xlarge"
- "r4.16xlarge"

#### Metadata:

AWS::CloudFormation::Interface:

ParameterGroups:

- Label:

default: "Cluster Information"

Parameters:

- InfrastructureName
- Label:

default: "Host Information"

Parameters:

- WorkerInstanceType
- RhcosAmi
- IgnitionLocation
- CertificateAuthorities
- WorkerSecurityGroupId
- WorkerInstanceProfileName
- Label:

default: "Network Configuration"

Parameters:

- Subnet

ParameterLabels:

Subnet:

default: "Subnet" InfrastructureName:

default: "Infrastructure Name"

WorkerInstanceType:

default: "Worker Instance Type"

WorkerInstanceProfileName:

default: "Worker Instance Profile Name"

RhcosAmi:

default: "Red Hat Enterprise Linux CoreOS AMI ID"

IgnitionLocation:

default: "Worker Ignition Source"

CertificateAuthorities:

default: "Ignition CA String"

WorkerSecurityGroupId:

default: "Worker Security Group ID"

### Resources:

Worker0:

Type: AWS::EC2::Instance

Properties:

Imageld: !Ref RhcosAmi

```
BlockDeviceMappings:
   - DeviceName: /dev/xvda
     Ebs:
      VolumeSize: "120"
      VolumeType: "gp2"
   lamInstanceProfile: !Ref WorkerInstanceProfileName
   InstanceType: !Ref WorkerInstanceType
   NetworkInterfaces:
   - AssociatePublicIpAddress: "false"
     DeviceIndex: "0"
     GroupSet:
     - !Ref "WorkerSecurityGroupId"
     SubnetId: !Ref "Subnet"
   UserData:
     Fn::Base64: !Sub
     - '{"ignition":{"config":{"append":[{"source":"${SOURCE}}","verification":{}}]},"security":{"tls":
{"certificateAuthorities":[{"source":"${CA_BUNDLE}","verification":{}}]}},"timeouts":
{},"version":"2.2.0"},"networkd":{},"passwd":{},"storage":{},"systemd":{}}'
      SOURCE: !Ref IgnitionLocation,
      CA BUNDLE: !Ref CertificateAuthorities,
    }
   Tags:
   - Key: !Join ["", ["kubernetes.io/cluster/", !Ref InfrastructureName]]
     Value: "shared"
Outputs:
 PrivateIP:
  Description: The compute node private IP address.
  Value: !GetAtt Worker0.Privatelp
```

# 1.8.14. Logging in to the cluster

You can log in to your cluster as a default system user by exporting the cluster **kubeconfig** file. The **kubeconfig** file contains information about the cluster that is used by the CLI to connect a client to the correct cluster and API server. The file is specific to a cluster and is created during OpenShift Container Platform installation.

#### **Prerequisites**

- Deploy an OpenShift Container Platform cluster.
- Install the oc CLI.

### **Procedure**

1. Export the **kubeadmin** credentials:



For **<installation\_directory>**, specify the path to the directory that you stored the installation files in.

2. Verify you can run **oc** commands successfully using the exported configuration:

\$ oc whoami system:admin

# 1.8.15. Approving the CSRs for your machines

When you add machines to a cluster, two pending certificates signing request (CSRs) are generated for each machine that you added. You must confirm that these CSRs are approved or, if necessary, approve them yourself.

### **Prerequisites**

- You added machines to your cluster.
- Install the jq package.

#### **Procedure**

1. Confirm that the cluster recognizes the machines:

```
$ oc get nodes

NAME STATUS ROLES AGE VERSION
master-0 Ready master 63m v1.16.2
master-1 Ready master 63m v1.16.2
master-2 Ready master 64m v1.16.2
worker-0 NotReady worker 76s v1.16.2
worker-1 NotReady worker 70s v1.16.2
```

The output lists all of the machines that you created.

2. Review the pending certificate signing requests (CSRs) and ensure that the you see a client and server request with **Pending** or **Approved** status for each machine that you added to the cluster:

```
NAME AGE REQUESTOR CONDITION csr-8b2br 15m system:serviceaccount:openshift-machine-config-operator:node-bootstrapper Pending 1 csr-8vnps 15m system:serviceaccount:openshift-machine-config-operator:node-bootstrapper Pending csr-bfd72 5m26s system:node:ip-10-0-50-126.us-east-2.compute.internal Pending 2 csr-c57lv 5m26s system:node:ip-10-0-95-157.us-east-2.compute.internal Pending ...
```

- 1 A client request CSR.
- 2 A server request CSR.

In this example, two machines are joining the cluster. You might see more approved CSRs in the list.

3. If the CSRs were not approved, after all of the pending CSRs for the machines you added are in **Pending** status, approve the CSRs for your cluster machines:



### NOTE

Because the CSRs rotate automatically, approve your CSRs within an hour of adding the machines to the cluster. If you do not approve them within an hour, the certificates will rotate, and more than two certificates will be present for each node. You must approve all of these certificates. After you approve the initial CSRs, the subsequent node client CSRs are automatically approved by the cluster **kube-controller-manager**. You must implement a method of automatically approving the kubelet serving certificate requests.

- To approve them individually, run the following command for each valid CSR:
  - \$ oc adm certificate approve <csr\_name> 1
  - **csr\_name>** is the name of a CSR from the list of current CSRs.
- If all the CSRs are valid, approve them all by running the following command:

# 1.8.16. Initial Operator configuration

After the control plane initializes, you must immediately configure some Operators so that they all become available.

### **Prerequisites**

Your control plane has initialized.

#### **Procedure**

1. Watch the cluster components come online:

\$ watch -n5 oc get clusteroperators

NAME SINCE	VERSION	I AVAILABLE	PROGRESSING	DEGRADED
authentication	4.3.0	True False	False 69s	
cloud-credential	4.3.0	True False	False 12m	1
cluster-autoscaler	4.3.0	True False	False 11r	n
console	4.3.0 Tru	ue False	False 46s	
dns	4.3.0 True	e False	False 11m	
image-registry	4.3.0	True False	False 5m2	6s
ingress	4.3.0 Tru	ue False	False 5m36s	
kube-apiserver	4.3.0	True False	False 8m5	53s
kube-controller-manage	4.3.	0 True F	alse False	7m24s
kube-scheduler	4.3.0	True False	e False 12r	n
machine-api	4.3.0	True False	False 12m	
machine-config	4.3.0	True False	False 7m	36s

marketplace	4.3.0	True	False	False	7m54m	
monitoring	4.3.0	True	False	False	7h54s	
network	4.3.0	True	False	False	5m9s	
node-tuning	4.3.0	True	False	False	11m	
openshift-apiserver	4.3	.0 True	e False	False	e 11m	
openshift-controller-mana	ger	4.3.0	True Fa	alse l	False 5m94	3s
openshift-samples	4.3	.0 True	e False	Fals	e 3m55s	
operator-lifecycle-manage	er	4.3.0	rue Fa	lse F	alse 11m	
operator-lifecycle-manage	er-catalo	g 4.3.0	True	False	False 11r	n
service-ca	4.3.0	True	False	False	11m	
service-catalog-apiserver	4	.3.0 Tı	ue Fals	se Fa	lse 5m26s	
service-catalog-controller-	-manage	er 4.3.0	True	False	False 5m	25s
storage	4.3.0	True	False	False	5m30s	

2. Configure the Operators that are not available.

# 1.8.16.1. Image registry storage configuration

If the **image-registry** Operator is not available, you must configure storage for it. Instructions for both configuring a PersistentVolume, which is required for production clusters, and for configuring an empty directory as the storage location, which is available for only non-production clusters, are shown.

## 1.8.16.1.1. Configuring registry storage for AWS with user-provisioned infrastructure

During installation, your cloud credentials are sufficient to create an S3 bucket and the Registry Operator will automatically configure storage.

If the Registry Operator cannot create an S3 bucket, and automatically configure storage, you can create an S3 bucket and configure storage with the following procedure.

## **Prerequisites**

- A cluster on AWS with user-provisioned infrastructure.
- For S3 on AWS storage the secret is expected to contain two keys:
  - REGISTRY\_STORAGE\_S3\_ACCESSKEY
  - REGISTRY STORAGE S3 SECRETKEY

## Procedure

Use the following procedure if the Registry Operator cannot create an S3 bucket and automatically configure storage.

- 1. Set up a Bucket Lifecycle Policy to abort incomplete multipart uploads that are one day old.
- 2. Fill in the storage configuration in **configs.imageregistry.operator.openshift.io/cluster**:

\$ oc edit configs.imageregistry.operator.openshift.io/cluster

storage: s3:

bucket: <bucket-name> region: <region-name>



### **WARNING**

To secure your registry images in AWS, block public access to the S3 bucket.

# 1.8.16.1.2. Configuring storage for the image registry in non-production clusters

You must configure storage for the image registry Operator. For non-production clusters, you can set the image registry to an empty directory. If you do so, all images are lost if you restart the registry.

### Procedure

• To set the image registry storage to an empty directory:

\$ oc patch configs.imageregistry.operator.openshift.io cluster --type merge --patch '{"spec": {"storage":{"emptyDir":{}}}}'



#### **WARNING**

Configure this option for only non-production clusters.

If you run this command before the Image Registry Operator initializes its components, the **oc patch** command fails with the following error:

Error from server (NotFound): configs.imageregistry.operator.openshift.io "cluster" not found

Wait a few minutes and run the command again.

# 1.8.17. Deleting the bootstrap resources

After you complete the initial Operator configuration for the cluster, remove the bootstrap resources from Amazon Web Services (AWS).

## **Prerequisites**

• You completed the initial Operator configuration for your cluster.

#### Procedure

- 1. Delete the bootstrap resources. If you used the CloudFormation template, delete its stack:
  - \$ aws cloudformation delete-stack --stack-name <name> 1
  - **1 <name>** is the name of your bootstrap stack.

## 1.8.18. Creating the Ingress DNS Records

If you removed the DNS Zone configuration, manually create DNS records that point to the Ingress load balancer. You can create either a wildcard record or specific records. While the following procedure uses A records, you can use other record types that you require, such as CNAME or alias.

## **Prerequisites**

- You deployed an OpenShift Container Platform cluster on Amazon Web Services (AWS) by using infrastructure that you provisioned.
- Install the OpenShift Command-line Interface (CLI), commonly known as oc.
- Install the jq package.
- Download the AWS CLI and install it on your computer. See Install the AWS CLI Using the Bundled Installer (Linux, macOS, or Unix).

#### **Procedure**

- 1. Determine the routes to create.
  - To create a wildcard record, use \*.apps.<cluster\_name>.<domain\_name>, where
     <cluster\_name> is your cluster name, and <domain\_name> is the Route53 base domain for your OpenShift Container Platform cluster.
  - To create specific records, you must create a record for each route that your cluster uses, as shown in the output of the following command:

```
$ oc get --all-namespaces -o jsonpath='{range .items[*]}{range .status.ingress[*]}{.host} {\"\n"}{end}{end}' routes
oauth-openshift.apps.<cluster_name>.<domain_name>
console-openshift-console.apps.<cluster_name>.<domain_name>
downloads-openshift-console.apps.<cluster_name>.<domain_name>
alertmanager-main-openshift-monitoring.apps.<cluster_name>.<domain_name>
grafana-openshift-monitoring.apps.<cluster_name>.<domain_name>
prometheus-k8s-openshift-monitoring.apps.<cluster_name>.<domain_name>
```

2. Retrieve the Ingress Operator load balancer status and note the value of the external IP address that it uses, which is shown in the **EXTERNAL-IP** column:

```
$ oc -n openshift-ingress get service router-default

NAME TYPE CLUSTER-IP EXTERNAL-IP PORT(S)

AGE

router-default LoadBalancer 172.30.62.215 ab3...28.us-east-2.elb.amazonaws.com
80:31499/TCP,443:30693/TCP 5m
```

3. Locate the hosted zone ID for the load balancer:

 $\$  aws elb describe-load-balancers | jq -r '.LoadBalancerDescriptions[] | select(.DNSName == "<external\_ip>").CanonicalHostedZoneNameID' 1

Z3AADJGX6KTTL2

For **<external\_ip>**, specify the value of the external IP address of the Ingress Operator load balancer that you obtained.

The output of this command is the load balancer hosted zone ID.

4. Obtain the public hosted zone ID for your cluster's domain:

```
$ aws route53 list-hosted-zones-by-name \
--dns-name "<domain_name>" \
--query 'HostedZones[? Config.PrivateZone != `true` && Name ==
`<domain_name>.`].Id' 2
--output text
```

/hostedzone/Z3URY6TWQ91KVV

12 For **<domain\_name>**, specify the Route53 base domain for your OpenShift Container Platform cluster.

The public hosted zone ID for your domain is shown in the command output. In this example, it is **Z3URY6TWQ91KVV**.

5. Add the alias records to your private zone:

```
$ aws route53 change-resource-record-sets --hosted-zone-id "rivate_hosted_zone_id>" --
change-batch '{
   "Changes": [
     "Action": "CREATE",
     "ResourceRecordSet": {
      "Name": "\\052.apps.<cluster_domain>", 2
      "Type": "A",
>
      "AliasTarget":{
       "HostedZoneId": "<hosted_zone_id>", 3
       "DNSName": "<external ip>.", 4
       "EvaluateTargetHealth": false
>
>
>
   }
> ]
```

- For <pri>private\_hosted\_zone\_id>, specify the value from the output of the CloudFormation template for DNS and load balancing.
- For **<cluster\_domain>**, specify the domain or subdomain that you use with your OpenShift Container Platform cluster.
- For <hosted\_zone\_id>, specify the public hosted zone ID for the load balancer that you obtained.
- For **<external\_ip>**, specify the value of the external IP address of the Ingress Operator load balancer. Ensure that you include the trailing period (.) in this parameter value.

6. Add the records to your public zone:

```
$ aws route53 change-resource-record-sets --hosted-zone-id "<public_hosted_zone_id>"" --
change-batch '{
   "Changes": [
    {
>
     "Action": "CREATE",
>
     "ResourceRecordSet": {
      "Name": "\\052.apps.<cluster domain>", 2
>
      "Type": "A",
>
>
      "AliasTarget":{
       "HostedZoneId": "<hosted_zone_id>", 3
>
       "DNSName": "<external_ip>.", 4
       "EvaluateTargetHealth": false
>
      }
>
     }
>
> ]
```

- For **<public\_hosted\_zone\_id>**, specify the public hosted zone for your domain.
- For **<cluster\_domain>**, specify the domain or subdomain that you use with your OpenShift Container Platform cluster.
- For **<hosted\_zone\_id>**, specify the public hosted zone ID for the load balancer that you obtained.
- For **<external\_ip>**, specify the value of the external IP address of the Ingress Operator load balancer. Ensure that you include the trailing period (.) in this parameter value.

# 1.8.19. Completing an AWS installation on user-provisioned infrastructure

After you start the OpenShift Container Platform installation on Amazon Web Service (AWS) user-provisioned infrastructure, monitor the deployment to completion.

### **Prerequisites**

- Removed the bootstrap node for an OpenShift Container Platform cluster on user-provisioned AWS infrastructure.
- Install the **oc** CLI and log in.

# Procedure

• Complete the cluster installation:

```
$ ./openshift-install --dir=<installation_directory> wait-for install-complete 1

INFO Waiting up to 30m0s for the cluster to initialize...
```

For **<installation\_directory>**, specify the path to the directory that you stored the installation files in.



#### **IMPORTANT**

The Ignition config files that the installation program generates contain certificates that expire after 24 hours. You must keep the cluster running for 24 hours in a non-degraded state to ensure that the first certificate rotation has finished.

1. Register your cluster on the Cluster registration page.

## **Next steps**

- Customize your cluster.
- If necessary, you can opt out of remote health reporting .

# 1.9. UNINSTALLING A CLUSTER ON AWS

You can remove a cluster that you deployed to Amazon Web Services (AWS).

# 1.9.1. Removing a cluster that uses installer-provisioned infrastructure

You can remove a cluster that uses installer-provisioned infrastructure from your cloud.

### **Prerequisites**

- Have a copy of the installation program that you used to deploy the cluster.
- Have the files that the installation program generated when you created your cluster.

#### Procedure

- 1. From the computer that you used to install the cluster, run the following command:
  - \$ ./openshift-install destroy cluster \
    --dir=<installation\_directory> --log-level=info 1 2
  - For **<installation\_directory>**, specify the path to the directory that you stored the installation files in.
  - To view different details, specify warn, debug, or error instead of info.



#### **NOTE**

You must specify the directory that contains the cluster definition files for your cluster. The installation program requires the **metadata.json** file in this directory to delete the cluster.

2. Optional: Delete the **<installation\_directory>** directory and the OpenShift Container Platform installation program.