

Module IN3031 / INM378 Digital Signal Processing and Audio Programming

Johan Pauwels johan.pauwels@city.ac.uk based on slides by Tillman Weyde



Digital Signals: Sampling and Quantisation



Signals in the Time Domain

- signals (one channel)
 - analogue $x_a(t)$: ℝ → ℝ
 - digital $x_d[n]: \mathbb{Z} \to \mathbb{Z}$
- $x_{d}[n] = x_{a}(n \cdot 1/Fs)$ where f_{s} is the

Sampling Frequency or Sample Rate



Spatial Signals: Images

- signals (one channel)
 - analogue $\chi_a(x,y): \mathbb{R}^2 \to \mathbb{R}$
 - digital $X_d[n,m]: \mathbb{Z}^2 \to \mathbb{Z}$
- $x_d[n,m] = x_a(n\cdot 1/f_s, m\cdot 1/f_s)$ where f_s is the

Sampling Frequency

We focus on digital signals from here on



Operations in the Time or Space Domain

- changing amplitude = multiplying with a number a
 y = a · x, i.e. y[n] = a · x[n]
 |a| > 1 : louder/brighter signals, |a| < 1 softer/darker signal
- mixing signals = **add**ition $y = x_1 + x_2$, i.e. $y[n] = x_1[n] + x_2[n]$
- delay = time-**shift**ing y[n] = x[n-k]



Frequencies and Spectra


 Most signals contain multiple frequencies (harmonic, inharmonic, noise ...)

Amplitude of the signal per frequency is called the

spectrum

The square of the spectrum is the power spectrum

 We will address later how to calculate the spectrum






Example: Digital Sound

- Analogue systems use continuous values
- Digital systems use discrete (non-continuous) values
- Digitisation reduces from continuous to discrete:
 - time (by sampling)
 - amplitude (by quantisation)



Digitising Time: Sampling

- Sample/Hold electronics:
 take a value at regular time intervals and hold it
- Sampling Frequency (sample rate, often Fs or fs):
 Number of samples per time, i.e. time resolution







Digital Images: Spatial Sampling

- Spatial resolution (raster size) spatial sampling frequency
- Sample resolution per dimension, often in dots per inch (DPI)
- Typically same resolution in both dimensions












Digitising Values: Quantisation

- Rounding a continuous to a discrete value (from a fixed set)
- Sample Resolution (Depth): number of bits per sample Defines the possible range of values e.g. 8 bits (28=256), 16 bits (216,~65k), 24 bits (224,~16m)






Sample number

Quantisation Error

- Difference between the sampled and quantised signal (rounding error)
- Different values are mapped to one -> information loss.






Sampling, Quantisation and Signal Quality

Sampling rate: time resolution

Bit depth: value resolution

- Higher resolution:
 lower quantisation error
 (closer to the original)
- Crucial for signal quality







Sampling and frequency

 a problem with high input frequencies relative to Fs sampled signal looks quite different from input

low input frequency



Time (or sample number)



high input frequency

Time (or sample number)



Aliasing


- Intuition: 2 samples needed per wave cycle (one for each peak and trough)
- Output frequencies are different (aliased) too low if too few samples, i.e. temporal/spatial resolution too low



Spatial Aliasing (Moire)

- In 2D, the same problem occurs
- E.g. woven patterns can exceed camera resolution
- Effect can be different per colour channel








'Digital' Aliasing

- Aliasing occurs not only when sampling physical signals.
- In in the digital domain aliasing can occur by:
 - Downsampling digital signals (reducing resolution)
 - Sampling mathematical functions (synthesizing signals)









Sampling Theorem

- Sampling cannot capture frequencies greater than half the sampling frequency every wave cycle needs two points
- f_s/2 called <u>Nyquist-Frequency</u>
- Frequencies in the signal above the Nyquist-Frequency get mirrored down at the Nyquist-Frequency (Aliasing)
- $f_{al} = -abs([f_i \mod f_s] f_s/2) + f_s/2$







Filters

- Filters signal processing units (typically) designed to remove frequency components
- Filter types named mostly by frequency ranges (bands) that can pass through the filter, e.g.

high pass

low pass

band pass

band reject


• Typical examples are **EQ** in stereos and mobile phones



Aliasing Solution

 Increase time or space resolution not always possible/practical may not (fully) resolve the problem

Anti-alias filter:
 Remove components
 above the Nyquist frequency
 before (down-)sampling
 (with a low-pass filter)






Reconstruction of a Sampled Signal


- Goal: reconstruction of the original signal (within the limits of the sampling theorem)
- Problem: samples provide discrete values that we need to connect continuously
- Reconstructed signal should have the same frequency content as the original



Signal Reconstruction

Reconstruction should reproduce the original signal and spectrum









Signal Reconstruction

- Ideal impulses contain infinite frequency content, which repeats at f_s multiples.
- Easy to filter (analogue) but not practical to generate









Signal Reconstruction

- Signal reconstruction by holding the value effectively multiplies the spectrum with a sinc function (sin(x) / x), still not ideal.
- Further filtering is needed, more in the next weeks.








Filtering in the ADA Chain

- Analog input must not contain frequencies higher than Nyquist-F.
 - anti-alias filtering (low-pass)
- Output created from digital contains additional frequencies
 - reconstruction filtering (low-pass)





Generating Signals

- Generating a signal can be done
 - off line or in real time
 - digital or analogue
 - (re-)using signal waveforms
 - simple periodic
 - noise (random)
 - recorded signal




Oscillators

- Simple signal generators
- Periodic waveforms (typical)
 - sine
 - square
 - pulse
 - sawtooth
- Noise: different 'colours'



Oscillator Waveforms


Periodic waveforms








Frequencies and Waveforms


- Simple periodic waveforms create harmonic signals (frequency components at integer multiples)
- How can we determine the frequency content of a given signal? We'll see next week :-)































Noise Oscillators

- Noise oscillators can create random signals
 - white noise has evenly distributed frequency components
 - pink noise has weaker high-frequency components (amplitude ~ 1/f).
- Some rarely used forms of noise
 - brown noise (1/f²)
 - blue noise (f)
 - violet noise (f²)





Control

- Most components of a signal synthesiser have some parameters to control
- In analogue systems, electronic control signals were used:
 - voltage controlled oscillator
 - voltage controlled filter
 - voltage controlled amplifier
- External control sources can be, e.g., a musician playing on a keyboard, nowadays done in MIDI (musical instrument digital interface)
- Internal control sources are low frequency oscillator (LFO) and envelope generator (ADSR)



Amplitude Control (Gain)

 In a computer, a gain control unit multiplies every sample with a gain factor:

```
y[t] = x[t] * c
in Python (NumPy arrays) y = x * c
```

 c can change over time, in that case the unit is called time variant




Envelope Generator

- Natural sounds change over time
- This is modelled by an envelope generator that can control gain and other system parameters
- Envelopes are typically triggered by events
 - in music, typically a MIDI note-on message
 - in games, an event from the game play
- The **envelope** is **modulating signal properties** (e.g. amplitude, spectrum).



Envelope Generator (2)

 The most common form is an Attack, Decay, Sustain, Release (ADSR) generator.



Attack, Decay and Release have rate parameters, Sustain has a level parameter (usually not changed in real time).



READING

http://www.dspguide.com/ Chapter 3

Maths refresher: Rochesso, D.: Introduction to Sound Processing

Appendix pp. 154: Vectors and Matrices, Exponentials and

Logarithms, Trigonometric Functions



NEXT WEEK: Frequency Analysis