#### **NAME**

rgbds — object file format documentation

#### DESCRIPTION

This is the description of the object files used by rgbasm(1) and rgblink(1). Please note that the specifications may change. This toolchain is in development and new features may require adding more information to the current format, or modifying some fields, which would break compatibility with older versions.

## FILE STRUCTURE

The following types are used:

LONG is a 32-bit integer stored in little-endian format. BYTE is an 8-bit integer. STRING is a 0-terminated string of BYTE.

```
; Header
BYTE
        ID[4]
                         ; "RGB9"
LONG
        RevisionNumber
                         ; The format's revision number this file uses.
        NumberOfSymbols ; The number of symbols used in this file.
LONG
        NumberOfSections; The number of sections used in this file.
LONG
; File info
                            ; The number of nodes contained in this file.
LONG
        NumberOfNodes
REPT NumberOfNodes
                            ; IMPORTANT NOTE: the nodes are actually written in
                            ; **reverse** order, meaning the node with ID 0 is
                             ; the last one in the file!
    LONG
            ParentID
                            ; ID of the parent node, -1 means this is the root.
    LONG
            ParentLineNo
                            ; Line at which the parent context was exited.
                            ; Meaningless on the root node.
    BYTE
            Type
                            ; 0 = REPT node
                             ; 1 = File node
                             ; 2 = Macro node
    IF Type != 0
                            ; If the node is not a REPT...
                            ; The node's name: either a file name, or macro name
        STRING Name
                             ; prefixed by its definition file name.
    ELSE
                             ; If the node is a REPT, it also contains the iter
                             ; counts of all the parent REPTs.
                            ; Size of the array below.
        LONG
```

Iter[Depth] ; The number of REPT iterations by increasing depth.

ENDR

; Symbols

**ENDC** 

LONG

```
REPT
       NumberOfSymbols
                          ; Number of symbols defined in this object file.
    STRING Name
                          ; The name of this symbol. Local symbols are stored
                           ; as "Scope.Symbol".
    BYTE
                          ; 0 = LOCAL symbol only used in this file.
           Type
                           ; 1 = IMPORT this symbol from elsewhere
                           ; 2 = EXPORT this symbol to other objects.
    IF (Type & 0x7F) != 1 ; If symbol is defined in this object file.
       LONG
               SourceFile; File where the symbol is defined.
       LONG
                         ; Line number in the file where the symbol is defined.
               LineNum
       LONG
               SectionID ; The section number (of this object file) in which
                           ; this symbol is defined. If it doesn't belong to any
                           ; specific section (like a constant), this field has
                           ; the value -1.
               Value
       LONG
                          ; The symbols value. It's the offset into that
                           ; symbol's section.
    ENDC
ENDR
; Sections
REPT NumberOfSections
    STRING Name ; Name of the section
    LONG
           Size ; Size in bytes of this section
           Type ; 0 = WRAM0
    BYTE
                  ; 1 = VRAM
                  ; 2 = ROMX
                  ; 3 = ROM0
                  ; 4 = HRAM
                  ; 5 = WRAMX
                  ; 6 = SRAM
                  ; 7 = OAM
                  ; Bits 7 and 6 are independent from the above value:
                  ; Bit 7 encodes whether the section is unionized
                  ; Bit 6 encodes whether the section is a fragment
                  ; Bits 6 and 7 may not be both set at the same time!
    LONG
                  ; Address to fix this section at. -1 if the linker should
            Org
                  ; decide (floating address).
           Bank ; Bank to load this section into. -1 if the linker should
    LONG
                  ; decide (floating bank). This field is only valid for ROMX,
```

; VRAM, WRAMX and SRAM sections.

```
BYTE
           Align; Alignment of this section, as N bits. 0 when not specified.
    LONG
           Ofs ; Offset relative to the alignment specified above.
                  ; Must be below 1 << Align.
            (Type == ROMX) | | (Type == ROM0); Sections that can contain data.
    ΙF
                                ; Raw data of the section.
        BYTE
               Data[Size]
               NumberOfPatches; Number of patches to apply.
        LONG
        REPT
               NumberOfPatches
                    SourceFile ; ID of the source file node (for printing
           LONG
                                ; error messages).
            LONG
                   LineNo
                                ; Line at which the patch was created.
            LONG
                   Offset
                                 ; Offset into the section where patch should
                                 ; be applied (in bytes).
                    PCSectionID ; Index within the file of the section in which
            LONG
                                ; PC is located.
                                ; This is usually the same section that the
                                 ; patch should be applied into, except e.g.
                                 ; with LOAD blocks.
            LONG
                    PCOffset
                                ; PC's offset into the above section.
                                 ; Used because the section may be floating, so
                                 ; PC's value is not known to RGBASM.
            BYTE
                                ; 0 = BYTE patch.
                    Type
                                 ; 1 = little endian WORD patch.
                                 ; 2 = little endian LONG patch.
                                 ; 3 = JR offset value BYTE patch.
            LONG
                    RPNSize
                                ; Size of the buffer with the RPN.
                                 ; expression.
                   RPN[RPNSize] ; RPN expression. Definition below.
            BYTE
        ENDR
    ENDC
ENDR
; Assertions
LONG NumberOfAssertions
REPT NumberOfAssertions
```

LONG SourceFile ; ID of the source file node (for printing the failure).

LONG	LineNo	e at which the assertion wa	as created.
LONG	Offset	set into the section where	the assertion is located.
LONG	SectionID	ex within the file of the sated, or -1 if defined outs	
LONG	PCOffset	s offset into the above sed d because the section may b not known to RGBASM.	
BYTE	Type	Prints the message but all Prints the message and eva but linking fails afterwar Prints the message and imm	aluates other assertions,
LONG	RPNSize	e of the RPN expression's k	ouffer.
BYTE	RPN[RPNSize]	expression, same as patche	es. Assert fails if == 0.
STRING	Message	essage displayed when the a	

#### ENDR

## **RPN DATA**

Expressions in the object file are stored as RPN. This is an expression of the form "2 5 +". This will first push the value "2" to the stack, then "5". The "+" operator pops two arguments from the stack, adds them, and then pushes the result on the stack, effectively replacing the two top arguments with their sum. In the RGB format, RPN expressions are stored as BYTEs with some bytes being special prefixes for integers and symbols.

Value	Meaning		
\$00	+ operator		
\$01	- operator		
\$02	* operator		
\$03	/ operator		
\$04	% operator		
\$05	unary -		
\$06	** operator		
\$10	operator		
\$11	& operator		
\$12	^ operator		
\$13	unary ~		
\$21	&& comparison		
\$22	comparison		
\$23	unary!		
\$30	== comparison		
\$31	!= comparison		
\$32	> comparison		
\$33	< comparison		
\$34	>= comparison		
\$35	<= comparison		

;	\$40	<< operator
;	\$41	>> operator
:	\$50	BANK (symbol), a LONG Symbol ID follows, where -1 means PC
:	\$51	BANK (section_name), a null-terminated string follows.
1	\$52	Current BANK()
1	\$53	SIZEOF (section_name), a null-terminated string follows.
1	\$54	STARTOF (section_name), a null-terminated string follows.
1	\$60	HRAMCheck. Checks if the value is in HRAM, ANDs it with 0xFF.
:	\$61	RSTCheck. Checks if the value is a RST vector, ORs it with 0xC7.
1	\$80	LONG integer follows.
;	\$81	LONG symbol ID follows.

# SEE ALSO

rgbasm(1), rgblink(1), rgbds(7), gbz80(7)

## **HISTORY**

**rgbds** was originally written by Carsten Sørensen as part of the ASMotor package, and was later packaged in RGBDS by Justin Lloyd. It is now maintained by a number of contributors at https://github.com/gbdev/rgbds.