CS348: Computer Networks



Congestion Control in TCP

Dr. Manas Khatua

Assistant Professor Dept. of CSE, IIT Guwahati

E-mail: manaskhatua@iitg.ac.in

Principles of Congestion Control




- We have discussed: reliable data transfer service in the face of packet loss
 - such loss typically results from the overflowing of router buffers as the network becomes congested
- Packet retransmission treats a symptom of network congestion but not the cause of network congestion

congestion:

- "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
 - lost packets (buffer overflow at routers)
 - long delays (queueing in router buffers)
- a top-10 problem!

Causes/Cost of Congestion: scenario 1





- max. per-connection throughput: R/2 large delays as arrival rate no matter how high their sending rates!
- as the router buffer is shared among them.




Conclusion:

- while operating at an aggregate throughput of near R
 - may be ideal from a throughput standpoint,
 - but, it is far from ideal from a delay standpoint!
- Even in this (extremely) idealized scenario
 - "cost" of a congested network
 - large queuing delays are experienced as the packet arrival rate nears the link capacity.
 - assuming that: (i) the connections operate at these sending rates for an infinite period of time, (ii) there is an infinite amount of buffering available
 - → the above delay between source and destination becomes infinite

Causes/costs of Congestion: scenario 2




- one router, finite buffers
- sender retransmission of timed-out packet
 - application-layer input = application-layer output: $\lambda_{in} = \lambda_{out}$
 - transport-layer input includes *retransmissions* : $\lambda'_{in} >= \lambda_{in}$
- Sending rate: λ_{in} ; Offered load: λ_{in}






Assume idealization: perfect knowledge with sender

sender sends only when router buffers available








Assume Idealization: know when loss occur


sender only re-sends if packet known to be lost






Assume Idealization: know when loss occur

sender only re-sends if packet known to be lost









Realistic: duplicates

- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered








Realistic: duplicates

- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered



"costs" of congestion:

- more work (retrans) for given "goodput"
- unneeded retransmissions: link carries multiple copies of pkt
 - decreasing goodput


Causes/costs of congestion: scenario 3



- four senders
- multihop paths
- timeout/retransmit
- Overlapping paths
- \Leftrightarrow all have same value of λ_{in}


Q: what happens if all λ_{in} and λ_{in} increase ?

A: as red λ_{in} increases, all arriving blue pkts at upper queue (RI) are dropped; blue throughput $\rightarrow 0$





- For extremely small values of λ_{in} , buffer overflows are rare
 - the throughput approximately equals the offered load
- For slightly larger values of λ_{in} , overflows are still rare
 - the corresponding throughput is also larger,
- * Thus, for small values of λ_{in} , an increase in λ_{in} results in an increase in λ_{out}



As red λ_{in} increases, all arriving blue pkts at upper queue (in R1) are dropped, as R1 will give priority to red pkts; So, blue throughput \rightarrow 0

another "cost" of congestion:

 when packet is dropped, any "upstream transmission capacity" used for that packet was wasted! (e.g. work by R4 in above figure)

Congestion v/s Flow Control



- TCP cannot ignore the congestion in network (at the intermediate points) as it wants to provide end-to-end reliability
- The use of flow control in TCP cannot avoid congestion in intermediate routers because
 - a router may receive data from more than one sender
 - Flow control is for individual TCP sender
 - There is no congestion at the either end
 - there may be congestion in the middle.

Approaches to Congestion Control



two broad approaches towards congestion control:

end-to-end congestion control

- no explicit feedback from network
- congestion inferred from end-system who observed loss, delay
- approach taken by TCP
- suitable in datagram approach

network-assisted congestion control

- routers/switches provide feedback to end systems
 - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM ABR)
 - explicit rate for sender to send at
 - Direct feedback: sent from a network router to the sender
 - Indirect feedback: router marks a field in a packet flowing from sender to receiver
- suitable for virtual-circuit approach

TCP Congestion control



- Basic approach:
 - each sender limit the rate at which it sends traffic into its connection
 - set the rate as a function of perceived network congestion.

- perceives less congestion along the path → increases its send rate
- perceives huge congestion along the path → reduces its send rate

- It should not aggressively send segments to the network
- It can not be very conservative, either, sending a small number of segments in each time interval



- Questions need to answer:
 - How does a TCP sender limit the rate at which it sends traffic into its connection?
 - How does a TCP sender perceive that there is congestion on the path between itself and the destination?
 - What congestion control algorithm should the sender use to change its send rate as a function of perceived end-to-end congestion?

Answer of 1st Question:

- To control the number of segments to transmit, TCP uses another variable called Congestion Window (cwnd)
- Actually, the <u>cwnd</u> variable and the <u>rwnd</u> variable (used for flow control) together define the <u>size</u> of the <u>send</u> window in TCP
 - Actual send window size = min (rwnd, cwnd)
- The constraint above limits the amount of unacknowledged data at the sender and therefore indirectly limits the sender's send rate.



Answer of 2nd Question:


- TCP sender uses the occurrence of two events as signs of congestion:
 - time-out
 - 3 duplicate ACKs

Answer of 3rd Question:

- There exist many congestion control algorithm for adjusting the value of cwnd based upon end-to-end congestion
 - Default/basic approach
- Modified TCP with congestion control algorithms
 - Tahoe TCP: both signs of occurrence are treated equally
 - Reno TCP: both signs of occurrence are treated differently
 - New Reno TCP: TCP checks to see if more than one segment is lost in the current window when 3 duplicate ACKs arrive

TCP Congestion Control: details





sender limits transmission:

cwnd is dynamic, function of perceived network congestion

TCP sending rate:

roughly: send cwnd bytes, wait RTT for ACKs, then send more bytes

rate
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec


TCP congestion control algo has three components:

- slow start
- congestion avoidance
- fast recovery

Slow Start



- when connection begins, increase rate exponentially until first loss event:
 - initially cwnd = 1 MSS (maximumsized segments)
 - double cwnd every RTT
 - done by incrementing cwnd for every ACK received
- summary: initial rate is slow but ramps up exponentially fast
- This process results in a doubling of the sending rate every RTT.



When growth ends?



- 1st case, a loss event indicated by a timeous
 - Indicates congestion
 - cwnd sets to 1 MSS
 - begins the slow start process anew.
 - ssthresh (slow start threshold) sets to cwnd/2.
- 2nd case, when the value of cwnd equals ssthresh,
 - TCP transitions into congestion avoidance state
 - cwnd grows linearly
- 3rd case, if 3 duplicate ACKs are detected,
 - dupACKs indicate network capable of delivering some segments
 - TCP performs a fast retransmit and enters fast recovery state
 - ssthresh sets to cwnd/2.
 - cwnd sets to ssthresh + 3 MSS.
 - cwnd grows linearly

Slow-start strategy is slower in the case of delayed ACK.

If two segments are ACKed cumulatively, the size of the *cwnd* increases by 1, not 2. With one ACK for every two segments, the growth is a power of 1.5, but still exponential


Congestion Avoidance



 On entry to this state, the value of cwnd is approx half its value when congestion was last encountered

If a new ACK arrives, cwnd = cwnd + MSS. (MSS/cwnd)

- To avoid congestion before it happens, we must slow down the exponential growth of cwnd
- the additive phase begins.
- If 3 dupACKs are detected at this state,
 - TCP performs a fast retransmit and enters the fast recovery state
- If timeout occurs at this state
 - TCP enters into slow start



Fast Recovery




- this algorithm is also an additive increase, but it starts when 3 duplicate ACK arrives
- If a duplicate ACK arrives (after the 3 duplicate ACK which triggers the recovery)
 - cwnd = cwnd + (1/ cwnd)

- If timeout occurs, TCP moves back to slow start state
- If any new ACK arrives, TCP moves back to congestion avoidance state

This state is recommended, but not mandatory in TCP

FSM of TCP Congestion Control





Different Versions



TCP Tahoe

- signs of congestion occurrence (time-out, 3 duplicate ACK) are treated equally
- uses only slow start and congestion avoidance states

TCP Reno

- signs of congestion occurrence (time-out, 3 duplicate ACK) are treated differently
- three states in FSM: *slow start, congestion avoidance, fast recovery*

TCP New Reno

- It differs from RENO in that it doesn't exit fast-recovery until all the data which was outstanding at the time it entered fast recovery is ACKed.
- It is most common today


TCP Vegas

- variations of the Reno algorithm
- attempts to avoid congestion while maintaining good throughput
- The basic idea of Vegas is to
 - (1) detect congestion in the routers between source and destination before packet loss occurs, and
 - (2) lower the rate linearly when this imminent packet loss is detected.

Additive Increase Multiplicative Decrease

- TCP congestion control is often refereed to as AIMD form of congestion control.
- approach: sender increases transmission rate (window size), probing for usable bandwidth, until loss occurs
 - additive increase: increase window by 1 MSS every RTT until loss detected
 - multiplicative decrease: cut window in half after loss

AIMD saw-toothed behavior: probing for bandwidth




TCP Throughput



- What the average throughput of a long-lived TCP connection would be?
- we'll ignore the slow-start phases that occur after timeout events as these phases are typically very short.
- the rate at which TCP sends data is a function of cwnd and current RTT
 - Rate = cwnd/RTT
- Let, cwnd = W when a loss event occurs.

If we ignore slow-start then



- Assume that RTT and W are approximately constant over the duration of the connection (i.e. in steady-state)
 - the TCP transmission rate ranges from (W /2 RTT) to (W /RTT)
- So, the average throughput of a connection = ½ ((W /2 RTT) + (W /RTT)) = 0.75*(W/RTT)

TCP over "High-Bandwidth" path



- Example of high speed TCP needed in present era:
 - 1500 byte segments, 100ms RTT,
 - We want 10 Gbps throughput
- So, using previous formula --> it requires W = 83,333 in-flight segments
- What would happen the case of loss?
- throughput in terms of segment loss probability, L [Mathis 1997]:


TCP throughput =
$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- → to achieve 10 Gbps throughput, need a loss rate of L = 2·10⁻¹⁰ it means very small loss rate!
- new versions of TCP for high-speed

TCP Fairness



fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K





Thanks!

Content of this PPT are taken from:

- 1) Computer Networks: A Top Down Approach, by J.F. Kuros and K.W. Ross, 6th Eds, 2013, Pearson Education.
- **2)** Data Communications and Networking, by B. A. Forouzan, 5th Eds, 2012, McGraw-Hill.
- **3)** Chapter **3**: Transport Layer, PowerPoint slides of "Computer Networking: A Top Down Approach", 6th Eds, J.F. Kurose, K.W. Ross