# Heat & Thermodynamics

#### Concepts in Thermal Physics

Stephen J. Blundell & Katherine M. Blundell


Chapter 11, 12, 13, 14, 16, 18.


## System and surroundings

A thermodynamic system is the part of the universe we are considering. Everything else is referred to as the surroundings.


We are free to define the 'system' anyway we chose. However, how we define it may determine whether we can successfully apply thermodynamics.

A thermodynamic system includes anything whose thermodynamic properties are of interest.





## Four kinds of 'systems'



State of a system is the condition of a system.


State variables: P, V, n, T

For ideal gas

$$PV = nRT$$

## Thermodynamic process

A thermodynamic process is a passage of a thermodynamic system from an initial to a final state.





## Thermodynamic process


- Isobaric: pressure of the system remains constant
- Isochoric: the volume of the system remains constant
- Isothermal: the temperature of the system remains constant
- Adiabatic: the amount of heat of the system remains constant

## Isothermal Process

It is a process in which Temprature remains Constant throughout the process.








## Zeroth Law of Thermodynamics

Two systems, each separately in thermal equilibrium with a third, are in equilibrium with each other.



## First Law of Thermodynamics

Energy is conserved and heat and work are both forms of energy.

$$\Delta U = \Delta Q + \Delta W$$

 $\Delta Q$  is the heat supplied to the system


 $\Delta W$  is the work done on the system

 $\Delta U$  is the change in internal energy of the system

## First Law of Thermodynamics

$$\mathrm{d}U = \mathrm{d}Q + \mathrm{d}W$$

$$dW = -p \, dV$$



## **Heat Capacity**

In general, the internal energy is a function of temperature and volume, so that we can write U = U(T, V).

Hence a small change in *U* can be related to changes in *T* and *V* by

$$dU = \left(\frac{\partial U}{\partial T}\right)_V dT + \left(\frac{\partial U}{\partial V}\right)_T dV$$

From first law of thermodynamics

$$dQ = dU + p dV$$

$$\frac{\mathrm{d}Q}{\mathrm{d}T} = \left(\frac{\partial U}{\partial T}\right)_V + \left[\left(\frac{\partial U}{\partial V}\right)_T + p\right] \frac{\mathrm{d}V}{\mathrm{d}T}$$

## **Heat Capacity**

$$\frac{\mathrm{d}Q}{\mathrm{d}T} = \left(\frac{\partial U}{\partial T}\right)_V + \left[\left(\frac{\partial U}{\partial V}\right)_T + p\right] \frac{\mathrm{d}V}{\mathrm{d}T}$$

Heat capacity at constant volume  $C_V = \left(\frac{\partial Q}{\partial T}\right)_V = \left(\frac{\partial U}{\partial T}\right)_V$ 

Heat capacity at constant pressure  $C_p = \left(\frac{\partial Q}{\partial T}\right)_m$ 

$$C_p - C_V = \left[ \left( \frac{\partial U}{\partial V} \right)_T + p \right] \left( \frac{\partial V}{\partial T} \right)_p \quad \boxed{\mathbf{J} \mathbf{K}^{-1}}$$

$$= \left(\frac{\partial U}{\partial T}\right)_V + \left[\left(\frac{\partial U}{\partial V}\right)_T + p\right] \left(\frac{\partial V}{\partial T}\right)_p$$

## Heat capacity of an ideal monatomic gas

For an ideal monatomic gas, the internal energy U is due to the kinetic energy and

$$U = \frac{3}{2}RT$$

This means that U is only a function of temperature.

Hence

$$\left(\frac{\partial U}{\partial V}\right)_T = 0.$$

The equation of state for 1 mole of ideal gas is pV = RT

$$\left(\frac{\partial V}{\partial T}\right)_p = \frac{R}{p}$$

$$C_p - C_V = \left[ \left( \frac{\partial U}{\partial V} \right)_T + p \right] \left( \frac{\partial V}{\partial T} \right)_p = R$$

$$C_V = \left(\frac{\partial U}{\partial T}\right)_V = \frac{3}{2}R$$
 per mole

$$C_p = C_V + R = \frac{5}{2}R$$
 per mole

The adiabatic index 
$$\gamma = \frac{C_p}{C_V} = \frac{5}{3}$$

#### Example 11.3

Is it always true that  $dU = C_V dT$ ?

Solution: No, in general eqn 11.10 and eqn 11.15 imply that


$$dU = C_V dT + \left(\frac{\partial U}{\partial V}\right)_T dV.$$


For an ideal gas,  $\left(\frac{\partial U}{\partial V}\right)_T = 0$  (eqn 11.22) so it is true that

$$\mathrm{d}U = C_V \,\mathrm{d}T,$$

but for non-ideal gases,  $\left(\frac{\partial U}{\partial V}\right)_T \neq 0$  and hence  $dU \neq C_v dT$ .

## An ideal gas expanding into vacuum to twice its original volume





Gas fills the container

## Reversible processes

A reversible process is a process in which the system and environment can be restored to exactly the same initial states that they were in before the process occurred, if we go backward along the path of the process. The necessary condition for a reversible process is therefore the quasistatic requirement. Note that it is quite easy to restore a system to its original state; the hard part is to have its environment restored to its original state at the same time. For example, an ideal gas expanding into vacuum to twice its original volume, we can easily push it back with a piston and restore its temperature and pressure by removing some heat from the gas. The problem is that we cannot do it without changing something in its surroundings, such as dumping some heat there.

## Irreversible processes

An irreversible process is a process in which the system and its environment cannot be restored to their original states at the same time. Because this is what happens in nature, it is also called a natural process. The sign of an irreversible process comes from the finite gradient between the states occurring in the actual process. For example, when heat flows from one object to another, there is a finite temperature difference (gradient) between the two objects. More importantly, at any given moment of the process, the system most likely is not at equilibrium or in a well-defined state. This phenomenon is called irreversibility.

The *reversible* process is the ideal process which rarely occurs, while the *irreversible process* is the natural process that is commonly found in nature.

We can make certain processes close to reversible and therefore use the consequences of the corresponding reversible processes as a starting point or reference. In reality, almost all processes are irreversible, and some properties of the environment are altered when the properties of the system are restored. The expansion of an ideal gas, as we have just outlined, is irreversible because the process is not even quasi-static, that is, not in an equilibrium state at any moment of the expansion.

# Isothermal expansion of an ideal gas

The word isothermal means 'at constant temperature', and hence in an isothermal process

$$\Delta T = 0.$$

$$dU = C_V dT = 0$$

$$dW = -dQ$$

$$dW = -p dV$$

$$\Delta Q = \int dQ = \int_{V_1}^{V_2} p \, dV = RT \ln \frac{V_2}{V_1}.$$

For an expansion,  $V_2 > V_1$ , and so  $\Delta Q > 0$ .

## Adiabatic expansion of an ideal gas

The word adiathermal means 'without flow of heat'. A system bounded by adiathermal walls is said to be thermally isolated. Any work done on such a system produces an adiathermal change. We define a change to be adiabatic if it is both adiathermal and reversible. In an adiabatic expansion, therefore, there is no flow of heat and we have

$$dQ = 0.$$

The first law of thermodynamics therefore implies that

$$\mathrm{d}U = \mathrm{d}W.$$

For an ideal gas,  $dU = C_V dT$ , and using dW = -p dV for a reversible change, we find that, for 1 mole of ideal gas,

$$C_V dT = -p dV = -\frac{RT}{V} dV,$$

so that

$$\ln \frac{T_2}{T_1} = -\frac{R}{C_V} \ln \frac{V_2}{V_1}.$$

Now  $C_p = C_V + R$ , and dividing this by  $C_V$  yields  $\gamma = C_p/C_V = 1 + R/C_V$ , and therefore  $-(R/C_V) = 1 - \gamma$ , so that

$$TV^{\gamma-1} = \text{constant},$$

or equivalently (using  $pV \propto T$  for an ideal gas)  $p^{1-\gamma}T^{\gamma} = \text{constant}$ 

$$pV^{\gamma} = \text{constant}$$

## Second Law of Thermodynamics

#### Clausius' statement of the second law of thermodynamics:

'No process is possible whose sole result is the transfer of heat from a colder to a hotter body.'


#### Kelvin's statement of the second law of thermodynamics:

'No process is possible whose sole result is the complete conversion of heat into work.'

## The Carnot engine

An engine is a system operating a cyclic process that converts heat into work. It has to be cyclic so that it can be continuously operated, producing a steady power.


The Carnot engine, which is based upon a process called a Carnot cycle.




## The Carnot engine

$$\eta_{
m Carnot} = rac{Q_{
m h} - Q_{\ell}}{Q_{
m h}}$$


T





#### Carnot's theorem:

Of all the heat engines working between two given temperatures, none is more efficient than a Carnot engine.





## The Entropy, S

Entropy is a thermodynamic quantity representing the unavailability of a system's thermal energy for conversion into mechanical work, often interpreted as the degree of disorder or randomness in the system.


Entropy is the measure of a system's thermal energy per unit temperature that is unavailable for doing useful work. Because work is obtained from ordered molecular motion, the amount of entropy is also a measure of the molecular disorder, or randomness, of a system.

## **Entropy & Disorder**





If you tossed bricks off a truck, which kind of pile of bricks would you more likely produce?



Disorder is more probable than order.



Assuming that the Universe can be treated as an isolated system, the first two laws of thermodynamics become:

- (1)  $U_{\text{Universe}} = \text{constant.}$
- (2)  $S_{\text{Universe}}$  can only increase.

### The first law revisited

$$\mathrm{d}U = \mathrm{d}Q + \mathrm{d}W$$

For a reversible change:

$$dQ = TdS$$

$$dW = -pdV$$

$$dU = TdS - pdV$$

always true

The internal energy is a function of entropy and volume, so that we can write U = U(S, V). Hence a small change in U can be related to changes in S and V by

$$dU = \left(\frac{\partial U}{\partial S}\right)_V dS + \left(\frac{\partial U}{\partial V}\right)_S dV$$

$$T = \left(\frac{\partial U}{\partial S}\right)_{V}$$

$$p = -\left(\frac{\partial U}{\partial V}\right)_{S}$$

## Thermodynamics Functions

Internal energy

Enthalpy

$$H = U + pV$$

Helmholtz function F = U - TS

$$F = U - TS$$

Gibbs function

$$G = H - TS$$

# Thermodynamics Functions

Function of state		Differential	Natural variables	First derivatives	
Internal energy	U	$\mathrm{d}U = T\mathrm{d}S - p\mathrm{d}V$	U = U(S, V)	$T = \left(\frac{\partial U}{\partial S}\right)_V,$	$p = -\left(\frac{\partial U}{\partial V}\right)_S$
Enthalpy	H = U + pV	$\mathrm{d}H = T\mathrm{d}S + V\mathrm{d}p$	H = H(S, p)	$T = \left(\frac{\partial H}{\partial S}\right)_p,$	$V = \left(\frac{\partial H}{\partial p}\right)_S$
Helmholtz function	F = U - TS	$\mathrm{d}F = -S\mathrm{d}T - p\mathrm{d}V$	F = F(T, V)	$S = -\left(\frac{\partial F}{\partial T}\right)_V,$	$p = -\left(\frac{\partial F}{\partial V}\right)_T$
Gibbs function	G = H - TS	$\mathrm{d}G = -S\mathrm{d}T + V\mathrm{d}p$	G = G(T, p)	$S = -\left(\frac{\partial G}{\partial T}\right)_p,$	$V = \left(\frac{\partial G}{\partial p}\right)_T$

## Maxwell's relation

If a state function f is a function of variables x and y then a change in f can be written as

 $\mathrm{d}f = \left(\frac{\partial f}{\partial x}\right)_{x} \mathrm{d}x + \left(\frac{\partial f}{\partial y}\right)_{x} \mathrm{d}y.$ 

Because df is an exact differential, we have  $\left(\frac{\partial^2 f}{\partial x \partial u}\right) = \left(\frac{\partial^2 f}{\partial u \partial x}\right)$ .

$$\left(\frac{\partial^2 f}{\partial x \partial y}\right) = \left(\frac{\partial^2 f}{\partial y \partial x}\right).$$

Hence writing

$$F_x = \left(\frac{\partial f}{\partial x}\right)_y$$
 and  $F_y = \left(\frac{\partial f}{\partial y}\right)_x$ ,

we have that

$$\left(\frac{\partial F_y}{\partial x}\right) = \left(\frac{\partial F_x}{\partial y}\right).$$

The Maxwell relation based on G can be derived as follows. We write down an expression for dG:

$$dG = -SdT + Vdp.$$

We can also write

$$dG = \left(\frac{\partial G}{\partial T}\right)_p dT + \left(\frac{\partial G}{\partial p}\right)_T dp,$$

and hence we can write  $S = -\left(\frac{\partial G}{\partial T}\right)_p$  and  $V = \left(\frac{\partial G}{\partial p}\right)_T$ .

Because dG is an exact differential, we have that

$$\left(\frac{\partial^2 G}{\partial T \partial P}\right) = \left(\frac{\partial^2 G}{\partial p \partial T}\right),\,$$

and hence we have the following Maxwell relation:

$$-\left(\frac{\partial S}{\partial p}\right)_T = \left(\frac{\partial V}{\partial T}\right)_p$$

#### Maxwell's relations:

$$\left(\frac{\partial T}{\partial V}\right)_{S} = -\left(\frac{\partial p}{\partial S}\right)_{V} \\
\left(\frac{\partial T}{\partial p}\right)_{S} = \left(\frac{\partial V}{\partial S}\right)_{p} \\
\left(\frac{\partial S}{\partial V}\right)_{T} = \left(\frac{\partial p}{\partial T}\right)_{V} \\
\left(\frac{\partial S}{\partial p}\right)_{T} = -\left(\frac{\partial V}{\partial T}\right)_{p}$$

## Third Law of Thermodynamics

#### Nernst's statement of the third law

Near absolute zero, all reactions in a system in internal equilibrium take place with no change in entropy.

#### Planck's statement of the third law

The entropy of all systems in internal equilibrium is the same at absolute zero, and may be taken to be zero.

#### Simon's statement of the third law

The contribution to the entropy of a system by each aspect of the system which is in internal thermodynamic equilibrium tends to zero as  $T \to 0$ .

## The Clausius-Clapeyron Equation

$$rac{dP_0}{dT} = rac{\Delta S}{\Delta V} \qquad \qquad rac{dP_0}{dT} = rac{Q_L}{T\Delta V}$$

The latent heat  $Q_L$  is the quantity of heat which is required to convert the substance from phase 1 to phase 2:

$$Q_L = T\Delta S$$
.

The ratio of the specific volume of water to that of ice is 1.000:1.091 at 0°C and 1 atm. The heat of melting is 80 cal/g. Calculate the slope of the melting curve.

The volume change upon melting if ice is  $V_{\rm L} - V_{\rm S} = (1.00 - 1.091) \, {\rm cm}^3/{\rm g} = -0.091 \, {\rm cm}^3 {\rm g}^{-1}$ . The latent heat of melting per g is  $Q = 80 \, {\rm cal/g} = 80 \times 42.7 \, {\rm atm} \, {\rm cm}^3/{\rm g}$ . From this, it follows that the slope of the melting curve of ice near  $0^{\circ}{\rm C}$  is

$$\frac{dP}{dT} = -\frac{80 \times 42.7}{273 \times 0.091} \frac{\text{atm}}{\text{K}} = -138 \,\text{atm/K} \ .$$