


Phase stabilities with path-dependence

Version 1 March 2019 (for help contact mjmayne@outlook.com)



Getting started

4
6
10
13
15
16
31
32
34
34

GETTING STARTED

Installation

Rcrust was developed using version 3.3.0 (2016-05-03) of R. Copyright © 2016 the R Foundation for Statistical Computing. To install Rcrust perform the following steps:

 Copy the Rcrust folder to a location of your choice (preferably a root directory for example C:\ or D:\). The result should be similar to the picture below with all the Rcrust files contained in single directory for example D:\\Rcrust\




Figure 1 - Rerust file structure located in the root directory D:\\Rerust\

Install a working version of R on your system (at least version 3.3.0). The latest version of R used in the development of Rcrust is located in the folder "R installs" for your convenience.
 Warning: Rcrust requires the 64 bit version of R. When installing R please ensure "64-bit Files" is ticked.





Figure 2 - R installation instruction ensuring at least "64-bit Files" is ticked

- *Alternatively newer versions of R (which may not be compatible with Rcrust) can be downloaded from http://www.r-project.org/ or for windows can be found directly at http://cran.r-project.org/bin/windows/base/
- 3. Open the folder called code in the Rcrust folder.



- 4. Copy the Rcrust file found in the code folder (~/Rcrust/code/Rcrust.RData). This can be done by right clicking on the file (circled in red above) and selecting "Copy" or by selecting the file and pressing "Ctrl"+"c".
- 5. Paste the Rcrust file as a **shortcut** on the Desktop. This can be done by right clicking on the Desktop and selecting "**Paste shortcut**".



Figure 4 – Paste shortcut option selected for Rcrust file

- 6. Rename this file to "Rcrust". Double click on this shortcut to open Rcrust.
- 7. Rcrust requires the R package called "shiny", If this is not installed on your computer when you open Rcrust, Rcrust will try to install it (this requires an internet connection). Follow the prompts to complete installation of the package (it may ask you if you wish to create a personal library choose yes). Alternatively, shiny can be downloaded here: http://shiny.rstudio.com/.

Each new project will be automatically saved in the "Projects" folder along with its associated inputs and outputs. To load a previously saved project simply double click the "xxx.RData" file in the associated project folder or open Rcrust from the desktop shortcut and load the project via the Rcrust GUI.

Concept

Rcrust is an R program aimed at modelling with path dependence. The program functions by calculating a number of points in P-T-X space where a bulk composition is passed between points. This creates path dependence as points within the path rely on the outcomes of previous points for their calculation. The bulk composition can be altered at each point by phase manipulations consisting of phase additions and/or phase extractions. Phase stabilities for each point are calculated by using a compiled form of Perple_X (Connolly & Kerrick, 1987; Connolly, 2005, 2009).

Rcrust manages calculations by splitting the full thermodynamic system (FS) into 3 subsystems: The reactive subsystem (RS) which contains the phases in thermodynamic equilibrium; The addition subsystem (AS) where phases are waiting to be added to the reactive subsystem; and the extract subsystem (ES) where phases extracted from the reactive subsystem are stored. The reactive subsystem is in thermodynamic equilibrium with the P-T-X conditions of each point and is reequilibrated after each P-T-X change. The addition and extract subsystems are in thermodynamic isolation from other subsystems and from the P-T-X conditions of each point.




Figure 5 - Relationships between systems (left) and flow chart (right) illustrating the Rcrust program structure for a single path. The user inputs the calculation's resolution, starting bulk composition, P-T path and phase manipulation settings. Each step in a path consists of two runs and an output. The first run is shown in a solid line, the second run in a dashed line and the outputs in a dotted line. Circles show the system or subsystem involved in each step as AS (addition subsystem), ES (extract subsystem), FS (full system) or RS (reactive subsystem). Arrows show interactions between systems. From (Mayne et al., 2016)

Parameters for calculations are accessible to the user via the Rcrust Graphical User Interface (GUI). This GUI writes data to a text file which is then input to the program thus allowing the user to edit the file 'behind' the GUI as well as save inputs for re-use. The code files are extensively commented, and described in this document. The calculations routines are defined in several files, written in a modular way that should allow easy addition of features if required. For example, the Phase Extraction routine has been modified to suit the needs of magma extraction where additional capabilities allow melt extraction to leave a set melt retention amount behind.




Figure 6 - Flow chart of the magma extraction routine. Grey hexagon shaped boxes are decision points. Coding variables are in italics. The for phase loop (dotted line) is repeated until each phase tagged for extraction has been considered. If Retention mode is active melt is considered last so that other phases extracted are accounted for in its calculation. From (Mayne et al., 2016)

Rcrust results should easily be loaded into GCDkit and examined from there.

It is important to remember a few things:

- Rcrust is in development. It is not mature software. It is very unstable at the best of times, and
 very unforgiving in terms of improperly formatted inputs, etc. When Rcrust fails, it will try to
 generate some human-readable error messages: read them! It may well give you hints at things
 you can correct in your inputs.
- Most of the errors you will see are related to incorrect input (files with incorrect number of lines etc.); or to exotic phases being produced by meemum.

Rcrust calls a set of binary files containing the thermodynamic equations thus relying on published databases (Holland and Powell typically). The output will never be better than the underlying thermodynamic model. Since we focus on melting, we are tied to the capacities (and limitations) of the melt models. For example, melt(HP) does not include Titanium therefore its use in a system containing Ti can over/under estimate melt abundance.

Examples

Below are 3 example simulations to get you started using Rcrust. All you need to do to complete the examples is to perform the actions written in bold numbered text. Explanations of what these actions achieve are given between steps.

Example1 - Simple

Follow the bold numbered steps

To begin the first example open Rcrust via the desktop shortcut.

1. Double click the Rcrust desktop shortcut

This will launch the R console and an empty Rcrust Graphical User Interface (GUI) in your default web browser. The "Working File" (circled in red) shows you which file is currently being worked on and the "Projects Directory" (circled in green) shows you where the projects folder is located. The Rcrust toolbar (in grey) contains buttons for file management.





Figure 7 -Rcrust GUI and R Console (blue). Highlighted are the positions of the Projects Directory (green), Working File (red) and Rcrust toolbar (black).

2. Type "Example1" into the text box on the right of Working File and then click the Load button from the Rerust toolbar

The data previously saved in the "Example1" file is now loaded into R and previously saved input parameters are loaded into the Rcrust GUI. To ensure that we do not overwrite any data lets rename the Working File.

3. Rename Example1 by typing "Example_simple" into the Working File textbox then click the Save button from the Rcrust toolbar

This will save the current Rcrust GUI inputs into a new file named "Example_simple". The Rcrust GUI should now look similar to Figure 8.



 $Figure~8-Rcrust~GUI~with~Example1~(Example_simple)~parameters~loaded.~The~GUI~consists~of~a~number~of~tabs.\\ The~Input~Parameters~tab~sets~the~size,~P-T~conditions~and~bulk~composition~(X)~of~the~simulation.$

This example calculates the phases encountered at points in P-T-X space. Input parameters are grouped into collapsible panels:

Size Panel

The **Size** panel sets the number of points in the simulation (here 4 points in the **X** direction multiplied by 3 in the **Y** direction). Points in the simulation space are identified by **tuples** written as $\{x_i : y_i\}$ where i denotes the current point.




Figure 9 – Simulation space with point coordinates defined by tuples $\{x_i\ ;\ y_i\}$

• Pressure and Temperature Panel

Parameters in the simulation space are filled by a number of definitions. Each unique definition is applied over a range between the tuples $From \{ x_a ; y_a \}$ and $To \{ x_b ; y_b \}$ where a and b denote the start and end points of a rectangular range. Each definition sets its attributes as constants or as functions of the point's position. X and Y positions of points are accessed by the variables x_i and y_i respectively. In the **Pressure and Temperature Panel** we set the Pressure in kilobars and

Temperature in degrees Celsius for each point. In this example **Pressure** decreases along the y-axis by 1 kbar per point (7-y_i) and **Temperature** increases along the x-axis by 20 °C per point (670+x_i*20).

• Bulk Composition Panel

The **bulk composition** of the system is made up of a number of major elements expressed as wt.% elemental oxides. For this simple example we define the bulk composition to be constant across the full P-T space, and we give it the value of the average amphibolite-facies pelite composition considered in (Mayne et al., 2016).

	Na ₂ O	MgO	Al_2O_3	SiO ₂	K_2O	CaO	TiO_2	FeO	O_2	H_2O
wt.%	1.82	3.28	20.45	56.97	4.09	1.56	1.05	8.5	0.62	1.96
Table 1 -	- Average	amphibol	ite facies _l	pelite com	position	considered	l in (Mayı	ne et al., 2	016).	

To get started let's run a reconnaissance simulation:

4. Click the Run button from the Rcrust toolbar

This will save inputs in the Rcrust GUI and launch the calculation procedure into the R console. The R console should now have a few lines of text in it (like the figure below). If your simulation successfully initialized, then it will print out the "Initiation successful" message and begin the calculation (highlighted in red). If your console failed to initialize the program try reloading the original "Example1" file by closing Rcrust then starting from step 1 again, if problems persist try reinstalling Rcrust or report the problem to the developers (mjmayne@outlook.com). The calculation will run for 12 points :4 in the X direction by 3 in the Y direction. The results will automatically be saved to file and you will be prompted to select outputs.



Figure 10 - The Rcrust calculation is launched into the R Console if initiation is successful the message "Initiation successful" is printed and the calculation will begin.

Once the calculation is complete, navigate back to the Rcrust GUI and Select the Outputs tab

Here we see a compilation data file for the points in our simulation. To compare points, click the "Select Output" drop down and choose "Grid".

6. Choose "Grid" under "Select Output"

Grid allows easy comparisons between points for example choose:

- Select Output = Grid
 - o Variable = wt% and Melt_rs

7. Choose Variable="wt%" and "Melt_rs"

The output should now match Figure 11. This shows us the amount of melt in the Reactive Subsystem (RS) over our point selection in P-T-X space. For further outputs you can deal directly with the data in the R console (hint: you can plot data directly into GCDkit). To access the data in R console, click the "Console" button on the Rcrust toolbar to launch a browser access. To return to the Rgui at any point type "c" then press [enter].

Melt	_rs wt%	on (X,	Y) grid	
	V1	V2	V3	V4
1	6.88	19.40	22.34	25.80
2	14.09	15.66	19.08	21.91
3	4.81	14 23	15.82	17.61

Figure 11 – Grid output Data for Example_simple showing weight percentage of melt in the reactive subsystem for the P-T-X points selected

To view a graphical output of this data toggle the "View" selection to "Plot". This will plot a filled contour graph of the selected data which can be saved directly as a .ps file through the "Save To File" button at the bottom of the selection panel.

8. Toggle the "View" selection from "Data" to "Plot" and choose "Bottom Axis" as "Temperature", "Left Axis" as "Pressure"




Figure 12 – Grid output Plot for Example_simple showing weight percentage of melt in the reactive subsystem for the P-T-X points selected as a filled contour plot

Example2 - Phase extraction

Phase extractions can remove phases from the reactive subsystem. This is used to simulate scenarios such as melt loss or fractional crystallization.




Figure 13 – Example of melt extraction along a P-T-X path from (Mayne et al., 2016): Weight percentage of phases verses temperature in degrees Celsius for a fixed pressure of 12 kbar. Starting composition taken as an average amphibolite facies pelite (Table 1). Melt is extracted whenever a 7 vol.% threshold is met.

Let's perform melt extraction along a path in the P-T-X space explored by Example1.

Load Example by opening Rcrust, typing 'Example 2' in working file and clicking "Load"

To ensure that we do not overwrite any data lets rename the Working File.

2. Rename the file by typing "Example_extract" into Working File then click the Save button from the Rcrust toolbar

This will save the current Rcrust GUI inputs into a new file named "Example_extract". The Rcrust GUI should now look like the images below:




Figure 14 - Rcrust GUI inputs for Example_extract

This example calculates an open system dependent path in P-T-X space. The bulk composition of the Reactive Subsystem is altered by phase manipulations encountered along the path. Phase Manipulations are grouped into collapsible panels:

Phase Addition

Phases such as intruding fluids, segregated melts or residual crystals can be incorporated into the reactive subsystem. These additions are defined by the major elemental oxides chosen in "Bulk composition".

• Phase Extraction

Phases in the reactive subsystem can be extracted when set conditions are met. These conditions are defined as logical arguments such as "TRUE"/"FALSE" to extract for every point/no points respectively. Alternatively a logical argument can be built of the form "phase, operand, value, unit" where phase = name of the phase/solution model, operand = (<,<=,==,>=,>,!=), value = a number and unit = the phase property to test. In this example we want to trigger extraction whenever a melt threshold is reached so our conditional argument is "Melt,>=,7,wt%". Note that each argument in the condition is separated by a comma.

When the condition is met phase extraction is triggered on the reactive subsystem. For each phase listed in **Phases for Extraction** we need to define the amount of the phase to extract. This can be a numeric value (interpreted as mass relative to the starting mass defined in the Bulk Composition Panel), or a percentage of the current value. In this example we extract all melt (100%).



Figure 15 - Phase extraction definition for Example_extract

To save you time we have pre-run this calculation so you can directly view the results by selecting the **Outputs** tab.

3. Select the Outputs tab in the Rcrust GUI

A custom output selection is available for viewing phase abundances along a path.

4. Choose "Phase Abundance Along Path" under "Select Output"

Here you can select which axis the path traverses (axis), which path you wish to consider (path), select the (Start Point) and (End Point) of the path and add a label for the column names.

5. Set "End Point" as 25

The output should now match Figure 16.

	1	2	3	4	5	6	7	8	9	10	- 11	12	13	14	15	16	17	18	19	20	21	22	23	24	25
Melt_rs	3.75	4.01	4.38	4.63	5.04	0.00	0.00	0.00	0.00	0.00	0.00	0.28	0.62	0.95	1.43	1.84	2.39	3.04	3.76	0.00	0.89	1.66	2.63	3.28	3.37
Mica_rs	22.88	22.32	21.75	21.33	20.59	19.79	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00
Bio_rs	13.37	13.51	13.64	13.72	13.97	14.15	14.41	14.42	14.42	14.41	14.41	13.80	13.02	12.30	11.38	10.51	9.50	8.27	6.99	5.79	4.11	2.71	1.07	0.00	0.00
Pl_rs	12.48	13.01	13.48	13.77	14.27	14.83	3.52	3.35	3.37	3.54	3.95	3.81	3.49	3.31	2.93	2.82	2.40	1.80	1.16	0.84	0.18	0.00	0.00	0.00	0.00
Cpx_rs	6.33	5.99	5.65	5.44	5.09	4.71	7.57	7.57	7.55	7.41	7.09	6.92	6.81	6.63	6.49	6.27	6.16	6.10	5.93	5.88	5.76	5.52	5.12	4.86	4.82
llm_rs	7.39	7.44	7.48	7.48	7.53	7.58	7.32	7.33	7.34	7.37	7.40	7.45	7.47	7.52	7.55	7.61	7.64	7.69	7.74	7.79	7.85	7.93	8.01	8.08	8.08
ky_rs	9.38	9.38	9.43	9.54	9.52	9.61	17.45	17.44	17.43	17.40	17.24	17.12	17.02	16.87	16.69	16.52	16.37	18.22	16.01	15.85	15.58	15.32	14.98	14.72	14.69
q_rs	24.47	24.35	24.20	24.08	23.99	23.80	19.98	19.98	19.98	19.95	19.93	19.68	19.34	19.04	18.62	18.26	17.82	17.27	16.70	16.13	15.40	14.77	14.00	13.50	13.47
Kf_rs	0.00	0.00	0.00	0.00	0.00	0.00	14.74	14.93	14.92	14.91	14.88	15.30	15.84	18.32	16.98	17.44	18.11	18.97	19.94	20.72	21.62	22.28	22.91	23.31	23.30
Gt_rs	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.10	0.67	1.40	2.05	2.94	3.71	4.61	5.63	6.77	7.74	9.16	10.37	11.84	12.78	12.80
Bulk_rs	100.00	100.00	100.00	100.00	100.00	94.45	85.00	85.00	85.00	85.00	85.00	85.00	85.00	85.00	85.00	85.00	85.00	85.00	85.00	80.54	80.54	80.54	80.54	80.54	80.54
Melt_es	0.00	0.00	0.00	0.00	0.00	5.54	9.45	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	4.48	0.00	0.00	0.00	0.00	0.00
Bulk_es	0.00	0.00	0.00	0.00	0.00	5.54	9.45	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	4.48	0.00	0.00	0.00	0.00	0.00
Melt_es_cumul	0.00	0.00	0.00	0.00	0.00	5.54	14.98	14.98	14.98	14.98	14.98	14.98	14.98	14.98	14.98	14.98	14.98	14.98	14.98	19.45	19.45	19.45	19.45	19.45	19.45
Bulk_es_cumul	0.00	0.00	0.00	0.00	0.00	5.54	14.98	14.98	14.98	14.98	14.98	14.98	14.98	14.98	14.98	14.98	14.98	14.98	14.98	19.45	19.45	19.45	19.45	19.45	19.45

Phase adundance vs Point for {1;1} to {25;1}




Figure 16 – Phase Abundance Along Path output for Example_extract showing mass of each phase in the full system (FS) across the P-T-X points selected.

This output highlights a few key features of the phase extraction function:

- Outputs in the Phase Abundance along path plotter are expressed as wt.%
- The second melt extraction event extracts more than 7 vol.% melt (relative to the full system)(red box) even though the melt extraction threshold was set to be 7 vol.%

Reason -> Evaluations are only performed at each point thus if the resolution (number of points) is low then large changes can occur between each point.

 Subsequent melt extraction events may appear less than the melt extraction threshold (green boxes)

Reason -> The melt extraction threshold is evaluated relative to the Reactive Subsystem (which itself is shrinking due to melt extraction events) thus equivalent proportions of melt equate to different proportions when compared to the full system (FS).

Example3 - Multi-path functionality

Multiple paths can be compiled in P-T-X space to produce path-dependent P-T mode diagrams. In these diagrams a plane in P-T space is filled with points originating from dependent paths.




Figure 17 – Example of a composite path-dependent P-T mode diagram from (Mayne et al., 2016): Colours scale the weight percentage of melt in the reactive subsystem (RS). Starting composition at 640 °C and 12 kbar taken as an average amphibolite facies pelite (Table 1). Melt is extracted whenever a 7 wt.% threshold is met and leaves behind 1 wt.% approximating melt retention on grain boundaries. The simulation space is filled by a number of isothermal decompression paths that each originate off a 12 kbar isobaric heating path.

Let's create a path-dependent P-T mode diagram by decompressing off of the path investigated in Example2.

1. Load Example 3 by opening Rcrust, typing 'Example 3' in working file and clicking "Load"

To ensure that we do not overwrite any data lets rename the Working File.

2. Rename the file by typing "Example_multi" into Working File then click the Save button from the Rcrust toolbar

This will save the current Rcrust GUI inputs into a new file named "Example_multi". The Rcrust GUI should now look like Figure 18.




Figure 18 - Rcrust GUI inputs for Example_multi

This example creates a composite path-dependent P-T mode diagram. It does this by first calculating an open system isobaric heating path at 12 kbar (IBH12) and then calculating a number of isothermal decompression paths that each originate from a point on IBH12. Points along IBH12 are each dependent on the reactive subsystem of the point one to the left of itself on the x-axis. Points along decompression paths are each dependent on the point one above itself on the y-axis. Melt loss is

defined to occur whenever a 7 vol.% melt threshold is met and melt is extracted until 1 wt.% melt is left behind (this is achieved using the "retain(amount,unit)" function).





Figure 19 - Grid output for Example_multi showing volume percent of melt in the reactive subsystem (RS)



 $Figure\ 20-Phase\ assemblage\ map\ for\ Example_multi\ labelling\ fields\ by\ phase\ assemblage$

REFERENCE MANUAL

Rcrust File Management

The top line of the Rcrust GUI hosts a toolbar of file management buttons. User inputs are saved in a text document (**Working File**) which is located in the Projects folder of Rcrust (**Projects Directory**). This file is written, read or run in Rcrust by the **Save**, **Load** and **Run** buttons.



Save

Saves the **Working File's** inputs and calculation results. Each working file is assigned its own project folder in the **Projects Directory**. Parameters currently in the Rcrust GUI are saved to the Inputs folder as a text document. Additional parameters can be passed to Rcrust by placing them in the text document after the line (# Additional Parameters). Calculation results are saved as an R workspace in the project folder.

Load

Loads the **Working File's** inputs and calculation results. Reads the working file from the inputs folder and loads its options in the Rcrust GUI. Replaces the current workspace with that of the **Working File's**.

Run

Saves the current Rcrust GUI inputs and runs the Rcrust calculation according to these parameters. Follow prompts in the R console to calculate the results. Once the results are complete you will be prompted to select outputs through the Rcrust GUI. Outputs written to file are saved in the Ouputs folder of the project Advanced users can access the results directly in the R console by pressing [esc] to activate the console (this is helpful for loading data into GCDkit). To relaunch the Rcrust GUI type 'runApp()' then press [Enter]

Clear

Clears current values in the Rcrust GUI

Console

Launches a browser in the R console giving you direct access to the coding environment and all calculated data

List of Parameters

User inputs are listed here in a systematic fashion for clarity. The parameter name (the name that appears in the Rcrust GUI) is listed first followed by the variable name (the name of the variable accessible in the R console). The data type required for the parameter is listed in the second box. The third box contains possible values for the parameter and identifies any default value. Below this is a description as to what the parameter controls.

Parame	eter name	Data type	Possible values	
Example Parameter	Integer		0 = closed	
{ex_par}	{ex_par} Variable name			
			Default = 0	
Example definition for the	parameter		R	
Par	ameter description		Default value	
Input Paramete	ers			
Tuple definitions				
From		Tuple	{1;1}<=	
{pt_from_#}			pt_from_#<={x_n;y_n}	
	The beginning of the o	definition selection	l	
То	Tuple		pt_from_#<=pt_to_#<={x_n;y_n}	
{pt_to_#}				
The end of the definition s	selection			
Size				
Specify here the size of the and Y directions.	e simulation (resolution	on) you want to ca	lculate: how many points in the X	

Y	Numeric	1< y_n
{y_n}		
The total number of points in the	Y direction	

Pressu	re and Ten	nperature			
		Temperature T definitions			
	From {1;1}	To {19;11}	Pressure (kbar) 12-(y_i-1)*0.3	Temperature (C) 660+(x_i-1)*10	
Number of PT d {n_pt_def}	lefinitions	Nun	neric	1< n_pt_def	
The number of o	definitions to	o use for as	signing pressure a	nd temperature values	

Pressure (kbar)	Numeric/Expression	0 <p< th=""></p<>
{pressure_#}		
The pressure in kilobars of the	Reactive Subsystem (RS) *(1 kba	r = 0.1 GPa = 986.92 atm

The pressure in kilobars of the Reactive Subsystem (RS). *(1 kbar = 0.1 GPa = 986,92 atm). This can be a constant or an expression built using the variables x_i, y_i, real numbers and Arithmetic Operators. e.g. 12-(y_i-1)*0.3 to decompress along the y-axis by 0.3kbar per step starting at 12 kbar.

Temperature (°C)	Numeric/Expression	0 <t< th=""></t<>
{temperature_#}		

The temperature in degrees Celsius of the Reactive Subsystem (RS). $*(1 \, ^{\circ}\text{C} = 274.15 \, \text{K} = 33.8 \, ^{\circ}\text{F})$ This can be a constant or an expression built using the variables x_i , y_i , real numbers and Arithmetic Operators. e.g. $660+(x_i-1)*50$ to heat along the x-axis by $50 \, ^{\circ}\text{C}$ per step starting at $660 \, ^{\circ}\text{C}$.

PT definition	String	Options: input				
{pt_def}						
Advanced setting toggling the PT definition mode. Used to allow PT definition from file. *pt						
definition from file still to come						

{pt_definitions}	Listed Definition						
Pressure and temperature definitions of the form							
pt_definitions<-list("{x_a,y_a}_{x_b,y_b}"=c("pressure_#","temperature_#"),							
$\{x_a,y_a\}_{x_b,y_b}=c(\text{"press})$							

Additional Settings (main.r)

{PT_restrictions}	Comma-separated-strings			
P-T conditions which should not be calculated. Use if projecting array through array where points				
should be ignored				

Bulk	compos	itior

1	mponent Transfo	
100		
Replace component	New	NA2O,MGO,AL2O3,SIO2,K2O,CAO,TIO2,MNO,FEO,NIO,ZRO2,CL2,O2,H2O,C
O2	component	0.0.0,0,0,0,0,0,0,0,0,0,0,0,0
02	O.	
Major element	ta .	
NAZO MGO		O CAO TIO2 FEO O H2O
	AL203 SIO2 K2	O CAO TIO2 FED O H2O
Number of but	AL203 SIO2 K2	0 CAO TI02 FED O H20
	AL203 SIO2 K2	O CAO TIOZ FED O H2O
Number of but	AL203 SIO2 K2	O CAO TIO2 FED O HIDO NAZO MIDO ALZOS SIOZ XZO, CAO, TIOZ FED, O HIZO, MINIS
Number of bul 2	AL203 SIO2 K2	
Number of bul 2 From	AL203 SIG2 K2 lk definitions	NA2O,MGO AL 203, SIO2,K2O,CAO,TIO2,FEO,O,M2O,mass

Number of Component	Numeric	0<= n_comp_trans
Transformations		_
{n_comp_trans}		
TC1 1 C	C 1	.1 .1.1.1

The number of component transformations to apply to the currently available chemical components: the possible components for transformation are set by the thermodynamic data file

Replace component	String	
{old_comp_#}		
The current component to repla	ace	

New component	String	<6 characters, All capitals
{new_comp_#}		
The many of the many common and	This manner must a maint of lane	

The name of the new component. This name must consist of less than 6 characters and must be all in capital letters.

NA2O,MGO,	Comma-separated numeric
{comp #}	

The value of the new component as a factor of the available components:. This must be a string of comma separated numbers of which a total of no-more-than 11 can be non-zero. For example, if we wish to use the component O instead of O2 and our starting chemical components are NA2O,MGO,AL2O3,SIO2,K2O,CAO,TIO2,MNO,FEO,NIO,ZRO2,CL2,02,H2O,C02 we would use: 0,0,0,0,0,0,0,0,0,0,0,0,0,0,0 If we wish to use FE2O3 we would use: 0,0,0,0,0,0,0,0,0,0,0,0,0,0,0,0

Major elements	Comma-separated-strings	
{major_elements}		
The major element components u	sed to define the bulk composition.	

Number of bulk definitions {n_bulk_def}	Numeric	1<= n_bulk_def
The number of definitions to use for assigning bulk compositional values.		

NA2O,MGO,,mass	Comma-separated-	e.g. 1.5, 20.2, 40.8, 100
	values/expressions	e.g. $rs\{x_i-1;y_i\}$

The wt.% of each elemental oxide listed in "Major elements" (above) as well as the relative starting mass (in grams) of the Reactive Subsystem (RS).

Expressions can use real numbers, Arithmetic Operators, x_i , y_i , x_n , y_n and any tuples of the form $xs\{\#,\#\}$ where xs is any of rs, as, a


If $xs\{\#;\#\}$ is of length 1 it will be repeated to fill the required terms.

i.e. To make the full bulk composition of one point dependent on another first initialise the starting composition and then set the dependent points as $rs\{x_i-1; y_i\}$ for dependence on the x-axis or $rs\{x_i, y_i-1\}$ for dependence on the y-axis

Import definitions from file	Boolean	TRUE = Import from file
{bulk_def_file}		FALSE = definition via input
Choose whether bulk definition	s are read from input or importe	d from a text file (.txt) located in the
Inputs folder		

Bulk file	Character string	e.g. bulk.txt
{bulk_file}		

The name of the input file containing the bulk composition definitions (the name must end with .txt). The bulk file must be a tab delimited text file (.txt) containing the columns "From", "To", your selection of major elements and "Mass". For example:



This text file can be easily exported from an excel file using File\Save As\Text (tab delimited) (*.txt)



The input file must provide bulk definitions for all points in the chosen modelling space $\{x_n; y_n\}$ with numbers in the "From" and "To" arguments separated by a semicolon (;).

The bulk definitions describe the wt.% of each elemental oxide as well as the relative starting mass (in grams) of the Reactive Subsystem (RS). Expressions can use real numbers, r operators, x_i , y_i , x_n , y_n and any tuples of the form $xs\{\#;\#\}$ where xs is any of rs,as,es,fs and # uses real numbers, r operators, x_i , y_i , x_n and/or y_n

Phase Manipulations

Phase Addition



Perform Phase Addition?	Boolean	TRUE/FALSE
{ph_add}		
Add phases/components into th	e Reactive Subsystem (RS) at sp	pecified points?

Number of addition	Numeric	
definitions		
{n_ph_add_def}		
The number of definitions to u	se for assigning phase additions.	

Condition	Logical/expression	Options:
{ph_add_con_#}		TRUE
		FALSE
		ph{Melt,vol%}>=7

A conditional argument that evaluates to a Boolean answer of TRUE or FALSE. Note: if directly providing argument as TRUE or FALSE ensure all capitals.

For example to add phases whenever melt exceeds a 7 vol% threshold you would use the following condition: $ph\{Melt,vol\%\} >= 7$ if "Melt" is the alias assigned in the solution model file used

Phases for addition	Comma-separated-strings	
{ph_add_phs_#}		

Phases to be considered for phase addition in each definition. This can be any name as it is only the respective chemical components that are added to the system not the phase itself, thus the phase name is just a place holder for the user to remember what they are adding.

#,#,mass	Comma-separated-values	
TT1 - + 0/ C 1 1	4 1 '1 1' 4 1' 60 6 ' 1	4 22 (TD - 11 - '4' 4 1) 11

The wt.% of each elemental oxide listed in "Major elements" (Bulk composition tab) as well as the relative mass (in grams) of the phases/components to add.

	Phase Extra	action				
	Number of ext	ase Extraction?	system after phase extraction?			
	1					
	From	То	Condition	Phases		
	{1;1}	{4;1}	ph{Melt,wt%}>=7	Melt		
	Melt					
	retain{2,wt%}					
Perfo	rm Phase Extra	ction?	Boolean		TRUE/FALSE	<u> </u>
ph_e		1 5	Subsystem (RS) when s	101 1		
sub ext {re	-equilibrate reactory cosystem after pharaction? eequilibrate_step	nase ps}	Boolean		TRUE/FALSE	•
Us	e the bulk comp	position at the	he end of extraction to re-	calculate ph	ase stabilities	
	imber of extract	ion	Numeric			
	_ph_extr_def}	C::4:	use for assigning phase ex			
1 11	e number of de	imuons to	use for assigning phase e.	xtractions.		
	Condition {ph_extr_con	n_#}	Logical/expression		Options: TRUE FALSE ph{Melt,vol%	}>=7
			hat evaluates to a Boolea g argument as TRUE or l		TRUE or FAL	
	Expressions s	should be of	the form described in "E	Extraction ex	xpressions" belo	w.
			nases whenever melt exce Melt,vol%}>=7 if "Melt'			

Phases for extraction	Comma-separated-strings	
{ph_extr_phs_#}		
Phases to be considered	for phase extraction in each def	inition. These can be any alias in the
solution model file chos	en (Phase Models tab) or any pu	are phase output by Perple_X (see
Perple_X		
http://www.perplex.et	hz.ch/	
Perple_X Solution Mod	el Glossary) and THERMOCA	LC's list of mineral abbreviations).
*Can use "any phase" t	o set generic arguments	

[Phase extraction	Numeric / percentage /	e.g.
proportions]	expression	10%
{ph_extr_phs_#_phase}		5 (mass relative to a starting
		mass of 100 for the full system)
		retain{2;vol%;Melt}
		delta{Melt; x_i-1; y_i; mass}*0.5

Define the proportion of phase to extract for each phase listed in "Phases for extraction". Proportions can be given as:

 A percentage of what is present (e.g. 10%) *you must include the percentage sign for this

or

2. A set mass relative to the full system (100). If this amount is larger than what is present the full amount of the present phase will be extracted.

or

3. As functions of the form described in "Extraction expressions" below.

*Can use "any_phase" to set generic arguments for all phases that are present but don't already have a phase extraction proportion set i.e. pre existing definitions take precedence.

Extraction	Numeric / percentage /	
expressions	expression	

Extraction expressions can be evaluated for conditions or proportions consisting of x_i , y_i , real numbers, Arithmetic Operators, Logical Operators, $\{\}$ and $\{\}$ separate terms for calculation order and $\{\}$ are reserved for solution model names.

The following functions can be called by placing the function name before {} with function terms inside the brackets separated by commas (,) or semi-colons (;).

- retain{amount; unit; phase}
 - Retention extracts all but a set amount of a phase from the reactive subsystem
 where unit can be "mass", "wt%" or "vol%". In phase proportion boxes can
 omit "phase" to extract current phase.
 - e.g. retain{2;vol%;Melt} will extract melt from the reactive subsystem until 2 vol% of melt remains, this is useful for approximating melt retention on grain boundaries. This can also be written as retain{2;vol%}
 - *Warning: when utilising multiple phase extraction definitions ensure that the retention definition is last in order to retain to the finalised bulk.
- delta{phase; x_a; y_a; unit}
 - Delta calculates the incremental difference of a phase between the current point (point b) and a previous point (point a) such that:

delta=phase_mode_b - phase_mode_a.

*point a may be described as "prev_ext_X" where X is the name of any phase or "prev_ext" to use the name of the extracting phase as default

 phase = phase for extraction; x_a and y_a describe the position of the previous calculated point and unit is one of "mass" or "wt%". *phase may be described with "+" separating individual phase terms e.g. to calculate deltas for the alumina silicates phase would be "ky+and+sill"

- e.g. delta{Melt; x_i-1; y_i; mass}*0.5 to extract half of the delta mass for Melt when paths progress with increasing x_i values.
- $\bullet \quad ph\{phase;unit;x_i;y_i\}$
 - returns the requested variable (unit) for the given phase in the reactive subsystem. Where unit can be any column name in calc_phases and x_i and y_i are the current point by default, if ph{} is only given two arguments the current point will be evaluated by default.

Modelling Options Modelling Data Meemum version Perple_X Option File Thermodynamic Data File Solution Models File Bi(W) Cpx(HP) Crd(W) Ep(HP11) Fsp(C1) Gt(W) Ilm(WPH) melt(W) Mica(W) Opx(W) Sp(WPC) St(W) Meemum version String Example = meemum.exe {meemum_path} The name of the meemum executable to be used in ~Rcrust/data for phase stability calculations. Perple_X Option File Strings Example = perplex_option.dat {perplex_option_file} The perplex option file present in ~Rcrust/data which controls extra settings for phase stability calculations. Thermodynamic Data File Example = hp11ver.dat String {thermodynamic_data_file} The thermodynamic data file present in ~Rcrust/data to be used for phase stability calculations. Solution Models File String $Example = solution_model_673.dat$ {solution_models_file}

Solution models Comma-separated-strings {use_sol_models}

The solution models to use in phase stability calculations sourced from the Solution Models File. (see Perple_X

The solution model file present in ~Rcrust/data from which solution models can be chosen.

http://www.perplex.ethz.ch/

Perple_X Solution Model Glossary)

Additional optional parameters

Additional optional parameters			
Saturated components			
Saturated phase components	Saturated phase components		
Independent potential/fugacity/activity			
Exclude phases			
Saturated components	String		
{saturated_components}	2		
Set saturated components			
Saturated phase components	String		
{saturated_phase_components}			
Set saturated phase components			
•			
T. I			
Independent potential/fugacity/{ {independent_potential_fugacit			
Set independent potentials fuga			
Set macpendent potentials raga	enes of dedivines		
Exclude phases	String		
{exclude_phases}	consideration during Cibbs and	ary minimisation	
Set phases to be excluded from	consideration during Gibbs ener	rgy minimisation	
Extra Settings			
Extra Settings			
When calculation is complete:		.	
When calculation is	String	Options:	
complete:		Return to interface	
{end_of_calc}		Logout	
		Shutdown	
		Default = Return to interface	
Action to be performed when a	calculation is complete.		


Outputs

Phase Aliases	Comma separated strings	e.g. TiBio(HP)=Bt,Gt(WPH)=Gt
{ phase_aliases}		
A list of aliases to use for renaming phases of the form TiBio(HP)=Bt,Gt(WPH)=Gt,etc.		
To hide a phase from plotting use the alias "hide" e.g. TiBio(HP)=hide.		

Commented [MM1]: Explain mergers


Select Output = Data File


View the output data as a single filtered table



Select Output = Grid

View the output data by selecting a single variable to express on a grid of x_i and y_i coordinates. Contour plotting can be achieved by selecting View>Plot.






Select Output = Phase Abundance Along Path


View phase abundance data by weight along a path in the x or y direction.

Phase abundance graphs can be viewed as 100% stacked column graphs by selecting View>Plot



Select Output = PAM

Create a phase assemblage map by merging fields in x-y space with identical assemblages.



File Management

Functions for file management. See Rcrust File management for more details

Projects Directory	String	
{projects_directory}		
Absolute location of the projects	directory within the Rcrust folder.	

Working File {working_file}	String	
Name of the current file under on	aration Each file has its own folder	r within the projects directory

Name of the current file under operation. Each file has its own folder within the projects directory containing results of simulations (#.RData file), "Inputs" and "Outputs".

Save	Function call	
{on_save}		
Saves the current GUI inputs and workspace to the working_file.		

Load	Function call	
{on_load}		
Loads the previously saved worki	ng_file into the GUI inputs and wo	rkspace.

Run	Function call	
{manual_load}		
Saves the current GUI inputs and workspace to the working_file. Then launches the Rcrust		
calculation		

Clear	Function call	
{on_clear}		
Clears the current GUI inputs and workspace.		

Console {stopApp}	Function call	
Closes the current GUI to allow interaction with the R console. To relaunch the Rcrust GUI type		

Closes the current GUI to allow interaction with the R console. To relaunch the Rcrust GUI type 'runApp()' then press [Enter].

Perple_x options

Options parsed to wrapper calculation set in init_meem.r

Number of chemical	Integer	Default = 15
components		
{number_components}		
The number of chemical components to build the major elements from		

Unit for bulk	Integer	0 = molar %
composition	_	1 = weight %
definition		Default = 1
The unit proportion to use for bulk composition definition.		

Advanced user options
Static variable options accessible through main.r

Calculation mode	Character vector	normal
{calc_mode}		Default = normal
Advanced setting toggling the calculation mode.		

Reaction buffering {reaction_buffering}	Boolean	T (TRUE) F (FALSE) Default = FALSE
		Deragre Theor

Allows reaction buffering (threshold buffering) whereby phase extractions set on conditions are postponed by the number of reaction buffer steps to ensure continued exceedance of the threshold.

Useful functions in the R Console

c Continue steps in a browser (if accessed by clicking "Console" in the Rcrust GUI then closes the browser and returns to the Rcrust GUI)

ls() List all objects in the current environment

ls(envir=.GlobalEnv) List all objects in the global environment

Q() Quits the current session

[Ctrl]+[w] Toggles buffering of outputs

Rcrust () Manually launches the Rcrust GUI

To access the R console out of a browser click anywhere in the R console window and press [esc]. This will close the Rcrust GUI which has current control over the console. To relaunch the Rcrust GUI at any time simply type runApp() and press [enter].

Rcrust variables

PT[[bulk]][[step]]\$press\$temp	list
List of pressure and temperature conditions for each step in each bulk	

crust[[bulk]][[step]][phase,detail]

lıst

The full system (FS). Contains details of the reactive subsystem (RS) at each step along with cumulative extract (ES) and addition (AS) subsystems. Phases in crust are reported as cumulative weighted averages.

c0[detail]	vector
Bulk composition passed between points	

workingfile	Character vector
The current Working File	

work_dir	Character vector
The current Working Directory. This is the location of the folder containing the Wo	rking File

Running Rcrust

<u> </u>		
Relaunch GUI	Function call	
{.First()} or {Rcrust()}		
Relaunches the Rcrust GUI from	the R console	

Manually initiate calculation {manual_load}	Function call	
Sends the current working file to	be calculated	

Rcrust Outputs

Data file	Function call	
{data_file()}		

Compiles calculation results into a table Write data file Function call {write_data_file} Writes compilation table to file Grid data Function call {grid_data()} Compiles an X Y grid of the values of a given variable Write grid file Function call {write_grid_file} Writes X Y grid to file R Syntax Arithmetic Operators Operator Description

addition

* multiplication

/ division

^ or ** exponentiation

x %% y modulus (x mod y) 5%%2 is 1

x %% y integer division 5%/%2 is 2

less than less than or equal to greater than greater than or equal to exactly equal to not equal to	operator	Description
greater than or equal to exactly equal to	<	less than
greater than or equal to exactly equal to	<=	less than or equal to
exactly equal to	>	greater than
	>=	greater than or equal to
not equal to	==	exactly equal to
	!=	not equal to
Not x	!x	Not x
x OR y	x y	x OR y
x AND y	х & у	x AND y

Developers of new features should know a few things on the structure of the code. When developing custom functions please stick to these conventions.

The following files are required; they must all be in the same directory (these are contained within the Rcrust folder which should simply be copied to the desired location):

- 1) From **Perple_X** suite (in the folder called "data"):
 - a. The various datafiles you wish to use, these include: thermodynamic datafiles and solution model files, typically *hp04ver.dat* and *solution_model.dat* as well as the Perple_X option file, *perplex_option.dat*.
 - b. Meemum.exe
 - c. The rest of Perple_X (vertex, build, werami, etc.) are not required.
- 2) From **Rcrust** (in the folder called "code"):
 - a. ui.r and server.r, these build the Rcrust Graphical User Interface (GUI)
 - b. main.r, this houses the main calls to run Rcrust
 - c. meemum_connect.r, the functions for calling and interpreting outputs from meemum
 - d. Various init_xxx files, used to transform user input in data structures that Rcrust can understand.

```
i. init_bulk.r
ii. init_pt.r
iii. init_pt.add.r
iv. init_ph_extr.r
vi. init_dependence
vii. init_wrapper
sets the bulk composition(s) of the system
sets the P-T conditions
sets the phases to add
sets the phases to extract
writes user inputs into a meemum build file determines the calculation order of points
the phase stability calculator from Perple_X
```

e. parse_meem, a temporary Perple_X build file created to pass data into the wrapper f. run.Rcrust.r, the Rcrust calculation loop to be called for each point

Technically, each function works c0 which tracks the bulk compositional changes invoked by phase manipulations. main.r loops through each point, calculating and modifying the phases according to the chosen definitions and eventually stores the final product in a list called crust, whose structure is $\texttt{crust}[[y_i]][[x_i]]$. So, for instance the SiO2 content in the melt of point $y_i=4$ and $x_i=2$ is crust[[4]][[2]]["melt(HP)","SIO2"]

 Various xxx.dll files which contain compiled libraries needed to perform calculations within R

Troubleshooting

A list of known errors that are unavoidable or are still to be fixed.

Bulk_ss system properties

Warning: some bulk system properties are reported as molar properties but perplex considers the bulk system to be one mol thus all molar properties need to be adjusted accordingly

Molar phase proportions

Only weight definitions of bulk and phases is currently possible, read.meemum cannot read molar phase proportions. If molar proportions for bulk are entered, then bulk is molar but individual phases are weights thus phase extractions crash.

Buffered Output

The R console by default returns a buffered output which forces the console to only refresh when flush.console() is called. To disable the buffering and view run data live deselect from R toolbar Misc/Buffered Output.

External Sources

Perple_X

http://www.perplex.ethz.ch/

Perple_X Solution Model Glossary

http://www.perplex.ethz.ch/PerpleX_solution_model_glossary.html

THERMOCALC's list of mineral abbreviations

http://www.metamorph.geo.uni-mainz.de/thermocalc/documentation/abbreviations/index.html

REFERENCES

Mayne, M. J., Moyen, J. F., Stevens, G., & Kaislaniemi, L. (2016). Rcrust: a tool for calculating path-dependent open system processes and application to melt loss. *Journal of Metamorphic Geology*, **34**(7), 663-682

Connolly, J.A.D., 2005. Computation of phase equilibria by linear programming: a tool for geodynamic modeling and its application to subduction zone decarbonation. Earth and Planetary Science Letters, **236**, 524–541.

Connolly, J.A.D., 2009. The geodynamic equation of state: what and how. Geochemistry, Geophysics, Geosystems, 10, 1-19.

Connolly, J.A.D. & Kerrick, D.M., 1987. An algorithm and computer program for calculating composition phase diagrams. Calphad, **11**, 1–55.