Lecture 30 — The Producer-Consumer Problem


Jeff Zarnett jzarnett@uwaterloo.ca

Department of Electrical and Computer Engineering University of Waterloo

March 9, 2024

MTE 241 Spring 2024 1/27

Monty Python and the Holy Compiler



The producer-consumer problem, the readers-writers problem, and the dining philosophers problem.

MTE 241 Spring 2024 2/27

Produce and Consume

First: the producer-consumer problem, also sometimes called the bounded-buffer-problem.

Two processes share a common buffer that is of fixed size.

One process is the producer: it generates data and puts it in the buffer.

The other is the consumer: it takes data out of the buffer.

This problem can be generalized to have p producers and c consumers.

MTE 241 Spring 2024 3/27

Rules:

- The buffer is of capacity BUFFER_SIZE.
- Cannot write into a full buffer
- Cannot read from an empty buffer

To keep track of the number of items in the buffer, we will have some variable count.

This is a shared variable, so we need a mutex for it.

MTE 241 Spring 2024 4/27

If busy-waiting is permitted, we can get away with one mutex.

Shown below is one loop iteration for each of the producer & consumer.

Producer

```
1. [produce item]
2. added = false
3. while added is false
4. wait( mutex )
5. if count < BUFFER_SIZE
6. [add item to buffer]
7. count++
8. added = true
9. end if
10. post( mutex )
11. end while</pre>
```

Consumer

MTE 241 Spring 2024 5/27

No Busy-Waiting

While this accomplishes what we want, it is inefficient.


Let's add a new rule that says we want to avoid busy-waiting.

The producer gets blocked if there are no available spaces.

The consumer gets blocked if there's nothing to consume.

MTE 241 Spring 2024 6/27

When You Lose Track of the Number of Sets...



MTE 241 Spring 2024 7/27

Use Semaphores To Count

Use 2 general semaphores, each with maximum value of BUFFER_SIZE.

items: starts at 0 and represents how many spaces in the buffer are full.

spaces: starts at BUFFER_SIZE and represents the number of spaces in the buffer that are currently empty.

MTE 241 Spring 2024 8 / 27

Producer-Consumer with Waiting

Producer

- [produce item]
- 2. wait(spaces)
- 3. [add item to buffer]
- 4. post(items)

Does this work?

Are there any implicit assumptions?

Consumer

- 1. wait(items)
- [remove item from buffer]
- 3. post(spaces)
- 4. [consume item]

MTE 241 Spring 2024 9/27

Assumptions made? I assume so...

(1) The actions of adding an item to the buffer and removing an item from the buffer add to and remove from the "next" space.

(2) There is exactly one producer and one consumer in the system.

If we have two producers, for example, they might be trying to write into the same space at the same time, and this would be a problem.

MTE 241 Spring 2024 10 / 2

Mmmmmmmulti-Consume!

To generalize this solution to allow multiple producers and multiple consumers, we need a mutex.

Producer

- 1. [produce item]
- 2. wait(spaces)
- 3. wait(mutex)
- 4. [add item to buffer]
- 5. post(mutex)
- 6. post(items)

Consumer

- 1. wait(items)
- 2. wait(mutex)
- 3. [remove item from buffer]
- 4. post(mutex)
- 5. post(spaces)
- [consume item]

Does this work?

Anything... worrying?

MTE 241 Spring 2024 11/27

Cancel Red Alert

The hint that we might have a problem is one wait statement inside another.

But it doesn't guarantee a problem...

We should be able to reason through why there is (or isn't) a problem.

MTE 241 Spring 2024 12/27

Alternative Solution: PC

Producer

- [produce item]
- 2. wait(mutex)
- 3. wait(spaces)
- 4. [add item to buffer]
- 5. post(items)
- 6. post(mutex)

Does this work?

Consumer

```
1. wait( mutex )
```

- 2. wait(items)
- 3. [remove item from buffer]
- 4. post(spaces)
- 5. post(mutex)
- 6. [consume item]

MTE 241 Spring 2024 13/27

The Tiny Details...

This solution does have the deadlock problem!

Imagine at the start of execution, the buffer is empty and the consumer runs first...

Do you see the problem now?

This could also happen with the producer.

MTE 241 Spring 2024 14/27

Problems are Only Sometimes a Problem

If this solution were implemented, it wouldn't guarantee a deadlock occurs.

In fact, it probably works fine most of the time.

Once, however, we have found one scenario that can lead to deadlock, there is no need to look for other failure cases.

We can replace this solution with a better one.

MTE 241 Spring 2024 15/27

P-C Example

```
#include < stdio h>
#include < stdlib .h>
#include <pthread.h>
#include < unistd h>
#include <semaphore.h>
#define BUFFER_SIZE 20
sem_t spaces;
sem_t items:
int counter = 0;
int* buffer;
int produce() {
 ++counter;
  return counter:
void consume( int value ) {
  printf("Consumed_%d.\n", value);
```

MTE 241 Spring 2024 16 / 27

```
void* producer( void* arg ) {
  int pindex = 0;
  while ( counter < 10000 ) {
    int v = produce():
    sem_wait( &spaces );
    buffer[pindex] = v;
    pindex = (pindex + 1) % BUFFER_SIZE;
    sem_post( &items );
  pthread_exit( NULL );
void* consumer( void* arg ) {
  int cindex = 0:
  int ctotal = 0:
  while ( ctotal < 10000 ) {
    sem_wait( &items ):
    int temp = buffer[cindex]:
    buffer[cindex] = -1;
    cindex = (cindex + 1) % BUFFER_SIZE;
    sem_post( &spaces );
    consume( temp );
    ++ctotal:
  pthread_exit( NULL ):
```

MTE 241 Spring 2024 17/27

```
int main( int argc. char** argv ) {
  buffer = malloc( BUFFER_SIZE * sizeof( int ) );
  for ( int i = 0; i < BUFFER_SIZE; i++ ) {</pre>
    buffer[i] = -1:
  sem_init( &spaces. O. BUFFER_SIZE ):
  sem_init( &items, 0, 0 );
  pthread_t prod:
  pthread_t con;
  pthread_create( &prod. NULL. producer. NULL ):
  pthread_create( &con, NULL, consumer, NULL );
  pthread_join( prod, NULL );
  pthread_join( con, NULL );
  free( buffer ):
  sem_destrov( &spaces ):
  sem_destroy( &items );
  pthread_exit( 0 ):
```

MTE 241 Spring 2024 18 / 27



MTE 241 Spring 2024 19 / 27

Mutex Syntax

We should take a moment to learn about the syntax of the pthread mutex.

While it is possible, of course, to use a semaphore as a mutex, frequently we will use the more specialized tool for this task.

In fact, it's generally good practice to use the more specialized tool.

MTE 241 Spring 2024 20 / 27

The structure representing the mutex is of type pthread_mutex_t.

```
pthread_mutex_init( pthread_mutex_t *mutex, pthread_mutexattr_t *attributes )
```

mutex: the mutex to intiialize.

attributes: the attributes; NULL is fine for defaults.

Shortcut if you do not want to set attributes:

```
pthread_mutex_t mymutex = PTHREAD_MUTEX_INITIALIZER;
```

By default, the mutex is created as unlocked.

MTE 241 Spring 2024 21/27

Lock and Unlock

```
pthread_mutex_lock( pthread_mutex_t *mutex )
pthread_mutex_trylock( pthread_mutex_t *mutex ) /* Returns O on success */
pthread_mutex_unlock( pthread_mutex_t *mutex )
```

Unlock is self-explanatory.

pthread_mutex_lock is blocking.

pthread_mutex_trylock is nonblocking.

Trylock will come up again soon when we look at another classical synchronization problem.

MTE 241 Spring 2024 22 / 27

Destroy the Mutex

pthread_mutex_destroy(pthread_mutex_t *mutex)

Destroy is also self-explanatory.

An attempt to destroy the mutex may fail if the mutex is currently locked.

Attempting to destroy a locked one results in undefined behaviour.

MTE 241 Spring 2024 23 / 27

```
#include < stdlib b>
#include <pthread.h>
#include < stdio.h>
#include <math h>
#include <semaphore.h>
#define BUFFER_SIZE 100
int buffer[BUFFER_SIZE];
int pindex = 0;
int cindex = 0;
sem_t spaces;
sem_t items:
pthread_mutex_t mutex;
int produce( int id ) {
  int r = rand();
  printf("Producer %d produced %d.\n", id, r):
  return r:
void consume( int id, int number ) {
  printf("Consumer_%d_consumed_%d.\n", id, number);
```

MTE 241 Spring 2024 24/27

```
void* producer( void* arg ) {
    int* id = (int*) arg;
    for(int i = 0; i < 10000; ++i) {
        int num = produce(*id);
        sem_wait( &spaces );
        pthread_mutex_lock( &mutex );
        buffer[pindex] = num;
        pindex = (pindex + 1) % BUFFER_SIZE;
        pthread_mutex_unlock( &mutex );
        sem_post( &items );
    }
    free( arg );
    pthread_exit( NULL );
}</pre>
```

MTE 241 Spring 2024 25 / 27

```
void* consumer( void* arg ) {
  int* id = (int*) arg;
  for(int i = 0; i < 10000; ++i) {
    sem_wait( &items );
    pthread_mutex_lock( &mutex );
    int num = buffer[cindex];
    buffer[cindex] = -1;
    cindex = (cindex + 1) % BUFFER_SIZE;
    pthread_mutex_unlock( &mutex );
    sem_post( &spaces );
    consume( *id, num );
  }
  free( id );
  pthread_exit( NULL );
}</pre>
```

MTE 241 Spring 2024 26 / 27

```
int main( int argc. char** argv ) {
  sem_init( &spaces, 0, BUFFER_SIZE );
  sem_init( &items, 0, 0 );
  pthread_mutex_init( &mutex. NULL ):
  pthread_t threads[20]:
  for ( int i = 0; i < 10; i++ ) {
    int* id = malloc(sizeof(int)):
    *id = i:
   pthread_create(&threads[i], NULL, producer, id);
  for ( int j = 10; j < 20; j++ ) {
    int* jd = malloc(sizeof(int));
    *id = i-10:
    pthread_create(&threads[j], NULL, consumer, jd);
  for (int k = 0: k < 20: k++){}
    pthread_join(threads[k], NULL);
  sem_destroy( &spaces );
  sem_destroy( &items );
  pthread_mutex_destroy( &mutex );
  pthread_exit( 0 );
```

MTE 241 Spring 2024 27 / 27